

Run-Time Library (RTL) :
Reference guide.

Free Pascal version 3.0.4:
Reference guide for RTL units.
Document version 3.0.4
February 2019

Michaël Van Canneyt

Contents

0.1	Overview	123
1	Reference for unit 'BaseUnix'	124
1.1	Used units	124
1.2	Overview	124
1.3	Constants, types and variables	124
1.3.1	Constants	124
1.3.2	Types	148
1.4	Procedures and functions	167
1.4.1	CreateShellArgV	167
1.4.2	FpAccess	167
1.4.3	FpAlarm	168
1.4.4	FpChdir	169
1.4.5	FpChmod	169
1.4.6	FpChown	170
1.4.7	FpClose	171
1.4.8	FpClosedir	172
1.4.9	FpDup	172
1.4.10	FpDup2	173
1.4.11	FpExecv	174
1.4.12	FpExecve	175
1.4.13	FpExit	176
1.4.14	FpFcntl	176
1.4.15	fpdffillset	177
1.4.16	fpFD_CLR	177
1.4.17	fpFD_ISSET	177
1.4.18	fpFD_SET	177
1.4.19	fpFD_ZERO	178
1.4.20	FpFork	178
1.4.21	FPFStat	178
1.4.22	FpFtruncate	179

1.4.23	FpGetcwd	180
1.4.24	FpGetegid	180
1.4.25	FpGetEnv	180
1.4.26	fpgeterrno	181
1.4.27	FpGeteuid	181
1.4.28	FpGetgid	182
1.4.29	FpGetgroups	182
1.4.30	FpGetpggrp	182
1.4.31	FpGetpid	183
1.4.32	FpGetppid	183
1.4.33	fpGetPriority	184
1.4.34	FpGetRLimit	184
1.4.35	FpGetsid	184
1.4.36	FpGetuid	185
1.4.37	FpIOCtl	185
1.4.38	FpKill	186
1.4.39	FpLink	186
1.4.40	FpLseek	187
1.4.41	fpLstat	188
1.4.42	FpMkdir	189
1.4.43	FpMkfifo	190
1.4.44	Fpmmmap	190
1.4.45	Fpmunmap	191
1.4.46	FpNanoSleep	192
1.4.47	fpNice	193
1.4.48	FpOpen	193
1.4.49	FpOpendir	194
1.4.50	FpPause	196
1.4.51	FpPipe	196
1.4.52	FpPoll	197
1.4.53	FppRead	197
1.4.54	FppWrite	197
1.4.55	FpRead	198
1.4.56	FpReaddir	199
1.4.57	fpReadLink	199
1.4.58	FpReadV	200
1.4.59	FpRename	200
1.4.60	FpRmdir	201
1.4.61	fpSelect	202
1.4.62	fpseterrno	203

1.4.63	FpSetgid	203
1.4.64	fpSetPriority	204
1.4.65	FpSetRLimit	204
1.4.66	FpSetsid	204
1.4.67	fpsettimeofday	205
1.4.68	FpSetuid	205
1.4.69	FPSigaction	205
1.4.70	FpSigAddSet	206
1.4.71	FpSigDelSet	207
1.4.72	FpsigEmptySet	207
1.4.73	FpSigFillSet	207
1.4.74	FpSigIsMember	207
1.4.75	FpSignal	208
1.4.76	FpSigPending	208
1.4.77	FpSigProcMask	209
1.4.78	FpSigSuspend	209
1.4.79	FpSigTimedWait	209
1.4.80	FpSleep	210
1.4.81	FpStat	210
1.4.82	fpSymlink	211
1.4.83	fpS_ISBLK	212
1.4.84	fpS_ISCHR	213
1.4.85	fpS_ISDIR	213
1.4.86	fpS_ISFIFO	213
1.4.87	fpS_ISLNK	214
1.4.88	fpS_ISREG	214
1.4.89	fpS_ISSOCK	215
1.4.90	fpTime	215
1.4.91	FpTimes	215
1.4.92	FpUmask	216
1.4.93	FpUname	216
1.4.94	FpUnlink	216
1.4.95	FpUtime	217
1.4.96	FpWait	218
1.4.97	FpWaitPid	218
1.4.98	FpWrite	219
1.4.99	FpWriteV	219
1.4.100	FreeShellArgV	219
1.4.101	wexitStatus	220
1.4.102	wifexited	220

1.4.103	wifsignaled	220
1.4.104	wstopsig	220
1.4.105	wtermSIG	221
2	Reference for unit 'character'	222
2.1	Used units	222
2.2	Overview	222
2.3	Constants, types and variables	222
2.3.1	Types	222
3	Reference for unit 'charset'	225
3.1	Used units	225
3.2	Overview	225
3.3	Constants, types and variables	225
3.3.1	Constants	225
3.3.2	Types	225
3.4	Procedures and functions	227
3.4.1	getascii	227
3.4.2	getmap	228
3.4.3	getunicode	228
3.4.4	loadbinaryunicodemapping	228
3.4.5	loadunicodemapping	229
3.4.6	mappingavailable	229
3.4.7	registerbinarymapping	229
3.4.8	registermapping	230
4	Reference for unit 'Classes'	231
4.1	Used units	231
4.2	Overview	231
4.3	Constants, types and variables	231
4.3.1	Constants	231
4.3.2	Types	234
4.3.3	Variables	249
4.4	Procedures and functions	250
4.4.1	ActivateClassGroup	250
4.4.2	BeginGlobalLoading	250
4.4.3	BinToHex	251
4.4.4	Bounds	251
4.4.5	CheckSynchronize	251
4.4.6	ClassGroupOf	252
4.4.7	CollectionsEqual	252

4.4.8	EndGlobalLoading	252
4.4.9	ExtractStrings	252
4.4.10	FindClass	253
4.4.11	FindGlobalComponent	253
4.4.12	FindIdentToInt	253
4.4.13	FindIntToIdent	253
4.4.14	FindNestedComponent	254
4.4.15	GetClass	254
4.4.16	GetFixupInstanceNames	254
4.4.17	GetFixupReferenceNames	254
4.4.18	GlobalFixupReferences	255
4.4.19	GroupDescendentsWith	255
4.4.20	HexToBin	255
4.4.21	IdentToInt	255
4.4.22	InitComponentRes	256
4.4.23	InitInheritedComponent	256
4.4.24	IntToIdent	256
4.4.25	InvalidPoint	256
4.4.26	LineStart	257
4.4.27	NotifyGlobalLoading	257
4.4.28	ObjectBinaryToText	257
4.4.29	ObjectResourceToText	257
4.4.30	ObjectTextToBinary	257
4.4.31	ObjectTextToResource	258
4.4.32	Point	258
4.4.33	PointsEqual	258
4.4.34	ReadComponentRes	258
4.4.35	ReadComponentResEx	259
4.4.36	ReadComponentResFile	259
4.4.37	Rect	259
4.4.38	RedirectFixupReferences	259
4.4.39	RegisterClass	260
4.4.40	RegisterClassAlias	260
4.4.41	RegisterClasses	260
4.4.42	RegisterComponents	260
4.4.43	RegisterFindGlobalComponentProc	261
4.4.44	RegisterInitComponentHandler	261
4.4.45	RegisterIntegerConsts	261
4.4.46	RegisterNoIcon	262
4.4.47	RegisterNonActiveX	262

4.4.48	RemoveFixupReferences	262
4.4.49	RemoveFixups	263
4.4.50	SmallPoint	263
4.4.51	StartClassGroup	263
4.4.52	UnRegisterClass	263
4.4.53	UnRegisterClasses	263
4.4.54	UnregisterFindGlobalComponentProc	264
4.4.55	UnRegisterModuleClasses	264
4.4.56	WriteComponentResFile	264
4.5	EBitsError	264
4.5.1	Description	264
4.6	EClassNotFound	265
4.6.1	Description	265
4.7	EComponentError	265
4.7.1	Description	265
4.8	EFCCreateError	265
4.8.1	Description	265
4.9	EFileError	265
4.9.1	Description	265
4.10	EFOpenError	265
4.10.1	Description	265
4.11	EInvalidImage	266
4.11.1	Description	266
4.12	EInvalidOperation	266
4.12.1	Description	266
4.13	EListError	266
4.13.1	Description	266
4.14	EMethodNotFound	266
4.14.1	Description	266
4.15	EObserver	266
4.15.1	Description	266
4.16	EOutOfResources	267
4.16.1	Description	267
4.17	EParseError	267
4.17.1	Description	267
4.18	EReadError	267
4.18.1	Description	267
4.19	EResNotFound	267
4.19.1	Description	267
4.20	EStreamError	267

4.20.1	Description	267
4.21	EStringListError	268
4.21.1	Description	268
4.22	EThread	268
4.22.1	Description	268
4.23	EThreadDestroyCalled	268
4.23.1	Description	268
4.24	EThreadExternalException	268
4.24.1	Description	268
4.25	EWriteError	268
4.25.1	Description	268
4.26	IDesignerNotify	269
4.26.1	Description	269
4.26.2	Method overview	269
4.26.3	IDesignerNotify.Modified	269
4.26.4	IDesignerNotify.Notification	269
4.27	IFPObserved	269
4.27.1	Description	269
4.27.2	Method overview	270
4.27.3	IFPObserved.FPOAttachObserver	270
4.27.4	IFPObserved.FPODetachObserver	270
4.27.5	IFPObserved.FPONotifyObservers	270
4.28	IFPObserver	271
4.28.1	Description	271
4.28.2	Method overview	271
4.28.3	IFPObserver.FPOObservedChanged	271
4.29	IInterfaceComponentReference	271
4.29.1	Description	271
4.29.2	Method overview	272
4.29.3	IInterfaceComponentReference.GetComponent	272
4.30	IInterfaceList	272
4.30.1	Description	272
4.30.2	Method overview	272
4.30.3	Property overview	273
4.30.4	IInterfaceList.Get	273
4.30.5	IInterfaceList.GetCapacity	273
4.30.6	IInterfaceList.GetCount	273
4.30.7	IInterfaceList.Put	273
4.30.8	IInterfaceList.SetCapacity	274
4.30.9	IInterfaceList.SetCount	274

4.30.10	IInterfaceList.Clear	274
4.30.11	IInterfaceList.Delete	274
4.30.12	IInterfaceList.Exchange	275
4.30.13	IInterfaceList.First	275
4.30.14	IInterfaceList.IndexOf	275
4.30.15	IInterfaceList.Add	275
4.30.16	IInterfaceList.Insert	275
4.30.17	IInterfaceList.Last	276
4.30.18	IInterfaceList.Remove	276
4.30.19	IInterfaceList.Lock	276
4.30.20	IInterfaceList.Unlock	276
4.30.21	IInterfaceList.Capacity	276
4.30.22	IInterfaceList.Count	277
4.30.23	IInterfaceList.Items	277
4.31	IStreamPersist	277
4.31.1	Description	277
4.31.2	Method overview	277
4.31.3	IStreamPersist.LoadFromStream	278
4.31.4	IStreamPersist.SaveToStream	278
4.32	IStringsAdapter	278
4.32.1	Description	278
4.32.2	Method overview	278
4.32.3	IStringsAdapter.ReferenceStrings	278
4.32.4	IStringsAdapter.ReleaseStrings	278
4.33	IVCLComObject	279
4.33.1	Description	279
4.33.2	Method overview	279
4.33.3	IVCLComObject.GetTypeInfoCount	279
4.33.4	IVCLComObject.GetTypeInfo	279
4.33.5	IVCLComObject.GetIDsOfNames	280
4.33.6	IVCLComObject.Invoke	280
4.33.7	IVCLComObject.SafeCallException	280
4.33.8	IVCLComObject.FreeOnRelease	280
4.34	TAbstractObjectReader	281
4.34.1	Description	281
4.34.2	Method overview	281
4.34.3	TAbstractObjectReader.NextValue	281
4.34.4	TAbstractObjectReader.ReadValue	282
4.34.5	TAbstractObjectReader.BeginRootComponent	282
4.34.6	TAbstractObjectReader.BeginComponent	282

4.34.7	TAbstractObjectReader.BeginProperty	283
4.34.8	TAbstractObjectReader.Read	283
4.34.9	TAbstractObjectReader.ReadBinary	283
4.34.10	TAbstractObjectReader.ReadFloat	283
4.34.11	TAbstractObjectReader.ReadSingle	284
4.34.12	TAbstractObjectReader.ReadDate	284
4.34.13	TAbstractObjectReader.ReadCurrency	284
4.34.14	TAbstractObjectReader.ReadIdent	284
4.34.15	TAbstractObjectReader.ReadInt8	285
4.34.16	TAbstractObjectReader.ReadInt16	285
4.34.17	TAbstractObjectReader.ReadInt32	286
4.34.18	TAbstractObjectReader.ReadInt64	286
4.34.19	TAbstractObjectReader.ReadSet	286
4.34.20	TAbstractObjectReader.ReadSignature	287
4.34.21	TAbstractObjectReader.ReadStr	287
4.34.22	TAbstractObjectReader.ReadString	287
4.34.23	TAbstractObjectReader.ReadWideString	288
4.34.24	TAbstractObjectReader.ReadUnicodeString	288
4.34.25	TAbstractObjectReader.SkipComponent	288
4.34.26	TAbstractObjectReader.SkipValue	288
4.35	TAbstractObjectWriter	289
4.35.1	Description	289
4.35.2	Method overview	289
4.35.3	TAbstractObjectWriter.BeginCollection	289
4.35.4	TAbstractObjectWriter.BeginComponent	289
4.35.5	TAbstractObjectWriter.WriteSignature	290
4.35.6	TAbstractObjectWriter.BeginList	290
4.35.7	TAbstractObjectWriter.EndList	290
4.35.8	TAbstractObjectWriter.BeginProperty	290
4.35.9	TAbstractObjectWriter.EndProperty	290
4.35.10	TAbstractObjectWriter.Write	291
4.35.11	TAbstractObjectWriter.WriteBinary	291
4.35.12	TAbstractObjectWriter.WriteBoolean	291
4.35.13	TAbstractObjectWriter.WriteFloat	291
4.35.14	TAbstractObjectWriter.WriteSingle	291
4.35.15	TAbstractObjectWriter.WriteDate	292
4.35.16	TAbstractObjectWriter.WriteCurrency	292
4.35.17	TAbstractObjectWriter.WriteIdent	292
4.35.18	TAbstractObjectWriter.WriteInteger	292
4.35.19	TAbstractObjectWriter.WriteUInt64	292

4.35.20	TAbstractObjectWriter.WriteVariant	293
4.35.21	TAbstractObjectWriter.WriteMethodName	293
4.35.22	TAbstractObjectWriter.WriteSet	293
4.35.23	TAbstractObjectWriter.WriteString	293
4.35.24	TAbstractObjectWriter.WriteWideString	293
4.35.25	TAbstractObjectWriter.WriteUnicodeString	294
4.36	TBasicAction	294
4.36.1	Description	294
4.36.2	Method overview	294
4.36.3	Property overview	294
4.36.4	TBasicAction.Create	294
4.36.5	TBasicAction.Destroy	295
4.36.6	TBasicAction.HandlesTarget	295
4.36.7	TBasicAction.UpdateTarget	295
4.36.8	TBasicAction.ExecuteTarget	296
4.36.9	TBasicAction.Execute	296
4.36.10	TBasicAction.RegisterChanges	296
4.36.11	TBasicAction.UnRegisterChanges	296
4.36.12	TBasicAction.Update	297
4.36.13	TBasicAction.ActionComponent	297
4.36.14	TBasicAction.OnExecute	297
4.36.15	TBasicAction.OnUpdate	298
4.37	TBasicActionLink	298
4.37.1	Description	298
4.37.2	Method overview	298
4.37.3	Property overview	298
4.37.4	TBasicActionLink.Create	298
4.37.5	TBasicActionLink.Destroy	299
4.37.6	TBasicActionLink.Execute	299
4.37.7	TBasicActionLink.Update	299
4.37.8	TBasicActionLink.Action	300
4.37.9	TBasicActionLink.OnChange	300
4.38	TBinaryObjectReader	300
4.38.1	Description	300
4.38.2	Method overview	301
4.38.3	TBinaryObjectReader.Create	301
4.38.4	TBinaryObjectReader.Destroy	301
4.38.5	TBinaryObjectReader.NextValue	302
4.38.6	TBinaryObjectReader.ReadValue	302
4.38.7	TBinaryObjectReader.BeginRootComponent	302

4.38.8	TBinaryObjectReader.BeginComponent	302
4.38.9	TBinaryObjectReader.BeginProperty	303
4.38.10	TBinaryObjectReader.Read	303
4.38.11	TBinaryObjectReader.ReadBinary	303
4.38.12	TBinaryObjectReader.ReadFloat	303
4.38.13	TBinaryObjectReader.ReadSingle	303
4.38.14	TBinaryObjectReader.ReadDate	304
4.38.15	TBinaryObjectReader.ReadCurrency	304
4.38.16	TBinaryObjectReader.ReadIdent	304
4.38.17	TBinaryObjectReader.ReadInt8	304
4.38.18	TBinaryObjectReader.ReadInt16	304
4.38.19	TBinaryObjectReader.ReadInt32	305
4.38.20	TBinaryObjectReader.ReadInt64	305
4.38.21	TBinaryObjectReader.ReadSet	305
4.38.22	TBinaryObjectReader.ReadSignature	305
4.38.23	TBinaryObjectReader.ReadStr	306
4.38.24	TBinaryObjectReader.ReadString	306
4.38.25	TBinaryObjectReader.ReadWideString	306
4.38.26	TBinaryObjectReader.ReadUnicodeString	306
4.38.27	TBinaryObjectReader.SkipComponent	307
4.38.28	TBinaryObjectReader.SkipValue	307
4.39	TBinaryObjectWriter	307
4.39.1	Description	307
4.39.2	Method overview	308
4.39.3	TBinaryObjectWriter.Create	308
4.39.4	TBinaryObjectWriter.Destroy	308
4.39.5	TBinaryObjectWriter.WriteSignature	308
4.39.6	TBinaryObjectWriter.BeginCollection	309
4.39.7	TBinaryObjectWriter.BeginComponent	309
4.39.8	TBinaryObjectWriter.BeginList	309
4.39.9	TBinaryObjectWriter.EndList	309
4.39.10	TBinaryObjectWriter.BeginProperty	309
4.39.11	TBinaryObjectWriter.EndProperty	309
4.39.12	TBinaryObjectWriter.Write	310
4.39.13	TBinaryObjectWriter.WriteBinary	310
4.39.14	TBinaryObjectWriter.WriteBoolean	310
4.39.15	TBinaryObjectWriter.WriteFloat	310
4.39.16	TBinaryObjectWriter.WriteSingle	310
4.39.17	TBinaryObjectWriter.WriteDate	310
4.39.18	TBinaryObjectWriter.WriteCurrency	311

4.39.19	TBinaryObjectWriter.WriteIdent	311
4.39.20	TBinaryObjectWriter.WriteInteger	311
4.39.21	TBinaryObjectWriter.WriteUInt64	311
4.39.22	TBinaryObjectWriter.WriteMethodName	311
4.39.23	TBinaryObjectWriter.WriteSet	311
4.39.24	TBinaryObjectWriter.WriteString	312
4.39.25	TBinaryObjectWriter.WriteString	312
4.39.26	TBinaryObjectWriter.WriteWideString	312
4.39.27	TBinaryObjectWriter.WriteUnicodeString	312
4.39.28	TBinaryObjectWriter.WriteVariant	312
4.40	TBits	313
4.40.1	Description	313
4.40.2	Method overview	313
4.40.3	Property overview	313
4.40.4	TBits.Create	313
4.40.5	TBits.Destroy	314
4.40.6	TBits.GetFSize	314
4.40.7	TBits.SetOn	314
4.40.8	TBits.Clear	314
4.40.9	TBits.Clearall	315
4.40.10	TBits.AndBits	315
4.40.11	TBits.OrBits	315
4.40.12	TBits.XorBits	315
4.40.13	TBits.NotBits	316
4.40.14	TBits.Get	316
4.40.15	TBits.Grow	316
4.40.16	TBits.Equals	317
4.40.17	TBits.SetIndex	317
4.40.18	TBits.FindFirstBit	317
4.40.19	TBits.FindNextBit	318
4.40.20	TBits.FindPrevBit	318
4.40.21	TBits.OpenBit	318
4.40.22	TBits.Bits	319
4.40.23	TBits.Size	319
4.41	TBytesStream	319
4.41.1	Description	319
4.41.2	Method overview	319
4.41.3	Property overview	319
4.41.4	TBytesStream.Create	320
4.41.5	TBytesStream.Bytes	320

4.42	TCollection	320
4.42.1	Description	320
4.42.2	Method overview	321
4.42.3	Property overview	321
4.42.4	TCollection.Create	321
4.42.5	TCollection.Destroy	321
4.42.6	TCollection.Owner	322
4.42.7	TCollection.Add	322
4.42.8	TCollection.Assign	322
4.42.9	TCollection.BeginUpdate	322
4.42.10	TCollection.Clear	323
4.42.11	TCollection.EndUpdate	323
4.42.12	TCollection.Delete	323
4.42.13	TCollection.GetEnumerator	324
4.42.14	TCollection.GetNamePath	324
4.42.15	TCollection.Insert	324
4.42.16	TCollection.FindItemID	324
4.42.17	TCollection.Exchange	325
4.42.18	TCollection.Sort	325
4.42.19	TCollection.Count	325
4.42.20	TCollection.ItemClass	326
4.42.21	TCollection.Items	326
4.43	TCollectionEnumerator	326
4.43.1	Description	326
4.43.2	Method overview	326
4.43.3	Property overview	327
4.43.4	TCollectionEnumerator.Create	327
4.43.5	TCollectionEnumerator.GetCurrent	327
4.43.6	TCollectionEnumerator.MoveNext	327
4.43.7	TCollectionEnumerator.Current	327
4.44	TCollectionItem	328
4.44.1	Description	328
4.44.2	Method overview	328
4.44.3	Property overview	328
4.44.4	TCollectionItem.Create	328
4.44.5	TCollectionItem.Destroy	328
4.44.6	TCollectionItem.GetNamePath	329
4.44.7	TCollectionItem.Collection	329
4.44.8	TCollectionItem.ID	329
4.44.9	TCollectionItem.Index	330

4.44.10	TCollectionItem.DisplayName	330
4.45	TComponent	330
4.45.1	Description	330
4.45.2	Interfaces overview	331
4.45.3	Method overview	331
4.45.4	Property overview	331
4.45.5	TComponent.Notification	332
4.45.6	TComponent.WriteState	332
4.45.7	TComponent.Create	332
4.45.8	TComponent.Destroy	333
4.45.9	TComponent.BeforeDestruction	333
4.45.10	TComponent.DestroyComponents	333
4.45.11	TComponent.Destroying	333
4.45.12	TComponent.ExecuteAction	334
4.45.13	TComponent.FindComponent	334
4.45.14	TComponent.FreeNotification	334
4.45.15	TComponent.RemoveFreeNotification	334
4.45.16	TComponent.FreeOnRelease	334
4.45.17	TComponent.GetEnumerator	335
4.45.18	TComponent.GetNamePath	335
4.45.19	TComponent.GetParentComponent	335
4.45.20	TComponent.HasParent	335
4.45.21	TComponent.InsertComponent	336
4.45.22	TComponent.RemoveComponent	336
4.45.23	TComponent.SafeCallException	336
4.45.24	TComponent.SetSubComponent	336
4.45.25	TComponent.UpdateAction	337
4.45.26	TComponent.IsImplementorOf	337
4.45.27	TComponent.ReferenceInterface	337
4.45.28	TComponent.ComObject	337
4.45.29	TComponent.Components	338
4.45.30	TComponent.ComponentCount	338
4.45.31	TComponent.ComponentIndex	338
4.45.32	TComponent.ComponentState	338
4.45.33	TComponent.ComponentStyle	339
4.45.34	TComponent.DesignInfo	339
4.45.35	TComponent.Owner	339
4.45.36	TComponent.VCLComObject	340
4.45.37	TComponent.Name	340
4.45.38	TComponent.Tag	340

4.46	TComponentEnumerator	341
4.46.1	Description	341
4.46.2	Method overview	341
4.46.3	Property overview	341
4.46.4	TComponentEnumerator.Create	341
4.46.5	TComponentEnumerator.GetCurrent	341
4.46.6	TComponentEnumerator.MoveNext	342
4.46.7	TComponentEnumerator.Current	342
4.47	TCustomMemoryStream	342
4.47.1	Description	342
4.47.2	Method overview	342
4.47.3	Property overview	343
4.47.4	TCustomMemoryStream.Read	343
4.47.5	TCustomMemoryStream.Seek	343
4.47.6	TCustomMemoryStream.SaveToStream	343
4.47.7	TCustomMemoryStream.SaveToFile	344
4.47.8	TCustomMemoryStream.Memory	344
4.48	TDataModule	344
4.48.1	Description	344
4.48.2	Method overview	345
4.48.3	Property overview	345
4.48.4	TDataModule.Create	345
4.48.5	TDataModule.CreateNew	345
4.48.6	TDataModule.Destroy	346
4.48.7	TDataModule.AfterConstruction	346
4.48.8	TDataModule.BeforeDestruction	346
4.48.9	TDataModule.DesignOffset	346
4.48.10	TDataModule.DesignSize	347
4.48.11	TDataModule.DesignPPI	347
4.48.12	TDataModule.OnCreate	347
4.48.13	TDataModule.OnDestroy	347
4.48.14	TDataModule.OldCreateOrder	348
4.49	TFiler	348
4.49.1	Description	348
4.49.2	Method overview	348
4.49.3	Property overview	348
4.49.4	TFiler.DefineProperty	348
4.49.5	TFiler.DefineBinaryProperty	349
4.49.6	TFiler.Root	349
4.49.7	TFiler.LookupRoot	349

4.49.8	TFiler.Ancestor	349
4.49.9	TFiler.IgnoreChildren	350
4.50	TFileStream	350
4.50.1	Description	350
4.50.2	Method overview	350
4.50.3	Property overview	350
4.50.4	TFileStream.Create	350
4.50.5	TFileStream.Destroy	351
4.50.6	TFileStream.FileName	351
4.51	TFPList	352
4.51.1	Description	352
4.51.2	Method overview	352
4.51.3	Property overview	352
4.51.4	TFPList.Destroy	352
4.51.5	TFPList.AddList	353
4.51.6	TFPList.Add	353
4.51.7	TFPList.Clear	353
4.51.8	TFPList.Delete	353
4.51.9	TFPList.Error	354
4.51.10	TFPList.Exchange	354
4.51.11	TFPList.Expand	354
4.51.12	TFPList.Extract	354
4.51.13	TFPList.First	355
4.51.14	TFPList.GetEnumerator	355
4.51.15	TFPList.IndexOf	355
4.51.16	TFPList.IndexOfItem	355
4.51.17	TFPList.Insert	356
4.51.18	TFPList.Last	356
4.51.19	TFPList.Move	356
4.51.20	TFPList.Assign	356
4.51.21	TFPList.Remove	357
4.51.22	TFPList.Pack	357
4.51.23	TFPList.Sort	357
4.51.24	TFPList.ForEachCall	357
4.51.25	TFPList.Capacity	358
4.51.26	TFPList.Count	358
4.51.27	TFPList.Items	358
4.51.28	TFPList.List	359
4.52	TFPListEnumerator	359
4.52.1	Description	359

4.52.2	Method overview	359
4.52.3	Property overview	359
4.52.4	TFPListEnumerator.Create	359
4.52.5	TFPListEnumerator.GetCurrent	359
4.52.6	TFPListEnumerator.MoveNext	360
4.52.7	TFPListEnumerator.Current	360
4.53	THandleStream	360
4.53.1	Description	360
4.53.2	Method overview	361
4.53.3	Property overview	361
4.53.4	THandleStream.Create	361
4.53.5	THandleStream.Read	361
4.53.6	THandleStream.Write	361
4.53.7	THandleStream.Seek	362
4.53.8	THandleStream.Handle	362
4.54	TInterfacedPersistent	362
4.54.1	Description	362
4.54.2	Interfaces overview	362
4.54.3	Method overview	362
4.54.4	TInterfacedPersistent.QueryInterface	362
4.54.5	TInterfacedPersistent.AfterConstruction	363
4.55	TInterfaceList	363
4.55.1	Description	363
4.55.2	Interfaces overview	363
4.55.3	Method overview	363
4.55.4	Property overview	364
4.55.5	TInterfaceList.Create	364
4.55.6	TInterfaceList.Destroy	364
4.55.7	TInterfaceList.Clear	364
4.55.8	TInterfaceList.Delete	364
4.55.9	TInterfaceList.Exchange	365
4.55.10	TInterfaceList.First	365
4.55.11	TInterfaceList.GetEnumerator	365
4.55.12	TInterfaceList.IndexOf	365
4.55.13	TInterfaceList.Add	366
4.55.14	TInterfaceList.Insert	366
4.55.15	TInterfaceList.Last	366
4.55.16	TInterfaceList.Remove	366
4.55.17	TInterfaceList.Lock	367
4.55.18	TInterfaceList.Unlock	367

4.55.19	TInterfaceList.Expand	367
4.55.20	TInterfaceList.Capacity	367
4.55.21	TInterfaceList.Count	368
4.55.22	TInterfaceList.Items	368
4.56	TInterfaceListEnumerator	368
4.56.1	Description	368
4.56.2	Method overview	368
4.56.3	Property overview	368
4.56.4	TInterfaceListEnumerator.Create	369
4.56.5	TInterfaceListEnumerator.GetCurrent	369
4.56.6	TInterfaceListEnumerator.MoveNext	369
4.56.7	TInterfaceListEnumerator.Current	369
4.57	TList	370
4.57.1	Description	370
4.57.2	Interfaces overview	370
4.57.3	Method overview	370
4.57.4	Property overview	371
4.57.5	TList.Create	371
4.57.6	TList.Destroy	371
4.57.7	TList.FPOAttachObserver	371
4.57.8	TList.FPODetachObserver	371
4.57.9	TList.FPONotifyObservers	372
4.57.10	TList.AddList	372
4.57.11	TList.Add	372
4.57.12	TList.Clear	373
4.57.13	TList.Delete	373
4.57.14	TList.Error	373
4.57.15	TList.Exchange	373
4.57.16	TList.Expand	373
4.57.17	TList.Extract	374
4.57.18	TList.First	374
4.57.19	TList.GetEnumerator	374
4.57.20	TList.IndexOf	375
4.57.21	TList.Insert	375
4.57.22	TList.Last	375
4.57.23	TList.Move	375
4.57.24	TList.Assign	376
4.57.25	TList.Remove	376
4.57.26	TList.Pack	376
4.57.27	TList.Sort	376

4.57.28	TList.Capacity	377
4.57.29	TList.Count	377
4.57.30	TList.Items	377
4.57.31	TList.List	377
4.58	TListEnumerator	378
4.58.1	Description	378
4.58.2	Method overview	378
4.58.3	Property overview	378
4.58.4	TListEnumerator.Create	378
4.58.5	TListEnumerator.GetCurrent	378
4.58.6	TListEnumerator.MoveNext	378
4.58.7	TListEnumerator.Current	379
4.59	TMemoryStream	379
4.59.1	Description	379
4.59.2	Method overview	379
4.59.3	TMemoryStream.Destroy	379
4.59.4	TMemoryStream.Clear	380
4.59.5	TMemoryStream.LoadFromStream	380
4.59.6	TMemoryStream.LoadFromFile	380
4.59.7	TMemoryStream.SetSize	381
4.59.8	TMemoryStream.Write	381
4.60	TOwnedCollection	381
4.60.1	Description	381
4.60.2	Method overview	381
4.60.3	TOwnedCollection.Create	381
4.61	TOwnerStream	382
4.61.1	Description	382
4.61.2	Method overview	382
4.61.3	Property overview	382
4.61.4	TOwnerStream.Create	382
4.61.5	TOwnerStream.Destroy	382
4.61.6	TOwnerStream.Source	383
4.61.7	TOwnerStream.SourceOwner	383
4.62	TParser	383
4.62.1	Description	383
4.62.2	Method overview	384
4.62.3	Property overview	384
4.62.4	TParser.Create	384
4.62.5	TParser.Destroy	384
4.62.6	TParser.CheckToken	385

4.62.7	TParser.CheckTokenSymbol	385
4.62.8	TParser.Error	385
4.62.9	TParser.ErrorFmt	385
4.62.10	TParser.ErrorStr	385
4.62.11	TParser.HexToBinary	386
4.62.12	TParser.NextToken	386
4.62.13	TParser.SourcePos	386
4.62.14	TParser.TokenComponentIdent	387
4.62.15	TParser.TokenFloat	387
4.62.16	TParser.TokenInt	387
4.62.17	TParser.TokenString	388
4.62.18	TParser.TokenWideString	388
4.62.19	TParser.TokenSymbolIs	388
4.62.20	TParser.FloatType	389
4.62.21	TParser.SourceLine	389
4.62.22	TParser.Token	389
4.63	TPersistent	390
4.63.1	Description	390
4.63.2	Interfaces overview	390
4.63.3	Method overview	390
4.63.4	TPersistent.Destroy	390
4.63.5	TPersistent.Assign	391
4.63.6	TPersistent.FPOAttachObserver	391
4.63.7	TPersistent.FPODetachObserver	392
4.63.8	TPersistent.FPONotifyObservers	392
4.63.9	TPersistent.GetNamePath	392
4.64	TProxyStream	392
4.64.1	Description	392
4.64.2	Method overview	393
4.64.3	TProxyStream.Create	393
4.64.4	TProxyStream.Read	393
4.64.5	TProxyStream.Write	393
4.64.6	TProxyStream.Seek	393
4.64.7	TProxyStream.Check	393
4.65	TReader	394
4.65.1	Description	394
4.65.2	Method overview	395
4.65.3	Property overview	396
4.65.4	TReader.Create	396
4.65.5	TReader.Destroy	396

4.65.6	TReader.BeginReferences	396
4.65.7	TReader.CheckValue	397
4.65.8	TReader.DefineProperty	397
4.65.9	TReader.DefineBinaryProperty	397
4.65.10	TReader.EndOfList	397
4.65.11	TReader.EndReferences	397
4.65.12	TReader.FixupReferences	398
4.65.13	TReader.NextValue	398
4.65.14	TReader.Read	398
4.65.15	TReader.ReadBoolean	398
4.65.16	TReader.ReadChar	398
4.65.17	TReader.ReadWideChar	399
4.65.18	TReader.ReadUnicodeChar	399
4.65.19	TReader.ReadCollection	399
4.65.20	TReader.ReadComponent	399
4.65.21	TReader.ReadComponents	399
4.65.22	TReader.ReadFloat	400
4.65.23	TReader.ReadSingle	400
4.65.24	TReader.ReadDate	400
4.65.25	TReader.ReadCurrency	400
4.65.26	TReader.ReadIdent	400
4.65.27	TReader.ReadInteger	401
4.65.28	TReader.ReadInt64	401
4.65.29	TReader.ReadSet	401
4.65.30	TReader.ReadListBegin	401
4.65.31	TReader.ReadListEnd	401
4.65.32	TReader.ReadRootComponent	402
4.65.33	TReader.ReadVariant	402
4.65.34	TReader.ReadSignature	402
4.65.35	TReader.ReadString	402
4.65.36	TReader.ReadWideString	403
4.65.37	TReader.ReadUnicodeString	403
4.65.38	TReader.ReadValue	403
4.65.39	TReader.CopyValue	403
4.65.40	TReader.Driver	403
4.65.41	TReader.Owner	404
4.65.42	TReader.Parent	404
4.65.43	TReader.OnError	404
4.65.44	TReader.OnPropertyNotFound	404
4.65.45	TReader.OnFindMethod	405

4.65.46	TReader.OnSetMethodProperty	405
4.65.47	TReader.OnSetName	405
4.65.48	TReader.OnReferenceName	405
4.65.49	TReader.OnAncestorNotFound	405
4.65.50	TReader.OnCreateComponent	406
4.65.51	TReader.OnFindComponentClass	406
4.65.52	TReader.OnReadStringProperty	406
4.66	TRecall	406
4.66.1	Description	406
4.66.2	Method overview	407
4.66.3	Property overview	407
4.66.4	TRecall.Create	407
4.66.5	TRecall.Destroy	407
4.66.6	TRecall.Store	407
4.66.7	TRecall.Forget	408
4.66.8	TRecall.Reference	408
4.67	TResourceStream	408
4.67.1	Description	408
4.67.2	Method overview	408
4.67.3	TResourceStream.Create	409
4.67.4	TResourceStream.CreateFromID	409
4.67.5	TResourceStream.Destroy	409
4.68	TStream	409
4.68.1	Description	409
4.68.2	Method overview	410
4.68.3	Property overview	410
4.68.4	TStream.Read	410
4.68.5	TStream.Write	411
4.68.6	TStream.Seek	411
4.68.7	TStream.ReadBuffer	412
4.68.8	TStream.WriteBuffer	412
4.68.9	TStream.CopyFrom	413
4.68.10	TStream.ReadComponent	413
4.68.11	TStream.ReadComponentRes	413
4.68.12	TStream.WriteComponent	414
4.68.13	TStream.WriteComponentRes	414
4.68.14	TStream.WriteDescendent	414
4.68.15	TStream.WriteDescendentRes	414
4.68.16	TStream.WriteResourceHeader	415
4.68.17	TStream.FixupResourceHeader	415

4.68.18	TStream.ReadResHeader	415
4.68.19	TStream.ReadByte	415
4.68.20	TStream.ReadWord	416
4.68.21	TStream.ReadDWord	416
4.68.22	TStream.ReadQWord	416
4.68.23	TStream.ReadAnsiString	417
4.68.24	TStream.WriteByte	417
4.68.25	TStream.WriteWord	417
4.68.26	TStream.WriteDWord	417
4.68.27	TStream.WriteQWord	418
4.68.28	TStream.WriteAnsiString	418
4.68.29	TStream.Position	418
4.68.30	TStream.Size	419
4.69	TStreamAdapter	419
4.69.1	Description	419
4.69.2	Interfaces overview	419
4.69.3	Method overview	419
4.69.4	Property overview	420
4.69.5	TStreamAdapter.Create	420
4.69.6	TStreamAdapter.Destroy	420
4.69.7	TStreamAdapter.Read	420
4.69.8	TStreamAdapter.Write	420
4.69.9	TStreamAdapter.Seek	421
4.69.10	TStreamAdapter.SetSize	421
4.69.11	TStreamAdapter.CopyTo	421
4.69.12	TStreamAdapter.Commit	422
4.69.13	TStreamAdapter.Revert	422
4.69.14	TStreamAdapter.LockRegion	422
4.69.15	TStreamAdapter.UnlockRegion	422
4.69.16	TStreamAdapter.Stat	423
4.69.17	TStreamAdapter.Clone	423
4.69.18	TStreamAdapter.Stream	423
4.69.19	TStreamAdapter.StreamOwnership	423
4.70	TStringList	424
4.70.1	Description	424
4.70.2	Method overview	424
4.70.3	Property overview	424
4.70.4	TStringList.Destroy	424
4.70.5	TStringList.Add	425
4.70.6	TStringList.Clear	425

4.70.7	TStringList.Delete	425
4.70.8	TStringList.Exchange	425
4.70.9	TStringList.Find	426
4.70.10	TStringList.IndexOf	426
4.70.11	TStringList.Insert	426
4.70.12	TStringList.Sort	426
4.70.13	TStringList.CustomSort	427
4.70.14	TStringList.Duplicates	427
4.70.15	TStringList.Sorted	427
4.70.16	TStringList.CaseSensitive	428
4.70.17	TStringList.OnChange	428
4.70.18	TStringList.OnChanging	428
4.70.19	TStringList.OwnsObjects	429
4.70.20	TStringList.SortStyle	429
4.71	TStrings	429
4.71.1	Description	429
4.71.2	Method overview	430
4.71.3	Property overview	431
4.71.4	TStrings.Destroy	431
4.71.5	TStrings.Add	431
4.71.6	TStrings.AddObject	431
4.71.7	TStrings.Append	432
4.71.8	TStrings.AddStrings	432
4.71.9	TStrings.AddText	432
4.71.10	TStrings.Assign	433
4.71.11	TStrings.BeginUpdate	433
4.71.12	TStrings.Clear	433
4.71.13	TStrings.Delete	434
4.71.14	TStrings.EndUpdate	434
4.71.15	TStrings.Equals	434
4.71.16	TStrings.Exchange	435
4.71.17	TStrings.GetEnumerator	435
4.71.18	TStrings.GetText	435
4.71.19	TStrings.IndexOf	435
4.71.20	TStrings.IndexOfName	436
4.71.21	TStrings.IndexOfObject	436
4.71.22	TStrings.Insert	436
4.71.23	TStrings.InsertObject	437
4.71.24	TStrings.LoadFromFile	437
4.71.25	TStrings.LoadFromStream	437

4.71.26	TStrings.Move	437
4.71.27	TStrings.SaveToFile	438
4.71.28	TStrings.SaveToStream	438
4.71.29	TStrings.SetText	439
4.71.30	TStrings.GetNameValue	439
4.71.31	TStrings.ExtractName	439
4.71.32	TStrings.TextLineBreakStyle	439
4.71.33	TStrings.Delimiter	440
4.71.34	TStrings.DelimitedText	440
4.71.35	TStrings.LineBreak	440
4.71.36	TStrings.StrictDelimiter	441
4.71.37	TStrings.QuoteChar	441
4.71.38	TStrings.NameValueSeparator	441
4.71.39	TStrings.ValueFromIndex	442
4.71.40	TStrings.Capacity	442
4.71.41	TStrings.CommaText	442
4.71.42	TStrings.Count	443
4.71.43	TStrings.Names	443
4.71.44	TStrings.Objects	444
4.71.45	TStrings.Values	444
4.71.46	TStrings.Strings	444
4.71.47	TStrings.Text	445
4.71.48	TStrings.StringsAdapter	445
4.71.49	TStrings.SkipLastLineBreak	445
4.72	TStringsEnumerator	446
4.72.1	Description	446
4.72.2	Method overview	446
4.72.3	Property overview	446
4.72.4	TStringsEnumerator.Create	446
4.72.5	TStringsEnumerator.GetCurrent	446
4.72.6	TStringsEnumerator.MoveNext	447
4.72.7	TStringsEnumerator.Current	447
4.73	TStringStream	447
4.73.1	Description	447
4.73.2	Method overview	447
4.73.3	Property overview	447
4.73.4	TStringStream.Create	448
4.73.5	TStringStream.Read	448
4.73.6	TStringStream.ReadString	448
4.73.7	TStringStream.Seek	448

4.73.8	TStringStream.Write	449
4.73.9	TStringStream.WriteString	449
4.73.10	TStringStream.DataString	449
4.74	TTextObjectWriter	449
4.74.1	Description	449
4.75	TThread	449
4.75.1	Description	449
4.75.2	Method overview	450
4.75.3	Property overview	450
4.75.4	TThread.Execute	450
4.75.5	TThread.Synchronize	451
4.75.6	TThread.Queue	451
4.75.7	TThread.Create	451
4.75.8	TThread.Destroy	451
4.75.9	TThread.CreateAnonymousThread	452
4.75.10	TThread.NameThreadForDebugging	452
4.75.11	TThread.SetReturnValue	452
4.75.12	TThread.CheckTerminated	452
4.75.13	TThread.RemoveQueuedEvents	453
4.75.14	TThread.SpinWait	453
4.75.15	TThread.Sleep	453
4.75.16	TThread.Yield	454
4.75.17	TThread.GetSystemTimes	454
4.75.18	TThread.GetTickCount	454
4.75.19	TThread.GetTickCount64	454
4.75.20	TThread.ExecuteInThread	454
4.75.21	TThread.AfterConstruction	459
4.75.22	TThread.Start	459
4.75.23	TThread.Resume	460
4.75.24	TThread.Suspend	460
4.75.25	TThread.Terminate	460
4.75.26	TThread.WaitFor	460
4.75.27	TThread.CurrentThread	461
4.75.28	TThread.ProcessorCount	461
4.75.29	TThread.IsSingleProcessor	461
4.75.30	TThread.FreeOnTerminate	462
4.75.31	TThread.Handle	462
4.75.32	TThread.ExternalThread	462
4.75.33	TThread.Priority	462
4.75.34	TThread.Suspended	462

4.75.35	TThread.Finished	463
4.75.36	TThread.ThreadID	463
4.75.37	TThread.OnTerminate	463
4.75.38	TThread.FatalException	463
4.76	TThreadList	464
4.76.1	Description	464
4.76.2	Method overview	464
4.76.3	Property overview	464
4.76.4	TThreadList.Create	464
4.76.5	TThreadList.Destroy	464
4.76.6	TThreadList.Add	465
4.76.7	TThreadList.Clear	465
4.76.8	TThreadList.LockList	465
4.76.9	TThreadList.Remove	465
4.76.10	TThreadList.UnlockList	466
4.76.11	TThreadList.Duplicates	466
4.77	TWriter	466
4.77.1	Description	466
4.77.2	Method overview	467
4.77.3	Property overview	467
4.77.4	TWriter.Create	467
4.77.5	TWriter.Destroy	468
4.77.6	TWriter.DefineProperty	468
4.77.7	TWriter.DefineBinaryProperty	468
4.77.8	TWriter.Write	468
4.77.9	TWriter.WriteBoolean	468
4.77.10	TWriter.WriteCollection	469
4.77.11	TWriter.WriteComponent	469
4.77.12	TWriter.WriteChar	469
4.77.13	TWriter.WriteWideChar	469
4.77.14	TWriter.WriteDescendent	469
4.77.15	TWriter.WriteFloat	470
4.77.16	TWriter.WriteSingle	470
4.77.17	TWriter.WriteDate	470
4.77.18	TWriter.WriteCurrency	470
4.77.19	TWriter.WriteIdent	470
4.77.20	TWriter.WriteInteger	471
4.77.21	TWriter.WriteSet	471
4.77.22	TWriter.WriteListBegin	471
4.77.23	TWriter.WriteListEnd	471

4.77.24	TWriter.WriteSignature	471
4.77.25	TWriter.WriteRootComponent	472
4.77.26	TWriter.WriteString	472
4.77.27	TWriter.WriteWideString	472
4.77.28	TWriter.WriteUnicodeString	472
4.77.29	TWriter.WriteVariant	472
4.77.30	TWriter.RootAncestor	473
4.77.31	TWriter.OnFindAncestor	473
4.77.32	TWriter.OnWriteMethodProperty	473
4.77.33	TWriter.OnWriteStringProperty	473
4.77.34	TWriter.Driver	474
4.77.35	TWriter.PropertyPath	474
5	Reference for unit 'clocale'	475
5.1	Used units	475
5.2	Overview	475
6	Reference for unit 'cmem'	476
6.1	Used units	476
6.2	Overview	476
6.3	Constants, types and variables	476
6.3.1	Constants	476
6.4	Procedures and functions	476
6.4.1	CAlloc	476
6.4.2	Free	477
6.4.3	Malloc	477
6.4.4	ReAlloc	477
7	Reference for unit 'collation_de'	478
7.1	Used units	478
7.2	Overview	478
8	Reference for unit 'collation_es'	479
8.1	Used units	479
8.2	Overview	479
9	Reference for unit 'collation_fr_ca'	480
9.1	Used units	480
9.2	Overview	480
10	Reference for unit 'collation_ja'	481
10.1	Used units	481

10.2	Overview	481
11	Reference for unit 'collation_ko'	482
11.1	Used units	482
11.2	Overview	482
12	Reference for unit 'collation_ru'	483
12.1	Used units	483
12.2	Overview	483
13	Reference for unit 'collation_sv'	484
13.1	Used units	484
13.2	Overview	484
14	Reference for unit 'collation_zh'	485
14.1	Used units	485
14.2	Overview	485
15	Reference for unit 'cp1250'	486
15.1	Used units	486
15.2	Overview	486
16	Reference for unit 'cp1251'	487
16.1	Used units	487
16.2	Overview	487
17	Reference for unit 'cp1252'	488
17.1	Used units	488
17.2	Overview	488
18	Reference for unit 'cp1253'	489
18.1	Used units	489
18.2	Overview	489
19	Reference for unit 'cp1254'	490
19.1	Used units	490
19.2	Overview	490
20	Reference for unit 'cp1255'	491
20.1	Used units	491
20.2	Overview	491
21	Reference for unit 'cp1256'	492
21.1	Used units	492

21.2	Overview	492
22	Reference for unit 'cp1257'	493
22.1	Used units	493
22.2	Overview	493
23	Reference for unit 'cp1258'	494
23.1	Used units	494
23.2	Overview	494
24	Reference for unit 'cp437'	495
24.1	Used units	495
24.2	Overview	495
25	Reference for unit 'cp646'	496
25.1	Used units	496
25.2	Overview	496
26	Reference for unit 'cp850'	497
26.1	Used units	497
26.2	Overview	497
27	Reference for unit 'cp852'	498
27.1	Used units	498
27.2	Overview	498
28	Reference for unit 'cp856'	499
28.1	Used units	499
28.2	Overview	499
29	Reference for unit 'cp866'	500
29.1	Used units	500
29.2	Overview	500
30	Reference for unit 'cp874'	501
30.1	Used units	501
30.2	Overview	501
31	Reference for unit 'cp8859_1'	502
31.1	Used units	502
31.2	Overview	502
32	Reference for unit 'cp8859_2'	503
32.1	Used units	503

32.2	Overview	503
33	Reference for unit 'cp8859_5'	504
33.1	Used units	504
33.2	Overview	504
34	Reference for unit 'cp895'	505
34.1	Used units	505
34.2	Overview	505
35	Reference for unit 'cp932'	506
35.1	Used units	506
35.2	Overview	506
36	Reference for unit 'cp936'	507
36.1	Used units	507
36.2	Overview	507
37	Reference for unit 'cp949'	508
37.1	Used units	508
37.2	Overview	508
38	Reference for unit 'cp950'	509
38.1	Used units	509
38.2	Overview	509
39	Reference for unit 'cpall'	510
39.1	Used units	510
39.2	Overview	510
40	Reference for unit 'Crt'	511
40.1	Used units	511
40.2	Overview	511
40.3	Constants, types and variables	512
40.3.1	Constants	512
40.3.2	Types	514
40.3.3	Variables	514
40.4	Procedures and functions	515
40.4.1	AssignCrt	515
40.4.2	ClrEol	516
40.4.3	ClrScr	517
40.4.4	cursorbig	517
40.4.5	cursoroff	517

40.4.6	cursoron	518
40.4.7	Delay	518
40.4.8	DelLine	518
40.4.9	GotoXY	519
40.4.10	HighVideo	520
40.4.11	InsLine	520
40.4.12	KeyPressed	521
40.4.13	LowVideo	521
40.4.14	NormVideo	522
40.4.15	NoSound	522
40.4.16	ReadKey	522
40.4.17	Sound	523
40.4.18	TextBackground	523
40.4.19	TextColor	524
40.4.20	TextMode	525
40.4.21	WhereX	525
40.4.22	WhereY	525
40.4.23	Window	526
41	Reference for unit 'cthreads'	527
41.1	Used units	527
41.2	Overview	527
41.3	Procedures and functions	528
41.3.1	SetCThreadManager	528
42	Reference for unit 'ctypes'	529
42.1	Used units	529
42.2	Overview	529
42.3	Constants, types and variables	529
42.3.1	Types	529
43	Reference for unit 'cwstring'	535
43.1	Used units	535
43.2	Overview	535
43.3	Procedures and functions	535
43.3.1	SetCWidestringManager	535
44	Reference for unit 'dateutils'	537
44.1	Used units	537
44.2	Overview	537
44.3	Constants, types and variables	537

44.3.1	Constants	537
44.4	Procedures and functions	539
44.4.1	CompareDate	539
44.4.2	CompareDateTime	540
44.4.3	CompareTime	541
44.4.4	DateOf	542
44.4.5	DateTimeToDosDateTime	543
44.4.6	DateTimeToJulianDate	543
44.4.7	DateTimeToMac	543
44.4.8	DateTimeToModifiedJulianDate	544
44.4.9	DateTimeToUnix	544
44.4.10	DayOf	544
44.4.11	DayOfTheMonth	544
44.4.12	DayOfTheWeek	545
44.4.13	DayOfTheYear	545
44.4.14	DaysBetween	545
44.4.15	DaysInAMonth	546
44.4.16	DaysInAYear	547
44.4.17	DaysInMonth	547
44.4.18	DaysInYear	548
44.4.19	DaySpan	548
44.4.20	DecodeDateDay	549
44.4.21	DecodeDateMonthWeek	550
44.4.22	DecodeDateTime	550
44.4.23	DecodeDateWeek	551
44.4.24	DecodeDayOfWeekInMonth	552
44.4.25	DosDateTimeToDateTime	552
44.4.26	EncodeDateDay	553
44.4.27	EncodeDateMonthWeek	553
44.4.28	EncodeDateTime	553
44.4.29	EncodeDateWeek	554
44.4.30	EncodeDayOfWeekInMonth	554
44.4.31	EncodeTimeInterval	554
44.4.32	EndOfADay	555
44.4.33	EndOfAMonth	555
44.4.34	EndOfAWeek	556
44.4.35	EndOfAYear	557
44.4.36	EndOfTheDay	557
44.4.37	EndOfTheMonth	558
44.4.38	EndOfTheWeek	558

44.4.39	EndOfTheYear	559
44.4.40	HourOf	559
44.4.41	HourOfTheDay	559
44.4.42	HourOfTheMonth	560
44.4.43	HourOfTheWeek	560
44.4.44	HourOfTheYear	561
44.4.45	HoursBetween	561
44.4.46	HourSpan	562
44.4.47	IncDay	563
44.4.48	IncHour	563
44.4.49	IncMilliSecond	564
44.4.50	IncMinute	564
44.4.51	IncSecond	565
44.4.52	IncWeek	565
44.4.53	IncYear	566
44.4.54	InvalidDateDayError	566
44.4.55	InvalidDateMonthWeekError	566
44.4.56	InvalidDateTimeError	567
44.4.57	InvalidDateWeekError	567
44.4.58	InvalidDayOfWeekInMonthError	568
44.4.59	IsInLeapYear	568
44.4.60	IsPM	568
44.4.61	IsSameDay	569
44.4.62	IsSameMonth	569
44.4.63	IsToday	570
44.4.64	IsValidDate	570
44.4.65	IsValidDateDay	571
44.4.66	IsValidDateMonthWeek	571
44.4.67	IsValidDateTime	572
44.4.68	IsValidDateWeek	573
44.4.69	IsValidTime	574
44.4.70	JulianDateToDateTime	574
44.4.71	LocalTimeToUniversal	574
44.4.72	MacTimeStampToUnix	575
44.4.73	MacToDateTime	575
44.4.74	MilliSecondOf	575
44.4.75	MilliSecondOfTheDay	575
44.4.76	MilliSecondOfTheHour	576
44.4.77	MilliSecondOfTheMinute	576
44.4.78	MilliSecondOfTheMonth	576

44.4.79	MilliSecondOfTheSecond	577
44.4.80	MilliSecondOfTheWeek	577
44.4.81	MilliSecondOfTheYear	577
44.4.82	MilliSecondsBetween	578
44.4.83	MilliSecondSpan	579
44.4.84	MinuteOf	579
44.4.85	MinuteOfTheDay	580
44.4.86	MinuteOfTheHour	580
44.4.87	MinuteOfTheMonth	581
44.4.88	MinuteOfTheWeek	581
44.4.89	MinuteOfTheYear	581
44.4.90	MinutesBetween	581
44.4.91	MinuteSpan	582
44.4.92	ModifiedJulianDateToDateTime	583
44.4.93	MonthOf	583
44.4.94	MonthOfTheYear	584
44.4.95	MonthsBetween	584
44.4.96	MonthSpan	585
44.4.97	NthDayOfWeek	586
44.4.98	PeriodBetween	586
44.4.99	PreviousDayOfWeek	587
44.4.100	RecodeDate	587
44.4.101	RecodeDateTime	588
44.4.102	RecodeDay	589
44.4.103	RecodeHour	589
44.4.104	RecodeMilliSecond	590
44.4.105	RecodeMinute	591
44.4.106	RecodeMonth	591
44.4.107	RecodeSecond	592
44.4.108	RecodeTime	593
44.4.109	RecodeYear	593
44.4.110	SameDate	594
44.4.111	SameDateTime	595
44.4.112	SameTime	596
44.4.113	ScanDateTime	596
44.4.114	SecondOf	597
44.4.115	SecondOfTheDay	597
44.4.116	SecondOfTheHour	597
44.4.117	SecondOfTheMinute	598
44.4.118	SecondOfTheMonth	598

44.4.119	SecondOfTheWeek	598
44.4.120	SecondOfTheYear	599
44.4.121	SecondsBetween	599
44.4.122	SecondSpan	600
44.4.123	StartOfADay	601
44.4.124	StartOfAMonth	602
44.4.125	StartOfAWeek	602
44.4.126	StartOfAYear	603
44.4.127	StartOfTheDay	603
44.4.128	StartOfTheMonth	604
44.4.129	StartOfTheWeek	604
44.4.130	StartOfTheYear	605
44.4.131	TimeOf	605
44.4.132	Today	606
44.4.133	Tomorrow	606
44.4.134	TryEncodeDateDay	607
44.4.135	TryEncodeDateMonthWeek	607
44.4.136	TryEncodeDateTime	608
44.4.137	TryEncodeDateWeek	609
44.4.138	TryEncodeDayOfWeekInMonth	609
44.4.139	TryEncodeTimeInterval	610
44.4.140	TryJulianDateToDateTime	610
44.4.141	TryModifiedJulianDateToDateTime	611
44.4.142	TryRecodeDateTime	611
44.4.143	UniversalTimeToLocal	612
44.4.144	UnixTimeStampToMac	612
44.4.145	UnixToDateTime	612
44.4.146	WeekOf	613
44.4.147	WeekOfTheMonth	613
44.4.148	WeekOfTheYear	614
44.4.149	WeeksBetween	614
44.4.150	WeeksInAYear	615
44.4.151	WeeksInYear	616
44.4.152	WeekSpan	616
44.4.153	WithinPastDays	617
44.4.154	WithinPastHours	618
44.4.155	WithinPastMilliseconds	619
44.4.156	WithinPastMinutes	620
44.4.157	WithinPastMonths	621
44.4.158	WithinPastSeconds	622

44.4.159 WithinPastWeeks	623
44.4.160 WithinPastYears	624
44.4.161 YearOf	625
44.4.162 YearsBetween	626
44.4.163 YearSpan	627
44.4.164 Yesterday	627
45 Reference for unit 'Dos'	629
45.1 Used units	629
45.2 Overview	629
45.3 System information	629
45.4 Process handling	630
45.5 Directory and disk handling	630
45.6 File handling	631
45.7 File open mode constants.	631
45.8 File attributes	631
45.9 Constants, types and variables	632
45.9.1 Constants	632
45.9.2 Types	633
45.9.3 Variables	636
45.10 Procedures and functions	636
45.10.1 AddDisk	636
45.10.2 DiskFree	637
45.10.3 DiskSize	637
45.10.4 DosExitCode	638
45.10.5 DosVersion	638
45.10.6 DTToUnixDate	639
45.10.7 EnvCount	639
45.10.8 EnvStr	640
45.10.9 Exec	640
45.10.10 FExpand	641
45.10.11 FindClose	641
45.10.12 FindFirst	641
45.10.13 FindNext	642
45.10.14 FSearch	642
45.10.15 FSplit	643
45.10.16 GetCBreak	644
45.10.17 GetDate	644
45.10.18 GetEnv	645
45.10.19 GetFAttr	645

45.10.20	GetFTime	646
45.10.21	GetIntVec	647
45.10.22	GetLongName	647
45.10.23	GetMsCount	647
45.10.24	GetShortName	648
45.10.25	GetTime	648
45.10.26	GetVerify	649
45.10.27	Intr	649
45.10.28	Keep	649
45.10.29	MSDos	650
45.10.30	PackTime	650
45.10.31	SetCBreak	651
45.10.32	SetDate	651
45.10.33	SetFAttr	651
45.10.34	SetFTime	652
45.10.35	SetIntVec	652
45.10.36	SetTime	653
45.10.37	SetVerify	653
45.10.38	SwapVectors	653
45.10.39	UnixDateToDt	654
45.10.40	UnpackTime	654
45.10.41	weekday	654
46	Reference for unit 'dxeload'	655
46.1	Used units	655
46.2	Overview	655
46.3	Procedures and functions	655
46.3.1	dxeload	655
47	Reference for unit 'dynlibs'	656
47.1	Used units	656
47.2	Overview	656
47.3	Constants, types and variables	656
47.3.1	Constants	656
47.3.2	Types	656
47.4	Procedures and functions	657
47.4.1	FreeLibrary	657
47.4.2	GetLoadErrorStr	657
47.4.3	GetProcAddress	657
47.4.4	GetProcedureAddress	658
47.4.5	LoadLibrary	658

47.4.6	SafeLoadLibrary	658
47.4.7	UnloadLibrary	659
48	Reference for unit 'emu387'	660
48.1	Used units	660
48.2	Overview	660
48.3	Procedures and functions	660
48.3.1	npxsetup	660
49	Reference for unit 'errors'	662
49.1	Used units	662
49.2	Overview	662
49.3	Constants, types and variables	662
49.3.1	Constants	662
49.4	Procedures and functions	663
49.4.1	PError	663
49.4.2	StrError	664
50	Reference for unit 'exeinfo'	665
50.1	Used units	665
50.2	Overview	665
50.3	Constants, types and variables	665
50.3.1	Types	665
50.4	Procedures and functions	666
50.4.1	CloseExeFile	666
50.4.2	FindExeSection	666
50.4.3	GetModuleByAddr	666
50.4.4	OpenExeFile	667
50.4.5	ReadDebugLink	667
51	Reference for unit 'fgl'	668
51.1	Used units	668
51.2	Overview	668
51.3	Constants, types and variables	668
51.3.1	Constants	668
51.3.2	Types	668
51.4	EListError	669
51.4.1	Description	669
51.5	TFFPGInterfacedObjectList	669
51.5.1	Description	669
51.5.2	Method overview	669

51.5.3	Property overview	669
51.5.4	TFPGInterfacedObjectList.Create	670
51.5.5	TFPGInterfacedObjectList.Add	670
51.5.6	TFPGInterfacedObjectList.Extract	670
51.5.7	TFPGInterfacedObjectList.GetEnumerator	670
51.5.8	TFPGInterfacedObjectList.IndexOf	671
51.5.9	TFPGInterfacedObjectList.Insert	671
51.5.10	TFPGInterfacedObjectList.Assign	671
51.5.11	TFPGInterfacedObjectList.Remove	671
51.5.12	TFPGInterfacedObjectList.Sort	672
51.5.13	TFPGInterfacedObjectList.First	672
51.5.14	TFPGInterfacedObjectList.Last	672
51.5.15	TFPGInterfacedObjectList.Items	673
51.5.16	TFPGInterfacedObjectList.List	673
51.6	TFPGList	673
51.6.1	Description	673
51.6.2	Method overview	673
51.6.3	Property overview	674
51.6.4	TFPGList.Create	674
51.6.5	TFPGList.Add	674
51.6.6	TFPGList.Extract	674
51.6.7	TFPGList.GetEnumerator	674
51.6.8	TFPGList.IndexOf	675
51.6.9	TFPGList.Insert	675
51.6.10	TFPGList.Assign	675
51.6.11	TFPGList.Remove	675
51.6.12	TFPGList.Sort	676
51.6.13	TFPGList.First	676
51.6.14	TFPGList.Last	676
51.6.15	TFPGList.Items	676
51.6.16	TFPGList.List	677
51.7	TFPGListEnumerator	677
51.7.1	Description	677
51.7.2	Method overview	677
51.7.3	Property overview	677
51.7.4	TFPGListEnumerator.Create	677
51.7.5	TFPGListEnumerator.MoveNext	678
51.7.6	TFPGListEnumerator.Current	678
51.8	TFPGMap	678
51.8.1	Description	678

51.8.2	Method overview	678
51.8.3	Property overview	679
51.8.4	TFPGMap.Create	679
51.8.5	TFPGMap.Add	679
51.8.6	TFPGMap.Find	679
51.8.7	TFPGMap.TryGetData	680
51.8.8	TFPGMap.AddOrSetData	680
51.8.9	TFPGMap.IndexOf	680
51.8.10	TFPGMap.IndexOfData	680
51.8.11	TFPGMap.InsertKey	681
51.8.12	TFPGMap.InsertKeyData	681
51.8.13	TFPGMap.Remove	681
51.8.14	TFPGMap.Keys	681
51.8.15	TFPGMap.Data	682
51.8.16	TFPGMap.KeyData	682
51.8.17	TFPGMap.OnCompare	682
51.8.18	TFPGMap.OnKeyCompare	683
51.8.19	TFPGMap.OnDataCompare	683
51.9	TFPGMapInterfacedObjectData	683
51.9.1	Description	683
51.9.2	Method overview	684
51.9.3	Property overview	684
51.9.4	TFPGMapInterfacedObjectData.Create	684
51.9.5	TFPGMapInterfacedObjectData.Add	684
51.9.6	TFPGMapInterfacedObjectData.Find	685
51.9.7	TFPGMapInterfacedObjectData.TryGetData	685
51.9.8	TFPGMapInterfacedObjectData.AddOrSetData	685
51.9.9	TFPGMapInterfacedObjectData.IndexOf	685
51.9.10	TFPGMapInterfacedObjectData.IndexOfData	686
51.9.11	TFPGMapInterfacedObjectData.InsertKey	686
51.9.12	TFPGMapInterfacedObjectData.InsertKeyData	686
51.9.13	TFPGMapInterfacedObjectData.Remove	686
51.9.14	TFPGMapInterfacedObjectData.Keys	687
51.9.15	TFPGMapInterfacedObjectData.Data	687
51.9.16	TFPGMapInterfacedObjectData.KeyData	687
51.9.17	TFPGMapInterfacedObjectData.OnCompare	688
51.9.18	TFPGMapInterfacedObjectData.OnKeyCompare	688
51.9.19	TFPGMapInterfacedObjectData.OnDataCompare	688
51.10	TFPGMapObject	689
51.10.1	Description	689

51.10.2	Method overview	689
51.10.3	Property overview	689
51.10.4	TFPGMapObject.Create	689
51.10.5	TFPGMapObject.Add	689
51.10.6	TFPGMapObject.Find	690
51.10.7	TFPGMapObject.TryGetData	690
51.10.8	TFPGMapObject.AddOrSetData	690
51.10.9	TFPGMapObject.IndexOf	691
51.10.10	TFPGMapObject.IndexOfData	691
51.10.11	TFPGMapObject.InsertKey	691
51.10.12	TFPGMapObject.InsertKeyData	691
51.10.13	TFPGMapObject.Remove	692
51.10.14	TFPGMapObject.Keys	692
51.10.15	TFPGMapObject.Data	692
51.10.16	TFPGMapObject.KeyData	692
51.10.17	TFPGMapObject.OnCompare	693
51.10.18	TFPGMapObject.OnKeyCompare	693
51.10.19	TFPGMapObject.OnDataCompare	693
51.11	TFPGObjectList	694
51.11.1	Description	694
51.11.2	Method overview	694
51.11.3	Property overview	694
51.11.4	TFPGObjectList.Create	694
51.11.5	TFPGObjectList.Add	695
51.11.6	TFPGObjectList.Extract	695
51.11.7	TFPGObjectList.GetEnumerator	695
51.11.8	TFPGObjectList.IndexOf	695
51.11.9	TFPGObjectList.Insert	696
51.11.10	TFPGObjectList.Assign	696
51.11.11	TFPGObjectList.Remove	696
51.11.12	TFPGObjectList.Sort	697
51.11.13	TFPGObjectList.First	697
51.11.14	TFPGObjectList.Last	697
51.11.15	TFPGObjectList.Items	697
51.11.16	TFPGObjectList.List	698
51.11.17	TFPGObjectList.FreeObjects	698
51.12	TFPSList	698
51.12.1	Description	698
51.12.2	Method overview	699
51.12.3	Property overview	699

51.12.4	TFPSList.Create	699
51.12.5	TFPSList.Destroy	699
51.12.6	TFPSList.Add	700
51.12.7	TFPSList.Clear	700
51.12.8	TFPSList.Delete	700
51.12.9	TFPSList.Error	700
51.12.10	TFPSList.Exchange	701
51.12.11	TFPSList.Expand	701
51.12.12	TFPSList.Extract	701
51.12.13	TFPSList.IndexOf	701
51.12.14	TFPSList.Insert	702
51.12.15	TFPSList.Move	702
51.12.16	TFPSList.Assign	702
51.12.17	TFPSList.Remove	703
51.12.18	TFPSList.Pack	703
51.12.19	TFPSList.Sort	703
51.12.20	TFPSList.Capacity	704
51.12.21	TFPSList.Count	704
51.12.22	TFPSList.Items	704
51.12.23	TFPSList.ItemSize	705
51.12.24	TFPSList.List	705
51.12.25	TFPSList.First	705
51.12.26	TFPSList.Last	705
51.13	TFPSMap	706
51.13.1	Description	706
51.13.2	Method overview	706
51.13.3	Property overview	706
51.13.4	TFPSMap.Create	706
51.13.5	TFPSMap.Add	707
51.13.6	TFPSMap.Find	707
51.13.7	TFPSMap.IndexOf	707
51.13.8	TFPSMap.IndexOfData	708
51.13.9	TFPSMap.Insert	708
51.13.10	TFPSMap.InsertKey	708
51.13.11	TFPSMap.InsertKeyData	708
51.13.12	TFPSMap.Remove	709
51.13.13	TFPSMap.Sort	709
51.13.14	TFPSMap.Duplicates	709
51.13.15	TFPSMap.KeySize	710
51.13.16	TFPSMap.DataSize	710

51.13.17	TFPSMap.Keys	710
51.13.18	TFPSMap.Data	710
51.13.19	TFPSMap.KeyData	711
51.13.20	TFPSMap.Sorted	711
51.13.21	TFPSMap.OnPtrCompare	711
51.13.22	TFPSMap.OnKeyPtrCompare	711
51.13.23	TFPSMap.OnDataPtrCompare	712
52	Reference for unit 'fpwiderstring'	713
52.1	Used units	713
52.2	Overview	713
52.3	Constants, types and variables	714
52.3.1	Variables	714
52.4	Procedures and functions	714
52.4.1	GetActiveCollation	714
52.4.2	SetActiveCollation	714
53	Reference for unit 'getopts'	715
53.1	Used units	715
53.2	Overview	715
53.3	Constants, types and variables	715
53.3.1	Constants	715
53.3.2	Types	716
53.3.3	Variables	716
53.4	Procedures and functions	717
53.4.1	GetLongOpts	717
53.4.2	GetOpt	717
54	Reference for unit 'go32'	720
54.1	Used units	720
54.2	Overview	720
54.3	Real mode callbacks	720
54.4	Executing software interrupts	721
54.5	Software interrupts	724
54.6	Hardware interrupts	724
54.7	Disabling interrupts	726
54.8	Creating your own interrupt handlers	726
54.9	Protected mode interrupts vs. Real mode interrupts	727
54.10	Handling interrupts with DPMI	727
54.11	Interrupt redirection	727
54.12	Processor access	727

54.13 I/O port access	727
54.14 dos memory access	727
54.15 FPC specialities	728
54.16 Selectors and descriptors	728
54.17 What is DPMI	728
54.18 Constants, types and variables	728
54.18.1 Constants	728
54.18.2 Types	731
54.18.3 Variables	734
54.19 Procedures and functions	735
54.19.1 allocate_ldt_descriptors	735
54.19.2 allocate_memory_block	738
54.19.3 copyfromdos	738
54.19.4 copytodos	739
54.19.5 create_code_segment_alias_descriptor	739
54.19.6 disable	739
54.19.7 dpmi_dosmemfillchar	740
54.19.8 dpmi_dosmemfillword	740
54.19.9 dpmi_dosmemget	740
54.19.10 dpmi_dosmemmove	740
54.19.11 dpmi_dosmemput	741
54.19.12 enable	741
54.19.13 free_ldt_descriptor	741
54.19.14 free_linear_addr_mapping	741
54.19.15 free_memory_block	742
54.19.16 free_rm_callback	742
54.19.17 get_cs	742
54.19.18 get_descriptor_access_right	743
54.19.19 get_dpmi_version	743
54.19.20 get_ds	743
54.19.21 get_exception_handler	743
54.19.22 get_linear_addr	744
54.19.23 get_meminfo	744
54.19.24 get_next_selector_increment_value	745
54.19.25 get_page_attributes	746
54.19.26 get_page_size	746
54.19.27 get_pm_exception_handler	746
54.19.28 get_pm_interrupt	746
54.19.29 get_rm_callback	747
54.19.30 get_rm_interrupt	751

54.19.31	get_run_mode	752
54.19.32	get_segment_base_address	753
54.19.33	get_segment_limit	753
54.19.34	get_ss	753
54.19.35	global_dos_alloc	754
54.19.36	global_dos_free	756
54.19.37	inportb	757
54.19.38	inportl	757
54.19.39	inportw	757
54.19.40	lock_code	758
54.19.41	lock_data	758
54.19.42	lock_linear_region	758
54.19.43	map_device_in_memory_block	759
54.19.44	outportb	759
54.19.45	outportl	760
54.19.46	outportw	760
54.19.47	realintr	760
54.19.48	request_linear_region	761
54.19.49	segment_to_descriptor	762
54.19.50	seg_fillchar	762
54.19.51	seg_fillword	763
54.19.52	seg_move	764
54.19.53	set_descriptor_access_right	764
54.19.54	set_exception_handler	764
54.19.55	set_page_attributes	765
54.19.56	set_pm_exception_handler	765
54.19.57	set_pm_interrupt	765
54.19.58	set_rm_interrupt	767
54.19.59	set_segment_base_address	767
54.19.60	set_segment_limit	767
54.19.61	tb_offset	768
54.19.62	tb_segment	768
54.19.63	tb_size	768
54.19.64	transfer_buffer	769
54.19.65	unlock_code	769
54.19.66	unlock_data	769
54.19.67	unlock_linear_region	770
55	Reference for unit 'gpm'	771
55.1	Used units	771

55.2	Overview	771
55.3	Constants, types and variables	771
55.3.1	Constants	771
55.3.2	Types	773
55.3.3	Variables	775
55.4	Procedures and functions	776
55.4.1	Gpm_AnyDouble	776
55.4.2	Gpm_AnySingle	776
55.4.3	Gpm_AnyTriple	776
55.4.4	gpm_close	777
55.4.5	gpm_fitvalues	777
55.4.6	gpm_fitvaluesM	777
55.4.7	gpm_getevent	777
55.4.8	gpm_getsnapshot	779
55.4.9	gpm_lowerroi	779
55.4.10	gpm_open	779
55.4.11	gpm_poproi	780
55.4.12	gpm_pushroi	780
55.4.13	gpm_raiseroi	780
55.4.14	gpm_repeat	780
55.4.15	Gpm_StrictDouble	781
55.4.16	Gpm_StrictSingle	781
55.4.17	Gpm_StrictTriple	781
56	Reference for unit 'Graph'	782
56.1	Used units	782
56.2	Overview	782
56.3	Categorized functions: Text and font handling	782
56.4	Categorized functions: Filled drawings	783
56.5	Categorized functions: Drawing primitives	783
56.6	Categorized functions: Color management	784
56.7	Categorized functions: Screen management	784
56.8	Categorized functions: Initialization	785
56.9	Target specific issues: Linux	785
56.10	Target specific issues: DOS	786
56.11	A word about mode selection	786
56.12	Requirements	791
56.13	Constants, types and variables	791
56.13.1	Constants	791
56.13.2	Types	808

56.13.3	Variables	814
56.14	Procedures and functions	816
56.14.1	Arc	816
56.14.2	Bar	817
56.14.3	Bar3D	817
56.14.4	ClearDevice	817
56.14.5	Closegraph	817
56.14.6	DetectGraph	818
56.14.7	DrawPoly	818
56.14.8	Ellipse	818
56.14.9	FillEllipse	818
56.14.10	FillPoly	819
56.14.11	FloodFill	819
56.14.12	GetArcCoords	819
56.14.13	GetAspectRatio	820
56.14.14	GetColor	820
56.14.15	GetDefaultPalette	820
56.14.16	GetDirectVideo	820
56.14.17	GetDriverName	821
56.14.18	GetFillPattern	821
56.14.19	GetFillSettings	821
56.14.20	GetGraphMode	821
56.14.21	GetLineSettings	822
56.14.22	GetMaxColor	822
56.14.23	GetMaxMode	822
56.14.24	GetMaxX	822
56.14.25	GetMaxY	823
56.14.26	GetModeName	823
56.14.27	GetModeRange	823
56.14.28	GetPalette	823
56.14.29	GetPaletteSize	824
56.14.30	GetTextSettings	824
56.14.31	GetViewSettings	824
56.14.32	GetX	824
56.14.33	GetY	825
56.14.34	GraphDefaults	825
56.14.35	GraphErrorMsg	825
56.14.36	GraphResult	825
56.14.37	InitGraph	826
56.14.38	InstallUserDriver	826

56.14.39	InstallUserFont	827
56.14.40	LineRel	827
56.14.41	LineTo	827
56.14.42	MoveRel	828
56.14.43	MoveTo	828
56.14.44	OutText	828
56.14.45	PieSlice	828
56.14.46	queryadapterinfo	829
56.14.47	Rectangle	829
56.14.48	RegisterBGIDriver	829
56.14.49	RegisterBGIfont	829
56.14.50	RestoreCrtMode	830
56.14.51	Sector	830
56.14.52	SetAspectRatio	830
56.14.53	SetColor	830
56.14.54	SetDirectVideo	831
56.14.55	SetFillPattern	831
56.14.56	SetFillStyle	831
56.14.57	SetGraphMode	832
56.14.58	SetLineStyle	832
56.14.59	SetPalette	832
56.14.60	SetTextJustify	833
56.14.61	SetTextStyle	833
56.14.62	SetUserCharSize	834
56.14.63	SetViewPort	834
56.14.64	SetWriteMode	834
56.14.65	TextHeight	835
56.14.66	TextWidth	835
57	Reference for unit 'heaptrc'	836
57.1	Used units	836
57.2	Overview	836
57.3	Controlling HeapTrc with environment variables	836
57.4	HeapTrc Usage	837
57.5	Constants, types and variables	838
57.5.1	Constants	838
57.5.2	Types	839
57.6	Procedures and functions	840
57.6.1	CheckPointer	840
57.6.2	DumpHeap	840

57.6.3	SetHeapExtraInfo	840
57.6.4	SetHeapTraceOutput	842
58	Reference for unit 'ipc'	843
58.1	Used units	843
58.2	Overview	843
58.3	Constants, types and variables	843
58.3.1	Constants	843
58.3.2	Types	844
59	Reference for unit 'keyboard'	845
59.1	Used units	845
59.2	Overview	845
59.3	Unix specific notes	845
59.4	Writing a keyboard driver	847
59.5	Keyboard scan codes	850
59.6	Constants, types and variables	852
59.6.1	Constants	852
59.6.2	Types	857
59.7	Procedures and functions	858
59.7.1	DoneKeyboard	858
59.7.2	FunctionKeyName	858
59.7.3	GetKeyboardDriver	859
59.7.4	GetKeyEvent	859
59.7.5	GetKeyEventChar	860
59.7.6	GetKeyEventCode	861
59.7.7	GetKeyEventFlags	861
59.7.8	GetKeyEventShiftState	862
59.7.9	GetKeyEventUniCode	862
59.7.10	InitKeyboard	863
59.7.11	IsFunctionKey	863
59.7.12	KeyEventToString	864
59.7.13	KeyPressed	864
59.7.14	PollKeyEvent	864
59.7.15	PollShiftStateEvent	865
59.7.16	PutKeyEvent	866
59.7.17	SetKeyboardDriver	867
59.7.18	ShiftStateToString	867
59.7.19	TranslateKeyEvent	868
59.7.20	TranslateKeyEventUniCode	868

60	Reference for unit 'lineinfo'	869
60.1	Used units	869
60.2	Overview	869
60.3	Constants, types and variables	869
60.3.1	Types	869
60.3.2	Variables	869
60.4	Procedures and functions	870
60.4.1	CloseStabs	870
60.4.2	GetLineInfo	870
60.4.3	StabBackTraceStr	870
61	Reference for unit 'Linux'	871
61.1	Used units	871
61.2	Overview	871
61.3	Constants, types and variables	871
61.3.1	Constants	871
61.3.2	Types	886
61.4	Procedures and functions	889
61.4.1	capget	889
61.4.2	capset	889
61.4.3	clock_getres	889
61.4.4	clock_gettime	889
61.4.5	clock_settime	890
61.4.6	clone	890
61.4.7	epoll_create	891
61.4.8	epoll_ctl	891
61.4.9	epoll_wait	892
61.4.10	fdatasync	892
61.4.11	futex	892
61.4.12	futex_op	893
61.4.13	inotify_add_watch	893
61.4.14	inotify_init	894
61.4.15	inotify_init1	894
61.4.16	inotify_rm_watch	895
61.4.17	modify_ldt	895
61.4.18	sched_yield	895
61.4.19	setregid	895
61.4.20	setreuid	895
61.4.21	sync_file_range	896
61.4.22	Sysinfo	896

62 Reference for unit 'Infodwrf'	898
62.1 Used units	898
62.2 Overview	898
62.3 Constants, types and variables	898
62.3.1 Types	898
62.3.2 Variables	898
62.4 Procedures and functions	899
62.4.1 CloseDwarf	899
62.4.2 DwarfBackTraceStr	899
62.4.3 GetLineInfo	899
63 Reference for unit 'math'	900
63.1 Used units	900
63.2 Overview	900
63.3 Cash flow functions	900
63.4 Geometrical functions	901
63.5 Statistical functions	901
63.6 Number converting	902
63.7 Exponential and logarithmic functions	902
63.8 Hyperbolic functions	902
63.9 Trigonometric functions	903
63.10 Angle unit conversion	903
63.11 Min/max determination	903
63.12 Constants, types and variables	904
63.12.1 Types	904
64 Reference for unit 'matrix'	905
64.1 Used units	905
64.2 Overview	905
64.3 Constants, types and variables	906
64.3.1 Types	906
64.4 Procedures and functions	908
64.4.1 add(Tmatrix2_double,Double):Tmatrix2_double	908
64.4.2 add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	908
64.4.3 add(Tmatrix2_extended,extended):Tmatrix2_extended	909
64.4.4 add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	909
64.4.5 add(Tmatrix2_single,single):Tmatrix2_single	909
64.4.6 add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	909
64.4.7 add(Tmatrix3_double,Double):Tmatrix3_double	909
64.4.8 add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	910
64.4.9 add(Tmatrix3_extended,extended):Tmatrix3_extended	910

64.4.10	add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	910
64.4.11	add(Tmatrix3_single,single):Tmatrix3_single	910
64.4.12	add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	910
64.4.13	add(Tmatrix4_double,Double):Tmatrix4_double	911
64.4.14	add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	911
64.4.15	add(Tmatrix4_extended,extended):Tmatrix4_extended	911
64.4.16	add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	911
64.4.17	add(Tmatrix4_single,single):Tmatrix4_single	911
64.4.18	add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	912
64.4.19	add(Tvector2_double,Double):Tvector2_double	912
64.4.20	add(Tvector2_double,Tvector2_double):Tvector2_double	912
64.4.21	add(Tvector2_extended,extended):Tvector2_extended	912
64.4.22	add(Tvector2_extended,Tvector2_extended):Tvector2_extended	912
64.4.23	add(Tvector2_single,single):Tvector2_single	913
64.4.24	add(Tvector2_single,Tvector2_single):Tvector2_single	913
64.4.25	add(Tvector3_double,Double):Tvector3_double	913
64.4.26	add(Tvector3_double,Tvector3_double):Tvector3_double	913
64.4.27	add(Tvector3_extended,extended):Tvector3_extended	913
64.4.28	add(Tvector3_extended,Tvector3_extended):Tvector3_extended	914
64.4.29	add(Tvector3_single,single):Tvector3_single	914
64.4.30	add(Tvector3_single,Tvector3_single):Tvector3_single	914
64.4.31	add(Tvector4_double,Double):Tvector4_double	914
64.4.32	add(Tvector4_double,Tvector4_double):Tvector4_double	914
64.4.33	add(Tvector4_extended,extended):Tvector4_extended	915
64.4.34	add(Tvector4_extended,Tvector4_extended):Tvector4_extended	915
64.4.35	add(Tvector4_single,single):Tvector4_single	915
64.4.36	add(Tvector4_single,Tvector4_single):Tvector4_single	915
64.4.37	assign(Tmatrix2_double):Tmatrix2_extended	915
64.4.38	assign(Tmatrix2_double):Tmatrix2_single	916
64.4.39	assign(Tmatrix2_double):Tmatrix3_double	916
64.4.40	assign(Tmatrix2_double):Tmatrix3_extended	916
64.4.41	assign(Tmatrix2_double):Tmatrix3_single	916
64.4.42	assign(Tmatrix2_double):Tmatrix4_double	916
64.4.43	assign(Tmatrix2_double):Tmatrix4_extended	917
64.4.44	assign(Tmatrix2_double):Tmatrix4_single	917
64.4.45	assign(Tmatrix2_extended):Tmatrix2_double	917
64.4.46	assign(Tmatrix2_extended):Tmatrix2_single	917
64.4.47	assign(Tmatrix2_extended):Tmatrix3_double	918
64.4.48	assign(Tmatrix2_extended):Tmatrix3_extended	918
64.4.49	assign(Tmatrix2_extended):Tmatrix3_single	918

64.4.50	assign(Tmatrix2_extended):Tmatrix4_double	918
64.4.51	assign(Tmatrix2_extended):Tmatrix4_extended	919
64.4.52	assign(Tmatrix2_extended):Tmatrix4_single	919
64.4.53	assign(Tmatrix2_single):Tmatrix2_double	919
64.4.54	assign(Tmatrix2_single):Tmatrix2_extended	919
64.4.55	assign(Tmatrix2_single):Tmatrix3_double	919
64.4.56	assign(Tmatrix2_single):Tmatrix3_extended	920
64.4.57	assign(Tmatrix2_single):Tmatrix3_single	920
64.4.58	assign(Tmatrix2_single):Tmatrix4_double	920
64.4.59	assign(Tmatrix2_single):Tmatrix4_extended	920
64.4.60	assign(Tmatrix2_single):Tmatrix4_single	920
64.4.61	assign(Tmatrix3_double):Tmatrix2_double	921
64.4.62	assign(Tmatrix3_double):Tmatrix2_extended	921
64.4.63	assign(Tmatrix3_double):Tmatrix2_single	921
64.4.64	assign(Tmatrix3_double):Tmatrix3_extended	921
64.4.65	assign(Tmatrix3_double):Tmatrix3_single	921
64.4.66	assign(Tmatrix3_double):Tmatrix4_double	922
64.4.67	assign(Tmatrix3_double):Tmatrix4_extended	922
64.4.68	assign(Tmatrix3_double):Tmatrix4_single	922
64.4.69	assign(Tmatrix3_extended):Tmatrix2_double	922
64.4.70	assign(Tmatrix3_extended):Tmatrix2_extended	923
64.4.71	assign(Tmatrix3_extended):Tmatrix2_single	923
64.4.72	assign(Tmatrix3_extended):Tmatrix3_double	923
64.4.73	assign(Tmatrix3_extended):Tmatrix3_single	923
64.4.74	assign(Tmatrix3_extended):Tmatrix4_double	924
64.4.75	assign(Tmatrix3_extended):Tmatrix4_extended	924
64.4.76	assign(Tmatrix3_extended):Tmatrix4_single	924
64.4.77	assign(Tmatrix3_single):Tmatrix2_double	924
64.4.78	assign(Tmatrix3_single):Tmatrix2_extended	924
64.4.79	assign(Tmatrix3_single):Tmatrix2_single	925
64.4.80	assign(Tmatrix3_single):Tmatrix3_double	925
64.4.81	assign(Tmatrix3_single):Tmatrix3_extended	925
64.4.82	assign(Tmatrix3_single):Tmatrix4_double	925
64.4.83	assign(Tmatrix3_single):Tmatrix4_extended	926
64.4.84	assign(Tmatrix3_single):Tmatrix4_single	926
64.4.85	assign(Tmatrix4_double):Tmatrix2_double	926
64.4.86	assign(Tmatrix4_double):Tmatrix2_extended	926
64.4.87	assign(Tmatrix4_double):Tmatrix2_single	926
64.4.88	assign(Tmatrix4_double):Tmatrix3_double	927
64.4.89	assign(Tmatrix4_double):Tmatrix3_extended	927

64.4.90	assign(Tmatrix4_double):Tmatrix3_single	927
64.4.91	assign(Tmatrix4_double):Tmatrix4_extended	927
64.4.92	assign(Tmatrix4_double):Tmatrix4_single	927
64.4.93	assign(Tmatrix4_extended):Tmatrix2_double	928
64.4.94	assign(Tmatrix4_extended):Tmatrix2_extended	928
64.4.95	assign(Tmatrix4_extended):Tmatrix2_single	928
64.4.96	assign(Tmatrix4_extended):Tmatrix3_double	928
64.4.97	assign(Tmatrix4_extended):Tmatrix3_extended	929
64.4.98	assign(Tmatrix4_extended):Tmatrix3_single	929
64.4.99	assign(Tmatrix4_extended):Tmatrix4_double	929
64.4.100	assign(Tmatrix4_extended):Tmatrix4_single	929
64.4.101	assign(Tmatrix4_single):Tmatrix2_double	929
64.4.102	assign(Tmatrix4_single):Tmatrix2_extended	930
64.4.103	assign(Tmatrix4_single):Tmatrix2_single	930
64.4.104	assign(Tmatrix4_single):Tmatrix3_double	930
64.4.105	assign(Tmatrix4_single):Tmatrix3_extended	930
64.4.106	assign(Tmatrix4_single):Tmatrix3_single	931
64.4.107	assign(Tmatrix4_single):Tmatrix4_double	931
64.4.108	assign(Tmatrix4_single):Tmatrix4_extended	931
64.4.109	assign(Tvector2_double):Tvector2_extended	931
64.4.110	assign(Tvector2_double):Tvector2_single	931
64.4.111	assign(Tvector2_double):Tvector3_double	932
64.4.112	assign(Tvector2_double):Tvector3_extended	932
64.4.113	assign(Tvector2_double):Tvector3_single	932
64.4.114	assign(Tvector2_double):Tvector4_double	932
64.4.115	assign(Tvector2_double):Tvector4_extended	932
64.4.116	assign(Tvector2_double):Tvector4_single	933
64.4.117	assign(Tvector2_extended):Tvector2_double	933
64.4.118	assign(Tvector2_extended):Tvector2_single	933
64.4.119	assign(Tvector2_extended):Tvector3_double	933
64.4.120	assign(Tvector2_extended):Tvector3_extended	934
64.4.121	assign(Tvector2_extended):Tvector3_single	934
64.4.122	assign(Tvector2_extended):Tvector4_double	934
64.4.123	assign(Tvector2_extended):Tvector4_extended	934
64.4.124	assign(Tvector2_extended):Tvector4_single	935
64.4.125	assign(Tvector2_single):Tvector2_double	935
64.4.126	assign(Tvector2_single):Tvector2_extended	935
64.4.127	assign(Tvector2_single):Tvector3_double	935
64.4.128	assign(Tvector2_single):Tvector3_extended	935
64.4.129	assign(Tvector2_single):Tvector3_single	936

64.4.130	assign(Tvector2_single):Tvector4_double	936
64.4.131	assign(Tvector2_single):Tvector4_extended	936
64.4.132	assign(Tvector2_single):Tvector4_single	936
64.4.133	assign(Tvector3_double):Tvector2_double	937
64.4.134	assign(Tvector3_double):Tvector2_extended	937
64.4.135	assign(Tvector3_double):Tvector2_single	937
64.4.136	assign(Tvector3_double):Tvector3_extended	937
64.4.137	assign(Tvector3_double):Tvector3_single	937
64.4.138	assign(Tvector3_double):Tvector4_double	938
64.4.139	assign(Tvector3_double):Tvector4_extended	938
64.4.140	assign(Tvector3_double):Tvector4_single	938
64.4.141	assign(Tvector3_extended):Tvector2_double	938
64.4.142	assign(Tvector3_extended):Tvector2_extended	939
64.4.143	assign(Tvector3_extended):Tvector2_single	939
64.4.144	assign(Tvector3_extended):Tvector3_double	939
64.4.145	assign(Tvector3_extended):Tvector3_single	939
64.4.146	assign(Tvector3_extended):Tvector4_double	940
64.4.147	assign(Tvector3_extended):Tvector4_extended	940
64.4.148	assign(Tvector3_extended):Tvector4_single	940
64.4.149	assign(Tvector3_single):Tvector2_double	940
64.4.150	assign(Tvector3_single):Tvector2_extended	940
64.4.151	assign(Tvector3_single):Tvector2_single	941
64.4.152	assign(Tvector3_single):Tvector3_double	941
64.4.153	assign(Tvector3_single):Tvector3_extended	941
64.4.154	assign(Tvector3_single):Tvector4_double	941
64.4.155	assign(Tvector3_single):Tvector4_extended	942
64.4.156	assign(Tvector3_single):Tvector4_single	942
64.4.157	assign(Tvector4_double):Tvector2_double	942
64.4.158	assign(Tvector4_double):Tvector2_extended	942
64.4.159	assign(Tvector4_double):Tvector2_single	942
64.4.160	assign(Tvector4_double):Tvector3_double	943
64.4.161	assign(Tvector4_double):Tvector3_extended	943
64.4.162	assign(Tvector4_double):Tvector3_single	943
64.4.163	assign(Tvector4_double):Tvector4_extended	943
64.4.164	assign(Tvector4_double):Tvector4_single	944
64.4.165	assign(Tvector4_extended):Tvector2_double	944
64.4.166	assign(Tvector4_extended):Tvector2_extended	944
64.4.167	assign(Tvector4_extended):Tvector2_single	944
64.4.168	assign(Tvector4_extended):Tvector3_double	945
64.4.169	assign(Tvector4_extended):Tvector3_extended	945

64.4.170	assign(Tvector4_extended):Tvector3_single	945
64.4.171	assign(Tvector4_extended):Tvector4_double	945
64.4.172	assign(Tvector4_extended):Tvector4_single	946
64.4.173	assign(Tvector4_single):Tvector2_double	946
64.4.174	assign(Tvector4_single):Tvector2_extended	946
64.4.175	assign(Tvector4_single):Tvector2_single	946
64.4.176	assign(Tvector4_single):Tvector3_double	947
64.4.177	assign(Tvector4_single):Tvector3_extended	947
64.4.178	assign(Tvector4_single):Tvector3_single	947
64.4.179	assign(Tvector4_single):Tvector4_double	947
64.4.180	assign(Tvector4_single):Tvector4_extended	947
64.4.181	divide(Tmatrix2_double,Double):Tmatrix2_double	948
64.4.182	divide(Tmatrix2_extended,extended):Tmatrix2_extended	948
64.4.183	divide(Tmatrix2_single,single):Tmatrix2_single	948
64.4.184	divide(Tmatrix3_double,Double):Tmatrix3_double	948
64.4.185	divide(Tmatrix3_extended,extended):Tmatrix3_extended	948
64.4.186	divide(Tmatrix3_single,single):Tmatrix3_single	949
64.4.187	divide(Tmatrix4_double,Double):Tmatrix4_double	949
64.4.188	divide(Tmatrix4_extended,extended):Tmatrix4_extended	949
64.4.189	divide(Tmatrix4_single,single):Tmatrix4_single	949
64.4.190	divide(Tvector2_double,Double):Tvector2_double	949
64.4.191	divide(Tvector2_extended,extended):Tvector2_extended	950
64.4.192	divide(Tvector2_single,single):Tvector2_single	950
64.4.193	divide(Tvector3_double,Double):Tvector3_double	950
64.4.194	divide(Tvector3_extended,extended):Tvector3_extended	950
64.4.195	divide(Tvector3_single,single):Tvector3_single	950
64.4.196	divide(Tvector4_double,Double):Tvector4_double	951
64.4.197	divide(Tvector4_extended,extended):Tvector4_extended	951
64.4.198	divide(Tvector4_single,single):Tvector4_single	951
64.4.199	multiply(Tmatrix2_double,Double):Tmatrix2_double	951
64.4.200	multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	951
64.4.201	multiply(Tmatrix2_double,Tvector2_double):Tvector2_double	952
64.4.202	multiply(Tmatrix2_extended,extended):Tmatrix2_extended	952
64.4.203	multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	952
64.4.204	multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended	952
64.4.205	multiply(Tmatrix2_single,single):Tmatrix2_single	953
64.4.206	multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	953
64.4.207	multiply(Tmatrix2_single,Tvector2_single):Tvector2_single	953
64.4.208	multiply(Tmatrix3_double,Double):Tmatrix3_double	953
64.4.209	multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	953

64.4.210	multiply(Tmatrix3_double,Tvector3_double):Tvector3_double	954
64.4.211	multiply(Tmatrix3_extended,extended):Tmatrix3_extended	954
64.4.212	multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended . . .	954
64.4.213	multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended . . .	954
64.4.214	multiply(Tmatrix3_single,single):Tmatrix3_single	955
64.4.215	multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	955
64.4.216	multiply(Tmatrix3_single,Tvector3_single):Tvector3_single	955
64.4.217	multiply(Tmatrix4_double,Double):Tmatrix4_double	955
64.4.218	multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	955
64.4.219	multiply(Tmatrix4_double,Tvector4_double):Tvector4_double	956
64.4.220	multiply(Tmatrix4_extended,extended):Tmatrix4_extended	956
64.4.221	multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended . . .	956
64.4.222	multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended . . .	956
64.4.223	multiply(Tmatrix4_single,single):Tmatrix4_single	957
64.4.224	multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	957
64.4.225	multiply(Tmatrix4_single,Tvector4_single):Tvector4_single	957
64.4.226	multiply(Tvector2_double,Double):Tvector2_double	957
64.4.227	multiply(Tvector2_double,Tvector2_double):Tvector2_double	957
64.4.228	multiply(Tvector2_extended,extended):Tvector2_extended	958
64.4.229	multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended . . .	958
64.4.230	multiply(Tvector2_single,single):Tvector2_single	958
64.4.231	multiply(Tvector2_single,Tvector2_single):Tvector2_single	958
64.4.232	multiply(Tvector3_double,Double):Tvector3_double	958
64.4.233	multiply(Tvector3_double,Tvector3_double):Tvector3_double	959
64.4.234	multiply(Tvector3_extended,extended):Tvector3_extended	959
64.4.235	multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended . . .	959
64.4.236	multiply(Tvector3_single,single):Tvector3_single	959
64.4.237	multiply(Tvector3_single,Tvector3_single):Tvector3_single	959
64.4.238	multiply(Tvector4_double,Double):Tvector4_double	960
64.4.239	multiply(Tvector4_double,Tvector4_double):Tvector4_double	960
64.4.240	multiply(Tvector4_extended,extended):Tvector4_extended	960
64.4.241	multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended . . .	960
64.4.242	multiply(Tvector4_single,single):Tvector4_single	960
64.4.243	multiply(Tvector4_single,Tvector4_single):Tvector4_single	961
64.4.244	negative(Tmatrix2_double):Tmatrix2_double	961
64.4.245	negative(Tmatrix2_extended):Tmatrix2_extended	961
64.4.246	negative(Tmatrix2_single):Tmatrix2_single	961
64.4.247	negative(Tmatrix3_double):Tmatrix3_double	961
64.4.248	negative(Tmatrix3_extended):Tmatrix3_extended	961
64.4.249	negative(Tmatrix3_single):Tmatrix3_single	962

64.4.250	negative(Tmatrix4_double):Tmatrix4_double	962
64.4.251	negative(Tmatrix4_extended):Tmatrix4_extended	962
64.4.252	negative(Tmatrix4_single):Tmatrix4_single	962
64.4.253	negative(Tvector2_double):Tvector2_double	962
64.4.254	negative(Tvector2_extended):Tvector2_extended	962
64.4.255	negative(Tvector2_single):Tvector2_single	963
64.4.256	negative(Tvector3_double):Tvector3_double	963
64.4.257	negative(Tvector3_extended):Tvector3_extended	963
64.4.258	negative(Tvector3_single):Tvector3_single	963
64.4.259	negative(Tvector4_double):Tvector4_double	963
64.4.260	negative(Tvector4_extended):Tvector4_extended	964
64.4.261	negative(Tvector4_single):Tvector4_single	964
64.4.262	power(Tvector2_double,Tvector2_double):Double	964
64.4.263	power(Tvector2_extended,Tvector2_extended):extended	964
64.4.264	power(Tvector2_single,Tvector2_single):single	964
64.4.265	power(Tvector3_double,Tvector3_double):Double	965
64.4.266	power(Tvector3_extended,Tvector3_extended):extended	965
64.4.267	power(Tvector3_single,Tvector3_single):single	965
64.4.268	power(Tvector4_double,Tvector4_double):Double	965
64.4.269	power(Tvector4_extended,Tvector4_extended):extended	965
64.4.270	power(Tvector4_single,Tvector4_single):single	966
64.4.271	subtract(Tmatrix2_double,Double):Tmatrix2_double	966
64.4.272	subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double	966
64.4.273	subtract(Tmatrix2_extended,extended):Tmatrix2_extended	966
64.4.274	subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended	966
64.4.275	subtract(Tmatrix2_single,single):Tmatrix2_single	967
64.4.276	subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single	967
64.4.277	subtract(Tmatrix3_double,Double):Tmatrix3_double	967
64.4.278	subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double	967
64.4.279	subtract(Tmatrix3_extended,extended):Tmatrix3_extended	967
64.4.280	subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended	968
64.4.281	subtract(Tmatrix3_single,single):Tmatrix3_single	968
64.4.282	subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single	968
64.4.283	subtract(Tmatrix4_double,Double):Tmatrix4_double	968
64.4.284	subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double	968
64.4.285	subtract(Tmatrix4_extended,extended):Tmatrix4_extended	969
64.4.286	subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended	969
64.4.287	subtract(Tmatrix4_single,single):Tmatrix4_single	969
64.4.288	subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single	969
64.4.289	subtract(Tvector2_double,Double):Tvector2_double	969

64.4.290	<code>subtract(Tvector2_double,Tvector2_double):Tvector2_double</code>	970
64.4.291	<code>subtract(Tvector2_extended,extended):Tvector2_extended</code>	970
64.4.292	<code>subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended</code>	970
64.4.293	<code>subtract(Tvector2_single,single):Tvector2_single</code>	970
64.4.294	<code>subtract(Tvector2_single,Tvector2_single):Tvector2_single</code>	970
64.4.295	<code>subtract(Tvector3_double,Double):Tvector3_double</code>	971
64.4.296	<code>subtract(Tvector3_double,Tvector3_double):Tvector3_double</code>	971
64.4.297	<code>subtract(Tvector3_extended,extended):Tvector3_extended</code>	971
64.4.298	<code>subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended</code>	971
64.4.299	<code>subtract(Tvector3_single,single):Tvector3_single</code>	971
64.4.300	<code>subtract(Tvector3_single,Tvector3_single):Tvector3_single</code>	972
64.4.301	<code>subtract(Tvector4_double,Double):Tvector4_double</code>	972
64.4.302	<code>subtract(Tvector4_double,Tvector4_double):Tvector4_double</code>	972
64.4.303	<code>subtract(Tvector4_extended,extended):Tvector4_extended</code>	972
64.4.304	<code>subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended</code>	972
64.4.305	<code>subtract(Tvector4_single,single):Tvector4_single</code>	973
64.4.306	<code>subtract(Tvector4_single,Tvector4_single):Tvector4_single</code>	973
64.4.307	<code>symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double</code>	973
64.4.308	<code>symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended</code>	973
64.4.309	<code>symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single</code>	974
64.5	<code>Tmatrix2_double</code>	974
64.5.1	Description	974
64.5.2	Method overview	974
64.5.3	<code>Tmatrix2_double.init_zero</code>	974
64.5.4	<code>Tmatrix2_double.init_identity</code>	974
64.5.5	<code>Tmatrix2_double.init</code>	975
64.5.6	<code>Tmatrix2_double.get_column</code>	975
64.5.7	<code>Tmatrix2_double.get_row</code>	975
64.5.8	<code>Tmatrix2_double.set_column</code>	975
64.5.9	<code>Tmatrix2_double.set_row</code>	975
64.5.10	<code>Tmatrix2_double.determinant</code>	975
64.5.11	<code>Tmatrix2_double.inverse</code>	976
64.5.12	<code>Tmatrix2_double.transpose</code>	976
64.6	<code>Tmatrix2_extended</code>	976
64.6.1	Description	976
64.6.2	Method overview	976
64.6.3	<code>Tmatrix2_extended.init_zero</code>	976
64.6.4	<code>Tmatrix2_extended.init_identity</code>	977
64.6.5	<code>Tmatrix2_extended.init</code>	977
64.6.6	<code>Tmatrix2_extended.get_column</code>	977

64.6.7	Tmatrix2_extended.get_row	977
64.6.8	Tmatrix2_extended.set_column	977
64.6.9	Tmatrix2_extended.set_row	977
64.6.10	Tmatrix2_extended.determinant	978
64.6.11	Tmatrix2_extended.inverse	978
64.6.12	Tmatrix2_extended.transpose	978
64.7	Tmatrix2_single	978
64.7.1	Description	978
64.7.2	Method overview	978
64.7.3	Tmatrix2_single.init_zero	979
64.7.4	Tmatrix2_single.init_identity	979
64.7.5	Tmatrix2_single.init	979
64.7.6	Tmatrix2_single.get_column	979
64.7.7	Tmatrix2_single.get_row	979
64.7.8	Tmatrix2_single.set_column	979
64.7.9	Tmatrix2_single.set_row	980
64.7.10	Tmatrix2_single.determinant	980
64.7.11	Tmatrix2_single.inverse	980
64.7.12	Tmatrix2_single.transpose	980
64.8	Tmatrix3_double	980
64.8.1	Description	980
64.8.2	Method overview	981
64.8.3	Tmatrix3_double.init_zero	981
64.8.4	Tmatrix3_double.init_identity	981
64.8.5	Tmatrix3_double.init	981
64.8.6	Tmatrix3_double.get_column	981
64.8.7	Tmatrix3_double.get_row	982
64.8.8	Tmatrix3_double.set_column	982
64.8.9	Tmatrix3_double.set_row	982
64.8.10	Tmatrix3_double.determinant	982
64.8.11	Tmatrix3_double.inverse	982
64.8.12	Tmatrix3_double.transpose	982
64.9	Tmatrix3_extended	983
64.9.1	Description	983
64.9.2	Method overview	983
64.9.3	Tmatrix3_extended.init_zero	983
64.9.4	Tmatrix3_extended.init_identity	983
64.9.5	Tmatrix3_extended.init	983
64.9.6	Tmatrix3_extended.get_column	984
64.9.7	Tmatrix3_extended.get_row	984

64.9.8	Tmatrix3_extended.set_column	984
64.9.9	Tmatrix3_extended.set_row	984
64.9.10	Tmatrix3_extended.determinant	984
64.9.11	Tmatrix3_extended.inverse	984
64.9.12	Tmatrix3_extended.transpose	985
64.10	Tmatrix3_single	985
64.10.1	Description	985
64.10.2	Method overview	985
64.10.3	Tmatrix3_single.init_zero	985
64.10.4	Tmatrix3_single.init_identity	985
64.10.5	Tmatrix3_single.init	986
64.10.6	Tmatrix3_single.get_column	986
64.10.7	Tmatrix3_single.get_row	986
64.10.8	Tmatrix3_single.set_column	986
64.10.9	Tmatrix3_single.set_row	986
64.10.10	Tmatrix3_single.determinant	987
64.10.11	Tmatrix3_single.inverse	987
64.10.12	Tmatrix3_single.transpose	987
64.11	Tmatrix4_double	987
64.11.1	Description	987
64.11.2	Method overview	987
64.11.3	Tmatrix4_double.init_zero	988
64.11.4	Tmatrix4_double.init_identity	988
64.11.5	Tmatrix4_double.init	988
64.11.6	Tmatrix4_double.get_column	988
64.11.7	Tmatrix4_double.get_row	988
64.11.8	Tmatrix4_double.set_column	989
64.11.9	Tmatrix4_double.set_row	989
64.11.10	Tmatrix4_double.determinant	989
64.11.11	Tmatrix4_double.inverse	989
64.11.12	Tmatrix4_double.transpose	989
64.12	Tmatrix4_extended	990
64.12.1	Description	990
64.12.2	Method overview	990
64.12.3	Tmatrix4_extended.init_zero	990
64.12.4	Tmatrix4_extended.init_identity	990
64.12.5	Tmatrix4_extended.init	990
64.12.6	Tmatrix4_extended.get_column	991
64.12.7	Tmatrix4_extended.get_row	991
64.12.8	Tmatrix4_extended.set_column	991

64.12.9	Tmatrix4_extended.set_row	991
64.12.10	Tmatrix4_extended.determinant	991
64.12.11	Tmatrix4_extended.inverse	992
64.12.12	Tmatrix4_extended.transpose	992
64.13	Tmatrix4_single	992
64.13.1	Description	992
64.13.2	Method overview	992
64.13.3	Tmatrix4_single.init_zero	992
64.13.4	Tmatrix4_single.init_identity	993
64.13.5	Tmatrix4_single.init	993
64.13.6	Tmatrix4_single.get_column	993
64.13.7	Tmatrix4_single.get_row	993
64.13.8	Tmatrix4_single.set_column	993
64.13.9	Tmatrix4_single.set_row	994
64.13.10	Tmatrix4_single.determinant	994
64.13.11	Tmatrix4_single.inverse	994
64.13.12	Tmatrix4_single.transpose	994
64.14	Tvector2_double	994
64.14.1	Description	994
64.14.2	Method overview	995
64.14.3	Tvector2_double.init_zero	995
64.14.4	Tvector2_double.init_one	995
64.14.5	Tvector2_double.init	995
64.14.6	Tvector2_double.length	995
64.14.7	Tvector2_double.squared_length	995
64.15	Tvector2_extended	996
64.15.1	Description	996
64.15.2	Method overview	996
64.15.3	Tvector2_extended.init_zero	996
64.15.4	Tvector2_extended.init_one	996
64.15.5	Tvector2_extended.init	996
64.15.6	Tvector2_extended.length	996
64.15.7	Tvector2_extended.squared_length	997
64.16	Tvector2_single	997
64.16.1	Description	997
64.16.2	Method overview	997
64.16.3	Tvector2_single.init_zero	997
64.16.4	Tvector2_single.init_one	997
64.16.5	Tvector2_single.init	997
64.16.6	Tvector2_single.length	998

64.16.7	Tvector2_single.squared_length	998
64.17	Tvector3_double	998
64.17.1	Description	998
64.17.2	Method overview	998
64.17.3	Tvector3_double.init_zero	998
64.17.4	Tvector3_double.init_one	998
64.17.5	Tvector3_double.init	999
64.17.6	Tvector3_double.length	999
64.17.7	Tvector3_double.squared_length	999
64.18	Tvector3_extended	999
64.18.1	Description	999
64.18.2	Method overview	999
64.18.3	Tvector3_extended.init_zero	999
64.18.4	Tvector3_extended.init_one	1000
64.18.5	Tvector3_extended.init	1000
64.18.6	Tvector3_extended.length	1000
64.18.7	Tvector3_extended.squared_length	1000
64.19	Tvector3_single	1000
64.19.1	Description	1000
64.19.2	Method overview	1000
64.19.3	Tvector3_single.init_zero	1001
64.19.4	Tvector3_single.init_one	1001
64.19.5	Tvector3_single.init	1001
64.19.6	Tvector3_single.length	1001
64.19.7	Tvector3_single.squared_length	1001
64.20	Tvector4_double	1001
64.20.1	Description	1001
64.20.2	Method overview	1002
64.20.3	Tvector4_double.init_zero	1002
64.20.4	Tvector4_double.init_one	1002
64.20.5	Tvector4_double.init	1002
64.20.6	Tvector4_double.length	1002
64.20.7	Tvector4_double.squared_length	1002
64.21	Tvector4_extended	1003
64.21.1	Description	1003
64.21.2	Method overview	1003
64.21.3	Tvector4_extended.init_zero	1003
64.21.4	Tvector4_extended.init_one	1003
64.21.5	Tvector4_extended.init	1003
64.21.6	Tvector4_extended.length	1003

64.21.7	Tvector4_extended.squared_length	1004
64.22	Tvector4_single	1004
64.22.1	Description	1004
64.22.2	Method overview	1004
64.22.3	Tvector4_single.init_zero	1004
64.22.4	Tvector4_single.init_one	1004
64.22.5	Tvector4_single.init	1004
64.22.6	Tvector4_single.length	1005
64.22.7	Tvector4_single.squared_length	1005
65	Reference for unit 'mmx'	1006
65.1	Used units	1006
65.2	Overview	1006
65.3	Constants, types and variables	1006
65.3.1	Constants	1006
65.3.2	Types	1007
65.4	Procedures and functions	1008
65.4.1	emms	1008
65.4.2	femms	1009
66	Reference for unit 'Mouse'	1010
66.1	Used units	1010
66.2	Overview	1010
66.3	Writing a custom mouse driver	1010
66.4	Constants, types and variables	1012
66.4.1	Constants	1012
66.4.2	Types	1014
66.4.3	Variables	1014
66.5	Procedures and functions	1015
66.5.1	DetectMouse	1015
66.5.2	DoneMouse	1015
66.5.3	GetMouseButtons	1016
66.5.4	GetMouseDriver	1016
66.5.5	GetMouseEvent	1017
66.5.6	GetMouseX	1017
66.5.7	GetMouseY	1018
66.5.8	HideMouse	1018
66.5.9	InitMouse	1019
66.5.10	PollMouseEvent	1019
66.5.11	PutMouseEvent	1020
66.5.12	SetMouseDriver	1020

66.5.13	SetMouseXY	1020
66.5.14	ShowMouse	1021
67	Reference for unit 'Objects'	1022
67.1	Used units	1022
67.2	Overview	1022
67.3	Constants, types and variables	1022
67.3.1	Constants	1022
67.3.2	Types	1025
67.3.3	Variables	1028
67.4	Procedures and functions	1028
67.4.1	Abstract	1028
67.4.2	CallPointerConstructor	1029
67.4.3	CallPointerLocal	1029
67.4.4	CallPointerMethod	1029
67.4.5	CallPointerMethodLocal	1030
67.4.6	CallVoidConstructor	1030
67.4.7	CallVoidLocal	1030
67.4.8	CallVoidMethod	1031
67.4.9	CallVoidMethodLocal	1031
67.4.10	DisposeStr	1031
67.4.11	LongDiv	1031
67.4.12	LongMul	1032
67.4.13	NewStr	1032
67.4.14	RegisterObjects	1032
67.4.15	RegisterType	1033
67.4.16	SetStr	1034
67.5	TBufStream	1035
67.5.1	Description	1035
67.5.2	Method overview	1035
67.5.3	TBufStream.Init	1035
67.5.4	TBufStream.Done	1036
67.5.5	TBufStream.Close	1036
67.5.6	TBufStream.Flush	1036
67.5.7	TBufStream.Truncate	1037
67.5.8	TBufStream.Seek	1037
67.5.9	TBufStream.Open	1038
67.5.10	TBufStream.Read	1038
67.5.11	TBufStream.Write	1038
67.6	TCollection	1039

67.6.1	Description	1039
67.6.2	Method overview	1039
67.6.3	TCollection.Init	1039
67.6.4	TCollection.Load	1040
67.6.5	TCollection.Done	1041
67.6.6	TCollection.At	1041
67.6.7	TCollection.IndexOf	1042
67.6.8	TCollection.GetItem	1042
67.6.9	TCollection.LastThat	1043
67.6.10	TCollection.FirstThat	1044
67.6.11	TCollection.Pack	1044
67.6.12	TCollection.FreeAll	1045
67.6.13	TCollection.DeleteAll	1046
67.6.14	TCollection.Free	1047
67.6.15	TCollection.Insert	1048
67.6.16	TCollection.Delete	1048
67.6.17	TCollection.AtFree	1049
67.6.18	TCollection.FreeItem	1049
67.6.19	TCollection.AtDelete	1050
67.6.20	TCollection.ForEach	1050
67.6.21	TCollection.SetLimit	1051
67.6.22	TCollection.Error	1051
67.6.23	TCollection.AtPut	1052
67.6.24	TCollection.AtInsert	1052
67.6.25	TCollection.Store	1053
67.6.26	TCollection.PutItem	1053
67.7	TDosStream	1053
67.7.1	Description	1053
67.7.2	Method overview	1054
67.7.3	TDosStream.Init	1054
67.7.4	TDosStream.Done	1054
67.7.5	TDosStream.Close	1055
67.7.6	TDosStream.Truncate	1055
67.7.7	TDosStream.Seek	1056
67.7.8	TDosStream.Open	1057
67.7.9	TDosStream.Read	1057
67.7.10	TDosStream.Write	1058
67.8	TMemoryStream	1058
67.8.1	Description	1058
67.8.2	Method overview	1058

67.8.3	TMemoryStream.Init	1058
67.8.4	TMemoryStream.Done	1059
67.8.5	TMemoryStream.Truncate	1059
67.8.6	TMemoryStream.Read	1060
67.8.7	TMemoryStream.Write	1060
67.9	TObject	1060
67.9.1	Description	1060
67.9.2	Method overview	1060
67.9.3	TObject.Init	1060
67.9.4	TObject.Free	1061
67.9.5	TObject.Is_Object	1061
67.9.6	TObject.Done	1062
67.10	TPoint	1062
67.10.1	Description	1062
67.11	TRect	1062
67.11.1	Description	1062
67.11.2	Method overview	1062
67.11.3	TRect.Empty	1063
67.11.4	TRect.Equals	1064
67.11.5	TRect.Contains	1064
67.11.6	TRect.Copy	1064
67.11.7	TRect.Union	1065
67.11.8	TRect.Intersect	1065
67.11.9	TRect.Move	1066
67.11.10	TRect.Grow	1067
67.11.11	TRect.Assign	1067
67.12	TResourceCollection	1068
67.12.1	Description	1068
67.12.2	Method overview	1068
67.12.3	TResourceCollection.KeyOf	1068
67.12.4	TResourceCollection.GetItem	1069
67.12.5	TResourceCollection.FreeItem	1069
67.12.6	TResourceCollection.PutItem	1069
67.13	TResourceFile	1069
67.13.1	Description	1069
67.13.2	Method overview	1070
67.13.3	TResourceFile.Init	1070
67.13.4	TResourceFile.Done	1070
67.13.5	TResourceFile.Count	1070
67.13.6	TResourceFile.KeyAt	1071

67.13.7	TResourceFile.Get	1071
67.13.8	TResourceFile.SwitchTo	1071
67.13.9	TResourceFile.Flush	1071
67.13.10	TResourceFile.Delete	1072
67.13.11	TResourceFile.Put	1072
67.14	TSortedCollection	1072
67.14.1	Description	1072
67.14.2	Method overview	1073
67.14.3	TSortedCollection.Init	1073
67.14.4	TSortedCollection.Load	1073
67.14.5	TSortedCollection.KeyOf	1073
67.14.6	TSortedCollection.IndexOf	1074
67.14.7	TSortedCollection.Compare	1074
67.14.8	TSortedCollection.Search	1075
67.14.9	TSortedCollection.Insert	1076
67.14.10	TSortedCollection.Store	1077
67.15	TStrCollection	1078
67.15.1	Description	1078
67.15.2	Method overview	1078
67.15.3	TStrCollection.Compare	1078
67.15.4	TStrCollection.GetItem	1079
67.15.5	TStrCollection.FreeItem	1079
67.15.6	TStrCollection.PutItem	1079
67.16	TStream	1080
67.16.1	Description	1080
67.16.2	Method overview	1080
67.16.3	TStream.Init	1080
67.16.4	TStream.Get	1080
67.16.5	TStream.StrRead	1081
67.16.6	TStream.GetPos	1082
67.16.7	TStream.GetSize	1082
67.16.8	TStream.ReadStr	1083
67.16.9	TStream.Open	1084
67.16.10	TStream.Close	1084
67.16.11	TStream.Reset	1084
67.16.12	TStream.Flush	1085
67.16.13	TStream.Truncate	1085
67.16.14	TStream.Put	1085
67.16.15	TStream.StrWrite	1086
67.16.16	TStream.WriteStr	1086

67.16.17	TStream.Seek	1086
67.16.18	TStream.Error	1086
67.16.19	TStream.Read	1087
67.16.20	TStream.Write	1087
67.16.21	TStream.CopyFrom	1088
67.17	TStringCollection	1088
67.17.1	Description	1088
67.17.2	Method overview	1089
67.17.3	TStringCollection.GetItem	1089
67.17.4	TStringCollection.Compare	1089
67.17.5	TStringCollection.FreeItem	1090
67.17.6	TStringCollection.PutItem	1090
67.18	TStringList	1090
67.18.1	Description	1090
67.18.2	Method overview	1091
67.18.3	TStringList.Load	1091
67.18.4	TStringList.Done	1091
67.18.5	TStringList.Get	1091
67.19	TStrListMaker	1092
67.19.1	Description	1092
67.19.2	Method overview	1092
67.19.3	TStrListMaker.Init	1092
67.19.4	TStrListMaker.Done	1092
67.19.5	TStrListMaker.Put	1092
67.19.6	TStrListMaker.Store	1093
67.20	TUnSortedStrCollection	1093
67.20.1	Description	1093
67.20.2	Method overview	1093
67.20.3	TUnSortedStrCollection.Insert	1093
68	Reference for unit 'objpas'	1095
68.1	Used units	1095
68.2	Overview	1095
68.3	Constants, types and variables	1095
68.3.1	Constants	1095
68.3.2	Types	1095
69	Reference for unit 'ports'	1097
69.1	Used units	1097
69.2	Overview	1097
69.3	Constants, types and variables	1097

69.3.1	Variables	1097
69.4	tport	1098
69.4.1	Description	1098
69.4.2	Property overview	1098
69.4.3	tport.pp	1098
69.5	tportl	1099
69.5.1	Description	1099
69.5.2	Property overview	1099
69.5.3	tportl.pp	1099
69.6	tportw	1099
69.6.1	Description	1099
69.6.2	Property overview	1099
69.6.3	tportw.pp	1099
70	Reference for unit 'printer'	1100
70.1	Used units	1100
70.2	Overview	1100
70.3	Constants, types and variables	1100
70.3.1	Variables	1100
70.4	Procedures and functions	1100
70.4.1	AssignLst	1100
70.4.2	InitPrinter	1101
70.4.3	IsLstAvailable	1101
71	Reference for unit 'sharemem'	1102
71.1	Used units	1102
71.2	Overview	1102
72	Reference for unit 'Sockets'	1103
72.1	Used units	1103
72.2	Overview	1103
72.3	Constants, types and variables	1103
72.3.1	Constants	1103
72.3.2	Types	1124
72.4	Procedures and functions	1128
72.4.1	Accept	1128
72.4.2	Bind	1130
72.4.3	CloseSocket	1130
72.4.4	Connect	1130
72.4.5	fpaccept	1132
72.4.6	fpbind	1133

72.4.7	fpconnect	1134
72.4.8	fpgetpeername	1136
72.4.9	fpgetsockname	1136
72.4.10	fpgetsockopt	1137
72.4.11	fplisten	1137
72.4.12	fprecv	1137
72.4.13	fprecvfrom	1138
72.4.14	fpsend	1138
72.4.15	fpsendto	1139
72.4.16	fpsetsockopt	1139
72.4.17	fpshutdown	1140
72.4.18	fpsocket	1140
72.4.19	fpsocketpair	1141
72.4.20	HostAddrToStr	1141
72.4.21	HostAddrToStr6	1141
72.4.22	HostToNet	1141
72.4.23	htonl	1142
72.4.24	htons	1142
72.4.25	NetAddrToStr	1142
72.4.26	NetAddrToStr6	1142
72.4.27	NetToHost	1143
72.4.28	NToHl	1143
72.4.29	NToHs	1143
72.4.30	ShortHostToNet	1143
72.4.31	ShortNetToHost	1144
72.4.32	Sock2File	1144
72.4.33	Sock2Text	1144
72.4.34	socketerror	1144
72.4.35	Str2UnixSockAddr	1145
72.4.36	StrToHostAddr	1145
72.4.37	StrToHostAddr6	1145
72.4.38	StrToNetAddr	1145
72.4.39	StrToNetAddr6	1146
73	Reference for unit 'strings'	1147
73.1	Used units	1147
73.2	Overview	1147
73.3	Procedures and functions	1147
73.3.1	stralloc	1147
73.3.2	strcat	1147

73.3.3	strcmp	1148
73.3.4	strcpy	1148
73.3.5	strdispose	1149
73.3.6	strecopy	1150
73.3.7	strend	1150
73.3.8	stricmp	1151
73.3.9	stripos	1151
73.3.10	striscan	1152
73.3.11	strlcat	1152
73.3.12	strlcomp	1153
73.3.13	strlcopy	1153
73.3.14	strlen	1154
73.3.15	strlicomp	1154
73.3.16	strlower	1155
73.3.17	strmove	1155
73.3.18	strnew	1156
73.3.19	strpas	1157
73.3.20	strpcopy	1157
73.3.21	strpos	1158
73.3.22	strriscan	1158
73.3.23	strrscan	1159
73.3.24	strscan	1159
73.3.25	strupper	1159
74	Reference for unit 'strutils'	1160
74.1	Used units	1160
74.2	Constants, types and variables	1160
74.2.1	Resource strings	1160
74.2.2	Constants	1160
74.2.3	Types	1161
74.3	Procedures and functions	1163
74.3.1	AddChar	1163
74.3.2	AddCharR	1163
74.3.3	AnsiContainsStr	1163
74.3.4	AnsiContainsText	1163
74.3.5	AnsiEndsStr	1164
74.3.6	AnsiEndsText	1164
74.3.7	AnsiIndexStr	1164
74.3.8	AnsiIndexText	1165
74.3.9	AnsiLeftStr	1165

74.3.10	AnsiMatchStr	1165
74.3.11	AnsiMatchText	1165
74.3.12	AnsiMidStr	1166
74.3.13	AnsiProperCase	1166
74.3.14	AnsiReplaceStr	1166
74.3.15	AnsiReplaceText	1167
74.3.16	AnsiResemblesText	1167
74.3.17	AnsiReverseString	1167
74.3.18	AnsiRightStr	1167
74.3.19	AnsiStartsStr	1168
74.3.20	AnsiStartsText	1168
74.3.21	BinToHex	1168
74.3.22	Copy2Space	1169
74.3.23	Copy2SpaceDel	1169
74.3.24	Copy2Symb	1169
74.3.25	Copy2SymbDel	1170
74.3.26	Dec2Numb	1170
74.3.27	DecodeSoundexInt	1170
74.3.28	DecodeSoundexWord	1170
74.3.29	DelChars	1171
74.3.30	DelSpace	1171
74.3.31	DelSpace1	1171
74.3.32	DupeString	1171
74.3.33	ExtractDelimited	1172
74.3.34	ExtractSubstr	1172
74.3.35	ExtractWord	1172
74.3.36	ExtractWordPos	1173
74.3.37	FindMatchesBoyerMooreCaseInsensitive	1173
74.3.38	FindMatchesBoyerMooreCaseSensitive	1174
74.3.39	FindPart	1174
74.3.40	GetCmdLineArg	1175
74.3.41	Hex2Dec	1175
74.3.42	HexToBin	1175
74.3.43	IfThen	1176
74.3.44	IndexStr	1176
74.3.45	IntToBin	1176
74.3.46	IntToRoman	1176
74.3.47	IsEmptyStr	1177
74.3.48	IsWild	1177
74.3.49	IsWordPresent	1177

74.3.50	LeftBStr	1178
74.3.51	LeftStr	1178
74.3.52	MatchStr	1178
74.3.53	MidBStr	1179
74.3.54	MidStr	1179
74.3.55	NaturalCompareText	1179
74.3.56	NPos	1180
74.3.57	Numb2Dec	1180
74.3.58	Numb2USA	1180
74.3.59	PadCenter	1181
74.3.60	PadLeft	1181
74.3.61	PadRight	1181
74.3.62	PosEx	1181
74.3.63	PosSet	1182
74.3.64	PosSetEx	1182
74.3.65	RandomFrom	1182
74.3.66	Removeleadingchars	1183
74.3.67	RemovePadChars	1183
74.3.68	RemoveTrailingChars	1183
74.3.69	ReplaceStr	1184
74.3.70	ReplaceText	1184
74.3.71	ReverseString	1184
74.3.72	RightBStr	1184
74.3.73	RightStr	1185
74.3.74	RomanToInt	1185
74.3.75	RomanToIntDef	1185
74.3.76	RPos	1186
74.3.77	RPosex	1186
74.3.78	SearchBuf	1186
74.3.79	Soundex	1187
74.3.80	SoundexCompare	1187
74.3.81	SoundexInt	1187
74.3.82	SoundexProc	1188
74.3.83	SoundexSimilar	1188
74.3.84	SoundexWord	1188
74.3.85	StringReplace	1189
74.3.86	StringsReplace	1189
74.3.87	StuffString	1190
74.3.88	Tab2Space	1190
74.3.89	TrimLeftSet	1190

74.3.90	TrimRightSet	1190
74.3.91	TrimSet	1191
74.3.92	TryRomanToInt	1191
74.3.93	WordCount	1191
74.3.94	WordPosition	1192
74.3.95	XorDecode	1192
74.3.96	XorEncode	1192
74.3.97	XorString	1193
75	Reference for unit 'System'	1194
75.1	Overview	1194
75.2	Unicode and codepage support	1194
75.3	Miscellaneous functions	1195
75.4	Operating System functions	1196
75.5	String handling	1196
75.6	Mathematical routines	1197
75.7	Memory management functions	1198
75.8	File handling functions	1198
75.9	Run-Time Error behaviour	1199
75.10	Constants, types and variables	1199
75.10.1	Constants	1199
75.10.2	Types	1221
75.10.3	Variables	1261
75.11	Procedures and functions	1265
75.11.1	abs	1265
75.11.2	AbstractError	1266
75.11.3	AcquireExceptionObject	1266
75.11.4	add(variant,variant):variant	1266
75.11.5	AddExitProc	1266
75.11.6	Addr	1267
75.11.7	Align	1267
75.11.8	AllocMem	1268
75.11.9	AnsiToUtf8	1268
75.11.10	Append	1268
75.11.11	arctan	1269
75.11.12	ArrayStringToPPchar	1269
75.11.13	Assert	1270
75.11.14	Assign	1270
75.11.15	assign(ansistring):olevariant	1271
75.11.16	assign(ansistring):variant	1271

75.11.17	assign(Boolean):olevariant	1271
75.11.18	assign(Boolean):variant	1271
75.11.19	assign(Byte):olevariant	1272
75.11.20	assign(Byte):variant	1272
75.11.21	assign(Char):olevariant	1272
75.11.22	assign(Char):variant	1272
75.11.23	assign(comp):olevariant	1272
75.11.24	assign(comp):variant	1272
75.11.25	assign(currency):olevariant	1273
75.11.26	assign(currency):variant	1273
75.11.27	assign(Double):olevariant	1273
75.11.28	assign(Double):variant	1273
75.11.29	assign(DWord):olevariant	1273
75.11.30	assign(DWord):variant	1273
75.11.31	assign(extended):olevariant	1274
75.11.32	assign(extended):variant	1274
75.11.33	assign(Int64):olevariant	1274
75.11.34	assign(Int64):variant	1274
75.11.35	assign(longbool):olevariant	1274
75.11.36	assign(longbool):variant	1274
75.11.37	assign(LongInt):olevariant	1275
75.11.38	assign(LongInt):variant	1275
75.11.39	assign(olevariant):ansistring	1275
75.11.40	assign(olevariant):Boolean	1275
75.11.41	assign(olevariant):Byte	1275
75.11.42	assign(olevariant):Char	1275
75.11.43	assign(olevariant):comp	1276
75.11.44	assign(olevariant):currency	1276
75.11.45	assign(olevariant):Double	1276
75.11.46	assign(olevariant):DWord	1276
75.11.47	assign(olevariant):extended	1276
75.11.48	assign(olevariant):Int64	1276
75.11.49	assign(olevariant):longbool	1277
75.11.50	assign(olevariant):LongInt	1277
75.11.51	assign(olevariant):QWord	1277
75.11.52	assign(olevariant):Real	1277
75.11.53	assign(olevariant):ShortInt	1277
75.11.54	assign(olevariant):shortstring	1277
75.11.55	assign(olevariant):single	1278
75.11.56	assign(olevariant):SmallInt	1278

75.11.57	assign(olevariant):TDateTime	1278
75.11.58	assign(olevariant):TError	1278
75.11.59	assign(olevariant):UnicodeString	1278
75.11.60	assign(olevariant):variant	1278
75.11.61	assign(olevariant):WideChar	1279
75.11.62	assign(olevariant):widestring	1279
75.11.63	assign(olevariant):Word	1279
75.11.64	assign(olevariant):wordbool	1279
75.11.65	assign(QWord):olevariant	1279
75.11.66	assign(QWord):variant	1279
75.11.67	assign(Real):olevariant	1280
75.11.68	assign(Real):variant	1280
75.11.69	assign(real48):Double	1280
75.11.70	assign(real48):extended	1280
75.11.71	assign(ShortInt):olevariant	1280
75.11.72	assign(ShortInt):variant	1280
75.11.73	assign(shortstring):olevariant	1281
75.11.74	assign(shortstring):variant	1281
75.11.75	assign(single):olevariant	1281
75.11.76	assign(single):variant	1281
75.11.77	assign(SmallInt):olevariant	1281
75.11.78	assign(SmallInt):variant	1281
75.11.79	assign(TDateTime):olevariant	1282
75.11.80	assign(TDateTime):variant	1282
75.11.81	assign(TError):olevariant	1282
75.11.82	assign(TError):variant	1282
75.11.83	assign(UCS4String):variant	1282
75.11.84	assign(UnicodeString):olevariant	1282
75.11.85	assign(UnicodeString):variant	1283
75.11.86	assign(UTF8String):variant	1283
75.11.87	assign(variant):ansistring	1283
75.11.88	assign(variant):Boolean	1283
75.11.89	assign(variant):Byte	1283
75.11.90	assign(variant):Char	1283
75.11.91	assign(variant):comp	1284
75.11.92	assign(variant):currency	1284
75.11.93	assign(variant):Double	1284
75.11.94	assign(variant):DWord	1284
75.11.95	assign(variant):extended	1284
75.11.96	assign(variant):Int64	1284

75.11.97 assign(variant):longbool	1285
75.11.98 assign(variant):LongInt	1285
75.11.99 assign(variant):olevariant	1285
75.11.100 assign(variant):QWord	1285
75.11.101 assign(variant):Real	1285
75.11.102 assign(variant):ShortInt	1285
75.11.103 assign(variant):shortstring	1286
75.11.104 assign(variant):single	1286
75.11.105 assign(variant):SmallInt	1286
75.11.106 assign(variant):TDateTime	1286
75.11.107 assign(variant):TError	1286
75.11.108 assign(variant):unicodestring	1286
75.11.109 assign(variant):UTF8String	1287
75.11.110 assign(variant):WideChar	1287
75.11.111 assign(variant):widerstring	1287
75.11.112 assign(variant):Word	1287
75.11.113 assign(variant):wordbool	1287
75.11.114 assign(WideChar):olevariant	1287
75.11.115 assign(WideChar):variant	1288
75.11.116 assign(widerstring):olevariant	1288
75.11.117 assign(widerstring):variant	1288
75.11.118 assign(Word):olevariant	1288
75.11.119 assign(Word):variant	1288
75.11.120 assign(wordbool):olevariant	1288
75.11.121 assign(wordbool):variant	1289
75.11.122 Assigned	1289
75.11.123 BasicEventCreate	1289
75.11.124 basiceventdestroy	1290
75.11.125 basiceventResetEvent	1290
75.11.126 basiceventSetEvent	1290
75.11.127 basiceventWaitFor	1290
75.11.128 BeginThread	1290
75.11.129 BEtoN	1291
75.11.130 binStr	1291
75.11.131 BlockRead	1292
75.11.132 BlockWrite	1293
75.11.133 Break	1293
75.11.134 BsfByte	1294
75.11.135 BsfDWord	1294
75.11.136 BsfQWord	1295

75.11.137BsfWord	1295
75.11.138BsrByte	1295
75.11.139BsrDWord	1296
75.11.140BsrQWord	1296
75.11.141BsrWord	1296
75.11.142CaptureBacktrace	1296
75.11.143chdir	1297
75.11.144chr	1297
75.11.145Close	1298
75.11.146CloseThread	1298
75.11.147CompareByte	1298
75.11.148CompareChar	1299
75.11.149CompareChar0	1301
75.11.150CompareDWord	1301
75.11.151CompareWord	1302
75.11.152Concat	1303
75.11.153Continue	1304
75.11.154CopyArray	1305
75.11.155cos	1305
75.11.156Cseg	1306
75.11.157Dec	1306
75.11.158DefaultAnsi2UnicodeMove	1307
75.11.159DefaultAnsi2WideMove	1307
75.11.160DefaultUnicode2AnsiMove	1307
75.11.161Delete	1308
75.11.162Dispose	1308
75.11.163divide(variant,variant):variant	1309
75.11.164DoneCriticalSection	1309
75.11.165DoneThread	1310
75.11.166Dseg	1310
75.11.167DumpExceptionBackTrace	1310
75.11.168Dump_Stack	1311
75.11.169DynArrayBounds	1311
75.11.170DynArrayClear	1311
75.11.171DynArrayDim	1312
75.11.172DynArrayIndex	1312
75.11.173DynArraySetLength	1312
75.11.174DynArraySize	1313
75.11.175EmptyMethod	1313
75.11.176EndThread	1313

75.11.177EnterCriticalSection	1313
75.11.178EnumResourceLanguages	1314
75.11.179EnumResourceNames	1314
75.11.180EnumResourceTypes	1315
75.11.181EOF	1315
75.11.182EOLn	1316
75.11.183equal(variant,variant):Boolean	1316
75.11.184Erase	1317
75.11.185Error	1317
75.11.186Exclude	1317
75.11.187Exit	1319
75.11.188exp	1320
75.11.189FilePos	1320
75.11.190FileSize	1321
75.11.191FillByte	1322
75.11.192FillChar	1322
75.11.193FillDWord	1323
75.11.194FillQWord	1324
75.11.195FillWord	1324
75.11.196FinalizeArray	1324
75.11.197FindResource	1325
75.11.198FindResourceEx	1325
75.11.199float_raise	1326
75.11.200Flush	1326
75.11.201FlushThread	1327
75.11.202FMADouble	1327
75.11.203FMAExtended	1327
75.11.204FMASingle	1327
75.11.205fpc_SarInt64	1327
75.11.206FPower10	1327
75.11.207frac	1328
75.11.208Freemem	1328
75.11.209Freememory	1329
75.11.210FreeResource	1329
75.11.211Get8087CW	1329
75.11.212GetCPUCount	1329
75.11.213GetCurrentThreadId	1329
75.11.214getdir	1330
75.11.215GetFPCHeapStatus	1330
75.11.216GetHeapStatus	1330

75.11.217GetMem	1331
75.11.218GetMemory	1331
75.11.219GetMemoryManager	1331
75.11.220GetMXCSR	1331
75.11.221GetProcessID	1332
75.11.222GetResourceManager	1332
75.11.223GetSSECSR	1332
75.11.224GetTextCodePage	1332
75.11.225GetThreadID	1333
75.11.226GetThreadManager	1333
75.11.227GetUnicodeStringManager	1333
75.11.228GetVariantManager	1333
75.11.229GetWideStringManager	1334
75.11.230get_caller_addr	1334
75.11.231get_caller_frame	1334
75.11.232get_caller_stackinfo	1334
75.11.233get_frame	1335
75.11.234Get_pc_addr	1335
75.11.235greaterthan(variant,variant):Boolean	1335
75.11.236greaterthanorequal(variant,variant):Boolean	1335
75.11.237halt	1336
75.11.238hexStr	1336
75.11.239hi	1337
75.11.240High	1337
75.11.241HINSTANCE	1339
75.11.242Inc	1339
75.11.243Include	1340
75.11.244IndexByte	1340
75.11.245IndexChar	1341
75.11.246IndexChar0	1342
75.11.247IndexDWord	1342
75.11.248IndexQWord	1343
75.11.249Indexword	1343
75.11.250InitCriticalSection	1344
75.11.251InitializeArray	1344
75.11.252InitThread	1344
75.11.253InitThreadVars	1344
75.11.254Insert	1345
75.11.255int	1345
75.11.256intdivide(variant,variant):variant	1346

75.11.257InterlockedCompareExchange	1346
75.11.258InterlockedCompareExchange64	1346
75.11.259InterLockedDecrement	1347
75.11.260InterLockedDecrement64	1347
75.11.261InterLockedExchange	1347
75.11.262InterLockedExchange64	1347
75.11.263InterLockedExchangeAdd	1348
75.11.264InterLockedExchangeAdd64	1348
75.11.265InterLockedIncrement	1348
75.11.266InterLockedIncrement64	1348
75.11.267IOResult	1349
75.11.268IsDynArrayRectangular	1350
75.11.269IsMemoryManagerSet	1350
75.11.270Is_IntResource	1350
75.11.271KillThread	1351
75.11.272LeaveCriticalsection	1351
75.11.273leftshift(variant,variant):variant	1351
75.11.274lessthan(variant,variant):Boolean	1352
75.11.275lessthanorequal(variant,variant):Boolean	1352
75.11.276LEtoN	1352
75.11.277ln	1352
75.11.278lo	1353
75.11.279LoadResource	1354
75.11.280LockResource	1354
75.11.281logicaland(variant,variant):variant	1354
75.11.282logicalnot(variant):variant	1355
75.11.283logicalor(variant,variant):variant	1355
75.11.284logicalxor(variant,variant):variant	1355
75.11.285longjmp	1355
75.11.286Low	1356
75.11.287lowerCase	1356
75.11.288MakeLangID	1357
75.11.289MemSize	1357
75.11.290mkdir	1357
75.11.291modulus(variant,variant):variant	1358
75.11.292Move	1358
75.11.293MoveChar0	1358
75.11.294multiply(variant,variant):variant	1359
75.11.295negative(variant):variant	1359
75.11.296New	1360

75.11.297NtoBE	1360
75.11.298NtoLE	1360
75.11.299Null	1361
75.11.300OctStr	1361
75.11.301odd	1361
75.11.302Ofs	1362
75.11.303Ord	1362
75.11.304ParamCount	1363
75.11.305ParamStr	1364
75.11.306pi	1364
75.11.307PopCnt	1365
75.11.308Pos	1365
75.11.309power(variant,variant):variant	1366
75.11.310Pred	1366
75.11.311prefetch	1367
75.11.312ptr	1367
75.11.313RaiseList	1367
75.11.314Random	1368
75.11.315Randomize	1368
75.11.316Read	1369
75.11.317ReadBarrier	1369
75.11.318ReadDependencyBarrier	1370
75.11.319ReadLn	1370
75.11.320ReadWriteBarrier	1370
75.11.321Real2Double	1371
75.11.322ReAllocMem	1371
75.11.323ReAllocMemory	1372
75.11.324ReleaseExceptionObject	1372
75.11.325Rename	1372
75.11.326Reset	1373
75.11.327ResumeThread	1374
75.11.328Rewrite	1374
75.11.329rightshift(variant,variant):variant	1375
75.11.330rmdir	1375
75.11.331RolByte	1376
75.11.332RolDWord	1376
75.11.333RolQWord	1376
75.11.334RolWord	1376
75.11.335RorByte	1377
75.11.336RorDWord	1377

75.11.337RorQWord	1377
75.11.338RorWord	1377
75.11.339round	1378
75.11.340RTLEventCreate	1378
75.11.341RTLeventdestroy	1378
75.11.342RTLeventResetEvent	1379
75.11.343RTLeventSetEvent	1379
75.11.344RTLeventWaitFor	1379
75.11.345RunError	1379
75.11.346SarInt64	1380
75.11.347SarLongint	1380
75.11.348SarShortint	1380
75.11.349SarSmallint	1381
75.11.350Seek	1381
75.11.351SeekEOF	1382
75.11.352SeekEOLn	1382
75.11.353Seg	1383
75.11.354SemaphoreDestroy	1383
75.11.355SemaphoreInit	1384
75.11.356SemaphorePost	1384
75.11.357SemaphoreWait	1384
75.11.358Set8087CW	1385
75.11.359SetCodePage	1385
75.11.360Setjmp	1385
75.11.361SetMemoryManager	1386
75.11.362SetMultiByteConversionCodePage	1386
75.11.363SetMultiByteFileSystemCodePage	1386
75.11.364SetMultiByteRTLFileSystemCodePage	1387
75.11.365SetMXCSR	1387
75.11.366SetResourceManager	1387
75.11.367SetSSECSR	1387
75.11.368SetString	1388
75.11.369SetTextBuf	1388
75.11.370SetTextCodePage	1389
75.11.371SetTextLineEnding	1389
75.11.372SetThreadManager	1390
75.11.373SetUnicodeStringManager	1390
75.11.374SetVariantManager	1390
75.11.375SetWideStringManager	1391
75.11.376ShortCompareText	1391

75.11.377sin	1391
75.11.378SizeOf	1392
75.11.379SizeofResource	1392
75.11.380Space	1393
75.11.381Sptr	1393
75.11.382sqr	1393
75.11.383sqrt	1394
75.11.384Sseg	1394
75.11.385StackTop	1395
75.11.386Str	1395
75.11.387StringCodePage	1396
75.11.388StringElementSize	1397
75.11.389StringOfChar	1397
75.11.390StringRefCount	1398
75.11.391StringToPPChar	1398
75.11.392StringToUnicodeChar	1398
75.11.393StringToWideChar	1399
75.11.394strlen	1399
75.11.395strpas	1399
75.11.396subtract(variant,variant):variant	1399
75.11.397Succ	1400
75.11.398SuspendThread	1400
75.11.399Swap	1400
75.11.400SwapEndian	1401
75.11.401SysAllocMem	1401
75.11.402SysAssert	1401
75.11.403SysBackTraceStr	1402
75.11.404SysFlushStdIO	1402
75.11.405SysFreemem	1402
75.11.406SysFreememSize	1402
75.11.407SysGetFPCHeapStatus	1403
75.11.408SysGetHeapStatus	1403
75.11.409SysGetmem	1403
75.11.410SysInitExceptions	1403
75.11.411SysInitFPU	1404
75.11.412SysInitStdIO	1404
75.11.413SysMemSize	1404
75.11.414SysReAllocMem	1404
75.11.415SysResetFPU	1404
75.11.416SysSetCtrlBreakHandler	1405

75.11.417SysTryResizeMem	1405
75.11.418ThreadGetPriority	1405
75.11.419ThreadSetPriority	1405
75.11.420ThreadSwitch	1406
75.11.421ToSingleByteFileSystemEncodedFileName	1406
75.11.422trunc	1406
75.11.423Truncate	1407
75.11.424TryEnterCriticalsection	1407
75.11.425UCS4StringToUnicodeString	1408
75.11.426UCS4StringToWideString	1408
75.11.427Unassigned	1408
75.11.428UnicodeCharLenToString	1408
75.11.429UnicodeCharLenToStrVar	1408
75.11.430UnicodeCharToString	1409
75.11.431UnicodeCharToStrVar	1409
75.11.432UnicodeStringToUCS4String	1409
75.11.433UnicodeToUtf8	1410
75.11.434UniqueString	1410
75.11.435UnlockResource	1410
75.11.436upCase	1410
75.11.437Utf8CodePointLen	1411
75.11.438UTF8Decode	1412
75.11.439UTF8Encode	1412
75.11.440Utf8ToAnsi	1412
75.11.441Utf8ToUnicode	1413
75.11.442Val	1413
75.11.443VarArrayGet	1414
75.11.444VarArrayPut	1414
75.11.445VarArrayRedim	1414
75.11.446VarCast	1414
75.11.447WaitForThreadTerminate	1415
75.11.448WideCharLenToString	1415
75.11.449WideCharLenToStrVar	1415
75.11.450WideCharToString	1416
75.11.451WideCharToStrVar	1416
75.11.452WideStringToUCS4String	1416
75.11.453WriteBarrier	1416
75.12 TDoubleRec	1417
75.12.1 Method overview	1417
75.12.2 Property overview	1418

75.12.3	TDoubleRec.Mantissa	1418
75.12.4	TDoubleRec.Fraction	1418
75.12.5	TDoubleRec.Exponent	1418
75.12.6	TDoubleRec.SpecialType	1418
75.12.7	TDoubleRec.Sign	1419
75.12.8	TDoubleRec.Exp	1419
75.12.9	TDoubleRec.Frac	1419
75.13	TExtended80Rec	1419
75.13.1	Method overview	1420
75.13.2	Property overview	1420
75.13.3	TExtended80Rec.Mantissa	1420
75.13.4	TExtended80Rec.Fraction	1420
75.13.5	TExtended80Rec.Exponent	1421
75.13.6	TExtended80Rec.SpecialType	1421
75.13.7	TExtended80Rec.Sign	1421
75.13.8	TExtended80Rec.Exp	1421
75.14	TSingleRec	1422
75.14.1	Method overview	1422
75.14.2	Property overview	1423
75.14.3	TSingleRec.Mantissa	1423
75.14.4	TSingleRec.Fraction	1423
75.14.5	TSingleRec.Exponent	1423
75.14.6	TSingleRec.SpecialType	1423
75.14.7	TSingleRec.Sign	1424
75.14.8	TSingleRec.Exp	1424
75.14.9	TSingleRec.Frac	1424
75.15	IDispatch	1424
75.15.1	Description	1424
75.15.2	Method overview	1424
75.15.3	IDispatch.GetTypeInfoCount	1425
75.15.4	IDispatch.GetTypeInfo	1425
75.15.5	IDispatch.GetIDsOfNames	1425
75.15.6	IDispatch.Invoke	1425
75.16	IEnumerable	1425
75.16.1	Description	1425
75.16.2	Method overview	1425
75.16.3	IEnumerable.GetEnumerator	1426
75.17	IEnumerator	1426
75.17.1	Description	1426
75.17.2	Method overview	1426

75.17.3	Property overview	1427
75.17.4	IEnumerator.GetCurrent	1427
75.17.5	IEnumerator.MoveNext	1427
75.17.6	IEnumerator.Reset	1427
75.17.7	IEnumerator.Current	1427
75.18	IInvokable	1428
75.18.1	Description	1428
75.19	IUnknown	1428
75.19.1	Description	1428
75.19.2	Method overview	1428
75.19.3	IUnknown.QueryInterface	1428
75.19.4	IUnknown._AddRef	1428
75.19.5	IUnknown._Release	1429
75.20	TAggregatedObject	1429
75.20.1	Description	1429
75.20.2	Method overview	1429
75.20.3	Property overview	1429
75.20.4	TAggregatedObject.Create	1429
75.20.5	TAggregatedObject.Controller	1430
75.21	TContainedObject	1430
75.21.1	Description	1430
75.21.2	Interfaces overview	1430
75.22	TInterfacedObject	1430
75.22.1	Description	1430
75.22.2	Interfaces overview	1430
75.22.3	Method overview	1430
75.22.4	Property overview	1431
75.22.5	TInterfacedObject.AfterConstruction	1431
75.22.6	TInterfacedObject.BeforeDestruction	1431
75.22.7	TInterfacedObject.NewInstance	1431
75.22.8	TInterfacedObject.RefCount	1431
75.23	TObject	1432
75.23.1	Description	1432
75.23.2	Method overview	1432
75.23.3	TObject.Create	1433
75.23.4	TObject.Destroy	1433
75.23.5	TObject.newInstance	1433
75.23.6	TObject.FreeInstance	1433
75.23.7	TObject.SafeCallException	1434
75.23.8	TObject.DefaultHandler	1434

75.23.9	TObject.Free	1434
75.23.10	TObject.InitInstance	1434
75.23.11	TObject.CleanupInstance	1435
75.23.12	TObject.ClassType	1435
75.23.13	TObject.ClassInfo	1435
75.23.14	TObject.ClassName	1435
75.23.15	TObject.ClassNameIs	1436
75.23.16	TObject.ClassParent	1436
75.23.17	TObject.InstanceSize	1436
75.23.18	TObject.InheritsFrom	1436
75.23.19	TObject.StringMessageTable	1437
75.23.20	TObject.MethodAddress	1437
75.23.21	TObject.MethodName	1437
75.23.22	TObject.FieldAddress	1437
75.23.23	TObject.AfterConstruction	1438
75.23.24	TObject.BeforeDestruction	1438
75.23.25	TObject.DefaultHandlerStr	1438
75.23.26	TObject.Dispatch	1438
75.23.27	TObject.DispatchStr	1439
75.23.28	TObject.GetInterface	1439
75.23.29	TObject.GetInterfaceByStr	1439
75.23.30	TObject.GetInterfaceWeak	1440
75.23.31	TObject.GetInterfaceEntry	1440
75.23.32	TObject.GetInterfaceEntryByStr	1440
75.23.33	TObject.GetInterfaceTable	1440
75.23.34	TObject.UnitName	1441
75.23.35	TObject.Equals	1441
75.23.36	TObject.GetHashCode	1441
75.23.37	TObject.ToString	1441
76	Reference for unit 'sysutils'	1442
76.1	Used units	1442
76.2	Overview	1442
76.3	Type Helpers for basic types	1442
76.4	Localization support	1443
76.5	Unicode and codepage awareness	1443
76.6	Miscellaneous conversion routines	1444
76.7	Date/time routines	1445
76.8	FileName handling routines	1445
76.9	File input/output routines	1446

76.10 PChar related functions	1447
76.11 Date and time formatting characters	1448
76.12 Formatting strings	1449
76.13 String functions	1449
76.14 Constants, types and variables	1450
76.14.1 Constants	1450
76.14.2 Types	1457
76.14.3 Variables	1468
76.15 Procedures and functions	1473
76.15.1 AbandonSignalHandler	1473
76.15.2 Abort	1474
76.15.3 AddDisk	1474
76.15.4 AddTerminateProc	1474
76.15.5 AdjustLineBreaks	1475
76.15.6 AnsiCompareFileName	1475
76.15.7 AnsiCompareStr	1476
76.15.8 AnsiCompareText	1477
76.15.9 AnsiDequotedStr	1478
76.15.10 AnsiExtractQuotedStr	1478
76.15.11 AnsiLastChar	1479
76.15.12 AnsiLowerCase	1479
76.15.13 AnsiLowerCaseFileName	1480
76.15.14 AnsiPos	1480
76.15.15 AnsiQuotedStr	1480
76.15.16 AnsiSameStr	1481
76.15.17 AnsiSameText	1481
76.15.18 AnsiStrComp	1481
76.15.19 AnsiStrIComp	1482
76.15.20 AnsiStrLastChar	1483
76.15.21 AnsiStrLComp	1484
76.15.22 AnsiStrLIComp	1484
76.15.23 AnsiStrLower	1485
76.15.24 AnsiStrPos	1486
76.15.25 AnsiStrRScan	1486
76.15.26 AnsiStrScan	1486
76.15.27 AnsiStrUpper	1487
76.15.28 AnsiUpperCase	1487
76.15.29 AnsiUpperCaseFileName	1488
76.15.30 AppendStr	1488
76.15.31 ApplicationName	1489

76.15.32 AssignStr	1489
76.15.33 BCDToInt	1490
76.15.34 Beep	1490
76.15.35 BoolToStr	1490
76.15.36 ByteLength	1491
76.15.37 BytesOf	1491
76.15.38 ByteToCharIndex	1491
76.15.39 ByteToCharLen	1491
76.15.40 ByteType	1492
76.15.41 CallTerminateProcs	1492
76.15.42 ChangeFileExt	1492
76.15.43 CharInSet	1492
76.15.44 CharToByteLen	1493
76.15.45 CodePageNameToCodePage	1493
76.15.46 CodePageToCodePageName	1493
76.15.47 CompareMem	1493
76.15.48 CompareMemRange	1494
76.15.49 CompareStr	1494
76.15.50 CompareText	1495
76.15.51 ComposeDateTime	1496
76.15.52 ConcatPaths	1496
76.15.53 CreateDir	1497
76.15.54 CreateGUID	1497
76.15.55 CurrentYear	1498
76.15.56 CurrToStr	1498
76.15.57 CurrToStrF	1498
76.15.58 Date	1499
76.15.59 DateTimeToFileDate	1499
76.15.60 DateTimeToStr	1500
76.15.61 DateTimeToString	1500
76.15.62 DateTimeToSystemTime	1501
76.15.63 DateTimeToTimeStamp	1502
76.15.64 DateToStr	1502
76.15.65 DayOfWeek	1503
76.15.66 DecodeDate	1503
76.15.67 DecodeDateFully	1504
76.15.68 DecodeTime	1504
76.15.69 DeleteFile	1505
76.15.70 DirectoryExists	1505
76.15.71 DiskFree	1506

76.15.72 DiskSize	1506
76.15.73 DisposeStr	1507
76.15.74 DoDirSeparators	1507
76.15.75 EncodeDate	1508
76.15.76 EncodeTime	1509
76.15.77 ExceptAddr	1509
76.15.78 ExceptFrameCount	1509
76.15.79 ExceptFrames	1510
76.15.80 ExceptionErrorMessage	1510
76.15.81 ExceptObject	1510
76.15.82 ExcludeLeadingPathDelimiter	1511
76.15.83 ExcludeTrailingBackslash	1511
76.15.84 ExcludeTrailingPathDelimiter	1511
76.15.85 ExecuteProcess	1512
76.15.86 ExeSearch	1512
76.15.87 ExpandFileName	1513
76.15.88 ExpandFileNameCase	1513
76.15.89 ExpandUNCFileName	1514
76.15.90 ExtractFileDir	1515
76.15.91 ExtractFileDrive	1515
76.15.92 ExtractFileExt	1516
76.15.93 ExtractFileName	1516
76.15.94 ExtractFilePath	1516
76.15.95 ExtractRelativepath	1517
76.15.96 ExtractShortPathName	1517
76.15.97 FileAge	1518
76.15.98 FileClose	1518
76.15.99 FileCreate	1519
76.15.100 FileDateToDateTime	1520
76.15.101 FileExists	1521
76.15.102 FileFlush	1521
76.15.103 FileGetAttr	1521
76.15.104 FileGetDate	1522
76.15.105 FileIsReadOnly	1523
76.15.106 FileOpen	1523
76.15.107 FileRead	1524
76.15.108 FileSearch	1525
76.15.109 FileSeek	1526
76.15.110 FileSetAttr	1527
76.15.111 FileSetDate	1527

76.15.112FileTruncate	1528
76.15.113FileWrite	1528
76.15.114FindClose	1528
76.15.115FindCmdLineSwitch	1529
76.15.116FindFirst	1529
76.15.117FindNext	1530
76.15.118FloattoCurr	1531
76.15.119FloatToDateTime	1531
76.15.120FloatToDecimal	1531
76.15.121FloatToStr	1532
76.15.122FloatToStrF	1533
76.15.123FloatToText	1535
76.15.124FloatToTextFmt	1536
76.15.125FmtStr	1536
76.15.126ForceDirectories	1537
76.15.127Format	1537
76.15.128FormatBuf	1544
76.15.129FormatCurr	1544
76.15.130FormatDateTime	1545
76.15.131FormatFloat	1546
76.15.132FreeAndNil	1547
76.15.133FreeMemAndNil	1547
76.15.134GetAppConfigDir	1548
76.15.135GetAppConfigFile	1548
76.15.136GetCurrentDir	1549
76.15.137GetDirs	1549
76.15.138GetDriveIDFromLetter	1550
76.15.139GetEnvironmentString	1550
76.15.140GetEnvironmentVariable	1551
76.15.141GetEnvironmentVariableCount	1551
76.15.142GetFileHandle	1551
76.15.143GetLastOSError	1552
76.15.144GetLocalTime	1552
76.15.145GetLocalTimeOffset	1552
76.15.146GetModuleName	1552
76.15.147GetTempDir	1553
76.15.148GetTempFileName	1553
76.15.149GetTickCount	1553
76.15.150GetTickCount64	1554
76.15.151GetUserDir	1554

76.15.152GuidCase	1554
76.15.153GUIDToString	1554
76.15.154HashName	1555
76.15.155HookSignal	1555
76.15.156IncAMonth	1555
76.15.157IncludeLeadingPathDelimiter	1555
76.15.158IncludeTrailingBackslash	1556
76.15.159IncludeTrailingPathDelimiter	1556
76.15.160IncMonth	1556
76.15.161InquireSignal	1557
76.15.162IntToHex	1557
76.15.163IntToStr	1558
76.15.164IsDelimiter	1559
76.15.165IsEqualGUID	1559
76.15.166IsLeapYear	1559
76.15.167IsPathDelimiter	1560
76.15.168IsValidIdent	1560
76.15.169LastDelimiter	1561
76.15.170LeftStr	1561
76.15.171LoadStr	1562
76.15.172LowerCase	1562
76.15.173MSecsToTimeStamp	1563
76.15.174NewStr	1563
76.15.175Now	1564
76.15.176OutOfMemoryError	1564
76.15.177QuotedStr	1564
76.15.178RaiseLastError	1565
76.15.179RemoveDir	1565
76.15.180RenameFile	1565
76.15.181ReplaceDate	1566
76.15.182ReplaceTime	1566
76.15.183RightStr	1567
76.15.184SafeLoadLibrary	1567
76.15.185SameFileName	1567
76.15.186SameStr	1568
76.15.187SameText	1568
76.15.188SetCurrentDir	1568
76.15.189SetDirSeparators	1568
76.15.190ShowException	1569
76.15.191Sleep	1569

76.15.192SScanf	1569
76.15.193StrAlloc	1570
76.15.194StrBufSize	1570
76.15.195StrByteType	1571
76.15.196strcat	1571
76.15.197StrCharLength	1572
76.15.198strcomp	1572
76.15.199StrCopy	1572
76.15.200StrDispose	1573
76.15.201strecopy	1573
76.15.202strend	1574
76.15.203StrFmt	1575
76.15.204stricomp	1575
76.15.205StringOf	1576
76.15.206StringReplace	1576
76.15.207StringToGUID	1577
76.15.208strlcat	1577
76.15.209strlcomp	1578
76.15.210StrLCopy	1578
76.15.211StrLen	1579
76.15.212StrLFmt	1579
76.15.213strlicomp	1580
76.15.214strlower	1581
76.15.215StrMove	1581
76.15.216strnew	1582
76.15.217StrNextChar	1582
76.15.218StrPas	1583
76.15.219StrPCopy	1583
76.15.220StrPLCopy	1583
76.15.221strpos	1584
76.15.222strrscan	1584
76.15.223StrScan	1584
76.15.224StrToBool	1585
76.15.225StrToBoolDef	1585
76.15.226StrToCurr	1585
76.15.227StrToCurrDef	1586
76.15.228StrToDate	1586
76.15.229StrToDateDef	1587
76.15.230StrToDateTime	1587
76.15.231StrToDateTimeDef	1588

76.15.232StrToDWord	1589
76.15.233StrToDWordDef	1589
76.15.234StrToFloat	1589
76.15.235StrToFloatDef	1590
76.15.236StrToInt	1590
76.15.237StrToInt64	1591
76.15.238StrToInt64Def	1592
76.15.239StrToIntDef	1592
76.15.240StrToQWord	1593
76.15.241StrToQWordDef	1593
76.15.242StrToTime	1593
76.15.243StrToTimeDef	1594
76.15.244strupper	1594
76.15.245Supports	1594
76.15.246SysErrorMessage	1595
76.15.247SystemTimeToDateTime	1595
76.15.248TextToFloat	1596
76.15.249Time	1597
76.15.250TimeStampToDateTime	1598
76.15.251TimeStampToMsecs	1598
76.15.252TimeToStr	1599
76.15.253Trim	1599
76.15.254TrimLeft	1600
76.15.255TrimRight	1600
76.15.256TryEncodeDate	1601
76.15.257TryEncodeTime	1601
76.15.258TryFloatToCurr	1602
76.15.259TryStringToGUID	1602
76.15.260TryStrToBool	1602
76.15.261TryStrToCurr	1603
76.15.262TryStrToDate	1603
76.15.263TryStrToDateTime	1603
76.15.264TryStrToDWord	1604
76.15.265TryStrToFloat	1604
76.15.266TryStrToInt	1605
76.15.267TryStrToInt64	1605
76.15.268TryStrToQWord	1605
76.15.269TryStrToTime	1605
76.15.270UnhookSignal	1606
76.15.271UnicodeCompareStr	1606

76.15.272UnicodeCompareText	1606
76.15.273UnicodeFmtStr	1607
76.15.274UnicodeFormat	1607
76.15.275UnicodeFormatBuf	1608
76.15.276UnicodeLowerCase	1608
76.15.277UnicodeSameStr	1608
76.15.278UnicodeSameText	1608
76.15.279UnicodeStringReplace	1609
76.15.280UnicodeUpperCase	1609
76.15.281UpperCase	1609
76.15.282VendorName	1610
76.15.283WideBytesOf	1610
76.15.284WideCompareStr	1610
76.15.285WideCompareText	1611
76.15.286WideFmtStr	1611
76.15.287WideFormat	1611
76.15.288WideFormatBuf	1612
76.15.289WideLowerCase	1612
76.15.290WideSameStr	1612
76.15.291WideSameText	1613
76.15.292WideStrAlloc	1613
76.15.293WideStringOf	1613
76.15.294WideStringReplace	1613
76.15.295WideUpperCase	1614
76.15.296WrapText	1614
76.16 EAbort	1614
76.16.1 Description	1614
76.17 EAbstractError	1615
76.17.1 Description	1615
76.18 EAccessViolation	1615
76.18.1 Description	1615
76.19 EArgumentException	1615
76.19.1 Description	1615
76.20 EArgumentNilException	1615
76.20.1 Description	1615
76.21 EArgumentOutOfRangeException	1615
76.21.1 Description	1615
76.22 EAssertionFailed	1616
76.22.1 Description	1616
76.23 EBusError	1616

76.23.1	Description	1616
76.24	EControlC	1616
76.24.1	Description	1616
76.25	EConvertError	1616
76.25.1	Description	1616
76.26	EDirectoryNotFoundException	1616
76.26.1	Description	1616
76.27	EDivByZero	1616
76.27.1	Description	1616
76.28	EEncodingError	1616
76.28.1	Description	1616
76.29	EExternal	1617
76.29.1	Description	1617
76.30	EExternalException	1617
76.30.1	Description	1617
76.31	EFileNotFoundException	1617
76.31.1	Description	1617
76.32	EFormatError	1617
76.32.1	Description	1617
76.33	EHeapMemoryError	1617
76.33.1	Description	1617
76.33.2	Method overview	1618
76.33.3	EHeapMemoryError.FreeInstance	1618
76.34	EInOutError	1618
76.34.1	Description	1618
76.35	EInterror	1618
76.35.1	Description	1618
76.36	EIntfCastError	1618
76.36.1	Description	1618
76.37	EIntOverflow	1618
76.37.1	Description	1618
76.38	EInvalidCast	1619
76.38.1	Description	1619
76.39	EInvalidContainer	1619
76.39.1	Description	1619
76.40	EInvalidInsert	1619
76.40.1	Description	1619
76.41	EInvalidOp	1619
76.41.1	Description	1619
76.42	EInvalidPointer	1619

76.42.1	Description	1619
76.43	EMathError	1619
76.43.1	Description	1619
76.44	ENoConstructException	1619
76.44.1	Description	1619
76.45	ENoThreadSupport	1620
76.45.1	Description	1620
76.46	ENotImplemented	1620
76.46.1	Description	1620
76.47	ENotSupportedException	1620
76.47.1	Description	1620
76.48	ENoWideStringSupport	1620
76.48.1	Description	1620
76.49	EObjectCheck	1620
76.49.1	Description	1620
76.50	EOSError	1620
76.50.1	Description	1620
76.51	EOutOfMemory	1621
76.51.1	Description	1621
76.52	EOverflow	1621
76.52.1	Description	1621
76.53	EPackageError	1621
76.53.1	Description	1621
76.54	EPathNotFoundException	1621
76.54.1	Description	1621
76.55	EPathTooLongException	1621
76.55.1	Description	1621
76.56	EPrivilege	1622
76.56.1	Description	1622
76.57	EPropReadOnly	1622
76.57.1	Description	1622
76.58	EPropWriteOnly	1622
76.58.1	Description	1622
76.59	ERangeError	1622
76.59.1	Description	1622
76.60	ESafecallException	1622
76.60.1	Description	1622
76.61	EStackOverflow	1622
76.61.1	Description	1622
76.62	EUnderflow	1622

76.62.1	Description	1622
76.63	EVariantError	1623
76.63.1	Description	1623
76.63.2	Method overview	1623
76.63.3	EVariantError.CreateCode	1623
76.64	Exception	1623
76.64.1	Description	1623
76.64.2	Method overview	1623
76.64.3	Property overview	1624
76.64.4	Exception.Create	1624
76.64.5	Exception.CreateFmt	1624
76.64.6	Exception.CreateRes	1624
76.64.7	Exception.CreateResFmt	1624
76.64.8	Exception.CreateHelp	1625
76.64.9	Exception.CreateFmtHelp	1625
76.64.10	Exception.CreateResHelp	1625
76.64.11	Exception.CreateResFmtHelp	1625
76.64.12	Exception.ToString	1626
76.64.13	Exception.HelpContext	1626
76.64.14	Exception.Message	1626
76.65	EZeroDivide	1626
76.65.1	Description	1626
76.66	IReadWriteSync	1626
76.66.1	Description	1626
76.66.2	Method overview	1627
76.66.3	IReadWriteSync.BeginRead	1627
76.66.4	IReadWriteSync.EndRead	1627
76.66.5	IReadWriteSync.BeginWrite	1627
76.66.6	IReadWriteSync.EndWrite	1628
76.67	TBigEndianUnicodeEncoding	1628
76.67.1	Description	1628
76.67.2	Method overview	1628
76.67.3	TBigEndianUnicodeEncoding.Clone	1628
76.67.4	TBigEndianUnicodeEncoding.GetPreamble	1628
76.68	TBooleanHelper	1629
76.68.1	Description	1629
76.68.2	Method overview	1629
76.68.3	TBooleanHelper.Parse	1629
76.68.4	TBooleanHelper.Size	1629
76.68.5	TBooleanHelper.ToString	1629

76.68.6	TBooleanHelper.TryParse	1630
76.68.7	TBooleanHelper.ToInteger	1630
76.69	TByteBoolHelper	1630
76.69.1	Description	1630
76.69.2	Method overview	1631
76.69.3	TByteBoolHelper.Parse	1631
76.69.4	TByteBoolHelper.Size	1631
76.69.5	TByteBoolHelper.ToString	1631
76.69.6	TByteBoolHelper.TryParse	1632
76.69.7	TByteBoolHelper.ToInteger	1632
76.70	TByteHelper	1632
76.70.1	Description	1632
76.70.2	Method overview	1632
76.70.3	TByteHelper.Parse	1633
76.70.4	TByteHelper.Size	1633
76.70.5	TByteHelper.ToString	1633
76.70.6	TByteHelper.TryParse	1633
76.70.7	TByteHelper.ToBoolean	1634
76.70.8	TByteHelper.ToDouble	1634
76.70.9	TByteHelper.ToExtended	1634
76.70.10	TByteHelper.ToHexString	1634
76.70.11	TByteHelper.ToSingle	1635
76.71	TCardinalHelper	1635
76.71.1	Description	1635
76.71.2	Method overview	1635
76.71.3	TCardinalHelper.Parse	1635
76.71.4	TCardinalHelper.Size	1636
76.71.5	TCardinalHelper.ToString	1636
76.71.6	TCardinalHelper.TryParse	1636
76.71.7	TCardinalHelper.ToBoolean	1636
76.71.8	TCardinalHelper.ToDouble	1637
76.71.9	TCardinalHelper.ToExtended	1637
76.71.10	TCardinalHelper.ToHexString	1637
76.71.11	TCardinalHelper.ToSingle	1637
76.72	TDoubleHelper	1638
76.72.1	Description	1638
76.72.2	Method overview	1638
76.72.3	Property overview	1638
76.72.4	TDoubleHelper.IsInfinity	1638
76.72.5	TDoubleHelper.IsNan	1639

76.72.6	TDoubleHelper.IsNegativeInfinity	1639
76.72.7	TDoubleHelper.IsPositiveInfinity	1639
76.72.8	TDoubleHelper.Parse	1639
76.72.9	TDoubleHelper.Size	1640
76.72.10	TDoubleHelper.ToString	1640
76.72.11	TDoubleHelper.TryParse	1641
76.72.12	TDoubleHelper.BuildUp	1641
76.72.13	TDoubleHelper.Exponent	1641
76.72.14	TDoubleHelper.Fraction	1642
76.72.15	TDoubleHelper.Mantissa	1642
76.72.16	TDoubleHelper.SpecialType	1642
76.72.17	TDoubleHelper.Bytes	1642
76.72.18	TDoubleHelper.Words	1643
76.72.19	TDoubleHelper.Sign	1643
76.72.20	TDoubleHelper.Exp	1643
76.72.21	TDoubleHelper.Frac	1643
76.73	TEncoding	1644
76.73.1	Description	1644
76.73.2	Method overview	1644
76.73.3	Property overview	1644
76.73.4	TEncoding.FreeEncodings	1644
76.73.5	TEncoding.Clone	1645
76.73.6	TEncoding.Convert	1645
76.73.7	TEncoding.IsStandardEncoding	1645
76.73.8	TEncoding.GetBufferEncoding	1646
76.73.9	TEncoding.GetEncoding	1646
76.73.10	TEncoding.GetMaxByteCount	1646
76.73.11	TEncoding.GetMaxCharCount	1647
76.73.12	TEncoding.GetPreamble	1647
76.73.13	TEncoding.GetString	1647
76.73.14	TEncoding.CodePage	1647
76.73.15	TEncoding.EncodingName	1648
76.73.16	TEncoding.IsSingleByte	1648
76.73.17	TEncoding.ANSI	1648
76.73.18	TEncoding.ASCII	1648
76.73.19	TEncoding.BigEndianUnicode	1649
76.73.20	TEncoding.Default	1649
76.73.21	TEncoding.Unicode	1649
76.73.22	TEncoding.UTF7	1649
76.73.23	TEncoding.UTF8	1650

76.74	TExtendedHelper	1650
76.74.1	Description	1650
76.74.2	Method overview	1650
76.74.3	Property overview	1650
76.74.4	TExtendedHelper.ToString	1651
76.74.5	TExtendedHelper.Parse	1651
76.74.6	TExtendedHelper.TryParse	1652
76.74.7	TExtendedHelper.IsNan	1652
76.74.8	TExtendedHelper.IsInfinity	1652
76.74.9	TExtendedHelper.IsNegativeInfinity	1653
76.74.10	TExtendedHelper.IsPositiveInfinity	1653
76.74.11	TExtendedHelper.Size	1653
76.74.12	TExtendedHelper.BuildUp	1653
76.74.13	TExtendedHelper.Exponent	1654
76.74.14	TExtendedHelper.Fraction	1654
76.74.15	TExtendedHelper.Mantissa	1654
76.74.16	TExtendedHelper.SpecialType	1654
76.74.17	TExtendedHelper.Bytes	1655
76.74.18	TExtendedHelper.Words	1655
76.74.19	TExtendedHelper.Sign	1655
76.74.20	TExtendedHelper.Exp	1655
76.74.21	TExtendedHelper.Frac	1656
76.75	TGuidHelper	1656
76.75.1	Description	1656
76.75.2	Method overview	1656
76.75.3	TGuidHelper.Create	1656
76.75.4	TGuidHelper.NewGuid	1657
76.75.5	TGuidHelper.ToByteArray	1657
76.75.6	TGuidHelper.ToString	1657
76.76	TInt64Helper	1658
76.76.1	Description	1658
76.76.2	Method overview	1658
76.76.3	TInt64Helper.Parse	1658
76.76.4	TInt64Helper.Size	1658
76.76.5	TInt64Helper.ToString	1659
76.76.6	TInt64Helper.TryParse	1659
76.76.7	TInt64Helper.ToBoolean	1659
76.76.8	TInt64Helper.ToDouble	1659
76.76.9	TInt64Helper.ToExtended	1660
76.76.10	TInt64Helper.ToHexString	1660

76.76.11	TInt64Helper.ToSingle	1660
76.77	TIntegerHelper	1660
76.77.1	Description	1660
76.77.2	Method overview	1661
76.77.3	TIntegerHelper.Size	1661
76.77.4	TIntegerHelper.ToString	1661
76.77.5	TIntegerHelper.Parse	1661
76.77.6	TIntegerHelper.TryParse	1662
76.77.7	TIntegerHelper.ToBoolean	1662
76.77.8	TIntegerHelper.ToDouble	1662
76.77.9	TIntegerHelper.ToExtended	1662
76.77.10	TIntegerHelper.ToHexString	1663
76.77.11	TIntegerHelper.ToSingle	1663
76.78	TLongBoolHelper	1663
76.78.1	Description	1663
76.78.2	Method overview	1663
76.78.3	TLongBoolHelper.Parse	1663
76.78.4	TLongBoolHelper.Size	1664
76.78.5	TLongBoolHelper.ToString	1664
76.78.6	TLongBoolHelper.TryToParse	1664
76.78.7	TLongBoolHelper.ToInteger	1665
76.79	TMBCSEncoding	1665
76.79.1	Description	1665
76.79.2	Method overview	1665
76.79.3	TMBCSEncoding.Create	1665
76.79.4	TMBCSEncoding.Clone	1665
76.79.5	TMBCSEncoding.GetMaxByteCount	1666
76.79.6	TMBCSEncoding.GetMaxCharCount	1666
76.79.7	TMBCSEncoding.GetPreamble	1666
76.80	TMultiReadExclusiveWriteSynchronizer	1666
76.80.1	Description	1666
76.80.2	Interfaces overview	1667
76.80.3	Method overview	1667
76.80.4	TMultiReadExclusiveWriteSynchronizer.Create	1667
76.80.5	TMultiReadExclusiveWriteSynchronizer.Destroy	1667
76.80.6	TMultiReadExclusiveWriteSynchronizer.Beginwrite	1667
76.80.7	TMultiReadExclusiveWriteSynchronizer.Endwrite	1668
76.80.8	TMultiReadExclusiveWriteSynchronizer.Beginread	1668
76.80.9	TMultiReadExclusiveWriteSynchronizer.Endread	1668
76.81	TNativeIntHelper	1668

76.81.1	Description	1668
76.81.2	Method overview	1669
76.81.3	TNativeIntHelper.Parse	1669
76.81.4	TNativeIntHelper.Size	1669
76.81.5	TNativeIntHelper.ToString	1669
76.81.6	TNativeIntHelper.TryParse	1670
76.81.7	TNativeIntHelper.ToBoolean	1670
76.81.8	TNativeIntHelper.ToDouble	1670
76.81.9	TNativeIntHelper.ToExtended	1670
76.81.10	TNativeIntHelper.ToHexString	1671
76.81.11	TNativeIntHelper.ToSingle	1671
76.82	TNativeUIntHelper	1671
76.82.1	Description	1671
76.82.2	Method overview	1671
76.82.3	TNativeUIntHelper.Parse	1672
76.82.4	TNativeUIntHelper.Size	1672
76.82.5	TNativeUIntHelper.ToString	1672
76.82.6	TNativeUIntHelper.TryParse	1672
76.82.7	TNativeUIntHelper.ToBoolean	1673
76.82.8	TNativeUIntHelper.ToDouble	1673
76.82.9	TNativeUIntHelper.ToExtended	1673
76.82.10	TNativeUIntHelper.ToHexString	1673
76.82.11	TNativeUIntHelper.ToSingle	1674
76.83	TQWordHelper	1674
76.83.1	Description	1674
76.83.2	Method overview	1674
76.83.3	TQWordHelper.Parse	1674
76.83.4	TQWordHelper.Size	1675
76.83.5	TQWordHelper.ToString	1675
76.83.6	TQWordHelper.TryParse	1675
76.83.7	TQWordHelper.ToBoolean	1675
76.83.8	TQWordHelper.ToDouble	1676
76.83.9	TQWordHelper.ToExtended	1676
76.83.10	TQWordHelper.ToHexString	1676
76.83.11	TQWordHelper.ToSingle	1676
76.84	TShortIntHelper	1677
76.84.1	Description	1677
76.84.2	Method overview	1677
76.84.3	TShortIntHelper.Parse	1677
76.84.4	TShortIntHelper.Size	1677

76.84.5	TShortIntHelper.ToString	1678
76.84.6	TShortIntHelper.TryParse	1678
76.84.7	TShortIntHelper.ToBoolean	1678
76.84.8	TShortIntHelper.ToDouble	1678
76.84.9	TShortIntHelper.ToExtended	1679
76.84.10	TShortIntHelper.ToHexString	1679
76.84.11	TShortIntHelper.ToSingle	1679
76.85	TSimpleRWSync	1679
76.85.1	Description	1679
76.85.2	Interfaces overview	1679
76.85.3	Method overview	1680
76.85.4	TSimpleRWSync.Create	1680
76.85.5	TSimpleRWSync.Destroy	1680
76.85.6	TSimpleRWSync.Beginwrite	1680
76.85.7	TSimpleRWSync.Endwrite	1680
76.85.8	TSimpleRWSync.Beginread	1681
76.85.9	TSimpleRWSync.Endread	1681
76.86	TSingleHelper	1681
76.86.1	Description	1681
76.86.2	Method overview	1682
76.86.3	Property overview	1682
76.86.4	TSingleHelper.GetB	1682
76.86.5	TSingleHelper.GetW	1682
76.86.6	TSingleHelper.GetE	1682
76.86.7	TSingleHelper.GetF	1683
76.86.8	TSingleHelper.GetS	1683
76.86.9	TSingleHelper.SetB	1683
76.86.10	TSingleHelper.SetW	1683
76.86.11	TSingleHelper.SetE	1683
76.86.12	TSingleHelper.SetF	1683
76.86.13	TSingleHelper.SetS	1683
76.86.14	TSingleHelper.IsNan	1683
76.86.15	TSingleHelper.IsInfinity	1684
76.86.16	TSingleHelper.IsNegativeInfinity	1684
76.86.17	TSingleHelper.IsPositiveInfinity	1684
76.86.18	TSingleHelper.Parse	1685
76.86.19	TSingleHelper.Size	1685
76.86.20	TSingleHelper.ToString	1685
76.86.21	TSingleHelper.TryParse	1686
76.86.22	TSingleHelper.BuildUp	1686

76.86.23	TSingleHelper.Exponent	1686
76.86.24	TSingleHelper.Fraction	1687
76.86.25	TSingleHelper.Mantissa	1687
76.86.26	TSingleHelper.SpecialType	1687
76.86.27	TSingleHelper.Bytes	1687
76.86.28	TSingleHelper.Words	1688
76.86.29	TSingleHelper.Sign	1688
76.86.30	TSingleHelper.Exp	1688
76.86.31	TSingleHelper.Frac	1688
76.87	TSmallIntHelper	1689
76.87.1	Description	1689
76.87.2	Method overview	1689
76.87.3	TSmallIntHelper.Parse	1689
76.87.4	TSmallIntHelper.Size	1689
76.87.5	TSmallIntHelper.ToString	1690
76.87.6	TSmallIntHelper.TryParse	1690
76.87.7	TSmallIntHelper.ToBoolean	1690
76.87.8	TSmallIntHelper.ToHexString	1690
76.87.9	TSmallIntHelper.ToSingle	1691
76.87.10	TSmallIntHelper.ToDouble	1691
76.87.11	TSmallIntHelper.ToExtended	1691
76.88	TStringHelper	1691
76.88.1	Description	1691
76.88.2	Method overview	1693
76.88.3	Property overview	1694
76.88.4	TStringHelper.Compare	1694
76.88.5	TStringHelper.CompareOrdinal	1695
76.88.6	TStringHelper.CompareText	1695
76.88.7	TStringHelper.Copy	1695
76.88.8	TStringHelper.Create	1696
76.88.9	TStringHelper.EndsWith	1696
76.88.10	TStringHelper.Equals	1696
76.88.11	TStringHelper.Format	1697
76.88.12	TStringHelper.IsNullOrEmpty	1697
76.88.13	TStringHelper.IsNullOrEmptyOrWhiteSpace	1697
76.88.14	TStringHelper.Join	1697
76.88.15	TStringHelper.LowerCase	1698
76.88.16	TStringHelper.Parse	1698
76.88.17	TStringHelper.ToBoolean	1698
76.88.18	TStringHelper.ToDouble	1699

76.88.19	TStringHelper.ToExtended	1699
76.88.20	TStringHelper.ToInt64	1699
76.88.21	TStringHelper.ToInteger	1700
76.88.22	TStringHelper.ToSingle	1700
76.88.23	TStringHelper.UpperCase	1700
76.88.24	TStringHelper.CompareTo	1701
76.88.25	TStringHelper.Contains	1701
76.88.26	TStringHelper.CopyTo	1701
76.88.27	TStringHelper.CountChar	1701
76.88.28	TStringHelper.DeQuotedString	1702
76.88.29	TStringHelper.EndsWith	1702
76.88.30	TStringHelper.GetHashCode	1702
76.88.31	TStringHelper.IndexOf	1702
76.88.32	TStringHelper.IndexOfUnQuoted	1703
76.88.33	TStringHelper.IndexOfAny	1703
76.88.34	TStringHelper.IndexOfAnyUnquoted	1704
76.88.35	TStringHelper.Insert	1704
76.88.36	TStringHelper.IsDelimiter	1705
76.88.37	TStringHelper.IsEmpty	1705
76.88.38	TStringHelper.LastDelimiter	1705
76.88.39	TStringHelper.LastIndexOf	1705
76.88.40	TStringHelper.LastIndexOfAny	1706
76.88.41	TStringHelper.PadLeft	1706
76.88.42	TStringHelper.PadRight	1707
76.88.43	TStringHelper.QuotedString	1707
76.88.44	TStringHelper.Remove	1707
76.88.45	TStringHelper.Replace	1708
76.88.46	TStringHelper.Split	1708
76.88.47	TStringHelper.StartsWith	1709
76.88.48	TStringHelper.Substring	1709
76.88.49	TStringHelper.ToCharArray	1710
76.88.50	TStringHelper.ToLower	1710
76.88.51	TStringHelper.ToLowerInvariant	1710
76.88.52	TStringHelper.ToUpper	1710
76.88.53	TStringHelper.ToUpperInvariant	1711
76.88.54	TStringHelper.Trim	1711
76.88.55	TStringHelper.TrimLeft	1711
76.88.56	TStringHelper.TrimRight	1711
76.88.57	TStringHelper.TrimEnd	1712
76.88.58	TStringHelper.TrimStart	1712

76.88.59	TStringHelper.Chars	1712
76.88.60	TStringHelper.Length	1712
76.89	TUnicodeEncoding	1712
76.89.1	Description	1712
76.89.2	Method overview	1713
76.89.3	TUnicodeEncoding.Create	1713
76.89.4	TUnicodeEncoding.Clone	1713
76.89.5	TUnicodeEncoding.GetMaxByteCount	1713
76.89.6	TUnicodeEncoding.GetMaxCharCount	1713
76.89.7	TUnicodeEncoding.GetPreamble	1714
76.90	TUTF7Encoding	1714
76.90.1	Description	1714
76.90.2	Method overview	1714
76.90.3	TUTF7Encoding.Create	1714
76.90.4	TUTF7Encoding.Clone	1714
76.90.5	TUTF7Encoding.GetMaxByteCount	1715
76.90.6	TUTF7Encoding.GetMaxCharCount	1715
76.91	TUTF8Encoding	1715
76.91.1	Description	1715
76.91.2	Method overview	1715
76.91.3	TUTF8Encoding.Create	1715
76.91.4	TUTF8Encoding.Clone	1716
76.91.5	TUTF8Encoding.GetMaxByteCount	1716
76.91.6	TUTF8Encoding.GetMaxCharCount	1716
76.91.7	TUTF8Encoding.GetPreamble	1716
76.92	TWordBoolHelper	1717
76.92.1	Description	1717
76.92.2	Method overview	1717
76.92.3	TWordBoolHelper.Parse	1717
76.92.4	TWordBoolHelper.Size	1717
76.92.5	TWordBoolHelper.ToString	1717
76.92.6	TWordBoolHelper.TryToParse	1718
76.92.7	TWordBoolHelper.ToInteger	1718
76.93	TWordHelper	1718
76.93.1	Description	1718
76.93.2	Method overview	1719
76.93.3	TWordHelper.Parse	1719
76.93.4	TWordHelper.Size	1719
76.93.5	TWordHelper.ToString	1719
76.93.6	TWordHelper.TryParse	1720

76.93.7	TWordHelper.ToBoolean	1720
76.93.8	TWordHelper.ToDouble	1720
76.93.9	TWordHelper.ToExtended	1720
76.93.10	TWordHelper.ToHexString	1721
76.93.11	TWordHelper.ToSingle	1721
77	Reference for unit 'Types'	1722
77.1	Used units	1722
77.2	Overview	1722
77.3	Constants, types and variables	1722
77.3.1	Constants	1722
77.3.2	Types	1727
77.4	Procedures and functions	1733
77.4.1	Bounds	1733
77.4.2	CenterPoint	1734
77.4.3	EqualRect	1734
77.4.4	InflateRect	1734
77.4.5	IntersectRect	1734
77.4.6	IsRectEmpty	1735
77.4.7	OffsetRect	1735
77.4.8	Point	1735
77.4.9	PtInRect	1735
77.4.10	Rect	1736
77.4.11	Size	1736
77.4.12	UnionRect	1736
77.5	TPoint	1736
77.5.1	Method overview	1738
77.5.2	TPoint.Zero	1738
77.5.3	TPoint.Add	1738
77.5.4	TPoint.Distance	1738
77.5.5	TPoint.IsZero	1738
77.5.6	TPoint.Subtract	1738
77.5.7	TPoint.SetLocation	1738
77.5.8	TPoint.SetLocation	1739
77.5.9	TPoint.Offset	1739
77.5.10	TPoint.Offset	1739
77.5.11	TPoint.PointInCircle	1739
77.5.12	TPoint.equal(TPoint,TPoint):Boolean	1739
77.5.13	TPoint.notequal(TPoint,TPoint):Boolean	1739
77.5.14	TPoint.add(TPoint,TPoint):TPoint	1739

77.5.15	TPoint.subtract(TPoint,TPoint):TPoint	1739
77.5.16	TPoint.assign(TSmallPoint):TPoint	1740
77.5.17	TPoint.explicit(TPoint):TSmallPoint	1740
77.6	TPointF	1740
77.6.1	Method overview	1741
77.6.2	TPointF.Add	1741
77.6.3	TPointF.Add	1742
77.6.4	TPointF.Distance	1742
77.6.5	TPointF.DotProduct	1742
77.6.6	TPointF.IsZero	1742
77.6.7	TPointF.Subtract	1742
77.6.8	TPointF.Subtract	1742
77.6.9	TPointF.SetLocation	1742
77.6.10	TPointF.SetLocation	1742
77.6.11	TPointF.SetLocation	1742
77.6.12	TPointF.Offset	1743
77.6.13	TPointF.Offset	1743
77.6.14	TPointF.Offset	1743
77.6.15	TPointF.Scale	1743
77.6.16	TPointF.Ceiling	1743
77.6.17	TPointF.Truncate	1743
77.6.18	TPointF.Floor	1743
77.6.19	TPointF.Round	1743
77.6.20	TPointF.Length	1743
77.6.21	TPointF.equal(TPointF,TPointF):Boolean	1744
77.6.22	TPointF.notequal(TPointF,TPointF):Boolean	1744
77.6.23	TPointF.add(TPointF,TPointF):TPointF	1744
77.6.24	TPointF.subtract(TPointF,TPointF):TPointF	1744
77.6.25	TPointF.negative(TPointF):TPointF	1744
77.6.26	TPointF.multiply(TPointF,TPointF):Single	1744
77.6.27	TPointF.multiply(TPointF,single):TPointF	1744
77.6.28	TPointF.multiply(single,TPointF):TPointF	1744
77.7	TRect	1745
77.7.1	Method overview	1747
77.7.2	Property overview	1747
77.7.3	TRect.Create	1747
77.7.4	TRect.Create	1747
77.7.5	TRect.Create	1747
77.7.6	TRect.Create	1747
77.7.7	TRect.Create	1748

77.7.8	TRect.equal(TRect,TRect):Boolean	1748
77.7.9	TRect.notequal(TRect,TRect):Boolean	1748
77.7.10	TRect.add(TRect,TRect):TRect	1748
77.7.11	TRect.multiply(TRect,TRect):TRect	1748
77.7.12	TRect.Empty	1748
77.7.13	TRect.NormalizeRect	1748
77.7.14	TRect.IsEmpty	1748
77.7.15	TRect.Contains	1748
77.7.16	TRect.Contains	1749
77.7.17	TRect.IntersectsWith	1749
77.7.18	TRect.Intersect	1749
77.7.19	TRect.Intersect	1749
77.7.20	TRect.Union	1749
77.7.21	TRect.Union	1749
77.7.22	TRect.Union	1749
77.7.23	TRect.Offset	1749
77.7.24	TRect.Offset	1749
77.7.25	TRect.SetLocation	1750
77.7.26	TRect.SetLocation	1750
77.7.27	TRect.Inflate	1750
77.7.28	TRect.Inflate	1750
77.7.29	TRect.CenterPoint	1750
77.7.30	TRect.SplitRect	1750
77.7.31	TRect.SplitRect	1750
77.7.32	TRect.Height	1750
77.7.33	TRect.Width	1751
77.7.34	TRect.Size	1751
77.7.35	TRect.Location	1751
77.8	TRectF	1751
77.8.1	Method overview	1752
77.8.2	Property overview	1752
77.8.3	TRectF.Union	1752
77.8.4	TRectF.Offset	1752
77.8.5	TRectF.Width	1752
77.8.6	TRectF.Height	1752
77.9	TSize	1752
77.9.1	Method overview	1753
77.9.2	Property overview	1753
77.9.3	TSize.Add	1753
77.9.4	TSize.Distance	1753

77.9.5	TSize.IsZero	1753
77.9.6	TSize.Subtract	1754
77.9.7	TSize.equal(TSize,TSize):Boolean	1754
77.9.8	TSize.notequal(TSize,TSize):Boolean	1754
77.9.9	TSize.add(TSize,TSize):TSize	1754
77.9.10	TSize.subtract(TSize,TSize):TSize	1754
77.9.11	TSize.Width	1754
77.9.12	TSize.Height	1754
77.10	IClassFactory	1754
77.10.1	Description	1754
77.10.2	Method overview	1755
77.10.3	IClassFactory.CreateInstance	1755
77.10.4	IClassFactory.LockServer	1755
77.11	ISequentialStream	1755
77.11.1	Description	1755
77.11.2	Method overview	1755
77.11.3	ISequentialStream.Read	1755
77.11.4	ISequentialStream.Write	1756
77.12	IStream	1756
77.12.1	Description	1756
77.12.2	Method overview	1756
77.12.3	IStream.Seek	1756
77.12.4	IStream.SetSize	1756
77.12.5	IStream.CopyTo	1757
77.12.6	IStream.Commit	1757
77.12.7	IStream.Revert	1757
77.12.8	IStream.LockRegion	1757
77.12.9	IStream.UnlockRegion	1758
77.12.10	IStream.Stat	1758
77.12.11	IStream.Clone	1758
78	Reference for unit 'typinfo'	1759
78.1	Used units	1759
78.2	Overview	1759
78.3	Auxiliary functions	1759
78.4	Getting or setting property values	1760
78.5	Examining published property information	1760
78.6	Constants, types and variables	1761
78.6.1	Constants	1761
78.6.2	Types	1762

78.7	Procedures and functions	1778
78.7.1	FindPropInfo	1778
78.7.2	GetEnumName	1779
78.7.3	GetEnumNameCount	1780
78.7.4	GetEnumProp	1780
78.7.5	GetEnumValue	1781
78.7.6	GetFloatProp	1781
78.7.7	GetInt64Prop	1782
78.7.8	GetInterfaceProp	1783
78.7.9	GetMethodProp	1783
78.7.10	GetObjectProp	1785
78.7.11	GetObjectPropClass	1786
78.7.12	GetOrdProp	1787
78.7.13	GetPropInfo	1788
78.7.14	GetPropInfos	1788
78.7.15	GetPropList	1789
78.7.16	GetPropValue	1790
78.7.17	GetRawInterfaceProp	1791
78.7.18	GetSetProp	1791
78.7.19	GetStrProp	1792
78.7.20	GetTypeData	1793
78.7.21	GetUnicodeStrProp	1794
78.7.22	GetVariantProp	1794
78.7.23	GetWideStrProp	1794
78.7.24	IsPublishedProp	1795
78.7.25	IsStoredProp	1795
78.7.26	PropIsType	1796
78.7.27	PropType	1797
78.7.28	SetEnumProp	1798
78.7.29	SetFloatProp	1798
78.7.30	SetInt64Prop	1799
78.7.31	SetInterfaceProp	1799
78.7.32	SetMethodProp	1800
78.7.33	SetObjectProp	1800
78.7.34	SetOrdProp	1801
78.7.35	SetPropValue	1801
78.7.36	SetRawInterfaceProp	1801
78.7.37	SetSetProp	1802
78.7.38	SetStrProp	1802
78.7.39	SetToString	1803

78.7.40	SetUnicodeStrProp	1804
78.7.41	SetVariantProp	1804
78.7.42	SetWideStrProp	1804
78.7.43	StringToSet	1805
78.8	TProcedureSignature	1805
78.8.1	Method overview	1805
78.8.2	TProcedureSignature.GetParam	1805
78.9	EPropertyConvertError	1806
78.9.1	Description	1806
78.10	EPropertyError	1806
78.10.1	Description	1806
79	Reference for unit 'unicodedata'	1807
79.1	Used units	1807
79.2	Overview	1807
79.3	Constants, types and variables	1808
79.3.1	Resource strings	1808
79.3.2	Constants	1808
79.3.3	Types	1811
79.4	Procedures and functions	1813
79.4.1	CanonicalOrder	1813
79.4.2	CompareSortKey	1814
79.4.3	ComputeSortKey	1814
79.4.4	FindCollation	1814
79.4.5	FreeCollation	1815
79.4.6	FromUCS4	1815
79.4.7	GetCollationCount	1815
79.4.8	GetProps	1815
79.4.9	GetPropUCA	1816
79.4.10	IncrementalCompareString	1816
79.4.11	LoadCollation	1816
79.4.12	NormalizeNFD	1817
79.4.13	PrepareCollation	1817
79.4.14	RegisterCollation	1817
79.4.15	ToUCS4	1818
79.4.16	UnicodeIsHighSurrogate	1818
79.4.17	UnicodeIsLowSurrogate	1818
79.4.18	UnicodeIsSurrogatePair	1819
79.4.19	UnicodeToLower	1819
79.4.20	UnicodeToUpper	1819

79.4.21	UnregisterCollation	1820
79.4.22	UnregisterCollations	1820
79.5	TUCA_DataBook	1820
79.5.1	Method overview	1821
79.5.2	TUCA_DataBook.IsVariable	1821
79.6	TUCA_PropItemContextRec	1821
79.6.1	Method overview	1821
79.6.2	TUCA_PropItemContextRec.GetCodePoints	1821
79.6.3	TUCA_PropItemContextRec.GetWeights	1822
79.7	TUCA_PropItemContextTreeNodeRec	1822
79.7.1	Method overview	1822
79.7.2	TUCA_PropItemContextTreeNodeRec.GetLeftNode	1822
79.7.3	TUCA_PropItemContextTreeNodeRec.GetRightNode	1822
79.8	TUCA_PropItemContextTreeRec	1822
79.8.1	Method overview	1823
79.8.2	Property overview	1823
79.8.3	TUCA_PropItemContextTreeRec.GetData	1823
79.8.4	TUCA_PropItemContextTreeRec.Find	1823
79.8.5	TUCA_PropItemContextTreeRec.Data	1823
79.9	TUCA_PropItemRec	1824
79.9.1	Method overview	1824
79.9.2	Property overview	1825
79.9.3	TUCA_PropItemRec.HasCodePoint	1825
79.9.4	TUCA_PropItemRec.IsValid	1825
79.9.5	TUCA_PropItemRec.GetWeightArray	1825
79.9.6	TUCA_PropItemRec.GetSelfOnlySize	1825
79.9.7	TUCA_PropItemRec.GetContextual	1825
79.9.8	TUCA_PropItemRec.GetContext	1826
79.9.9	TUCA_PropItemRec.IsDeleted	1826
79.9.10	TUCA_PropItemRec.IsWeightCompress_1	1826
79.9.11	TUCA_PropItemRec.IsWeightCompress_2	1826
79.9.12	TUCA_PropItemRec.CodePoint	1826
79.9.13	TUCA_PropItemRec.Contextual	1826
79.10	TUC_Prop	1827
79.10.1	Property overview	1827
79.10.2	TUC_Prop.Category	1827
79.10.3	TUC_Prop.WhiteSpace	1828
79.10.4	TUC_Prop.HangulSyllable	1828
79.10.5	TUC_Prop.NumericValue	1828
79.11	TUInt24Rec	1828

79.11.1	Method overview	1832
79.11.2	TUInt24Rec.implicit(TUInt24Rec):Cardinal	1833
79.11.3	TUInt24Rec.implicit(TUInt24Rec):LongInt	1833
79.11.4	TUInt24Rec.implicit(TUInt24Rec):Word	1833
79.11.5	TUInt24Rec.implicit(TUInt24Rec):Byte	1833
79.11.6	TUInt24Rec.implicit(Cardinal):TUInt24Rec	1834
79.11.7	TUInt24Rec.equal(TUInt24Rec,TUInt24Rec):Boolean	1834
79.11.8	TUInt24Rec.equal(TUInt24Rec,Cardinal):Boolean	1834
79.11.9	TUInt24Rec.equal(Cardinal,TUInt24Rec):Boolean	1834
79.11.10	TUInt24Rec.equal(TUInt24Rec,LongInt):Boolean	1834
79.11.11	TUInt24Rec.equal(LongInt,TUInt24Rec):Boolean	1835
79.11.12	TUInt24Rec.equal(TUInt24Rec,Word):Boolean	1835
79.11.13	TUInt24Rec.equal(Word,TUInt24Rec):Boolean	1835
79.11.14	TUInt24Rec.equal(TUInt24Rec,Byte):Boolean	1835
79.11.15	TUInt24Rec.equal(Byte,TUInt24Rec):Boolean	1835
79.11.16	TUInt24Rec.notequal(TUInt24Rec,TUInt24Rec):Boolean	1835
79.11.17	TUInt24Rec.notequal(TUInt24Rec,Cardinal):Boolean	1836
79.11.18	TUInt24Rec.notequal(Cardinal,TUInt24Rec):Boolean	1836
79.11.19	TUInt24Rec.greaterthan(TUInt24Rec,TUInt24Rec):Boolean	1836
79.11.20	TUInt24Rec.greaterthan(TUInt24Rec,Cardinal):Boolean	1836
79.11.21	TUInt24Rec.greaterthan(Cardinal,TUInt24Rec):Boolean	1836
79.11.22	TUInt24Rec.greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean	1837
79.11.23	TUInt24Rec.greaterthanorequal(TUInt24Rec,Cardinal):Boolean	1837
79.11.24	TUInt24Rec.greaterthanorequal(Cardinal,TUInt24Rec):Boolean	1837
79.11.25	TUInt24Rec.less than(TUInt24Rec,TUInt24Rec):Boolean	1837
79.11.26	TUInt24Rec.less than(TUInt24Rec,Cardinal):Boolean	1837
79.11.27	TUInt24Rec.less than(Cardinal,TUInt24Rec):Boolean	1838
79.11.28	TUInt24Rec.less thanorequal(TUInt24Rec,TUInt24Rec):Boolean	1838
79.11.29	TUInt24Rec.less thanorequal(TUInt24Rec,Cardinal):Boolean	1838
79.11.30	TUInt24Rec.less thanorequal(Cardinal,TUInt24Rec):Boolean	1838
80	Reference for unit 'unicodeduct'	1839
80.1	Used units	1839
80.2	Overview	1839
81	Reference for unit 'Unix'	1840
81.1	Used units	1840
81.2	Constants, types and variables	1840
81.2.1	Constants	1840
81.2.2	Types	1847
81.2.3	Variables	1856

81.3	Procedures and functions	1856
81.3.1	AssignPipe	1856
81.3.2	AssignStream	1857
81.3.3	FpExecL	1858
81.3.4	FpExecLE	1859
81.3.5	FpExecLP	1860
81.3.6	FpExecLPE	1861
81.3.7	FpExecV	1861
81.3.8	FpExecVP	1862
81.3.9	FpExecVPE	1863
81.3.10	fpFlock	1864
81.3.11	fpfStatFS	1864
81.3.12	fpfsync	1865
81.3.13	fpgettimeofday	1865
81.3.14	fpStatFS	1865
81.3.15	fpSystem	1866
81.3.16	FSearch	1866
81.3.17	GetDomainName	1867
81.3.18	GetHostName	1867
81.3.19	GetLocalTimezone	1868
81.3.20	GetTimezoneFile	1868
81.3.21	PClose	1869
81.3.22	POpen	1869
81.3.23	ReadTimezoneFile	1870
81.3.24	ReReadLocalTime	1870
81.3.25	SeekDir	1871
81.3.26	SelectText	1871
81.3.27	SigRaise	1871
81.3.28	TellDir	1872
81.3.29	WaitProcess	1872
81.3.30	WIFSTOPPED	1873
81.3.31	W_EXITCODE	1873
81.3.32	W_STOPCODE	1873
82	Reference for unit 'unixcp'	1874
82.1	Used units	1874
82.2	Overview	1874
82.3	Constants, types and variables	1874
82.3.1	Constants	1874
82.3.2	Types	1877

82.4	Procedures and functions	1877
82.4.1	GetCodepageByName	1877
82.4.2	GetCodepageData	1878
82.4.3	GetSystemCodepage	1878
83	Reference for unit 'unixtype'	1879
83.1	Used units	1879
83.2	Overview	1879
83.3	Constants, types and variables	1879
83.3.1	Constants	1879
83.3.2	Types	1881
84	Reference for unit 'unixutil'	1894
84.1	Used units	1894
84.2	Overview	1894
84.3	Constants, types and variables	1894
84.3.1	Types	1894
84.3.2	Variables	1895
84.4	Procedures and functions	1895
84.4.1	ArrayStringToPPchar	1895
84.4.2	EpochToLocal	1895
84.4.3	GetFS	1896
84.4.4	GregorianToJulian	1897
84.4.5	JulianToGregorian	1897
84.4.6	LocalToEpoch	1897
84.4.7	StringToPPChar	1898
85	Reference for unit 'video'	1899
85.1	Used units	1899
85.2	Overview	1899
85.3	Examples utility unit	1900
85.4	Writing a custom video driver	1901
85.5	Constants, types and variables	1904
85.5.1	Constants	1904
85.5.2	Types	1908
85.5.3	Variables	1910
85.6	Procedures and functions	1910
85.6.1	ClearScreen	1910
85.6.2	DefaultErrorHandler	1911
85.6.3	DoneVideo	1911
85.6.4	GetCapabilities	1912

85.6.5	GetCursorType	1913
85.6.6	GetLockScreenCount	1914
85.6.7	GetVideoDriver	1914
85.6.8	GetVideoMode	1915
85.6.9	GetVideoModeCount	1915
85.6.10	GetVideoModeData	1917
85.6.11	InitVideo	1917
85.6.12	LockScreenUpdate	1917
85.6.13	SetCursorPos	1918
85.6.14	SetCursorType	1919
85.6.15	SetVideoDriver	1919
85.6.16	SetVideoMode	1919
85.6.17	UnlockScreenUpdate	1920
85.6.18	UpdateScreen	1920
86	Reference for unit 'winrt'	1922
86.1	Used units	1922
86.2	Overview	1922
86.3	Constants, types and variables	1922
86.3.1	Variables	1922
86.4	Procedures and functions	1922
86.4.1	delay	1922
86.4.2	keypressed	1923
86.4.3	nosound	1923
86.4.4	readkey	1923
86.4.5	sound	1923
86.4.6	textmode	1924
87	Reference for unit 'windirs'	1925
87.1	Used units	1925
87.2	Overview	1925
87.3	Constants, types and variables	1925
87.3.1	Constants	1925
87.4	Procedures and functions	1928
87.4.1	GetWindowsSpecialDir	1928
87.4.2	GetWindowsSpecialDirUnicode	1929
87.4.3	GetWindowsSystemDirectory	1929
87.4.4	GetWindowsSystemDirectoryUnicode	1929
88	Reference for unit 'x86'	1930
88.1	Used units	1930

88.2	Overview	1930
88.3	Procedures and functions	1930
88.3.1	fpIOperm	1930
88.3.2	fpIoPL	1931
88.3.3	ReadPort	1931
88.3.4	ReadPortB	1931
88.3.5	ReadPortL	1932
88.3.6	ReadPortW	1932
88.3.7	WritePort	1932
88.3.8	WritePortB	1933
88.3.9	WritePortl	1933
88.3.10	WritePortW	1933

About this guide

This document describes all constants, types, variables, functions and procedures as they are declared in the units that come standard with the Free Pascal Run-Time library (RTL).

Throughout this document, we will refer to functions, types and variables with `typewriter` font. Functions and procedures have their own subsections, and for each function or procedure we have the following topics:

Declaration The exact declaration of the function.

Description What does the procedure exactly do ?

Errors What errors can occur.

See Also Cross references to other related functions/commands.

0.1 Overview

The Run-Time Library is the basis of all Free Pascal programs. It contains the basic units that most programs will use, and are made available on all platforms supported by Free pascal (well, more or less).

There are units for compatibility with the Turbo Pascal Run-Time library, and there are units for compatibility with Delphi.

On top of these two sets, there are also a series of units to handle keyboard/mouse and text screens in a cross-platform way.

Other units include platform specific units that implement the specifics of a platform, these are usually needed to support the Turbo Pascal or Delphi units.

Units that fall outside the above outline do not belong in the RTL, but should be included in the packages, or in the FCL.

Chapter 1

Reference for unit 'BaseUnix'

1.1 Used units

Table 1.1: Used units by unit 'BaseUnix'

Name	Page
System	1194
unixtype	1879

1.2 Overview

The `BaseUnix` unit was implemented by Marco Van de Voort. It contains basic Unix functionality. It supersedes the Linux unit of version 1.0.X of the compiler, but only implements a cleaned up, portable subset of that unit.

For porting FPC to new Unix-like platforms, it should be sufficient to implement the functionality in this unit for the new platform.

1.3 Constants, types and variables

1.3.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`BITSINWORD = 8 * (cuLong)`

Number of bits in a word.

`ESysE2BIG = 7`

System error: Argument list too long

`ESysEACCES = 13`

System error: Permission denied

ESysEADDRINUSE = 98

System error: Address already in use

ESysEADDRNOTAVAIL = 99

System error: Cannot assign requested address

ESysEADV = 68

System error: Advertise error

ESysEAFNOSUPPORT = 97

System error: Address family not supported by protocol

ESysEAGAIN = 11

System error: Try again

ESysEALREADY = 114

System error: Operation already in progress

ESysEBADE = 52

System error: Invalid exchange

ESysEBADF = 9

System error: Bad file number

ESysEBADFD = 77

System error: File descriptor in bad state

ESysEBADMSG = 74

System error: Not a data message

ESysEBADR = 53

System error: Invalid request descriptor

ESysEBADRQC = 56

System error: Invalid request code

ESysEBADSLT = 57

System error: Invalid slot

ESysEBFONT = 59

System error: Bad font file format

ESysEBUSY = 16

System error: Device or resource busy

ESysECANCELED = 125

Operation canceled

ESysECHILD = 10

System error: No child processes

ESysECHRNG = 44

System error: Channel number out of range

ESysECOMM = 70

System error: Communication error on send

ESysECONNABORTED = 103

System error: Software caused connection abort

ESysECONNREFUSED = 111

System error: Connection refused

ESysECONNRESET = 104

System error: Connection reset by peer

ESysEDEADLK = 35

System error: Resource deadlock would occur

ESysEDEADLOCK = ESysEDEADLK

System error: File locking deadlock error

ESysEDESTADDRREQ = 89

System error: Destination address required

ESysEDOM = 33

System error: Math argument out of domain of func

ESysEDOTDOT = 73

System error: RFS specific error

ESysEDQUOT = 122

System error: Quota exceeded

ESysEEXIST = 17

System error: File exists

ESysEFAULT = 14

System error: Bad address

ESysEFBIG = 27

System error: File too large

ESysEHOSTDOWN = 112

System error: Host is down

ESysEHOSTUNREACH = 113

System error: No route to host

ESysEIDRM = 43

System error: Identifier removed

ESysEILSEQ = 84

System error: Illegal byte sequence

ESysEINPROGRESS = 115

System error: Operation now in progress

ESysEINTR = 4

System error: Interrupted system call

ESysEINVAL = 22

System error: Invalid argument

ESysEIO = 5

System error: I/O error

ESysEISCONN = 106

System error: Transport endpoint is already connected

ESysEISDIR = 21

System error: Is a directory

ESysEISNAM = 120

System error: Is a named type file

ESysEKEYEXPIRED = 127

Key has expired (Linux kernel module)

ESysEKEYREJECTED = 129

Key was rejected by service (Linux kernel module)

ESysEKEYREVOKED = 128

Key has been revoked (Linux kernel module)

ESysEL2HLT = 51

System error: Level 2 halted

ESysEL2NSYNC = 45

System error: Level 2 not synchronized

ESysEL3HLT = 46

System error: Level 3 halted

ESysEL3RST = 47

System error: Level 3 reset

ESysELIBACC = 79

System error: Can not access a needed shared library

ESysELIBBAD = 80

System error: Accessing a corrupted shared library

ESysELIBEXEC = 83

System error: Cannot exec a shared library directly

ESysELIBMAX = 82

System error: Attempting to link in too many shared libraries

ESysELIBSCN = 81

System error: .lib section in a.out corrupted

ESysELNRNG = 48

System error: Link number out of range

ESysELOOP = 40

System error: Too many symbolic links encountered

ESysEMEDIUMTYPE = 124

Wrong medium type

ESysEMFILE = 24

System error: Too many open files

ESysEMLINK = 31

System error: Too many links

ESysEMSGSIZE = 90

System error: Message too long

ESysEMULTIHOP = 72

System error: Multihop attempted

ESysENAMETOOLONG = 36

System error: File name too long

ESysENAVAIL = 119

System error: No XENIX semaphores available

ESysENETDOWN = 100

System error: Network is down

ESysENETRESET = 102

System error: Network dropped connection because of reset

ESysENETUNREACH = 101

System error: Network is unreachable

ESysENFILE = 23

System error: File table overflow

ESysENOANO = 55

System error: No anode

ESysENOBUFFS = 105

System error: No buffer space available

ESysENOCSSI = 50

System error: No CSI structure available

ESysENODATA = 61

System error: No data available

ESysENODEV = 19

System error: No such device

ESysENOENT = 2

System error: No such file or directory

ESysENOEXEC = 8

System error: Exec format error

ESysENOKEY = 126

Required key not available (Linux kernel module)

ESysENOLCK = 37

System error: No record locks available

ESysENOLINK = 67

System error: Link has been severed

ESysENOMEDIUM = 123

No medium present

ESysENOMEM = 12

System error: Out of memory

ESysENOMSG = 42

System error: No message of desired type

ESysENONET = 64

System error: Machine is not on the network

ESysENOPKG = 65

System error: Package not installed

ESysENOPROTOOPT = 92

System error: Protocol not available

ESysENOSPC = 28

System error: No space left on device

ESysENOSR = 63

System error: Out of streams resources

ESysENOSTR = 60

System error: Device not a stream

ESysENOSYS = 38

System error: Function not implemented

ESysENOTBLK = 15

System error: Block device required

ESysENOTCONN = 107

System error: Transport endpoint is not connected

ESysENOTDIR = 20

System error: Not a directory

ESysENOTEMPTY = 39

System error: Directory not empty

ESysENOTNAM = 118

System error: Not a XENIX named type file

ESysENOTRECOVERABLE = 131

State not recoverable (mutexes)

ESysENOTSOCK = 88

System error: Socket operation on non-socket

ESysENOTTY = 25

System error: Not a typewriter

ESysENOTUNIQ = 76

System error: Name not unique on network

ESysENXIO = 6

System error: No such device or address

ESysEOPNOTSUPP = 95

System error: Operation not supported on transport endpoint

ESysEOVERFLOW = 75

System error: Value too large for defined data type

ESysEOWNERDEAD = 130

Owner died (mutexes)

ESysEPERM = 1

System error: Operation not permitted.

ESysEPFNOSUPPORT = 96

System error: Protocol family not supported

ESysEPIPE = 32

System error: Broken pipe

ESysEPROTO = 71

System error: Protocol error

ESysEPROTONOSUPPORT = 93

System error: Protocol not supported

ESysEPROTOTYPE = 91

System error: Protocol wrong type for socket

ESysERANGE = 34

System error: Math result not representable

ESysEREMCHG = 78

System error: Remote address changed

ESysEREMOTE = 66

System error: Object is remote

ESysEREMOTEIO = 121

System error: Remote I/O error

ESysERESTART = 85

System error: Interrupted system call should be restarted

ESysERFKILL = 132

Operation not possible due to RF-Kill (wireless)

ESysEROFS = 30

System error: Read-only file system

ESysESHUTDOWN = 108

System error: Cannot send after transport endpoint shutdown

ESysESOCKTNOSUPPORT = 94

System error: Socket type not supported

ESysESPIPE = 29

System error: Illegal seek

ESysESRCH = 3

System error: No such process

ESysESRMNT = 69

System error: Srmount error

ESysESTALE = 116

System error: Stale NFS file handle

ESysESTRPIPE = 86

System error: Streams pipe error

ESysETIME = 62

System error: Timer expired

ESysETIMEDOUT = 110

System error: Connection timed out

ESysETOOMANYREFS = 109

System error: Too many references: cannot splice

ESysETXTBSY = 26

System error: Text (code segment) file busy

ESysEUCLEAN = 117

System error: Structure needs cleaning

ESysEUNATCH = 49

System error: Protocol driver not attached

ESysEUSERS = 87

System error: Too many users

ESysEWOULDBLOCK = ESysEAGAIN

System error: Operation would block

ESysEXDEV = 18

System error: Cross-device link

ESysEXFULL = 54

System error: Exchange full

`FD_MAXFDSET = 1024`

Maximum elements in a `TFDSet` (160) array.

`FPE_FLTDIV = 3`

Value signalling floating point divide by zero in case of `SIGFPE` signal

`FPE_FLTINV = 7`

Value signalling floating point invalid operation in case of `SIGFPE` signal

`FPE_FLTOVF = 4`

Value signalling floating point overflow in case of `SIGFPE` signal

`FPE_FLTRES = 6`

Value signalling floating point inexact result in case of `SIGFPE` signal

`FPE_FLTSUB = 8`

Value signalling floating point subscript out of range in case of `SIGFPE` signal

`FPE_FLTUND = 5`

Value signalling floating point underflow in case of `SIGFPE` signal

`FPE_INTDIV = 1`

Value signalling integer divide in case of `SIGFPE` signal

`FPE_INTOVF = 2`

Value signalling integer overflow in case of `SIGFPE` signal

`F_GetFd = 1`

`fpFCntl` (176) command: Get close-on-exec flag

`F_GetFl = 3`

`fpFCntl` (176) command: Get filedescriptor flags

`F_GetLk = 5`

`fpFCntl` (176) command: Get lock

`F_GetOwn = 9`

fpFCntl (176) command: get owner of filedescriptor events

F_OK = 0

fpAccess (167) call test: file exists.

F_SetFd = 2

fpFCntl (176) command: Set close-on-exec flag

F_SetFl = 4

fpFCntl (176) command: Set filedescriptor flags

F_SetLk = 6

fpFCntl (176) command: Set lock

F_SetLkW = 7

fpFCntl (176) command: Test lock

F_SetOwn = 8

fpFCntl (176) command: Set owner of filedescriptor events

ln2bitmask = 1 shl ln2bitsinword - 1

Last bit in word.

ln2bitsinword = 6

Power of 2 number of bits in word.

MAP_ANON = MAP_ANONYMOUS

Anonymous memory mapping (data private to application)

MAP_ANONYMOUS = \$20

FpMMap (190) map type: Don't use a file

MAP_DENYWRITE = \$800

FpMMap (190) option: Ignored.

MAP_EXECUTABLE = \$1000

FpMMap (190) option: Ignored.

MAP_FAILED = (-1)

Memory mapping failed error code

MAP_FIXED = \$10

FpMMap (190) map type: Interpret addr exactly

MAP_GROWSDOWN = \$100

FpMMap (190) option: Memory grows downward (like a stack)

MAP_LOCKED = \$2000

FpMMap (190) option: lock the pages in memory.

MAP_NORESERVE = \$4000

FpMMap (190) option: Do not reserve swap pages for this memory.

MAP_PRIVATE = \$2

FpMMap (190) map type: Changes are private

MAP_SHARED = \$1

FpMMap (190) map type: Share changes

MAP_TYPE = \$f

FpMMap (190) map type: Bitmask for type of mapping

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

O_APPEND = \$400

fpOpen (193) file open mode: Append to file

O_CREAT = \$40

fpOpen (193) file open mode: Create if file does not yet exist.

O_DIRECT = \$4000

fpOpen (193) file open mode: Minimize caching effects

O_DIRECTORY = \$10000

fpOpen (193) file open mode: File must be directory.

O_EXCL = \$80

`fpOpen (193)` file open mode: Open exclusively

`O_LARGEFILE = $8000`

`fpOpen (193)` file open mode: Open for 64-bit I/O

`O_NDELAY = O_NONBLOCK`

`fpOpen (193)` file open mode: Alias for `O_NonBlock (138)`

`O_NOCTTY = $100`

`fpOpen (193)` file open mode: No TTY control.

`O_NOFOLLOW = $20000`

`fpOpen (193)` file open mode: Fail if file is symbolic link.

`O_NONBLOCK = $800`

`fpOpen (193)` file open mode: Open in non-blocking mode

`O_RDONLY = 0`

`fpOpen (193)` file open mode: Read only

`O_RDWR = 2`

`fpOpen (193)` file open mode: Read/Write

`O_SYNC = $1000`

`fpOpen (193)` file open mode: Write to disc at once

`O_TRUNC = $200`

`fpOpen (193)` file open mode: Truncate file to length 0

`O_WRONLY = 1`

`fpOpen (193)` file open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`POLLERR = $0008`

Error condition on output file descriptor

`POLLHUP = $0010`

Hang up

POLLIN = \$0001

Data is available for reading

POLLNVAL = \$0020

Invalid request, file descriptor not open.

POLLOUT = \$0004

Writing data will not block the write call

POLLPRI = \$0002

Urgent data is available for reading.

POLLRDBAND = \$0080

Priority data ready for reading.

POLLRDNORM = \$0040

Same as POLLIN.

POLLWRBAND = \$0200

Priority data may be written.

POLLWRNORM = \$0100

Equivalent to POLLOUT.

PRIO_PGRP = `UnixType.PRIO_PGRP`

Easy access alias for `unixtype.PRIO_PGRP` ([1880](#))

PRIO_PROCESS = `UnixType.PRIO_PROCESS`

Easy access alias for `unixtype.PRIO_PROCESS` ([1880](#))

PRIO_USER = `UnixType.PRIO_USER`

Easy access alias for `unixtype.PRIO_USER` ([1880](#))

PROT_EXEC = \$4

`FpMMap` ([190](#)) memory access: page can be executed

PROT_NONE = \$0

FpMMap (190) memory access: page can not be accessed

PROT_READ = 1

FpMMap (190) memory access: page can be read

PROT_WRITE = 2

FpMMap (190) memory access: page can be written

RLIMIT_AS = 9

RLimit request address space limit

RLIMIT_CORE = 4

RLimit request max core file size

RLIMIT_CPU = 0

RLimit request CPU time in ms

RLIMIT_DATA = 2

RLimit request max data size

RLIMIT_FSIZE = 1

RLimit request maximum filesize

RLIMIT_LOCKS = 10

RLimit request maximum file locks held

RLIMIT_MEMLOCK = 8

RLimit request max locked-in-memory address space

RLIMIT_NOFILE = 7

RLimit request max number of open files

RLIMIT_NPROC = 6

RLimit request max number of processes

RLIMIT_RSS = 5

RLimit request max resident set size

RLIMIT_STACK = 3

RLimit request max stack size

R_OK = 4

fpAccess (167) call test: read allowed

SA_INTERRUPT = \$20000000

Sigaction options: ?

SA_NOCLDSTOP = 1

Sigaction options: Do not receive notification when child processes stop

SA_NOCLDWAIT = 2

Sigaction options: ?

SA_NODEFER = \$40000000

Sigaction options: Do not mask signal in its own signal handler

SA_NOMASK = SA_NODEFER

Sigaction options: Do not prevent the signal from being received when it is handled.

SA_ONESHOT = SA_RESETHAND

Sigaction options: Restore the signal action to the default state.

SA_ONSTACK = \$08000000

SA_ONSTACK is used in the `sigaction` (205) to indicate the signal handler must be called on an alternate signal stack provided by `sigaltstack(2)`. If an alternate stack is not available, the default stack will be used.

SA_RESETHAND = \$80000000

Sigaction options: Restore signal action to default state when signal handler exits.

SA_RESTART = \$10000000

Sigaction options: Provide behaviour compatible with BSD signal semantics

SA_RESTORER = \$04000000

Signal restorer handler

SA_SIGINFO = 4

Sigaction options: The signal handler takes 3 arguments, not one.

SEEK_CUR = 1

fpLSeek (187) option: Set position relative to current position.

SEEK_END = 2

fpLSeek (187) option: Set position relative to end of file.

SEEK_SET = 0

fpLSeek (187) option: Set absolute position.

SIGABRT = 6

Signal: ABRT (Abort)

SIGALRM = 14

Signal: ALRM (Alarm clock)

SIGBUS = 7

Signal: BUS (bus error)

SIGCHLD = 17

Signal: CHLD (child status changed)

SIGCONT = 18

Signal: CONT (Continue)

SIGFPE = 8

Signal: FPE (Floating point error)

SIGHUP = 1

Signal: HUP (Hangup)

SIGILL = 4

Signal: ILL (Illegal instruction)

SIGINT = 2

Signal: INT (Interrupt)

SIGIO = 29

Signal: IO (I/O operation possible)

SIGIOT = 6

Signal: IOT (IOT trap)

SIGKILL = 9

Signal: KILL (unblockable)

SIGPIPE = 13

Signal: PIPE (Broken pipe)

SIGPOLL = SIGIO

Signal: POLL (Pollable event)

SIGPROF = 27

Signal: PROF (Profiling alarm)

SIGPWR = 30

Signal: PWR (power failure restart)

SIGQUIT = 3

Signal: QUIT

SIGSEGV = 11

Signal: SEGV (Segmentation violation)

SIGSTKFLT = 16

Signal: STKFLT (Stack Fault)

SIGSTOP = 19

Signal: STOP (Stop, unblockable)

SIGTERM = 15

Signal: TERM (Terminate)

SIGTRAP = 5

Signal: TRAP (Trace trap)

SIGTSTP = 20

Signal: TSTP (keyboard stop)

SIGTTIN = 21

Signal: TTIN (Terminal input, background)

SIGTTOU = 22

Signal: TTOU (Terminal output, background)

SIGUNUSED = 31

Signal: Unused

SIGURG = 23

Signal: URG (Socket urgent condition)

SIGUSR1 = 10

Signal: USR1 (User-defined signal 1)

SIGUSR2 = 12

Signal: USR2 (User-defined signal 2)

SIGVTALRM = 26

Signal: VTALRM (Virtual alarm clock)

SIGWINCH = 28

Signal: WINCH (Window/Terminal size change)

SIGXCPU = 24

Signal: XCPU (CPU limit exceeded)

SIGXFSZ = 25

Signal: XFSZ (File size limit exceeded)

SIG_BLOCK = 0

Sigprocmask flags: Add signals to the set of blocked signals.

SIG_DFL = 0

Signal handler: Default signal handler

SIG_ERR = -1

Signal handler: error

`SIG_IGN = 1`

Signal handler: Ignore signal

`SIG_MAXSIG = UnixType.SIG_MAXSIG`

Maximum system signal number.

`SIG_SETMASK = 2`

Sigprocmask flags: Set of blocked signals is given.

`SIG_UNBLOCK = 1`

Sigprocmask flags: Remove signals from the set set of blocked signals.

`SI_PAD_SIZE = 128 div (longint) - 3`

Signal information pad size.

`SYS_NMLN = UnixType.SYS_NMLN`

Max system name length.

`S_IFBLK = 24576`

File (#rtl.baseunix.stat (160) record) mode: Block device

`S_IFCHR = 8192`

File (#rtl.baseunix.stat (160) record) mode: Character device

`S_IFDIR = 16384`

File (#rtl.baseunix.stat (160) record) mode: Directory

`S_IFIFO = 4096`

File (#rtl.baseunix.stat (160) record) mode: FIFO

`S_IFLNK = 40960`

File (#rtl.baseunix.stat (160) record) mode: Link

`S_IFMT = 61440`

File (#rtl.baseunix.stat (160) record) mode: File type bit mask

`S_IFREG = 32768`

File (#rtl.baseunix.stat (160) record) mode: Regular file

S_IFSOCK = 49152

File (#rtl.baseunix.stat (160) record) mode: Socket

S_IRGRP = %0000100000

Mode flag: Read by group.

S_IROTH = %0000000100

Mode flag: Read by others.

S_IRUSR = %0100000000

Mode flag: Read by owner.

S_IRWXG = S_IRGRP or S_IWGRP or S_IXGRP

Mode flag: Read, write, execute by groups.

S_IRWXO = S_IROTH or S_IWOTH or S_IXOTH

Mode flag: Read, write, execute by others.

S_IRWXU = S_IRUSR or S_IWUSR or S_IXUSR

Mode flag: Read, write, execute by user.

S_IWGRP = %0000010000

Mode flag: Write by group.

S_IWOTH = %0000000010

Mode flag: Write by others.

S_IWUSR = %0010000000

Mode flag: Write by owner.

S_IXGRP = %0000001000

Mode flag: Execute by group.

S_IXOTH = %0000000001

Mode flag: Execute by others.

S_IXUSR = %0001000000

Mode flag: Execute by owner.

UTSNAME_DOMAIN_LENGTH = UTSNAME_LENGTH

Max length of `utsname` (166) domain name.

UTSNAME_LENGTH = SYS_NMLN

Max length of `utsname` (166) system name, release, version, machine.

UTSNAME_NODENAME_LENGTH = UTSNAME_LENGTH

Max length of `utsname` (166) node name.

WNOHANG = 1

`#rtl.baseunix.fpWaitpid` (218) option: Do not wait for processes to terminate.

`wordsinfdset` = `FD_MAXFDSET` div `BITSINWORD`

Number of words in a `TFDSet` (160) array

`wordsinsigset` = `SIG_MAXSIG` div `BITSINWORD`

Number of words in a signal set.

WUNTRACED = 2

`#rtl.baseunix.fpWaitpid` (218) option: Also report children which were stopped but not yet reported

W_OK = 2

`fpAccess` (167) call test: write allowed

X_OK = 1

`fpAccess` (167) call test: execute allowed

`_STAT_VER` = `_STAT_VER_LINUX`

Stat version number

`_STAT_VER_KERNEL` = 0

Current version of stat record

`_STAT_VER_LINUX` = 1

Version of Linux stat record

1.3.2 Types

`Blkcnt64_t = cuint64`

64-bit block count

`Blkcnt_t = cuint`

Block count type.

`Blksize_t = cuint`

Block size type.

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1881](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

Character offset type

`cschar = UnixType.cschar`

Signed character type

`cshort = UnixType.cshort`

C type: short signed integer (half sized)

`csigned = UnixType.csigned`

`csigned` is an alias for `cint` ([148](#)).

`csint = UnixType.csint`

Signed integer

`csize_t = UnixType.size_t`

Character size type

`cslong = UnixType.cslong`

The size is CPU dependent.

`cslonglong = UnixType.cslonglong`

`cslonglong` is an alias for `clonglong` ([149](#)).

`csshort = UnixType.csshort`

Short signed integer type

`cuchar = UnixType.cuchar`

Alias for `#rtl.UnixType.cuchar` ([1882](#))

`cuint = UnixType.cuint`

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for #rtl.unixtype.cunsigned ([1883](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
Dir = record
  dd_fd : LongInt;
  dd_loc : LongInt;
  dd_size : LongInt
;
  dd_buf : pDirent;
  dd_nextoff : Cardinal;
  dd_max : Integer
;
  dd_lock : pointer;
end
```

Record used in `fpOpenDir` ([194](#)) and `fpReadDir` ([199](#)) calls

```
Dirent = record
  d_fileno : ino64_t;
  d_off : off_t;
  d_reclen
    : cushort;
  d_type : cuchar;
  d_name : Array[0..4095-sizeof(ino64_t
    )-sizeof(off_t)-sizeof(cushort)-sizeof(cuchar)] of Char;
end
```

Record used in the `fpReadDir` (199) function to return files in a directory.

```
FLock = record
  l_type : cushort;
  l_whence : cushort;
  l_start
    : kernel_off_t;
  l_len : kernel_off_t;
  l_pid : pid_t;
end
```

Lock description type for `fpFCntl` (176) lock call.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
iovec = record
  iov_base : pointer;
  iov_len : size_t;
end
```

`iovec` is used in `freadv` (200) for IO to multiple buffers to describe a buffer location.

```
kernel_gid_t = cuint
```

`kernel_gid_t` may differ from the `libc` type used to describe group IDs.

```
kernel_loff_t = clonglong
```

Long kernel offset type

```
kernel_mode_t = cuint
```

`kernel_mode_t` may differ from the `libc` type used to describe file modes.

```
kernel_off_t = clong
```


Kernel offset type

`kernel_uid_t = cuint`

`kernel_uid_t` may differ from the `libc` type used to describe user IDs.

`mode_t = UnixType.mode_t`

Inode mode type.

`nlink_t = UnixType.nlink_t`

Number of links type.

`off_t = UnixType.off_t`

Offset type.

`PBlkCnt = ^Blkcnt_t`

pointer to `TBlkCnt` (160) type.

`PBlkSize = ^Blksize_t`

Pointer to `TBlkSize` (160) type.

`pcbool = UnixType.pcbbool`

Pointer to boolean type `cbool` (148)

`pcchar = UnixType.pcchar`

Alias for `#rtl.UnixType.pcchar` (1884)

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (148) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (148) type.

`pcint = UnixType.pcint`

Pointer to `cInt` (148) type.

`pcint16 = UnixType.pcint16`

Pointer to 16-bit signed integer type

`pcint32 = UnixType.pcint32`

Pointer to signed 32-bit integer type

```
pcint64 = UnixType.pcint64
```

Pointer to signed 64-bit integer type

```
pcint8 = UnixType.pcint8
```

Pointer to 8-bits signed integer type

```
pClock = UnixType.pClock
```

Pointer to TClock (160) type.

```
pclong = UnixType.pclong
```

Pointer to cLong (149) type.

```
pclonglong = UnixType.pclonglong
```

Pointer to longlong type.

```
pcschar = UnixType.pcschar
```

Pointer to character type cchar (149).

```
pcshort = UnixType.pcsshort
```

Pointer to cShort (149) type.

```
pcsigned = UnixType.pcsigned
```

Pointer to signed integer type csigned (149).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type csint (149)

```
pcsize_t = UnixType.psize_t
```

Pointer to csize_t

```
pcslong = UnixType.pcslong
```

Pointer of the signed long cslong (149)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type cslonglong (149)

```
pcsshort = UnixType.pcsshort
```

Pointer to short signed integer type `csshort` (149)

```
pcuchar = UnixType.pcuchar
```

Alias for `#rtl.UnixType.pcuchar` (1886)

```
pcuint = UnixType.pcuint
```

Pointer to `cUInt` (150) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to `cuLong` (150) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

```
pcunsigned = UnixType.pcunsigned
```

Alias for `#rtl.unixtype.pcunsigned` (1886)

```
pcushort = UnixType.pcushort
```

Pointer to `cuShort` (150) type.

```
pDev = UnixType.pDev
```

Pointer to `TDev` (160) type.

```
pDir = ^Dir
```

Pointer to `TDir` (160) record

```
pDirent = ^Dirent
```

Pointer to TDirent (160) record.

```
pFDSet = ^TFDSet
```

Pointer to TFDSet (160) type.

```
pFilDes = ^TFilDes
```

Pointer to TFilDes (160) type.

```
pfpstate = ^tfpstate
```

Pointer to tfpstate (161) record.

```
pGid = UnixType.pGid
```

Pointer to TGid (161) type.

```
pGrpArr = ^TGrpArr
```

Pointer to TGrpArr (161) array.

```
pid_t = UnixType.pid_t
```

Process ID type.

```
pIno = UnixType.pIno
```

Pointer to TIno (162) type.

```
piovec = ^tiovec
```

pointer to a iovec (151) record

```
pMode = UnixType.pMode
```

Pointer to TMode (162) type.

```
pnLink = UnixType.pnLink
```

Pointer to TnLink (162) type.

```
pOff = UnixType.pOff
```

Pointer to TOff (162) type.

```
pollfd = record
  fd : cint;
  events : cshort;
  revents : cshort
;
end
```

`pollfd` is used in the `fpPoll` (197) call to describe the various actions.

`pPid = UnixType.pPid`

Pointer to `TPid` (162) type.

`ppollfd = ^pollfd`

Pointer to `tpollfd`.

`PRLimit = ^TRLimit`

Pointer to `TRLimit` (162) record

`psigactionrec = ^sigactionrec`

Pointer to `SigActionRec` (158) record type.

`PSigContext = ^TSigContext`

Pointer to `#rtl.baseunix.TSigContext` (163) record type.

`psiginfo = ^tsiginfo`

Pointer to `#rtl.baseunix.TSigInfo` (165) record type.

`psigset = ^tsigset`

Pointer to `SigSet` (158) type.

`pSize = UnixType.pSize`

Pointer to `TSize` (165) type.

`pSize_t = UnixType.pSize_t`

Pointer to `Size_t`

`pSocklen = UnixType.pSocklen`

Pointer to `TSockLen` (165) type.

`psSize = UnixType.psSize`

Pointer to `TsSize` (165) type

`PStat = ^Stat`

Pointer to `TStat` (165) type.

`pstatfs = UnixType.PStatFs`

This is an alias for the type defined in the `#rtl.unixtype` (1879) unit.

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (165) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (161) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (161) type.

```
ptimezone = ^timezone
```

Pointer to TimeZone (161) record.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (161) type.

```
PTms = ^tms
```

Pointer to TTms (166) type.

```
Pucontext = ^Tucontext
```

Pointer to TUContext (166) type.

```
pUId = UnixType.pUId
```

Pointer to TUid (166) type.

```
pUtimBuf = ^UTimBuf
```

Pointer to TUTimBuf (166) type.

```
PUtsName = ^TUTsName
```

Pointer to TUnitsName (166) type.

```
rlim_t = culong
```

rlim_t is used as the type for the various fields in the TRLimit (162) record.

```
sigactionhandler = sigactionhandler_t
```

When installing a signal handler, the actual signal handler must be of type SigActionHandler.

```
sigactionhandler_t = procedure(signal: LongInt; info: psiginfo;
    context: PSigContext)
```

Standard signal action handler prototype

```
sigactionrec = record
    sa_handler : sigactionhandler_t;
    sa_flags
    : culong;
    sa_restorer : sigrestorerhandler_t;
    sa_mask : sigset_t
;
end
```

Record used in fpSigAction (205) call.

```
signalhandler = signalhandler_t
```

Simple signal handler prototype

```
signalhandler_t = procedure(signal: LongInt)
```

Standard signal handler prototype

```
sigrestorerhandler = sigrestorerhandler_t
```

Alias for sigrestorerhandler_t (158) type.

```
sigrestorerhandler_t = procedure
```

Standard signal action restorer prototype

```
sigset = sigset_t
```

Signal set type

```
sigset_t = Array[0..wordsinsigset-1] of culong
```

Signal set type

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
Stat = packed record
case Byte of
0: (
  dev : QWorddeprecated;
  __pad0 : Array[0..3] of Bytedeprecated;
  __ino : Cardinaldeprecated
  ;
  mode : Cardinaldeprecated;
  nlink : Cardinaldeprecated;
  uid
  : Cardinaldeprecated;
  gid : Cardinaldeprecated;
  rdev : QWorddeprecated
  ;
  __pad3 : Array[0..3] of Bytedeprecated;
  size : QWorddeprecated
  ;
  blksize : Cardinaldeprecated;
  blocks : QWorddeprecated;
  atime
  : Cardinaldeprecated;
  atime_nsec : Cardinaldeprecated;
  mtime
  : Cardinaldeprecated;
  mtime_nsec : Cardinaldeprecated;
  ctime
  : Cardinaldeprecated;
  ctime_nsec : Cardinaldeprecated;
  ino :
  QWorddeprecated;
);
1: (
  st_dev : QWord;
  __pad0_ : Array[0..3
] of Byte;
  __st_ino_ : Cardinal;
  st_mode : Cardinal;
  st_nlink
  : Cardinal;
  st_uid : Cardinal;
  st_gid : Cardinal;
  st_rdev
  : QWord;
```



```

__pad3_ : Array[0..3] of Byte;
st_size : QWord;
st_blksize
: Cardinal;
st_blocks : QWord;
st_atime : Cardinal;
st_atime_nsec
: Cardinal;
st_mtime : Cardinal;
st_mtime_nsec : Cardinal;
st_ctime : Cardinal;
st_ctime_nsec : Cardinal;
st_ino : QWord
;
);
end

```

Record describing an inode (file) in the FPFstat (178) call.

TBlkCnt = Blkcnt_t

Alias for Blkcnt_t (148) type.

TBlkSize = Blksize_t

Alias for blksize_t (148) type.

TClock = UnixType.TClock

Alias for clock_t (149) type.

TDev = UnixType.TDev

Alias for dev_t (150) type.

TDir = Dir

Alias for Dir (150) type.

TDirent = Dirent

Alias for Dirent (151) type.

TFDSet = Array[0..(FD_MAXFDSETdivBITSINWORD)-1] of culong

File descriptor set for fpSelect (202) call.

TFilDes = Array[0..1] of cint

Array of file descriptors as used in fpPipe (196) call.

```
tfpreg = record
  significand : Array[0..3] of Word;
  exponent :
    Word;
end
```

Record describing floating point register in signal handler.

```
tfpstate = record
  cw : Cardinal;
  sw : Cardinal;
  tag : Cardinal
  ;
  ipoff : Cardinal;
  cssel : Cardinal;
  dataoff : Cardinal;
  datasel : Cardinal;
  st : Array[0..7] of tfpreg;
  status : Cardinal
  ;
end
```

Record describing floating point unit in signal handler.

```
TGid = UnixType.TGid
```

Alias for `gid_t` (151) type.

```
TGrpArr = Array[0..0] of TGid
```

Array of `gid_t` (151) IDs

```
timespec = UnixType.timespec
```

Short time specification type.

```
timeval = UnixType.timeval
```

Time specification type.

```
timezone = record
  tz_minuteswest : cint;
  tz_dsttime : cint;
end
```

Record describing a timezone

```
time_t = UnixType.time_t
```

Time span type

`TIno = UnixType.TIno`

Alias for `ino_t` (151) type.

`TIOCtlRequest = UnixType.TIOCtlRequest`

Easy access alias for `unixtype.TIOCtlRequest` (1891)

`tiovec = iovec`

Alias for the `iovec` (151) record type.

`TMode = UnixType.TMode`

Alias for `mode_t` (152) type.

```
tms = record
  tms_utime : clock_t;
  tms_stime : clock_t;
  tms_cutime
    : clock_t;
  tms_cstime : clock_t;
end
```

Record containing timings for `fpTimes` (215) call.

`TnLink = UnixType.TnLink`

Alias for `nlink_t` (152) type.

`Toff = UnixType.TOff`

Alias for `off_t` (152) type.

`TPid = UnixType.TPid`

Alias for `pid_t` (155) type.

`tpollfd = pollfd`

Alias for `pollfd` type

```
TRLimit = record
  rlim_cur : rlim_t;
  rlim_max : rlim_t;
end
```

`TRLimit` is the structure used by the kernel to return resource limit information in.

`tsigactionhandler = sigactionhandler_t`

Alias for sigactionhandler_t (158) type.

```
tsigaltstack = record
  ss_sp : pointer;
  ss_flags : LongInt;
  ss_size
    : LongInt;
end
```

Provide the location of an alternate signal handler stack.

```
TSigContext = record
  gs : Word;
  __gsh : Word;
  fs : Word;
  __fsh
    : Word;
  es : Word;
  __esh : Word;
  ds : Word;
  __dsh : Word
;
  edi : Cardinal;
  esi : Cardinal;
  ebp : Cardinal;
  esp : Cardinal
;
  ebx : Cardinal;
  edx : Cardinal;
  ecx : Cardinal;
  eax : Cardinal
;
  trapno : Cardinal;
  err : Cardinal;
  eip : Cardinal;
  cs :
    Word;
  __csh : Word;
  eflags : Cardinal;
  esp_at_signal : Cardinal
;
  ss : Word;
  __ssh : Word;
  fpstate : pfpstate;
  oldmask : Cardinal
;
  cr2 : Cardinal;
end
```

This type is CPU dependent. Cross-platform code should not use the contents of this record.

```
tsiginfo = record
  si_signo : LongInt;
```

```
si_errno : LongInt;
si_code
: LongInt;
_sifields : record
case LongInt of
0: (
    _pad
: Array[0..(SI_PAD_SIZE)-1] of LongInt;
);
1: (
    _kill : record
_pid : pid_t;
_uid : uid_t;
end;
);
2: (
_timer : record
    _timer1 : DWord;
    _timer2 : DWord;
end;
);
3: (
_rt : record
    _pid : pid_t;
    _uid
: uid_t;
    _sigval : pointer;
end;
);
4: (
_sigchld
: record
    _pid : pid_t;
    _uid : uid_t;
    _status :
LongInt;
    _utime : clock_t;
    _stime : clock_t;
end
;
);
5: (
_sigfault : record
    _addr : pointer;
end
;
);
6: (
_sigpoll : record
    _band : LongInt;
    _fd
: LongInt;
end;
);
```

```
    end;  
end
```

This type describes the signal that occurred.

```
tsignalhandler = signalhandler_t
```

Alias for `signalhandler_t` (158) type.

```
tsigrestorerhandler = sigrestorerhandler_t
```

Alias for `sigrestorerhandler_t` (158) type.

```
tsigset = sigset_t
```

Alias for `SigSet` (158) type.

```
TSize = UnixType.TSize
```

Alias for `size_t` (159) type

```
TSocklen = UnixType.TSocklen
```

Alias for `socklen_t` (159) type.

```
TsSize = UnixType.TsSize
```

Alias for `ssize_t` (159) type

```
TStat = Stat
```

Alias for `Stat` (160) type.

```
tstatfs = UnixType.TStatFs
```

Record describing a file system in the `unix.fpstatfs` (124) call.

```
TTime = UnixType.TTime
```

Alias for `TTime` (165) type.

```
Ttimespec = UnixType.Ttimespec
```

Alias for `TimeSpec` (161) type.

```
TTimeVal = UnixType.TTimeVal
```

Alias for `timeval` (161) type.

```
TTimeZone = timezone
```

Alias for TimeZone (161) record.

```
TTms = tms
```

Alias for Tms (162) record type.

```
TUcontext = record
  uc_flags : Cardinal;
  uc_link : Pucontext;
  uc_stack : tsigaltstack;
  uc_mcontext : TSigContext;
  uc_sigmask
    : tsigset;
end
```

This structure is used to describe the user context in a program or thread. It is not used in this unit, but is provided for completeness.

```
TUId = UnixType.TUId
```

Alias for uid_t (166) type.

```
TUtimBuf = UtimBuf
```

Alias for UtimBuf (166) type.

```
TUtsName = UtsName
```

Alias for UtsName (166) type.

```
uid_t = UnixType.uid_t
```

User ID type

```
UtimBuf = record
  actime : time_t;
  modtime : time_t;
end
```

Record used in fpUtime (217) to set file access and modification times.

```
UtsName = record
  Sysname : Array[0..UTSNAME_LENGTH-1] of Char;
  Nodename : Array[0..UTSNAME_NODENAME_LENGTH-1] of Char;
  Release
    : Array[0..UTSNAME_LENGTH-1] of Char;
  Version : Array[0..UTSNAME_LENGTH
    -1] of Char;
  Machine : Array[0..UTSNAME_LENGTH-1] of Char;
  Domain
    : Array[0..UTSNAME_DOMAIN_LENGTH-1] of Charplatform;
end
```

The elements of this record are null-terminated C style strings, you cannot access them directly. Note that the Domain field is a GNU extension, and may not be available on all platforms.

1.4 Procedures and functions

1.4.1 CreateShellArgV

Synopsis: Create a null-terminated array of strings from a command-line string

Declaration: `function CreateShellArgV(const prog: string) : PPChar`
`function CreateShellArgV(const prog: Ansistring) : PPChar`

Visibility: default

Description: `CreateShellArgV` creates a command-line string for executing a shell command using 'sh -c'. The result is a null-terminated array of null-terminated strings suitable for use in `fpExecv` (174) and friends.

Errors: If no more memory is available, a heap error may occur.

See also: `fpExecv` (174), `FreeShellArgV` (219)

1.4.2 FpAccess

Synopsis: Check file access

Declaration: `function FpAccess(pathname: PChar; aMode: cint) : cint`
`function FpAccess(const pathname: RawByteString; aMode: cint) : cint`

Visibility: default

Description: `FpAccess` tests user's access rights on the specified file. Mode is a mask existing of one or more of the following:

R_OKUser has read rights.

W_OKUser has write rights.

X_OKUser has execute rights.

F_OKFile exists.

The test is done with the real user ID, instead of the effective user ID. If the user has the requested rights, zero is returned. If access is denied, or an error occurred, a nonzero value is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

sys_eaccessThe requested access is denied, either to the file or one of the directories in its path.

sys_einvalMode was incorrect.

sys_enoentA directory component in `Path` doesn't exist or is a dangling symbolic link.

sys_enotdirA directory component in `Path` is not a directory.

sys_enomemInsufficient kernel memory.

sys_eloop`Path` has a circular symbolic link.

See also: `FpChown` (170), `FpChmod` (169)

Listing: `./bunixex/ex26.pp`

Program Example26;

{ Program to demonstrate the Access function. }

Uses BaseUnix;

```
begin
  if fpAccess ( '/etc/passwd',W_OK)=0 then
    begin
      Writeln ( 'Better check your system. ');
      Writeln ( 'I can write to the /etc/passwd file ! ');
    end;
  end.

```

1.4.3 FpAlarm

Synopsis: Schedule an alarm signal to be delivered

Declaration: `function FpAlarm(seconds: cuint) : cuint`

Visibility: default

Description: `FpAlarm` schedules an alarm signal to be delivered to your process in `Seconds` seconds. When `Seconds` seconds have elapsed, the system will send a `SIGALRM` signal to the current process. If `Seconds` is zero, then no new alarm will be set. Whatever the value of `Seconds`, any previous alarm is cancelled.

The function returns the number of seconds till the previously scheduled alarm was due to be delivered, or zero if there was none. A negative value indicates an error.

See also: `fpSigAction` ([205](#)), `fpPause` ([196](#))

Listing: `./bunixex/ex59.pp`

Program Example59;

{ Program to demonstrate the Alarm function. }

Uses BaseUnix;

Procedure AlarmHandler(Sig : cint);**cdecl**;

```
begin
  Writeln ( 'Got to alarm handler ');
end;

begin
  Writeln ( 'Setting alarm handler ');
  fpSignal(SIGALRM,SignalHandler(@AlarmHandler));
  Writeln ( 'Scheduling Alarm in 10 seconds ');
  fpAlarm(10);
  Writeln ( 'Pausing ');
  fpPause;
  Writeln ( 'Pause returned ');
end.

```

1.4.4 FpChdir

Synopsis: Change current working directory.

Declaration: `function FpChdir(path: PChar) : cint`
`function FpChdir(const path: RawByteString) : cint`

Visibility: default

Description: `fpChDir` sets the current working directory to `Path`.

It returns zero if the call was succesful, -1 on error.

Note: There exist a portable alternative to `fpChDir`: `system.chdir`. Please use `fpChDir` only if you are writing Unix specific code. `System.chdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

See also: `fpGetCwd` ([180](#))

1.4.5 FpChmod

Synopsis: Change file permission bits

Declaration: `function FpChmod(path: PChar; Mode: TMode) : cint`
`function FpChmod(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpChmod` sets the `Mode` bits of the file in `Path` to `Mode`. `Mode` can be specified by 'or'-ing the following values:

S_ISUIDSet user ID on execution.

S_ISGIDSet Group ID on execution.

S_ISVTXSet sticky bit.

S_IRUSRRead by owner.

S_IWUSRWrite by owner.

S_IXUSRExecute by owner.

S_IRGRPRead by group.

S_IWGRPWrite by group.

S_IXGRPExecute by group.

S_IROTHRead by others.

S_IWOTHWrite by others.

S_IXOTHExecute by others.

S_IRWXORead, write, execute by others.

S_IRWXGRead, write, execute by groups.

S_IRWXURead, write, execute by user.

If the function is successful, zero is returned. A nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe file is on a read-only filesystem.

sys_eloop`Path` has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChown` (170), `fpAccess` (167)

Listing: `./bunixex/ex23.pp`

Program `Example23`;

{ Program to demonstrate the Chmod function. }

Uses `BaseUnix`, `Unix`;

Var `F` : `Text`;

begin

```
{ Create a file }
Assign (f, 'testex21');
Rewrite (F);
Writeln (f, '#!/bin/sh');
Writeln (f, 'echo Some text for this file');
Close (F);
fpChmod ('testex21', &777);
{ File is now executable }
fpexecl ('./testex21', []);
```

end.

1.4.6 FpChown

Synopsis: Change owner of file

Declaration: `function FpChown(path: PChar; owner: TUid; group: TGid) : cint`
`function FpChown(const path: RawByteString; owner: TUid; group: TGid)`
`: cint`

Visibility: `default`

Description: `fpChown` sets the User ID and Group ID of the file in `Path` to `Owner,Group`.

The function returns zero if the call was succesfull, a nonzero return value indicates an error.

Errors: The following error codes are returned:

sys_epermThe effective UID doesn't match the ownership of the file, and is not zero. Owner or group were not specified correctly.

sys_eaccessOne of the directories in `Path` has no search (=execute) permission.

sys_enoentA directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enomemInsufficient kernel memory.

sys_erofs The file is on a read-only filesystem.

sys_eloop Path has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

See also: `fpChmod` ([169](#)), `fpAccess` ([167](#))

Listing: `./bunixex/ex24.pp`

Program Example24;

{ Program to demonstrate the Chown function. }

Uses BaseUnix;

Var UID : TUid;
 GID : TGid;
 F : Text;

begin

```

WriteLn ('This will only work if you are root. ');
Write ('Enter a UID : '); readln(UID);
Write ('Enter a GID : '); readln(GID);
Assign (f, 'test.txt');
Rewrite (f);
WriteLn (f, 'The owner of this file should become : ');
WriteLn (f, 'UID : ', UID);
WriteLn (f, 'GID : ', GID);
Close (F);
if fpChown ('test.txt', UID, GID) <> 0 then
  if fpgeterrno = ESysEPerm then
    WriteLn ('You are not root !')
  else
    WriteLn ('Chmod failed with exit code : ', fpgeterrno)
  else
    WriteLn ('Changed owner successfully !');
end.
```

1.4.7 FpClose

Synopsis: Close file descriptor

Declaration: `function FpClose(fd: cint) : cint`

Visibility: default

Description: `FpClose` closes a file with file descriptor `Fd`. The function returns zero if the file was closed successfully, a nonzero return value indicates an error.

For an example, see `FpOpen` ([193](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

See also: `FpOpen` ([193](#)), `FpRead` ([198](#)), `FpWrite` ([219](#)), `FpFTruncate` ([179](#)), `FpLSeek` ([187](#))

1.4.8 FpClosedir

Synopsis: Close directory file descriptor

Declaration: `function FpClosedir(var dirp: Dir) : cint`

Visibility: default

Description: `FpCloseDir` closes the directory pointed to by `dirp`. It returns zero if the directory was closed successfully, -1 otherwise.

For an example, see `fpOpenDir` (194).

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpOpenDir` (194), `FpReadDir` (199)

1.4.9 FpDup

Synopsis: Duplicate a file handle

Declaration: `function FpDup(fildes: cint) : cint`
`function FpDup(var oldfile: text; var newfile: text) : cint`
`function FpDup(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: `FpDup` returns a file descriptor that is a duplicate of the file descriptor `fildes`.

The second and third forms make `NewFile` an exact copy of `OldFile`, after having flushed the buffer of `OldFile` in case it is a Text file or untyped file. Due to the buffering mechanism of Pascal, these calls do not have the same functionality as the `dup` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns a negative value in case of an error, a positive value is a file handle, and indicates succes.

Errors: A negative value can be one of the following error codes:

`sys_ebadf` `OldFile` hasn't been assigned.

`sys_emfile` Maximum number of open files for the process is reached.

See also: `fpDup2` (173)

Listing: `./bunixex/ex31.pp`

```

program Example31 ;

{ Program to demonstrate the Dup function. }

uses baseunix ;

var f : text ;

begin
  if fpdup (output,f)=-1 then
    Writeln ('Dup Failed !');
    writeln ('This is written to stdout.');
```

```

    writeln (f, 'This is written to the dup file , and flushed');flush(f);
    writeln
end.

```

1.4.10 FpDup2

Synopsis: Duplicate one filehandle to another

Declaration: `function FpDup2(fildes: cint; fildes2: cint) : cint`
`function FpDup2(var oldfile: text; var newfile: text) : cint`
`function FpDup2(var oldfile: File; var newfile: File) : cint`

Visibility: default

Description: Makes `fildes2` or `NewFile` an exact copy of `fildes` or `OldFile`, after having flushed the buffer of `OldFile` in the case of text or untyped files.

After a call to `fdup2`, the 2 file descriptors point to the same physical device (a file, socket, or a terminal).

`NewFile` can be an assigned file. If `newfile` or `fildes` was open, it is closed first. Due to the buffering mechanism of Pascal, this has not the same functionality as the `dup2` call in C. The internal Pascal buffers are not the same after this call, but when the buffers are flushed (e.g. after output), the output is sent to the same file. Doing an `lseek` will, however, work as in C, i.e. doing a `lseek` will change the fileposition in both files.

The function returns the new file descriptor number, on error -1 is returned, and the error can be retrieved with `fpgeterrno` ([181](#))

Errors: In case of error, the following error codes can be reported:

`sys_ebadfOldFile` (or `fildes`) hasn't been assigned.

`sys_emfile`Maximum number of open files for the process is reached.

See also: `fpDup` ([172](#))

Listing: `./bunixex/ex32.pp`

```

program Example32;

{ Program to demonstrate the FpDup2 function. }

uses BaseUnix;

var f : text;
    i : longint;

begin
    Assign (f, 'text.txt');
    Rewrite (F);
    For i:=1 to 10 do writeln (F, 'Line : ',i);
    if fpdup2 (output,f)=-1 then
        Writeln ('Dup2 Failed !');
    writeln ('This is written to stdout. ');
    writeln (f, 'This is written to the dup file , and flushed');
    flush(f);
    writeln;
    { Remove file. Comment this if you want to check flushing.}

```

```
    fpUnlink ( 'text.txt' );
end.
```

1.4.11 FpExecv

Synopsis: Execute process

Declaration: `function FpExecv(path: PChar; argv: PPChar) : cint`
`function FpExecv(const path: RawByteString; argv: PPChar) : cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, `execv` does not return.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` ([181](#))

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eLOOPThe path contains a circular reference (via symlinks).

See also: `fpExecve` ([175](#)), `fpFork` ([178](#))

Listing: `./bunixex/ex8.pp`

Program Example8;

{ Program to demonstrate the Execv function. }

Uses Unix, strings;

Const Arg0 : PChar = '/bin/ls';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

```
  GetMem (PP, 3*SizeOf(Pchar));
  PP[0] := Arg0;
  PP[1] := Arg1;
  PP[3] := Nil;
  { Execute '/bin/ls -l', with current environment }
  fpExecv ('/bin/ls', pp);
```

end.

1.4.12 FpExecve

Synopsis: Execute process using environment

Declaration: `function FpExecve(path: PChar; argv: PPChar; envp: PPChar) : cint`
`function FpExecve(const path: RawByteString; argv: PPChar; envp: PPChar)`
`: cint`

Visibility: default

Description: Replaces the currently running program with the program, specified in `path`. It gives the program the options in `argv`, and the environment in `envp`. They are pointers to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. On success, `execve` does not return.

Errors: Extended error information can be retrieved with `fpGetErrno` (181), and includes the following:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted `\textit{noexec}`.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `fpExecv` (174), `fpFork` (178)

Listing: `./bunixex/ex7.pp`

Program Example7;

{ Program to demonstrate the Execve function. }

Uses BaseUnix, strings;

Const Arg0 : PChar = '/bin/lS';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3*SizeOf(Pchar));
 PP[0]:=Arg0;
 PP[1]:=Arg1;
 PP[3]:=Nil;
{ Execute '/bin/lS -l', with current environment }
{ Env is defined in system.inc }
 fpExecVe ('/bin/lS',pp,envp);

end.

1.4.13 FpExit

Synopsis: Exit the current process

Declaration: `procedure FpExit (Status: cint)`

Visibility: default

Description: `FpExit` exits the currently running process, and report `Status` as the exit status.

Remark: If this call is executed, the normal unit finalization code will not be executed. This may lead to unexpected errors and stray files on your system. It is therefore recommended to use the `Halt` call instead.

Errors: None.

See also: `FpFork` ([178](#)), `FpExecve` ([175](#))

1.4.14 FpFcntl

Synopsis: File control operations.

Declaration: `function FpFcntl(fildes: cint; cmd: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; arg: cint) : cint`
`function FpFcntl(fildes: cint; cmd: cint; var arg: FLock) : cint`

Visibility: default

Description: Read/set a file's attributes. `Fildes` a valid file descriptor. `Cmd` specifies what to do, and is one of the following:

F_GetFdRead the `close_on_exec` flag. If the low-order bit is 0, then the file will remain open across `execve` calls.

F_GetFlRead the descriptor's flags.

F_GetOwnGet the Process ID of the owner of a socket.

F_SetFdSet the `close_on_exec` flag of `fildes`. (only the least significant bit is used).

F_GetLkReturn the `flock` record that prevents this process from obtaining the lock, or set the `l_type` field of the lock of there is no obstruction. `Arg` is the `flock` record.

F_SetLkSet the lock or clear it (depending on `l_type` in the `flock` structure). if the lock is held by another process, an error occurs.

F_GetLkwSame as for **F_Setlk**, but wait until the lock is released.

F_SetOwnSet the Process or process group that owns a socket.

The function returns 0 if successful, -1 otherwise.

Errors: On error, -1 is returned. Use `fpGetErrno` ([181](#)) for extended error information.

sys_ebadf`Fd` has a bad file descriptor.

sys_eagain or sys_eaccessFor `\textbf{F_SetLk}`, if the lock is held by another process.

1.4.15 fpfdfillset

Synopsis: Set all filedescriptors in the set.

Declaration: `function fpfdfillset(var nset: TFDSet) : cint`

Visibility: default

Description: `fpfdfillset` sets all filedescriptors in `nset`.

See also: `FpSelect` (202), `FpFD_ZERO` (178), `FpFD_IsSet` (177), `FpFD_Clr` (177), `FpFD_Set` (177)

1.4.16 fpFD_CLR

Synopsis: Clears a filedescriptor in a set

Declaration: `function fpFD_CLR(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Clr` clears file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (202).

Errors: None.

See also: `FpSelect` (202), `FpFD_ZERO` (178), `FpFD_Set` (177), `FpFD_IsSet` (177)

1.4.17 fpFD_ISSET

Synopsis: Check whether a filedescriptor is set

Declaration: `function fpFD_ISSET(fdno: cint; const nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` Checks whether file descriptor `fdNo` in filedescriptor set `fds` is set. It returns zero if the descriptor is not set, 1 if it is set. If the number of the filedescriptor it wrong, -1 is returned.

For an example, see `FpSelect` (202).

Errors: If an invalid file descriptor number is passed, -1 is returned.

See also: `FpSelect` (202), `FpFD_ZERO` (178), `FpFD_Clr` (177), `FpFD_Set` (177)

1.4.18 fpFD_SET

Synopsis: Set a filedescriptor in a set

Declaration: `function fpFD_SET(fdno: cint; var nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_Set` sets file descriptor `fdno` in filedescriptor set `nset`.

For an example, see `FpSelect` (202).

Errors: None.

See also: `FpSelect` (202), `FpFD_ZERO` (178), `FpFD_Clr` (177), `FpFD_IsSet` (177)

1.4.19 fpFD_ZERO

Synopsis: Clear all file descriptors in set

Declaration: `function fpFD_ZERO(out nset: TFDSet) : cint`

Visibility: default

Description: `FpFD_ZERO` clears all the filedescriptors in the file descriptor set `nset`.

For an example, see `FpSelect` (202).

Errors: None.

See also: `FpSelect` (202), `FpFD_Clr` (177), `FpFD_Set` (177), `FpFD_IsSet` (177)

1.4.20 FpFork

Synopsis: Create child process

Declaration: `function FpFork : TPid`

Visibility: default

Description: `FpFork` creates a child process which is a copy of the parent process. `FpFork` returns the process ID in the parent process, and zero in the child's process. (you can get the parent's PID with `fpGetPPid` (183)).

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagainNot enough memory to create child process.

See also: `fpExecve` (175), `#rtl.linux.Clone` (890)

1.4.21 FPFStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpFStat(fd: cint; var sb: Stat) : cint`
`function FPFStat(var F: Text; var Info: Stat) : Boolean`
`function FPFStat(var F: File; var Info: Stat) : Boolean`

Visibility: default

Description: `FpFStat` gets information about the file specified in one of the following:

Fda valid file descriptor.

Fan opened text file or untyped file.

and stores it in `Info`, which is of type `stat` (160). The function returns zero if the call was succesfull, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

sys_enoent`Path` does not exist.

See also: `FpStat` (210), `FpLStat` (188)

Listing: `./bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
    { Make a file }
    assign (f, 'test.fil');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil', info) <= 0 then
        begin
            writeln ('Fstat failed. Errno : ', fpgeterrno);
            halt (1);
        end;
    writeln;
    writeln ('Result of fstat on file ''test.fil''.');
    writeln ('Inode   : ', info.st_ino);
    writeln ('Mode    : ', info.st_mode);
    writeln ('nlink   : ', info.st_nlink);
    writeln ('uid     : ', info.st_uid);
    writeln ('gid     : ', info.st_gid);
    writeln ('rdev    : ', info.st_rdev);
    writeln ('Size    : ', info.st_size);
    writeln ('Blksize : ', info.st_blksize);
    writeln ('Blocks  : ', info.st_blocks);
    writeln ('atime   : ', info.st_atime);
    writeln ('mtime   : ', info.st_mtime);
    writeln ('ctime   : ', info.st_ctime);
    { Remove file }
    erase (f);
end.

```

1.4.22 FpFtruncate

Synopsis: Truncate file on certain size.

Declaration: `function FpFtruncate(fd: cint; flength: TOff) : cint`

Visibility: default

Description: `FpFtruncate` sets the length of a file in `fd` on `flength` bytes, where `flength` must be less than or equal to the current length of the file in `fd`.

The function returns zero if the call was successful, a nonzero return value indicates that an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

See also: `FpOpen` ([193](#)), `FpClose` ([171](#)), `FpRead` ([198](#)), `FpWrite` ([219](#)), `FpLSeek` ([187](#))

1.4.23 FpGetcwd

Synopsis: Retrieve the current working directory.

Declaration: `function FpGetcwd(path: PChar; siz: TSize) : PChar`
`function FpGetcwd : RawByteString`

Visibility: default

Description: `fpgetCWD` returns the current working directory of the running process. It is returned in `Path`, which points to a memory location of at least `siz` bytes.

If the function is succesful, a pointer to `Path` is returned, or a string with the result. On error `Nil` or an empty string are returned.

Errors: On error `Nil` or an empty string are returned.

See also: `FpGetPID` ([183](#)), `FpGetUID` ([185](#))

1.4.24 FpGetegid

Synopsis: Return effective group ID

Declaration: `function FpGetegid : TGid`

Visibility: default

Description: `FpGetegid` returns the effective group ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([182](#)), `FpGetUid` ([185](#)), `FpGetEUid` ([181](#)), `FpGetPid` ([183](#)), `FpGetPPid` ([183](#)), `fpSetUID` ([205](#)), `FpSetGid` ([203](#))

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid);`
end.

1.4.25 FpGetEnv

Synopsis: Return value of environment variable.

Declaration: `function FpGetEnv(name: PChar) : PChar`
`function FpGetEnv(name: string) : PChar`

Visibility: default

Description: `FPGetEnv` returns the value of the environment variable in `Name`. If the variable is not defined, `nil` is returned. The value of the environment variable may be the empty string. A `PChar` is returned to accomodate for strings longer than 255 bytes, `TERMCAP` and `LS_COLORS`, for instance.

Errors: None.

Listing: ./bunixex/ex41.pp

```

Program Example41 ;

{ Program to demonstrate the GetEnv function. }

Uses BaseUnix ;

begin
  WriteLn ( 'Path is : ', fpGetenv ( 'PATH' ) );
end.

```

1.4.26 fpgeterrno

Synopsis: Retrieve extended error information.

Declaration: `function fpgeterrno : LongInt`

Visibility: default

Description: `fpgeterrno` returns extended information on the latest error. It is set by all functions that communicate with the kernel or C library.

Errors: None.

See also: `fpseterrno` ([203](#))

1.4.27 FpGeteuid

Synopsis: Return effective user ID

Declaration: `function FpGeteuid : TUid`

Visibility: default

Description: `FpGeteuid` returns the effective user ID of the currently running process.

Errors: None.

See also: `FpGetUid` ([185](#)), `FpGetGid` ([182](#)), `FpGetEGid` ([180](#)), `FpGetPid` ([183](#)), `FpGetPPid` ([183](#)), `fpSetUID` ([205](#)), `FpSetGid` ([203](#))

Listing: ./bunixex/ex17.pp

```

Program Example17 ;

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses BaseUnix ;

begin
  writeLn ( 'User Id = ', fpgetuid, ' Effective user Id = ', fpgeteuid );
end.

```

1.4.28 FpGetgid

Synopsis: Return real group ID

Declaration: `function FpGetgid : TGid`

Visibility: default

Description: `FpGetgid` returns the real group ID of the currently running process.

Errors: None.

See also: `FpGetEGid` (180), `FpGetUid` (185), `FpGetEUid` (181), `FpGetPid` (183), `FpGetPPid` (183), `fpSetUID` (205), `FpSetGid` (203)

Listing: `./bunixex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the GetGid and GetEGid functions. }

Uses `BaseUnix;`

begin

`writeln ('Group Id = ',fpgetgid , ' Effective group Id = ',fpgetegid);`
end.

1.4.29 FpGetgroups

Synopsis: Get the list of supplementary groups.

Declaration: `function FpGetgroups(gidsetsize: cint; var grouplist: TGrpArr) : cint`

Visibility: default

Description: `FpGetgroups` returns up to `gidsetsize` groups in `GroupList`

If the function is successful, then number of groups that were stored is returned. On error, -1 is returned.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (181)

See also: `FpGetpgrp` (182), `FpGetGID` (182), `FpGetEGID` (180)

1.4.30 FpGetpgrp

Synopsis: Get process group ID

Declaration: `function FpGetpgrp : TPid`

Visibility: default

Description: `FpGetpgrp` returns the process group ID of the current process.

Errors: None.

See also: `fpGetPID` (183), `fpGetPPID` (183), `FpGetGID` (182), `FpGetUID` (185)

1.4.31 FpGetpid

Synopsis: Return current process ID

Declaration: `function FpGetpid : TPid`

Visibility: default

Description: `FpGetpid` returns the process ID of the currently running process.

Note: There exist a portable alternative to `fpGetpid`: `system.GetProcessID`. Please use `fpGetpid` only if you are writing Unix specific code. `System.GetProcessID` will work on all operating systems.

Errors: None.

See also: `FpGetPPid` ([183](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.32 FpGetppid

Synopsis: Return parent process ID

Declaration: `function FpGetppid : TPid`

Visibility: default

Description: `FpGetppid` returns the Process ID of the parent process.

Errors: None.

See also: `FpGetPid` ([183](#))

Listing: `./bunixex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the GetPid, GetPPid function. }

Uses `BaseUnix;`

begin

`WriteLn ('Process Id = ',fpgetpid , ' Parent process Id = ',fpgetppid);`
end.

1.4.33 fpGetPriority

Synopsis: Return process priority

Declaration: `function fpGetPriority(Which: cint; Who: cint) : cint`

Visibility: default

Description: GetPriority returns the priority with which a process is running. Which process(es) is determined by the Which and Who variables. Which can be one of the pre-defined Prio_Process, Prio_PGrp, Prio_User, in which case Who is the process ID, Process group ID or User ID, respectively.

For an example, see FpNice (193).

Errors: Error information is returned solely by the FpGetErrno (181) function: a priority can be a positive or negative value.

sys_esrchNo process found using which and who.

sys_einvalWhich was not one of Prio_Process, Prio_Grp or Prio_User.

See also: FpSetPriority (204), FpNice (193)

1.4.34 FpGetRLimit

Synopsis: Get process resource limits

Declaration: `function FpGetRLimit(resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: FpGetRLimit gets the resource limits for the current process: resource determines the resource of which the kernel should return the limits (one of the many RLIMIT_* constants). rlim should point to a TRLimit (162) record and on success will contain the resource limits.

The function returns zero if the resource limits were correctly returned.

Errors: On error, -1 is returned and fpgeterrno (181) can be used to retrieve the error code.

See also: FpSetRLimit (204)

1.4.35 FpGetsid

Synopsis: Get current session ID

Declaration: `function FpGetsid(pid: TPid) : TPid`

Visibility: default

Description: FpGetsid returns the session ID of the process pid. The return value is the session ID of the process. (it equals the PID of the session leader). The process pid must be in the same session as the current process.

Errors: On error, -1 is returned, and extended error information can be obtained with fpGetErrno.

See also: FpGetpgid (182), FpGetpid (183), FpGetPpid (183)

1.4.36 FpGetuid

Synopsis: Return current user ID

Declaration: `function FpGetuid : TUid`

Visibility: default

Description: `FpGetuid` returns the real user ID of the currently running process.

Errors: None.

See also: `FpGetGid` ([182](#)), `FpGetEUid` ([181](#)), `FpGetEGid` ([180](#)), `FpGetPid` ([183](#)), `FpGetPPid` ([183](#)), `fpSetUID` ([205](#))

Listing: `./bunixex/ex17.pp`

Program `Example17;`

{ Program to demonstrate the GetUid and GetEUid functions. }

Uses `BaseUnix;`

begin

`writeln ('User Id = ',fpgetuid, ' Effective user Id = ',fpgeteuid);`
end.

1.4.37 FpIOctl

Synopsis: General kernel IOCTL call.

Declaration: `function FpIOctl(Handle: cint; Ndx: TIOctlRequest; Data: Pointer) : cint`

Visibility: default

Description: This is a general interface to the Unix/ Linux `ioctl` call. It performs various operations on the filedescriptor `Handle`. `Ndx` describes the operation to perform. `Data` points to data needed for the `Ndx` function. The structure of this data is function-dependent, so we don't elaborate on this here. For more information on this, see various manual pages under Linux.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

Listing: `./bunixex/ex54.pp`

Program `Example54;`

uses `BaseUnix, Termio;`

{ Program to demonstrate the IOCtl function. }

var

`tios : Termios;`

begin

`{$ifdef FreeBSD}`

`fpIOctl(1,TIOCGETA,@tios); // these constants are very OS dependant.`

`// see the tcgetattr example for a better way`

`{$endif}`

`WriteLn('Input Flags : $',hexstr(tios.c_iflag,8));`

```

WriteLn('Output Flags : $',hexstr(tios.c_oflag,8));
WriteLn('Line Flags   : $',hexstr(tios.c_lflag,8));
WriteLn('Control Flags: $',hexstr(tios.c_cflag,8));
end.

```

1.4.38 FpKill

Synopsis: Send a signal to a process

Declaration: `function FpKill(pid: TPid; sig: cint) : cint`

Visibility: default

Description: `fpKill` sends a signal `Sig` to a process or process group. If `Pid`>0 then the signal is sent to `Pid`, if it equals -1, then the signal is sent to all processes except process 1. If `Pid`<-1 then the signal is sent to process group -`Pid`.

The return value is zero, except in case three, where the return value is the number of processes to which the signal was sent.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)):

sys_einvalAn invalid signal is sent.

sys_esrchThe `Pid` or process group don't exist.

sys_epermThe effective userid of the current process doesn't math the one of process `Pid`.

See also: `FpSigAction` ([205](#)), `FpSignal` ([208](#))

1.4.39 FpLink

Synopsis: Create a hard link to a file

Declaration: `function FpLink(existing: PChar; newone: PChar) : cint`
`function FpLink(const existing: RawByteString;`
`const newone: RawByteString) : cint`

Visibility: default

Description: `fpLink` makes `NewOne` point to the same file als `Existing`. The two files then have the same inode number. This is known as a 'hard' link. The function returns zero if the call was succesfull, and returns a non-zero value if the call failed.

Errors: The following error codes are returned:

sys_exdev`Existing` and `NewOne` are not on the same filesystem.

sys_epermThe filesystem containing `Existing` and `NewOne` doesn't support linking files.

sys_eaccessWrite access for the directory containing `NewOne` is disallowed, or one of the directories in `Existing` or `NewOne` has no search (=execute) permission.

sys_enoentA directory entry in `Existing` or `NewOne` does not exist or is a symbolic link pointing to a non-existent directory.

sys_enotdirA directory entry in `Existing` or `NewOne` is nor a directory.

sys_enomemInsufficient kernel memory.

sys_erofsThe files are on a read-only filesystem.

sys_eexist NewOne already exists.

sys_emlink Existing has reached maximal link count.

sys_eloop existing or NewOne has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.

sys_enospc The device containing NewOne has no room for another entry.

sys_eperm Existing points to . or .. of a directory.

See also: [fpSymLink \(211\)](#), [fpUnLink \(216\)](#)

Listing: ./bunixex/ex21.pp

Program Example21;

{ Program to demonstrate the Link and UnLink functions. }

Uses BaseUnix;

Var F : Text;

 S : **String**;

begin

 Assign (F, 'test.txt');

Rewrite (F);

Writeln (F, 'This is written to test.txt');

 Close(f);

{ new.txt and test.txt are now the same file }

if fpLink ('test.txt', 'new.txt') <> 0 **then**

writeln ('Error when linking !');

{ Removing test.txt still leaves new.txt }

If fpUnlink ('test.txt') <> 0 **then**

Writeln ('Error when unlinking !');

 Assign (f, 'new.txt');

Reset (F);

While not EOF(f) **do**

begin

Readln(F,S);

Writeln ('> ',s);

end;

 Close (f);

{ Remove new.txt also }

If not FPUntlink ('new.txt') <> 0 **then**

Writeln ('Error when unlinking !');

end.

1.4.40 FpLseek

Synopsis: Set file pointer position.

Declaration: function FpLseek(fd: cint; offset: TOff; whence: cint) : TOff

Visibility: default

Description: FpLseek sets the current fileposition of file fd to Offset, starting from Whence, which can be one of the following:

Seek_SetOffset is the absolute position in the file.

Seek_CurOffset is relative to the current position.

Seek_endOffset is relative to the end of the file.

The function returns the new fileposition, or -1 if an error occurred.

For an example, see `FpOpen` (193).

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpOpen` (193), `FpWrite` (219), `FpClose` (171), `FpRead` (198), `FpFTruncate` (179)

1.4.41 `fpLstat`

Synopsis: Return information about symbolic link. Do not follow the link

Declaration: `function fpLstat(path: PChar; Info: PStat) : cint`
`function fpLstat(const path: RawByteString; Info: PStat) : cint`
`function fpLstat(path: PChar; var Info: Stat) : cint`
`function fpLstat(const Filename: RawByteString; var Info: Stat) : cint`

Visibility: default

Description: `FpLstat` gets information about the link specified in `Path` (or `FileName`, and stores it in `Info`, which points to a record of type `TStat`. Contrary to `FpFstat` (178), it stores information about the link, not about the file the link points to. The function returns zero if the call was succesful, a nonzero return value indicates failure. failed.

Errors: Extended error information is returned by the `FpGetErrno` (181) function.

`sys_enoentPath` does not exist.

See also: `FpFStat` (178), `#rtl.unixtype.TStatFS` (1892)

Listing: `./unixex/ex29.pp`

```

program example29;

  { Program to demonstrate the LStat function. }

  uses BaseUnix, Unix;

  var f : text;
      i : byte;
      info : stat;

  begin
    { Make a file }
    assign (f, 'test.fil ');
    rewrite (f);
    for i:=1 to 10 do writeln (f, 'Testline # ', i);
    close (f);
    { Do the call on made file. }
    if fpstat ('test.fil ', info) <> 0 then
      begin
        writeln ('Fstat failed. Errno : ', fpgeterrno);
        halt (1);
      end;
    writeln;
  
```

```

writeln ('Result of stat on file ''test.fil''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);

If fpSymLink ('test.fil','test.lnk')<>0 then
  writeln ('Link failed ! Errno : ',fpgeterrno);

if fplstat ('test.lnk',@info)<>0 then
  begin
    writeln('LStat failed. Errno : ',fpgeterrno);
    halt (1);
  end;
writeln;
writeln ('Result of fstat on file ''test.lnk''.');
writeln ('Inode   : ',info.st_ino);
writeln ('Mode    : ',info.st_mode);
writeln ('nlink   : ',info.st_nlink);
writeln ('uid     : ',info.st_uid);
writeln ('gid     : ',info.st_gid);
writeln ('rdev    : ',info.st_rdev);
writeln ('Size    : ',info.st_size);
writeln ('Blksize  : ',info.st_blksize);
writeln ('Blocks  : ',info.st_blocks);
writeln ('atime   : ',info.st_atime);
writeln ('mtime   : ',info.st_mtime);
writeln ('ctime   : ',info.st_ctime);
{ Remove file and link }
erase (f);
fpunlink ('test.lnk');
end.

```

1.4.42 FpMkdir

Synopsis: Create a new directory

Declaration: `function FpMkdir(path: PChar; Mode: TMode) : cint`
`function FpMkdir(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `FpMkDir` creates a new directory `Path`, and sets the new directory's mode to `Mode`. `Path` can be an absolute path or a relative path. Note that only the last element of the directory will be created, higher level directories must already exist, and must be writeable by the current user.

On succes, 0 is returned. if the function fails, -1 is returned.

Note: There exist a portable alternative to `fpMkDir`: `system.mkdir`. Please use `fpMkDir` only if you are writing Unix specific code. `System.mkdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `fpGetCWD` (180), `fpChDir` (169)

1.4.43 FpMkfifo

Synopsis: Create FIFO (named pipe) in file system

Declaration: `function FpMkfifo(path: PChar; Mode: TMode) : cint`
`function FpMkfifo(const path: RawByteString; Mode: TMode) : cint`

Visibility: default

Description: `fpMkFifo` creates named a named pipe in the filesystem, with name `Path` and mode `Mode`.

The function returns zero if the command was succesful, and nonzero if it failed.

Errors: The error codes include:

sys_enfileToo many file descriptors for this process.

sys_enfileThe system file table is full.

1.4.44 Fpmmmap

Synopsis: Create memory map of a file

Declaration: `function Fpmmmap(start: pointer; len: size_t; prot: cint; flags: cint; fd: cint; offst: off_t) : pointer`

Visibility: default

Description: `FpMMap` maps or unmaps files or devices into memory. The different arguments determine what and how the file is mapped:

adrAddress where to mmap the device. This address is a hint, and may not be followed.

lenSize (in bytes) of area to be mapped.

protProtection of mapped memory. This is a OR-ed combination of the following constants:

PROT_EXECThe memory can be executed.

PROT_READThe memory can be read.

PROT_WRITEThe memory can be written.

PROT_NONEThe memory can not be accessed.

flagsContains some options for the mmap call. It is an OR-ed combination of the following constants:

MAP_FIXEDDo not map at another address than the given address. If the address cannot be used, `MMap` will fail.

MAP_SHAREDShare this map with other processes that map this object.

MAP_PRIVATECreate a private map with copy-on-write semantics.

MAP_ANONYMOUS`fd` does not have to be a file descriptor.

One of the options `MAP_SHARED` and `MAP_PRIVATE` must be present, but not both at the same time.

fdFile descriptor from which to map.

offOffset to be used in file descriptor `fd`.

The function returns a pointer to the mapped memory, or a -1 in case of en error.

Errors: On error, -1 is returned and extended error information is returned by the FpGetErrno (181) function.

Sys_EBADFfd is not a valid file descriptor and MAP_ANONYMOUS was not specified.

Sys_EACCESSMAP_PRIVATE was specified, but fd is not open for reading. Or MAP_SHARED was asked and PROT_WRITE is set, fd is not open for writing

Sys_EINVALOne of the record fields Start, length or offset is invalid.

Sys_ETXTBUSYMAP_DENYWRITE was set but the object specified by fd is open for writing.

Sys_EAGAINfd is locked, or too much memory is locked.

Sys_ENOMEMNot enough memory for this operation.

See also: FpMUnMap (191)

Listing: ./unixex/ex66.pp

Program Example66;

{ Program to demonstrate the MMap function. }

Uses BaseUnix, Unix;

Var S : String;
 fd : cint;
 Len : longint;
 // args : tmmargs;
 P : PChar;

begin

 s:= 'This is the string';
 Len:=Length(S);
 fd:=fpOpen('testfile.txt',O_wrOnly or o_creat);
 If fd=-1 **then**
 Halt(1);
 If fpWrite(fd,S[1],Len)=-1 **then**
 Halt(2);
 fpClose(fd);
 fd:=fpOpen('testfile.txt',O_rdOnly);
 if fd=-1 **then**
 Halt(3);
 P:=Pchar(fpmmmap(nil, len+1, PROT_READ or PROT_WRITE, MAP_PRIVATE, fd, 0));

If longint(P)=-1 **then**
 Halt(4);
 Writeln('Read in memory :',P);
 fpclose(fd);
 if fpMUnMap(P, Len)<>0 **Then**
 Halt(fpgeterrno);

end.

1.4.45 Fpmunmap

Synopsis: Unmap previously mapped memory block

Declaration: function Fpmunmap(start: pointer; len: size_t) : cint

Visibility: default

Description: `FpMUnMap` unmaps the memory block of size `Len`, pointed to by `Adr`, which was previously allocated with `FpMMap` (190).

The function returns `True` if successful, `False` otherwise.

For an example, see `FpMMap` (190).

Errors: In case of error the function returns a nonzero value, extended error information is returned by the `FpGetErrno` (181) function. See `FpMMap` (190) for possible error values.

See also: `FpMMap` (190)

1.4.46 FpNanoSleep

Synopsis: Suspend process for a short time

Declaration: `function FpNanoSleep(req: ptimespec; rem: ptimespec) : cint`

Visibility: `default`

Description: `FpNanoSleep` suspends the process till a time period as specified in `req` has passed. Then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and `rem` will contain the remaining time till the end of the intended period. In this case the return value will be -1, and `ErrNo` will be set to `EINTR`.

If the function returns without error, the return value is zero.

Errors: If an error occurred or the call was interrupted, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpPause` (196), `FpAlarm` (168)

Listing: `./bunixex/ex72.pp`

```

program example72;

{ Program to demonstrate the NanoSleep function. }

uses BaseUnix;

Var
  Req, Rem : TimeSpec;
  Res : Longint;

begin
  With Req do
    begin
      tv_sec:=10;
      tv_nsec:=100;
    end;
  Write( 'NanoSleep returned : ');
  Flush( Output );
  Res:=( fpNanoSleep (@Req,@rem) );
  WriteLn( res );
  If ( res<>0) then
    With rem do
      begin
        WriteLn( 'Remaining seconds      : ',tv_sec );
        WriteLn( 'Remaining nanoseconds : ',tv_nsec );
      end;
end.
```

1.4.47 fpNice

Synopsis: Set process priority

Declaration: `function fpNice(N: cint) : cint`

Visibility: default

Description: `Nice` adds `-N` to the priority of the running process. The lower the priority numerically, the less the process is favored. Only the superuser can specify a negative `N`, i.e. increase the rate at which the process is run.

If the function is successful, zero is returned. On error, a nonzero value is returned.

Errors: Extended error information is returned by the `FpGetErrno` (181) function.

`sys_epermA` non-superuser tried to specify a negative `N`, i.e. do a priority increase.

See also: `FpGetPriority` (184), `FpSetPriority` (204)

Listing: `./unixex/ex15.pp`

Program Example15;

{ Program to demonstrate the Nice and Get/SetPriority functions. }

Uses BaseUnix, Unix;

begin

```

  writeln ('Setting priority to 5');
  fpsetpriority (prio_process, fpgetpid, 5);
  writeln ('New priority = ', fpgetpriority (prio_process, fpgetpid));
  writeln ('Doing nice 10');
  fpnice (10);
  writeln ('New Priority = ', fpgetpriority (prio_process, fpgetpid));
end.
```

1.4.48 FpOpen

Synopsis: Open file and return file descriptor

```

Declaration: function FpOpen(path: PChar; flags: cint; Mode: TMode) : cint
function FpOpen(path: PChar; flags: cint) : cint
function FpOpen(const path: RawByteString; flags: cint) : cint
function FpOpen(const path: RawByteString; flags: cint; Mode: TMode)
      : cint
function FpOpen(path: ShortString; flags: cint) : cint
function FpOpen(path: ShortString; flags: cint; Mode: TMode) : cint
```

Visibility: default

Description: `FpOpen` opens a file in `Path` with flags `flags` and mode `Mode` One of the following:

O_RdOnlyFile is opened Read-only

O_WrOnlyFile is opened Write-only

O_RdWrFile is opened Read-Write

The flags may be OR-ed with one of the following constants:

O_CreatFile is created if it doesn't exist.

O_ExclIf the file is opened with **O_Creat** and it already exists, the call will fail.

O_NoCttyIf the file is a terminal device, it will NOT become the process' controlling terminal.

O_TruncIf the file exists, it will be truncated.

O_Appendthe file is opened in append mode. *Before each write*, the file pointer is positioned at the end of the file.

O_NonBlockThe file is opened in non-blocking mode. No operation on the file descriptor will cause the calling process to wait till.

O_NDelayIdem as **O_NonBlock**

O_SyncThe file is opened for synchronous IO. Any write operation on the file will not return until the data is physically written to disk.

O_NoFollowif the file is a symbolic link, the open fails. (Linux 2.1.126 and higher only)

O_Directoryif the file is not a directory, the open fails. (Linux 2.1.126 and higher only)

Path can be of type **PChar** or **String**. The optional mode argument specifies the permissions to set when opening the file. This is modified by the umask setting. The real permissions are Mode and not umask. The return value of the function is the filedescriptor, or a negative value if there was an error.

Errors: Extended error information can be retrieved using **fpGetErrno** ([181](#)).

See also: **FpClose** ([171](#)), **FpRead** ([198](#)), **FpWrite** ([219](#)), **FpFTruncate** ([179](#)), **FpLSeek** ([187](#))

Listing: ./bunixex/ex19.pp

Program Example19;

{ Program to demonstrate the fdOpen, fdwrite and fdCLose functions. }

Uses BaseUnix;

Const Line : **String**[80] = 'This is easy writing !';

Var FD : **Cint**;

begin

FD:=fpOpen ('Test.dat',O_WrOnly or O_Creat);

if FD>0 then

begin

if length(Line)<>fpwrite (FD,Line[1],Length(Line)) then

Writeln ('Error when writing to file !');

fpClose(FD);

end;

end.

1.4.49 FpOpendir

Synopsis: Open a directory for reading

Declaration: function FpOpendir(dirname: PChar) : pDir
function FpOpendir(const dirname: RawByteString) : pDir
function FpOpendir(dirname: ShortString) : pDir

Visibility: default

Description: `FpOpenDir` opens the directory `DirName`, and returns a `pdir` pointer to a `Dir` (150) record, which can be used to read the directory structure. If the directory cannot be opened, `nil` is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpCloseDir` (172), `FpReadDir` (199)

Listing: `./bunixex/ex35.pp`

Program `Example35`;

```
{ Program to demonstrate the
  OpenDir, ReadDir, SeekDir and TellDir functions. }
```

Uses `BaseUnix`;

```
Var TheDir : PDir;
      ADirent : PDirent;
      Entry : Longint;
```

begin

```
  TheDir:=fpOpenDir( './. ' );
```

Repeat

```
  //    Entry:=fpTellDir (TheDir);
```

```
  ADirent:=fpReadDir (TheDir^);
```

```
  If ADirent<>Nil then
```

```
    With ADirent^ do
```

```
      begin
```

```
        Writeln ( 'Entry No : ',Entry );
```

```
        Writeln ( 'Inode   : ',d_fileno );
```

```
  //    Writeln ( 'Offset   : ',d_off );
```

```
        Writeln ( 'Reclen  : ',d_reclen );
```

```
        Writeln ( 'Name    : ',pchar(@d_name[0]));
```

```
      end;
```

```
  Until ADirent=Nil;
```

Repeat

```
  Write ( 'Entry No. you would like to see again (-1 to stop): ' );
```

```
  ReadLn ( Entry );
```

```
  If Entry<>-1 then
```

```
    begin
```

```
  //    fpSeekDir (TheDir, Entry);
```

```
// not implemented for various platforms
```

```
  ADirent:=fpReadDir (TheDir^);
```

```
  If ADirent<>Nil then
```

```
    With ADirent^ do
```

```
      begin
```

```
        Writeln ( 'Entry No : ',Entry );
```

```
        Writeln ( 'Inode   : ',d_fileno );
```

```
  //    Writeln ( 'Offset   : ',d_off );
```

```
        Writeln ( 'Reclen  : ',d_reclen );
```

```
        Writeln ( 'Name    : ',pchar(@d_name[0]));
```

```
      end;
```

```
  end;
```

```
  Until Entry=-1;
```

```
  fpCloseDir (TheDir^);
```

```
end.
```

1.4.50 FpPause

Synopsis: Wait for a signal to arrive

Declaration: `function FpPause : cint`

Visibility: default

Description: `FpPause` puts the process to sleep and waits until the application receives a signal. If a signal handler is installed for the received signal, the handler will be called and after that pause will return control to the process.

For an example, see `fpAlarm` ([168](#)).

1.4.51 FpPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function FpPipe(var fildes: TFilDes) : cint`

Visibility: default

Description: `FpPipe` creates a pipe, i.e. two file objects, one for input, one for output. The filehandles are returned in the array `fildes`. The input handle is in the 0-th element of the array, the output handle is in the 1-st element.

The function returns zero if everything went succesfully, a nonzero return value indicates an error.

Errors: In case the function fails, the following return values are possible:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `#rtl.unix.POpen` ([1869](#)), `fpMkFifo` ([190](#))

Listing: `./bunixex/ex36.pp`

Program `Example36`;

{ Program to demonstrate the AssignPipe function. }

Uses `BaseUnix, Unix`;

Var `pipi, pipo : Text;`
`s : String;`

begin

```

Writeln ('Assigning Pipes. ');
If assignpipe(pipi, pipo) <> 0 then
  Writeln ('Error assigning pipes !', fpgeterrno);
Writeln ('Writing to pipe, and flushing. ');
Writeln (pipo, 'This is a textstring '); close(pipo);
Writeln ('Reading from pipe. ');
While not eof(pipi) do
  begin
    Readln (pipi, s);
    Writeln ('Read from pipe : ', s);
  end;
  close (pipi);
writeln ('Closed pipes. ');

```

```

    writeln
end.

```

1.4.52 FpPoll

Synopsis: Poll a file descriptor for events.

Declaration: `function FpPoll(fds: ppollfd; nfd: cuint; timeout: clong) : cint`

Visibility: default

Description: `FpPoll` waits for events on file descriptors. `fds` points to an array of `tpollfd` records, each of these records describes a file descriptor on which to wait for events. The number of file descriptors is given by `nfd`. `>timeout` specifies the maximum time (in milliseconds) to wait for events.

On timeout, the result value is 0. If an event occurred on some descriptors, then the return value is the number of descriptors on which an event (or error) occurred. The `revents` field of the `tpollfd` records will contain the events for the file descriptor it described.

See also: `tpollfd` ([162](#))

1.4.53 FpPRead

Synopsis: Positional read: read from file descriptor at a certain position.

Declaration: `function FpPRead(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TSize`
`function FpPRead(fd: cint; var buf; nbytes: TSize; offset: TOff) : TSize`

Visibility: default

Description: `FpPRead` reads `nbytes` bytes from file descriptor `fd` into buffer `buf` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually read, or -1 on error.

Errors: On error, -1 is returned.

See also: `FpReadV` ([200](#)), `FpPWrite` ([197](#))

1.4.54 FpPWrite

Synopsis: Positional write: write to file descriptor at a certain position.

Declaration: `function FpPWrite(fd: cint; buf: PChar; nbytes: TSize; offset: TOff) : TSize`
`function FpPWrite(fd: cint; const buf; nbytes: TSize; offset: TOff) : TSize`

Visibility: default

Description: `FpPWrite` writes `nbytes` bytes from buffer `buf` into file descriptor `fd` starting at offset `offset`. Offset is measured from the start of the file. This function can only be used on files, not on pipes or sockets (i.e. any seekable file descriptor).

The function returns the number of bytes actually written, or -1 on error.

Errors: On error, -1 is returned.

See also: [FpPRead \(197\)](#), [FpWriteV \(219\)](#)

1.4.55 FpRead

Synopsis: Read data from file descriptor

Declaration: `function FpRead(fd: cint; buf: PChar; nbytes: TSize) : TSize`
`function FpRead(fd: cint; var buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpdRead` reads at most `nbytes` bytes from the file descriptor `fd`, and stores them in `buf`.

The function returns the number of bytes actually read, or -1 if an error occurred. No checking on the length of `buf` is done.

Errors: Extended error information can be retrieved using [fpGetErrno \(181\)](#).

See also: [FpOpen \(193\)](#), [FpClose \(171\)](#), [FpWrite \(219\)](#), [FpFTruncate \(179\)](#), [FpLSeek \(187\)](#)

Listing: `./bunixex/ex20.pp`

Program `Example20`;

{ Program to demonstrate the fdRead and fdTruncate functions. }

Uses `BaseUnix`;

Const `Data : string[10] = '1234567890'`;

Var `FD : cint;`
`l : longint;`

begin

`FD:=fpOpen('test.dat',o_wronly or o_creat,&666);`

`if fd>0 then`

`begin`

{ Fill file with data }

`for l:=1 to 10 do`

`if fpWrite (FD,Data[l],10)<>10 then`

`begin`

`writeln ('Error when writing !');`

`halt(1);`

`end;`

`fpClose(FD);`

`FD:=fpOpen('test.dat',o_rdonly);`

{ Read data again }

`If FD>0 then`

`begin`

`For l:=1 to 5 do`

`if fpRead (FD,Data[l],10)<>10 then`

`begin`

`Writeln ('Error when Reading !');`

`Halt(2);`

`end;`

`fpClose(FD);`

{ Truncating file at 60 bytes }

```

    { For truncating , file must be open or write }
    FD:=fpOpen( 'test.dat',o_wronly,&666);
    if FD>0 then
        begin
            if fpfTruncate(FD,60)<>0 then
                Writeln('Error when truncating !');
            fpClose (FD);
        end;
    end;
end.

```

1.4.56 FpReaddir

Synopsis: Read entry from directory

Declaration: `function FpReaddir(var dirp: Dir) : pDirent`

Visibility: default

Description: `FpReadDir` reads the next entry in the directory pointed to by `dirp`. It returns a `pdirent` pointer to a `dirent` (151) record describing the entry. If the next entry can't be read, `Nil` is returned.

For an example, see `FpOpenDir` (194).

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpCloseDir` (172), `FpOpenDir` (194)

1.4.57 fpReadLink

Synopsis: Read destination of symbolic link

Declaration: `function fpReadLink(name: PChar; linkname: PChar; maxlen: size_t) : cint`
`function fpReadLink(const Name: RawByteString) : RawByteString`

Visibility: default

Description: `FpReadLink` returns the file the symbolic link `name` is pointing to. The first form of this function accepts a buffer `linkname` of length `maxlen` where the filename will be stored. It returns the actual number of characters stored in the buffer.

The second form of the function returns simply the name of the file.

Errors: On error, the first form of the function returns -1; the second one returns an empty string. Extended error information is returned by the `FpGetErrno` (181) function.

SYS_ENOTDIRA part of the path in `Name` is not a directory.

SYS_EINVAL`maxlen` is not positive, or the file is not a symbolic link.

SYS_ENAMETOOLONGA pathname, or a component of a pathname, was too long.

SYS_ENOENTthe link name does not exist.

SYS_EACCESNo permission to search a directory in the path

SYS_ELOOPToo many symbolic links were encountered in translating the pathname.

SYS_EIOAn I/O error occurred while reading from the file system.

SYS_EFAULTThe buffer is not part of the process's memory space.

SYS_ENOMEM Not enough kernel memory was available.

See also: [FpSymLink \(211\)](#)

Listing: ./unixex/ex62.pp

Program Example62;

{ Program to demonstrate the ReadLink function. }

Uses BaseUnix, Unix;

Var F : Text;
 S : **String**;

```
begin
  Assign (F, 'test.txt');
  Rewrite (F);
  Writeln (F, 'This is written to test.txt');
  Close(f);
  { new.txt and test.txt are now the same file }
  if fpSymLink ('test.txt', 'new.txt') <> 0 then
    writeln ('Error when symlinking !');
  S := fpReadLink ('new.txt');
  if S = '' then
    Writeln ('Error reading link !')
  else
    Writeln ('Link points to : ', S);
  { Now remove links }
  if fpUnlink ('new.txt') <> 0 then
    Writeln ('Error when unlinking !');
  if fpUnlink ('test.txt') <> 0 then
    Writeln ('Error when unlinking !');
end.
```

1.4.58 FpReadV

Synopsis: Vector read: Read into multiple buffers

Declaration: function FpReadV(fd: cint; const iov: piovec; iovcnt: cint) : TsSize

Visibility: default

Description: FpReadV reads data from file descriptor fd and writes it into iovcnt buffers described by the tiovec (162) buffers pointed to by iov. It works like fpRead (198) only on multiple buffers.

Errors: On error, -1 is returned.

See also: [FpWriteV \(219\)](#), [FpPWrite \(197\)](#), [FpPRead \(197\)](#)

1.4.59 FpRename

Synopsis: Rename file

Declaration: function FpRename(old: PChar; newpath: PChar) : cint
 function FpRename(const old: RawByteString;
 const newpath: RawByteString) : cint

Visibility: default

Description: `fpRename` renames the file `Old` to `NewPath`. `NewPath` can be in a different directory than `Old`, but it cannot be on another partition (device). Any existing file on the new location will be replaced.

If the operation fails, then the `Old` file will be preserved.

The function returns zero on success, a nonzero value indicates failure.

Note: There exist a portable alternative to `fpRename`: `system.rename`. Please use `fpRename` only if you are writing Unix specific code. `System.rename` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

sys_eisdir `NewPath` exists and is a directory, but `Old` is not a directory.

sys_exdev `NewPath` and `Old` are on different devices.

sys_enotempty or sys_eexist `NewPath` is an existing, non-empty directory.

sys_ebusy `Old` or `NewPath` is a directory and is in use by another process.

sys_einval `NewPath` is part of `Old`.

sys_emlink `OldPath` or `NewPath` already have the maximum amount of links pointing to them.

sys_enotdir part of `Old` or `NewPath` is not directory.

sys_efault For the `pchar` case: One of the pointers points to an invalid address.

sys_eaccess access is denied when attempting to move the file.

sys_enametoolong Either `Old` or `NewPath` is too long.

sys_enoent a directory component in `Old` or `NewPath` didn't exist.

sys_enomem not enough kernel memory.

sys_erofs `NewPath` or `Old` is on a read-only file system.

sys_eloop too many symbolic links were encountered trying to expand `Old` or `NewPath`

sys_enospc the filesystem has no room for the new directory entry.

See also: `FpUnLink` ([216](#))

1.4.60 FpRmdir

Synopsis: Remove a directory.

Declaration: `function FpRmdir(path: PChar) : cint`
`function FpRmdir(const path: RawByteString) : cint`

Visibility: default

Description: `FpRmdir` removes the directory `Path` from the system. The directory must be empty for this call to succeed, and the user must have the necessary permissions in the parent directory. Only the last component of the directory is removed, i.e. higher-lying directories are not removed.

On success, zero is returned. A nonzero return value indicates failure.

Note: There exist a portable alternative to `fpRmdir`: `system.rmdir`. Please use `fpRmdir` only if you are writing Unix specific code. `System.rmdir` will work on all operating systems.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

1.4.61 fpSelect

Synopsis: Wait for events on file descriptors

Declaration: `function FPSelect (N: cint; readfds: pFDSet; writefds: pFDSet; exceptfds: pFDSet; TimeOut: ptimeval) : cint`
`function fpSelect (N: cint; readfds: pFDSet; writefds: pFDSet; exceptfds: pFDSet; TimeOut: cint) : cint`
`function fpSelect (var T: Text; TimeOut: ptimeval) : cint`
`function fpSelect (var T: Text; TimeOut: time_t) : cint`

Visibility: default

Description: `FpSelect` checks one of the file descriptors in the `FDSet`s to see if the following I/O operation on the file descriptors will block.

`readfds`, `writefds` and `exceptfds` are pointers to arrays of 256 bits. If you want a file descriptor to be checked, you set the corresponding element in the array to 1. The other elements in the array must be set to zero. Three arrays are passed : The entries in `readfds` are checked to see if the following read operation will block. The entries in `writefds` are checked to see if the following write operation will block, while entries in `exceptfds` are checked to see if an exception occurred on them.

You can use the functions `fpFD_ZERO` (178), `fpFD_Clr` (177), `fpFD_Set` (177) or `fpFD_IsSet` (177) to manipulate the individual elements of a set.

The pointers can be `Nil`.

`N` is the value of the largest file descriptor in one of the sets, + 1. In other words, it is the position of the last bit which is set in the array of bits.

`TimeOut` can be used to set a time limit. If `TimeOut` can be two types :

1. `TimeOut` is of type `ptimeval` and contains a zero time, the call returns immediately. If `TimeOut` is `Nil`, the kernel will wait forever, or until a status changed.
2. `TimeOut` is of type `cint`. If it is -1, this has the same effect as a `Timeout` of type `PTime` which is `Nil`. Otherwise, `TimeOut` contains a time in milliseconds.

When the `TimeOut` is reached, or one of the file descriptors has changed, the `Select` call returns. On return, it will have modified the entries in the array which have actually changed, and it returns the number of entries that have been changed. If the timeout was reached, and no descriptor changed, zero is returned; The arrays of indexes are undefined after that. On error, -1 is returned.

The variant with the text file will execute the `FpSelect` call on the file descriptor associated with the text file `T`

Errors: On error, the function returns -1. Extended error information can be retrieved using `fpGetErrno` (181).

SYS_EBADF An invalid descriptor was specified in one of the sets.

SYS_EINTRA non blocked signal was caught.

SYS_EINVAL `N` is negative or too big.

SYS_ENOMEM `Select` was unable to allocate memory for its internal tables.

See also: `fpFD_ZERO` (178), `fpFD_Clr` (177), `fpFD_Set` (177), `fpFD_IsSet` (177)

Listing: `./bunixex/ex33.pp`

Program Example33;

{ Program to demonstrate the Select function. }

Uses BaseUnix;

Var FDS : Tfdset;

begin

```

  fpfd_zero(FDS);
  fpfd_set(0,FDS);
  Writeln ('Press the <ENTER> to continue the program. ');
  { Wait until File descriptor 0 (=Input) changes }
  fpSelect (1,@FDS,nil ,nil ,nil );
  { Get rid of <ENTER> in buffer }
  readln;
  Writeln ('Press <ENTER> key in less than 2 seconds... ');
  Fpfd_zero(FDS);
  FpFd_set (0,FDS);
  if fpSelect (1,@FDS,nil ,nil ,2000)>0 then
    Writeln ('Thank you !')
    { FD_ISSET(0,FDS) would be true here. }
  else
    Writeln ('Too late !');
end.
```

1.4.62 fpseterrno

Synopsis: Set extended error information.

Declaration: `procedure fpseterrno(err: LongInt)`

Visibility: default

Description: `fpseterrno` sets the extended information on the latest error. It is called by all functions that communicate with the kernel or C library.

Unless a direct kernel call is performed, there should never be any need to call this function.

See also: `fpgeterrno` ([181](#))

1.4.63 FpSetgid

Synopsis: Set the current group ID

Declaration: `function FpSetgid(gid: TGid) : cint`

Visibility: default

Description: `fpSetUID` sets the group ID of the current process. This call will only work if it is executed as root, or the program is setgid root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([181](#)).

See also: `FpSetUid` ([205](#)), `FpGetGid` ([182](#)), `FpGetUid` ([185](#)), `FpGetEUid` ([181](#)), `FpGetEGid` ([180](#)), `FpGetPid` ([183](#)), `FpGetPPid` ([183](#))

1.4.64 fpSetPriority

Synopsis: Set process priority

Declaration: `function fpSetPriority(Which: cint; Who: cint; What: cint) : cint`

Visibility: default

Description: `fpSetPriority` sets the priority with which a process is running. Which process(es) is determined by the `Which` and `Who` variables. Which can be one of the pre-defined constants:

Prio_Process`Who` is interpreted as process ID

Prio_PGrp`Who` is interpreted as process group ID

Prio_User`Who` is interpreted as user ID

`Prio` is a value in the range -20 to 20.

For an example, see `FpNice` (193).

The function returns zero on success, -1 on failure

Errors: Extended error information is returned by the `FpGetErrno` (181) function.

sys_esrchNo process found using `which` and `who`.

sys_einval`Which` was not one of `Prio_Process`, `Prio_Grp` or `Prio_User`.

sys_epermA process was found, but neither its effective or real user ID match the effective user ID of the caller.

sys_eaccessA non-superuser tried to a priority increase.

See also: `FpGetPriority` (184), `FpNice` (193)

1.4.65 FpSetRLimit

Synopsis: Set process resource limits

Declaration: `function FpSetRLimit(Resource: cint; rlim: PRLimit) : cint`

Visibility: default

Description: `FpGetRLimit` sets the resource limits for the current process: `resource` determines the resource of which the kernel should set the limits (one of the many `RLIMIT_*` constants). `rlim` should point to a `TRLimit` (162) record which contains the new limits for the resource indicated in `resource`.

The function returns zero if the resource limits were successfully set.

Errors: On error, -1 is returned and `fpgeterrno` (181) can be used to retrieve the error code.

See also: `FpGetRLimit` (184)

1.4.66 FpSetsid

Synopsis: Create a new session.

Declaration: `function FpSetsid : TPid`

Visibility: default

Description: `FpSetsid` creates a new session (process group). It returns the new process group id (as returned by `FpGetpgrp` (182)). This call will fail if the current process is already the process group leader.

Errors: On error, -1 is returned. Extended error information can be retrieved with `fpGetErrNo` (181)

1.4.67 fpsettimeofday

Synopsis: Set kernel time

Declaration: `function fpsettimeofday(tp: ptimeval; tzp: ptimezone) : cint`

Visibility: default

Description: `FpSetTimeOfDay` sets the kernel time to the number of seconds since 00:00, January 1 1970, GMT specified in the `tp` record. This time NOT corrected any way, not taking into account time-zones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

See also: `#rtl.unix.FPGetTimeOfDay` ([1865](#))

1.4.68 FpSetuid

Synopsis: Set the current user ID

Declaration: `function FpSetuid(uid: TUid) : cint`

Visibility: default

Description: `fpSetUID` sets the user ID of the current process. This call will only work if it is executed as root, or the program is `setuid` root.

On success, zero is returned, on error -1 is returned.

Errors: Extended error information can be retrieved with `fpGetErrNo` ([181](#)).

See also: `FpGetGid` ([182](#)), `FpGetUid` ([185](#)), `FpGetEUid` ([181](#)), `FpGetEGid` ([180](#)), `FpGetPid` ([183](#)), `FpGetPPid` ([183](#)), `FpSetGid` ([203](#))

1.4.69 FPSigaction

Synopsis: Install signal handler

Declaration: `function FPSigaction(sig: cint; act: psigactionrec; oact: psigactionrec) : cint`

Visibility: default

Description: `FPSigaction` changes the action to take upon receipt of a signal. `Act` and `Oact` are pointers to a `SigActionRec` ([158](#)) record. `Sig` specifies the signal, and can be any signal except **SIGKILL** or **SIGSTOP**.

If `Act` is non-nil, then the new action for signal `Sig` is taken from it. If `Oact` is non-nil, the old action is stored there. `Sa_Handler` may be `SIG_DFL` for the default action or `SIG_IGN` to ignore the signal. `Sa_Mask` Specifies which signals should be ignored during the execution of the signal handler. `Sa_Flags` Specifies a series of flags which modify the behaviour of the signal handler. You can 'or' none or more of the following :

SA_NOCLDSTOP If `sig` is **SIGCHLD** do not receive notification when child processes stop.

SA_ONESHOT or **SA_RESETHAND** Restore the signal action to the default state once the signal handler has been called.

SA_RESTART For compatibility with BSD signals.

SA_NOMASK or **SA_NODEFER** Do not prevent the signal from being received from within its own signal handler.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

sys_einval an invalid signal was specified, or it was **SIGKILL** or **SIGSTOP**.

sys_efault `Act`, `OldAct` point outside this process address space

sys_eintr System call was interrupted.

See also: `FpSigProcMask` (209), `FpSigPending` (208), `FpSigSuspend` (209), `FpKill` (186)

Listing: `./bunixex/ex57.pp`

Program `example57`;

```
{ Program to demonstrate the SigAction function. }

{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}

uses BaseUnix;

Var
    oa, na : PSigActionRec;

Procedure DoSig(sig : cint); cdecl;

begin
    writeln ('Receiving signal: ', sig);
end;

begin
    new(na);
    new(oa);
    na^.sa_Handler := SigActionHandler (@DoSig);
    fillchar (na^.Sa_Mask, sizeof(na^.sa_mask), #0);
    na^.Sa_Flags := 0;
    { $ifdef Linux } // Linux specific
    na^.Sa_Restorer := Nil;
    { $endif }
    if fpSigAction (SigUsr1, na, oa) <> 0 then
        begin
            writeln ('Error: ', fpgeterrno, '.');
            halt (1);
        end;
    Writeln ('Send USR1 signal or press <ENTER> to exit');
    readln;
end.
```

1.4.70 FpSigAddSet

Synopsis: Set a signal in a signal set.

Declaration: `function FpSigAddSet (var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigAddSet` adds signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (207), `FpSigFillSet` (207), `FpSigDelSet` (207), `FpSigIsMember` (207)

1.4.71 `FpSigDelSet`

Synopsis: Remove a signal from a signal set.

Declaration: `function FpSigDelSet (var nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigDelSet` removes signal `Signo` to the signal set `nset`. The function returns 0 on success.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (207), `FpSigFillSet` (207), `FpSigAddSet` (206), `FpSigIsMember` (207)

1.4.72 `FpsigEmptySet`

Synopsis: Clear all signals from signal set.

Declaration: `function FpsigEmptySet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigEmptySet` clears all signals from the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigFillSet` (207), `FpSigAddSet` (206), `FpSigDelSet` (207), `FpSigIsMember` (207)

1.4.73 `FpSigFillSet`

Synopsis: Set all signals in signal set.

Declaration: `function FpSigFillSet (var nset: tsigset) : cint`

Visibility: default

Description: `FpSigFillSet` sets all signals in the signal set `nset`.

Errors: None. This function always returns zero.

See also: `FpSigEmptySet` (207), `FpSigAddSet` (206), `FpSigDelSet` (207), `FpSigIsMember` (207)

1.4.74 `FpSigIsMember`

Synopsis: Check whether a signal appears in a signal set.

Declaration: `function FpSigIsMember (const nset: tsigset; signo: cint) : cint`

Visibility: default

Description: `FpSigIsMember` checks whether `Signo` appears in the set `nset`. If it is a member, then 1 is returned. If not, zero is returned.

Errors: If an invalid signal number is given, -1 is returned.

See also: `FpSigEmptySet` (207), `FpSigFillSet` (207), `FpSigAddSet` (206), `FpSigDelSet` (207)

1.4.75 FpSignal

Synopsis: Install signal handler (deprecated)

Declaration: `function FpSignal(signum: LongInt; Handler: signalhandler)
: signalhandler`

Visibility: default

Description: `FpSignal` installs a new signal handler (specified by `Handler`) for signal `SigNum`.

This call has a subset of the functionality provided by the `FpSigAction` (205) call. The return value for `FpSignal` is the old signal handler, or nil on error.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

SIG_ERR An error occurred.

See also: `FpSigAction` (205), `FpKill` (186)

Listing: `./bunixex/ex58.pp`

Program `example58;`

{ Program to demonstrate the Signal function. }

*{
do a kill -USR1 pid from another terminal to see what happens.
replace pid with the real pid of this program.
You can get this pid by running 'ps'.
}*

uses `BaseUnix;`

Procedure `DoSig(sig : cint); cdecl;`

begin

`writeln('Receiving signal: ',sig);`

end;

begin

`if fpSignal(SigUsr1, SignalHandler(@DoSig))=signalhandler(SIG_ERR) then`

`begin`

`writeln('Error: ',fpGetErrno, '.');`

`halt(1);`

`end;`

`Writeln('Send USR1 signal or press <ENTER> to exit');`

`readln;`

end.

1.4.76 FpSigPending

Synopsis: Return set of currently pending signals

Declaration: `function FpSigPending(var nset: tsigset) : cint`

Visibility: default

Description: `fpSigpending` allows the examination of pending signals (which have been raised while blocked.)

The signal mask of pending signals is returned.

Errors: None

See also: [fpSigAction \(205\)](#), [fpSigProcMask \(209\)](#), [fpSigSuspend \(209\)](#), [fpSignal \(208\)](#), [fpKill \(186\)](#)

1.4.77 FpSigProcMask

Synopsis: Set list of blocked signals

Declaration:

```
function FpSigProcMask(how: cint; nset: psigset; oset: psigset) : cint
function FpSigProcMask(how: cint; constref nset: tsigset;
var oset: tsigset) : cint
```

Visibility: default

Description: Changes the list of currently blocked signals. The behaviour of the call depends on How :

SIG_BLOCKThe set of blocked signals is the union of the current set and the `nset` argument.

SIG_UNBLOCKThe signals in `nset` are removed from the set of currently blocked signals.

SIG_SETMASKThe list of blocked signals is set so `nset`.

If `oset` is non-nil, then the old set is stored in it.

Errors: `Errno` is used to report errors.

sys_efault`oset` or `nset` point to an adress outside the range of the process.

sys_eintrSystem call was interrupted.

See also: [fpSigAction \(205\)](#), [fpSigPending \(208\)](#), [fpSigSuspend \(209\)](#), [fpKill \(186\)](#)

1.4.78 FpSigSuspend

Synopsis: Set signal mask and suspend process till signal is received

Declaration:

```
function FpSigSuspend(const sigmask: tsigset) : cint
```

Visibility: default

Description: `fpSigSuspend` temporarily replaces the signal mask for the process with the one given in `SigMask`, and then suspends the process until a signal is received.

Errors: None

See also: [fpSigAction \(205\)](#), [fpSigProcMask \(209\)](#), [fpSigPending \(208\)](#), [fpSignal \(208\)](#), [fpKill \(186\)](#)

1.4.79 FpSigTimedWait

Synopsis: Wait for signal, with timeout

Declaration:

```
function FpSigTimedWait(const sigset: tsigset; info: psiginfo;
timeout: ptimespec) : cint
```

Visibility: default

Description: `FpSigTimedWait` will suspend the current thread and wait for one of the signals in `sigset` to be delivered. information on the delivered signal is placed in the location provided by `info` (or in `info` itself, if the `Var` variant of the call is used). If the signal is not delivered within the time limit set in `timeout`, then the call will return -1, and `fpGetErrno` will return `EAGAIN`.

On success, the signal number is returned.

Errors: On error, -1 is returned, and extended error information can be obtained with `fpGetErrno`.

See also: `FpSigSuspend` ([209](#))

1.4.80 FpSleep

Synopsis: Suspend process for several seconds

Declaration: `function FpSleep(seconds: cuint) : cuint`

Visibility: default

Description: `FpSleep` suspends the process till a time period as specified in `seconds` has passed, then the function returns. If the call was interrupted (e.g. by some signal) then the function may return earlier, and the return value is the remaining time till the end of the intended period.

If the function returns without error, the return value is zero.

See also: `fpPause` ([196](#)), `fpAlarm` ([168](#)), `fpNanoSleep` ([192](#))

Listing: `./bunixex/ex73.pp`

```

program example73;

  { Program to demonstrate the FpSleep function. }

uses BaseUnix;

Var
  Res : Longint;

begin
  Write('Sleep returned : ');
  Flush(Output);
  Res:=(fpSleep(10));
  Writeln(res);
  If (res<>0) then
    Writeln('Remaining seconds      : ',res);
end.

```

1.4.81 FpStat

Synopsis: Retrieve file information about a file descriptor.

Declaration: `function FpStat(path: PChar; var buf: Stat) : cint`
`function FpStat(const path: RawByteString; var buf: Stat) : cint`
`function FpStat(path: ShortString; var buf: Stat) : cint`

Visibility: default

Description: `FpFStat` gets information about the file specified in `Path`, and stores it in `Info`, which is of type `stat` ([160](#)). The function returns zero if the call was successful, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

`sys_enoent``Path` does not exist.

See also: [FpStat \(210\)](#), [FpLStat \(188\)](#)

Listing: `./bunixex/ex28.pp`

```

program example28;

{ Program to demonstrate the FStat function. }

uses BaseUnix;

var f : text;
    i : byte;
    info : stat;

begin
  { Make a file }
  assign (f, 'test.fil ');
  rewrite (f);
  for i:=1 to 10 do writeln (f, 'Testline # ', i);
  close (f);
  { Do the call on made file. }
  if fpstat ('test.fil ', info) <> 0 then
    begin
      writeln ('Fstat failed. Errno : ', fpgeterrno);
      halt (1);
    end;
  writeln;
  writeln ('Result of fstat on file ''test.fil''.');
  writeln ('Inode   : ', info.st_ino);
  writeln ('Mode    : ', info.st_mode);
  writeln ('nlink   : ', info.st_nlink);
  writeln ('uid     : ', info.st_uid);
  writeln ('gid     : ', info.st_gid);
  writeln ('rdev    : ', info.st_rdev);
  writeln ('Size    : ', info.st_size);
  writeln ('Blksize : ', info.st_blksize);
  writeln ('Blocks  : ', info.st_blocks);
  writeln ('atime   : ', info.st_atime);
  writeln ('mtime   : ', info.st_mtime);
  writeln ('ctime   : ', info.st_ctime);
  { Remove file }
  erase (f);
end.
```

1.4.82 fpSymlink

Synopsis: Create a symbolic link

Declaration: `function fpSymlink(oldname: PChar; newname: PChar) : cint`

Visibility: default

Description: `SymLink` makes `NewName` point to the file in `OldName`, which doesn't necessarily exist. The two files DO NOT have the same inode number. This is known as a 'soft' link.

The permissions of the link are irrelevant, as they are not used when following the link. Ownership of the file is only checked in case of removal or renaming of the link.

The function returns zero if the call was succesful, a nonzero value if the call failed.

Errors: Extended error information is returned by the `FpGetErrno` (181) function.

- sys_eperm**The filesystem containing oldpath and newpath does not support linking files.
- sys_eaccess**Write access for the directory containing Newpath is disallowed, or one of the directories in OldPath or NewPath has no search (=execute) permission.
- sys_enoent**A directory entry in OldPath or NewPath does not exist or is a symbolic link pointing to a non-existent directory.
- sys_enotdir**A directory entry in OldPath or NewPath is not a directory.
- sys_enomem**Insufficient kernel memory.
- sys_erofs**The files are on a read-only filesystem.
- sys_eexist**NewPath already exists.
- sys_eloop**OldPath or NewPath has a reference to a circular symbolic link, i.e. a symbolic link, whose expansion points to itself.
- sys_enospc**The device containing NewPath has no room for another entry.

See also: `FpLink` (186), `FpUnLink` (216), `FpReadLink` (199)

Listing: ./unixex/ex22.pp

Program Example22;

{ Program to demonstrate the SymLink and UnLink functions. }

Uses baseunix, Unix;

Var F : Text;
 S : String;

begin
 Assign (F, 'test.txt');
 Rewrite (F);
 Writeln (F, 'This is written to test.txt');
 Close(f);
 { new.txt and test.txt are now the same file }
 if fpSymLink ('test.txt', 'new.txt') <> 0 **then**
 writeln ('Error when symlinking !');
 { Removing test.txt still leaves new.txt }
 { Pointing now to a non-existent file ! }
 if fpUnlink ('test.txt') <> 0 **then**
 Writeln ('Error when unlinking !');
 Assign (f, 'new.txt');
 { This should fail, since the symbolic link }
 { points to a non-existent file ! }
 {\$i-}
 Reset (F);
 {\$i+}
 if IOResult=0 **then**
 Writeln ('This shouldn''t happen');
 { Now remove new.txt also }
 if fpUnlink ('new.txt') <> 0 **then**
 Writeln ('Error when unlinking !');
end.

1.4.83 fpS_ISBLK

Synopsis: Is file a block device

Declaration: `function fpS_ISBLK(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISBLK` checks the file mode `m` to see whether the file is a block device file. If so it returns `True`.

See also: `FpFStat` (178), `FpS_ISLNK` (214), `FpS_ISREG` (214), `FpS_ISDIR` (213), `FpS_ISCHR` (213), `FpS_ISFIFO` (213), `FpS_ISSOCK` (215)

1.4.84 fpS_ISCHR

Synopsis: Is file a character device

Declaration: `function fpS_ISCHR(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISCHR` checks the file mode `m` to see whether the file is a character device file. If so it returns `True`.

See also: `FpFStat` (178), `FpS_ISLNK` (214), `FpS_ISREG` (214), `FpS_ISDIR` (213), `FpS_ISBLK` (212), `FpS_ISFIFO` (213), `FpS_ISSOCK` (215)

1.4.85 fpS_ISDIR

Synopsis: Is file a directory

Declaration: `function fpS_ISDIR(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISDIR` checks the file mode `m` to see whether the file is a directory. If so, it returns `True`

See also: `FpFStat` (178), `FpS_ISLNK` (214), `FpS_ISREG` (214), `FpS_ISCHR` (213), `FpS_ISBLK` (212), `fpS_ISFIFO` (213), `FpS_ISSOCK` (215)

1.4.86 fpS_ISFIFO

Synopsis: Is file a FIFO

Declaration: `function fpS_ISFIFO(m: TMode) : Boolean`

Visibility: default

Description: `fpS_ISFIFO` checks the file mode `m` to see whether the file is a fifo (a named pipe). If so it returns `True`.

See also: `FpFStat` (178), `FpS_ISLNK` (214), `FpS_ISREG` (214), `FpS_ISCHR` (213), `FpS_ISBLK` (212), `FpS_ISDIR` (213), `FpS_ISSOCK` (215)

1.4.87 fpS_ISLNK

Synopsis: Is file a symbolic link

Declaration: `function fpS_ISLNK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISLNK` checks the file mode `m` to see whether the file is a symbolic link. If so it returns `True`

See also: `FpFStat` (178), `FpS_ISFIFO` (213), `FpS_ISREG` (214), `FpS_ISCHR` (213), `FpS_ISBLK` (212), `FpS_ISDIR` (213), `FpS_ISSOCK` (215)

Listing: `./bunixex/ex53.pp`

Program `Example53;`

{ Program to demonstrate the S_ISLNK function. }

Uses `BaseUnix, Unix;`

Var `Info : Stat;`

begin

```

  if fpLStat (paramstr(1), @info)=0 then
    begin
      if fpS_ISLNK(info.st_mode) then
        Writeln ('File is a link');
      if fpS_ISREG(info.st_mode) then
        Writeln ('File is a regular file');
      if fpS_ISDIR(info.st_mode) then
        Writeln ('File is a directory');
      if fpS_ISCHR(info.st_mode) then
        Writeln ('File is a character device file');
      if fpS_ISBLK(info.st_mode) then
        Writeln ('File is a block device file');
      if fpS_ISFIFO(info.st_mode) then
        Writeln ('File is a named pipe (FIFO)');
      if fpS_ISSOCK(info.st_mode) then
        Writeln ('File is a socket');
    end;

```

end.

1.4.88 fpS_ISREG

Synopsis: Is file a regular file

Declaration: `function fpS_ISREG(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISREG` checks the file mode `m` to see whether the file is a regular file. If so it returns `True`

See also: `FpFStat` (178), `FpS_ISFIFO` (213), `FpS_ISLNK` (214), `FpS_ISCHR` (213), `FpS_ISBLK` (212), `FpS_ISDIR` (213), `FpS_ISSOCK` (215)

1.4.89 fpS_ISSOCK

Synopsis: Is file a Unix socket

Declaration: `function fpS_ISSOCK(m: TMode) : Boolean`

Visibility: default

Description: `FpS_ISSOCK` checks the file mode `m` to see whether the file is a socket. If so it returns `True`.

See also: `FpFStat` (178), `FpS_ISFIFO` (213), `FpS_ISLNK` (214), `FpS_ISCHR` (213), `FpS_ISBLK` (212), `FpS_ISDIR` (213), `FpS_ISREG` (214)

1.4.90 fptime

Synopsis: Return the current Unix time

Declaration: `function FpTime(var tloc: TTime) : TTime`
`function fptime : time_t`

Visibility: default

Description: `FpTime` returns the number of seconds since 00:00:00 GMT, january 1, 1970. it is adjusted to the local time zone, but not to DST. The result is also stored in `tloc`, if it is specified.

Errors: On error, -1 is returned. Extended error information can be retrieved using `fpGetErrno` (181).

Listing: `./bunixex/ex1.pp`

Program Example1;

{ Program to demonstrate the fptime function. }

Uses baseunix;

begin

Write ('Secs past the start of the Epoch (00:00 1/1/1980) : ');

WriteLn (fptime);

end.

1.4.91 FpTimes

Synopsis: Return execution times for the current process

Declaration: `function FpTimes(var buffer: tms) : TClock`

Visibility: default

Description: `fpTimes` stores the execution time of the current process and child processes in `buffer`.

The return value (on Linux) is the number of clock ticks since boot time. On error, -1 is returned, and extended error information can be retrieved with `fpGetErrno` (181).

See also: `fpUTime` (217)

1.4.92 FpUmask

Synopsis: Set file creation mask.

Declaration: `function FpUmask (cmask: TMode) : TMode`

Visibility: default

Description: `fpUmask` changes the file creation mask for the current user to `cmask`. The current mask is returned.

See also: `fpChmod` ([169](#))

Listing: `./bunixex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Umask function. }

Uses `BaseUnix;`

begin

`WriteLn ('Old Umask was : ',fpUmask(&111));`

`WRiteln ('New Umask is : ',&111);`

end.

1.4.93 FpUname

Synopsis: Return system name.

Declaration: `function FpUname (var name: UtsName) : cint`

Visibility: default

Description: `Uname` gets the name and configuration of the current Linux kernel, and returns it in the `name` record.

On success, 0 is returned, on error, -1 is returned.

Errors: Extended error information can be retrieved using `fpGetErrno` ([181](#)).

See also: `FpUTime` ([217](#))

1.4.94 FpUnlink

Synopsis: Unlink (i.e. remove) a file.

Declaration: `function FpUnlink (path: PChar) : cint`

`function FpUnlink (const path: RawByteString) : cint`

Visibility: default

Description: `FpUnlink` decreases the link count on file `Path`. `Path` can be of type `AnsiString` or `PChar`. If the link count is zero, the file is removed from the disk.

The function returns zero if the call was succesfull, a nonzero value indicates failure.

Note: There exist a portable alternative to erase files: `system.erase`. Please use `fpUnlink` only if you are writing Unix specific code. `System.erase` will work on all operating systems.

For an example, see `FpLink` ([186](#)).

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

sys_eaccess You have no write access right in the directory containing `Path`, or you have no search permission in one of the directory components of `Path`.

sys_eperm The directory containing `pathname` has the sticky-bit set and the process's effective uid is neither the uid of the file to be deleted nor that of the directory containing it.

sys_enoent A component of the path doesn't exist.

sys_enotdir A directory component of the path is not a directory.

sys_eisdir `Path` refers to a directory.

sys_enomem Insufficient kernel memory.

sys_erofs `Path` is on a read-only filesystem.

See also: `FpLink` (186), `FpSymLink` (211)

1.4.95 FpUtime

Synopsis: Set access and modification times of a file (touch).

Declaration: `function FpUtime(path: PChar; times: pUtimBuf) : cint`
`function FpUtime(const path: RawByteString; times: pUtimBuf) : cint`

Visibility: default

Description: `FpUtime` sets the access and modification times of the file specified in `Path`. the `times` record contains 2 fields, `actime`, and `modtime`, both of type `time_t` (commonly a `longint`). They should be filled with an epoch-like time, specifying, respectively, the last access time, and the last modification time. For some filesystem (most notably, FAT), these times are the same.

The function returns zero on success, a nonzero return value indicates failure.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

sys_eaccess One of the directories in `Path` has no search (=execute) permission.

sys_enoent A directory entry in `Path` does not exist or is a symbolic link pointing to a non-existent directory.

Other errors may occur, but aren't documented.

See also: `FpTime` (215), `FpChown` (170), `FpAccess` (167)

Listing: `./bunixex/ex25.pp`

Program `Example25;`

{ Program to demonstrate the UTime function. }

Uses `Dos, BaseUnix, Unix, UnixUtil;`

Var `utim : utimbuf;`
`dow, msec, year, month, day, hour, minute, second : Word;`

begin

{ Set access and modification time of executable source }
`GetTime (hour, minute, second, msec);`
`GetDate (year, month, day, dow);`
`utim.actime := LocalToEpoch (year, month, day, hour, minute, second);`

```

    utim.modtime:=utim.actime;
    if Fputime('ex25.pp',@utim)<>0 then
        writeln('Call to UTime failed !')
    else
        begin
            Write('Set access and modification times to : ');
            Write(Hour:2,':',minute:2,':',second:', ');
            Writeln(Day:2,'/',month:2,'/',year:4);
        end;
    end.

```

1.4.96 FpWait

Synopsis: Wait for a child to exit.

Declaration: `function FpWait(var stat_loc: cint) : TPid`

Visibility: default

Description: `fpWait` suspends the current process and waits for any child to exit or stop due to a signal. It reports the exit status of the exited child in `stat_loc`.

The return value of the function is the process ID of the child that exited, or -1 on error.

Errors: Extended error information can be retrieved using `fpgetErrno` ([181](#)).

See also: `fpFork` ([178](#)), `fpExecve` ([175](#)), `fpWaitPid` ([218](#))

1.4.97 FpWaitPid

Synopsis: Wait for a process to terminate

Declaration: `function FpWaitpid(pid: TPid; stat_loc: pcint; options: cint) : TPid`
`function FpWaitPid(pid: TPid; var Status: cint; Options: cint) : TPid`

Visibility: default

Description: `fpWaitPid` waits for a child process with process ID `Pid` to exit. The value of `Pid` can be one of the following:

Pid < -1 Causes `fpWaitPid` to wait for any child process whose process group ID equals the absolute value of `pid`.

Pid = -1 Causes `fpWaitPid` to wait for any child process.

Pid = 0 Causes `fpWaitPid` to wait for any child process whose process group ID equals the one of the calling process.

Pid > 0 Causes `fpWaitPid` to wait for the child whose process ID equals the value of `Pid`.

The `Options` parameter can be used to specify further how `fpWaitPid` behaves:

WNOHANG Causes `fpWaitpid` to return immediately if no child has exited.

WUNTRACED Causes `fpWaitPid` to return also for children which are stopped, but whose status has not yet been reported.

__WCLONE Causes `fpWaitPid` also to wait for threads created by the `#rtl.linux.Clone` ([890](#)) call.

The exit status of the process that caused `fpWaitPID` is reported in `stat_loc` or `Status`.

Upon return, it returns the process id of the process that exited, 0 if no process exited, or -1 in case of failure.

For an example, see `fpFork` (178).

Errors: Extended error information can be retrieved using `fpgetErrno` (181).

See also: `fpFork` (178), `fpExecve` (175), `fpWait` (218)

1.4.98 FpWrite

Synopsis: Write data to file descriptor

Declaration: `function FpWrite(fd: cint; buf: PChar; nbytes: TSize) : TSize`
`function FpWrite(fd: cint; const buf; nbytes: TSize) : TSize`

Visibility: default

Description: `FpWrite` writes at most `nbytes` bytes from `buf` to file descriptor `fd`.

The function returns the number of bytes actually written, or -1 if an error occurred.

Errors: Extended error information can be retrieved using `fpGetErrno` (181).

See also: `FpOpen` (193), `FpClose` (171), `FpRead` (198), `FpFTruncate` (179), `FpLSeek` (187)

1.4.99 FpWriteV

Synopsis: Vector write: Write from multiple buffers to a file descriptor

Declaration: `function FpWriteV(fd: cint; const iov: piovec; iovcnt: cint) : TSize`

Visibility: default

Description: `FpWriteV` writes data to file descriptor `fd`. The data is taken from `iovcnt` buffers described by the `tiovec` (162) buffers pointed to by `iov`. It works like `fpWrite` (219) only from multiple buffers.

Errors: On error, -1 is returned.

See also: `FpReadV` (200), `FpPWrite` (197), `FpPRead` (197)

1.4.100 FreeShellArgV

Synopsis: Free the result of a `CreateShellArgV` (167) function

Declaration: `procedure FreeShellArgV(p: PPChar)`

Visibility: default

Description: `FreeShellArgV` frees the memory pointed to by `P`, which was allocated by a call to `CreateShellArgV` (167).

Errors: None.

See also: `CreateShellArgV` (167)

1.4.101 **wexitStatus**

Synopsis: Extract the exit status from the `fpWaitPID` (218) result.

Declaration: `function wexitStatus(Status: cint) : cint`

Visibility: default

Description: `WEXITSTATUS` can be used to extract the exit status from `Status`, the result of the `FpWaitPID` (218) call.

See also: `FpWaitPID` (218), `WTERMSIG` (221), `WSTOPSIG` (220), `WIFEXITED` (220), `WIFSIGNALED` (220)

1.4.102 **wifexited**

Synopsis: Check whether the process exited normally

Declaration: `function wifexited(Status: cint) : Boolean`

Visibility: default

Description: `WIFEXITED` checks `Status` and returns `True` if the status indicates that the process terminated normally, i.e. was not stopped by a signal.

See also: `FpWaitPID` (218), `WTERMSIG` (221), `WSTOPSIG` (220), `WIFSIGNALED` (220), `WEXITSTATUS` (220)

1.4.103 **wifsignaled**

Synopsis: Check whether the process was exited by a signal.

Declaration: `function wifsignaled(Status: cint) : Boolean`

Visibility: default

Description: `WIFSIGNALED` returns `True` if `Status` indicates that the process exited because it received a signal.

See also: `FpWaitPID` (218), `WTERMSIG` (221), `WSTOPSIG` (220), `WIFEXITED` (220), `WEXITSTATUS` (220)

1.4.104 **wstopsig**

Synopsis: Return the exit code from the process.

Declaration: `function wstopsig(Status: cint) : cint`

Visibility: default

Description: `WSTOPSIG` is an alias for `WEXITSTATUS` (220).

See also: `FpWaitPID` (218), `WTERMSIG` (221), `WIFEXITED` (220), `WIFSIGNALED` (220), `WEXITSTATUS` (220)

1.4.105 wtermsig

Synopsis: Return the signal that caused a process to exit.

Declaration: `function wtermsig(Status: cint) : cint`

Visibility: default

Description: `WTERMSIG` extracts from `Status` the signal number which caused the process to exit.

See also: `FpWaitPID` ([218](#)), `WSTOPSIG` ([220](#)), `WIFEXITED` ([220](#)), `WIFSIGNALED` ([220](#)), `WEXITSTATUS` ([220](#))

Chapter 2

Reference for unit 'character'

2.1 Used units

Table 2.1: Used units by unit 'character'

Name	Page
System	1194
unicodedata	1807

2.2 Overview

The character unit contains the TCharacter ([222](#)) class, which consists mainly of class functions. It should not be constructed, but its class methods can be used. All class methods also exist as regular methods.

Many routines depend on unicode collation data to be present in the binary (or distributed on disc with the application. This data can be loaded using the routines in the unicodedata ([1807](#)) unit.. The FPC project distributes some unicode collation data in .bco files which can be loaded using the LoadCollation ([1816](#)) routine from that unit.

2.3 Constants, types and variables

2.3.1 Types

TCharacterOption = (coIgnoreInvalidSequence)

Table 2.2: Enumeration values for type TCharacterOption

Value	Explanation
coIgnoreInvalidSequence	Ignore invalid unicodecode sequences

TCharacterOption is used in the toUpper ([222](#)) and toLower ([222](#)) functions to control the behaviour of the function.

TCharacterOptions = Set of TCharacterOption

TCharacterOptions is the set of TCharacterOption, used in toUpper (222) and toLower (222) functions to control the behaviour of the function.

```
TUnicodeCategory = (ucUppercaseLetter, ucLowercaseLetter,
    ucTitlecaseLetter, ucModifierLetter, ucOtherLetter,
    ucNonSpacingMark, ucCombiningMark, ucEnclosingMark
    ,
        ucDecimalNumber, ucLetterNumber, ucOtherNumber
    ,
        ucConnectPunctuation, ucDashPunctuation,
ucOpenPunctuation, ucClosePunctuation,
ucInitialPunctuation, ucFinalPunctuation,
ucOtherPunctuation, ucMathSymbol, ucCurrencySymbol,
ucModifierSymbol, ucOtherSymbol, ucSpaceSeparator,
ucLineSeparator, ucParagraphSeparator, ucControl,
ucFormat, ucSurrogate, ucPrivateUse, ucUnassigned)
```


Table 2.3: Enumeration values for type TUnicodeCategory

Value	Explanation
ucClosePunctuation	Punctuation, close (Pe)
ucCombiningMark	Mark, spacing combining (Mc)
ucConnectPunctuation	Punctuation, connector (Pc)
ucControl	Other, control (Cc)
ucCurrencySymbol	Symbol, currency (Sc)
ucDashPunctuation	Punctuation, dash (Pd)
ucDecimalNumber	Number, decimal digit (Nd)
ucEnclosingMark	Mark, enclosing (Me)
ucFinalPunctuation	Punctuation, final quote (Pf, may behave like Ps or Pe depending on usage)
ucFormat	Other, format (Cf)
ucInitialPunctuation	Punctuation, initial quote (Pi, may behave like Ps or Pe depending on usage)
ucLetterNumber	Number, letter (Nl)
ucLineSeparator	Separator, line (Zl)
ucLowercaseLetter	Letter, lowercase (Ll)
ucMathSymbol	Symbol, math (Sm)
ucModifierLetter	Letter, modifier (Lm)
ucModifierSymbol	Symbol, modifier (Sk)
ucNonSpacingMark	Mark, nonspacing (Mn)
ucOpenPunctuation	Punctuation, open (Ps)
ucOtherLetter	Letter, other (Lo)
ucOtherNumber	Number, other (No)
ucOtherPunctuation	Punctuation, other (Po)
ucOtherSymbol	Symbol, other (So)
ucParagraphSeparator	Separator, paragraph (Zp)
ucPrivateUse	Other, private use (Co)
ucSpaceSeparator	Separator, space (Zs)
ucSurrogate	Other, surrogate (Cs)
ucTitlecaseLetter	Letter, titlecase (Lt)
ucUnassigned	Other, not assigned (including noncharacters) (Cn)
ucUppercaseLetter	Letter, uppercase (Lu)

This enumeration type contains the characterization of all possible unicode characters. It is used in the `GetUnicodeCategory` (222) and `TCharacter.GetUnicodeCategory` (222) functions.

`TUnicodeCategorySet = Set of TUnicodeCategory`

`TUnicodeCategorySet` is the set of `TUnicodeCategory` (223). It is used internally in the `TCharacter` (222) class.

Chapter 3

Reference for unit 'charset'

3.1 Used units

Table 3.1: Used units by unit 'charset'

Name	Page
System	1194

3.2 Overview

The charset unit can be used to load single-byte character set (code page) descriptions. It is used in the `fpwidingstring` ([225](#)) unit to add support for converting single-byte codepage strings to unicode strings (and vice versa).

Data of a code page may be included using one of the ready-made units, or can be loaded (in a binary form) at runtime with the `loadbinaryunicodemapping` ([228](#)) function. The binary files have the `.bcm` extension and are produced by the `creumap` utility distributed with Free Pascal.

Pre-made units are available for the following codepages: `cp895` ([225](#)), `cp932` ([225](#)), `cp936` ([225](#)), `cp949` ([225](#)) and `cp950` ([225](#)).

3.3 Constants, types and variables

3.3.1 Constants

```
BINARY_MAPPING_FILE_EXT = '.bcm'
```

`BINARY_MAPPING_FILE_EXT` contains the default extension of a file containing a binary-coded map.

3.3.2 Types

```
preversecharmapping = ^treversecharmapping
```

Pointer to `treversecharmapping`

```
punicodecharmapping = ^tunicodecharmapping
```

Pointer to tunicodecharmapping

```
punicodemap = ^tunicodemap
```

Pointer to tunicodemap

```
treversecharmapping = packed record
  unicode : tunicodechar;
  char1
  : Byte;
  char2 : Byte;
end
```

treversecharmapping describes how a unicode character can be created in terms of single-byte characters.

```
TSerializedMapHeader = packed record
  cpName : string;
  cp : UInt16
  ;
  mapLength : UInt32;
  lastChar : Int32;
  reverseMapLength : UInt32
  ;
end
```

TSerializedMapHeader is a record describing the binary map data file. The contents of this record can be found at offset zero of a (.bcm) file containing a single-byte unicode map.

```
tunicodechar = Word
```

tunicodechar is a type used to represent unicode characters in this file, it should not be used for other unicode routines.

```
tunicodecharmapping = packed record
  unicode : tunicodechar;
  flag
  : tunicodecharmappingflag;
  reserved : Byte;
end
```

tunicodecharmapping describes a unicode character. An array of these mappings is built for each character in the single-byte character set,

```
tunicodecharmappingflag = (umf_noinfo, umf_leadbyte, umf_undefined,
  umf_unused)
```

Table 3.2: Enumeration values for type `tunicodecharmappingflag`

Value	Explanation
<code>umf_leadbyte</code>	Unicode character uses leading byte
<code>umf_noinfo</code>	No extra information about unicode character
<code>umf_undefined</code>	Currently unused
<code>umf_unused</code>	Unused position in code page

`tunicodecharmappingflag` contains various Flags describing information about a unicode character.

```
tunicodemap = record
  cpname : string;
  cp : Word;
  map : punicodecharmapping
;
  lastchar : LongInt;
  reversemap : preversecharmapping;
  reversemaplength
  : LongInt;
  next : tunicodemap;
  internalmap : Boolean;
end
```

`tunicodemap` describes a complete mapping between a single-byte code page and a unicode character set. It contains both a forward and backward mapping.

```
tunicodestring = ^tunicodechar
```

`tunicodestring` is a type used to represent unicode strings in this file, it should not be used for other unicode routines.

3.4 Procedures and functions

3.4.1 `getascii`

Synopsis: Convert unicode character or string to single-byte character or string.

Declaration:

```
function getascii(c: tunicodechar; p: tunicodemap) : string
function getascii(c: tunicodechar; p: tunicodemap; ABuffer: PAnsiChar;
  ABufferLen: LongInt) : LongInt
```

Visibility: default

Description: `getascii` converts a unicode character `c` to one or more single-byte characters according to the map in `p`. The result can be a string containing up to 2 characters, or the number of characters copied to the buffer `ABuffer` with length `ABufferLen`.

Errors: If the character cannot be translated, ASCII character 63 is returned (or copied to the buffer). In the case of the buffer variant of the function, -1 is then returned. If the buffer is not large enough, -1 is returned.

See also: `getunicode` ([228](#))

3.4.2 getmap

Synopsis: Find a codepage map

Declaration: `function getmap(const s: string) : puniconemap`
`function getmap(cp: Word) : puniconemap`

Visibility: default

Description: `getmap` looks in the registered codepage mappings and returns the mapping for the requested codepage. The codepage can be specified using a name `s` or a numerical identifier `cp`. The search is case sensitive.

Errors: if the requested map is not found, `Nil` is returned.

See also: `registermapping` (230), `registerbinarymapping` (229), `mappingavailable` (229)

3.4.3 getunicode

Synopsis: Map single-byte character to unicode character.

Declaration: `function getunicode(c: Char; p: puniconemap) : tuniconedchar`
`function getunicode(AAnsiStr: PAnsiChar; AAnsiLen: LongInt;`
`AMap: puniconemap; ADest: tuniconestring) : LongInt`

Visibility: default

Description: The first form of `getunicode` will map a single character `c` to its unicode equivalent for mapping `p`. If no equivalent can be found, 0 is returned.

The second form of `getunicode` will transform a string (specified using a pointer `AAnsiStr` to a buffer with length `AAnsiLen`) to a unicode string using single byte codepage map `AMap`. It returns the number of unicode characters. If `ADest` is `Nil` then just the number of characters is returned. If `ADest` is not `nil`, it must point to a buffer large enough to contain the unicode string, and the converted string will be copied to it.

Errors: No checking on the validity of the buffers is done.

See also: `getascii` (227)

3.4.4 loadbinaryunicodemapping

Synopsis: Load binary single-byte codepage to unicode map from file or memory

Declaration: `function loadbinaryunicodemapping(const directory: string;`
`const cpname: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const filename: string) : puniconemap`
`; Overload`
`function loadbinaryunicodemapping(const AData: Pointer;`
`const ADataLength: Integer)`
`: puniconemap; Overload`

Visibility: default

Description: `loadbinaryunicodemapping` loads a binary description of a single-byte unicode mapping. The mapping can reside in a file, in which case the file to load can be specified using a filename `filename` or using a directory `directory` and codepage name `cpname`. In the latter case, a

suffix consisting of `_le` or `_be` depending on the endianness of the current platform will be appended, and the filename extension is `.bcm`. Note that the file names may be case sensitive.

The data can also be loaded from a memory block `AData` with size `ADataLength`.

It will produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The resulting mapping can be registered using [registermapping \(230\)](#).

Errors: On error, `Nil` is returned.

See also: [loadunicodemapping \(229\)](#), [registermapping \(230\)](#)

3.4.5 loadunicodemapping

Synopsis: Load textual single-byte codepage to unicode map from file

Declaration: `function loadunicodemapping(const cpname: string; const f: string;
cp: Word) : puniconemap`

Visibility: default

Description: `loadunicodemapping` loads a text description of a single-byte unicode mapping. It will analyse the textual description in file `f`, and produce an in-memory map of the file. It returns a pointer to the map, or `Nil` if something went wrong. The unicode map name must be specified in `cpName`, and the numerical identifier in `cp`

The resulting mapping can be registered using [registermapping \(230\)](#).

Errors: On error, `Nil` is returned.

See also: [loadbinaryunicodemapping \(228\)](#), [registermapping \(230\)](#)

3.4.6 mappingavailable

Synopsis: Check if a mapping is available for a specified code page.

Declaration: `function mappingavailable(const s: string) : Boolean
function mappingavailable(cp: Word) : Boolean`

Visibility: default

Description: `mappingavailable` returns `True` if a mapping for a specified code page (using name `s` or numerical identifier `cp`) is available, or `False` if it is not.

See also: [registermapping \(230\)](#), [registerbinarymapping \(229\)](#), [getmap \(228\)](#)

3.4.7 registerbinarymapping

Synopsis: Load and register binary single-byte codepage to unicode map from file

Declaration: `function registerbinarymapping(const directory: string;
const cpname: string) : Boolean`

Visibility: default

Description: `registerbinarymapping` calls [loadbinaryunicodemapping \(228\)](#) using `directory` and `cpname` and registers the resulting mapping, if any was successfully loaded, using [registermapping \(230\)](#). It returns `True` if the operation was successful.

Errors: On error, `False` is returned.

See also: [loadbinaryunicodemapping \(228\)](#), [registermapping \(230\)](#)

3.4.8 registermapping

Synopsis: Register mapping

Declaration: `procedure registermapping(p: punicomemap)`

Visibility: default

Description: `RegisterMapping` registers mapping `p` in the registry of single-byte codepages. No attempt is made to avoid double registrations. In case of doubles, the last registered mapping will be used first.

See also: `loadunicodemapping` ([229](#)), `loadbinaryunicodemapping` ([228](#)), `registerbinarymapping` ([229](#))

Chapter 4

Reference for unit 'Classes'

4.1 Used units

Table 4.1: Used units by unit 'Classes'

Name	Page
rtlconsts	??
System	1194
sysutils	1442
Types	1722
typinfo	1759

4.2 Overview

This documentation describes the FPC `classes` unit. The `Classes` unit contains basic classes for the Free Component Library (FCL):

- a `TList` ([370](#)) class for maintaining lists of pointers,
- `TStringList` ([424](#)) for lists of strings,
- `TCollection` ([320](#)) to manage collections of objects
- `TStream` ([409](#)) classes to support streaming.

Furthermore it introduces methods for object persistence, and classes that understand an owner-owned relationship, with automatic memory management.

4.3 Constants, types and variables

4.3.1 Constants

`BITSHIFT` = 5

Used to calculate the size of a bits array

`dupAccept = Types.dupAccept`

Duplicate values can be added to the list.

`dupError = Types.dupError`

If an attempt is made to add a duplicate value to the list, an `EStringListError` (268) exception is raised.

`dupIgnore = Types.dupIgnore`

Duplicate values will not be added to the list, but no error will be triggered.

`FilerSignature : Array[1..4] of Char = 'TPF0'`

Constant that is found at the start of a binary stream containing a streamed component.

`fmCreate = $FF00`

`TFileStream.Create` (350) creates a new file if needed.

`fmOpenRead = 0`

`TFileStream.Create` (350) opens a file with read-only access.

`fmOpenReadWrite = 2`

`TFileStream.Create` (350) opens a file with read-write access.

`fmOpenWrite = 1`

`TFileStream.Create` (350) opens a file with write-only access.

`MASK = 31`

Bitmask with all bits on.

`MaxBitFlags = $7FFFFFFE0`

Maximum number of bits in `TBits` collection.

`MaxBitRec = MaxBitFlags div ((cardinal) * 8)`

Maximum number of bit records in `TBits`.

`MaxListSize = Maxint div 16`

This constant sets the maximum number of elements in a `TList` (370).

`scAlt = $8000`

Indicates ALT key in a keyboard shortcut.

```
scCtrl = $4000
```

indicates CTRL key in a keyboard shortcut.

```
scNone = 0
```

Indicates no special key is pressed in a keyboard shortcut.

```
scShift = $2000
```

Indicates Shift key in a keyboard shortcut.

```
SGUIDObserved = '{663C603C-3F3C-4CC5-823C-AC8079F979E5}'
```

Observed interface GUID as a string

```
SGUIDObserver = '{BC7376EA-199C-4C2A-8684-F4805F0691CA}'
```

Observer interface GUID as a string

```
soFromBeginning = 0
```

Seek (411) starts relative to the stream origin.

```
soFromCurrent = 1
```

Seek (411) starts relative to the current position in the stream.

```
soFromEnd = 2
```

Seek (411) starts relative to the stream end.

```
toEOF = (0)
```

Value returned by TParser.Token (389) when the end of the input stream was reached.

```
toFloat = (4)
```

Value returned by TParser.Token (389) when a floating point value was found in the input stream.

```
toInteger = (3)
```

Value returned by TParser.Token (389) when an integer was found in the input stream.

```
toString = (2)
```

Value returned by TParser.Token (389) when a string was found in the input stream.

```
toSymbol = (1)
```

Value returned by TParser.Token (389) when a symbol was found in the input stream.

```
toWString = (5)
```

Value returned by TParser.Token (389) when a widestring was found in the input stream.

4.3.2 Types

`HMODULE = PtrInt`

FPC doesn't support modules yet, so this is a dummy type.

`HRSRC = TFPResourceHandle deprecated`

This type is provided for Delphi compatibilty, it is used for resource streams.

`PPointerList = ^TPointerList`

Pointer to an array of pointers.

`PStringItem = ^TStringItem`

Pointer to a `TStringItem` (245) record.

`PStringItemList = ^TStringItemList`

Pointer to a `TStringItemList` (245).

`TActiveXRegType = (axrComponentOnly, axrIncludeDescendants)`

Table 4.2: Enumeration values for type `TActiveXRegType`

Value	Explanation
<code>axrComponentOnly</code>	
<code>axrIncludeDescendants</code>	

This type is provided for compatibility only, and is currently not used in Free Pascal.

`TAlignment = (taLeftJustify, taRightJustify, taCenter)`

Table 4.3: Enumeration values for type `TAlignment`

Value	Explanation
<code>taCenter</code>	Text is displayed centered.
<code>taLeftJustify</code>	Text is displayed aligned to the left
<code>taRightJustify</code>	Text is displayed aligned to the right.

The `TAlignment` type is used to specify the alignment of the text in controls that display a text.

```
TAncestorNotFoundEvent = procedure(Reader: TReader;
  const ComponentName: string;
  ComponentClass: TPersistentClass;
  var Component: TComponent) of object
```

This event occurs when an ancestor component cannot be found.

`TBasicActionClass = Class of TBasicAction`

`TBasicAction` (294) class reference.

`TBasicActionLinkClass = Class of TBasicActionLink`

`TBasicActionLink` (298) class reference.

`TBiDiMode = (bdLeftToRight, bdRightToLeft, bdRightToLeftNoAlign,
bdRightToLeftReadingOnly)`

Table 4.4: Enumeration values for type `TBiDiMode`

Value	Explanation
<code>bdLeftToRight</code>	Texts read from left to right.
<code>bdRightToLeft</code>	Texts read from right to left.
<code>bdRightToLeftNoAlign</code>	Texts read from right to left, but not right-aligned
<code>bdRightToLeftReadingOnly</code>	Texts read from right to left

`TBiDiMode` describes bi-directional support for displaying texts.

`TBitArray = Array[0..MaxBitRec-1] of Cardinal`

Array to store bits.

`TCollectionItemClass = Class of TCollectionItem`

`TCollectionItemClass` is used by the `TCollection.ItemClass` (326) property of `TCollection` (320) to identify the descendant class of `TCollectionItem` (328) which should be created and managed.

`TCollectionNotification = (cnAdded, cnExtracting, cnDeleting)`

Table 4.5: Enumeration values for type `TCollectionNotification`

Value	Explanation
<code>cnAdded</code>	An item is added to the collection.
<code>cnDeleting</code>	An item is deleted from the collection.
<code>cnExtracting</code>	An item is extracted from the collection.

`TCollectionNotification` is used in the `TCollection` (320) class to send notifications about changes to the collection.

`TCollectionSortCompare = function(Item1: TCollectionItem;
Item2: TCollectionItem) : Integer`

`TCollectionSortCompare` is the prototype for a callback used in the `TCollection.Sort` (325) method. The procedure should compare `Item1` and `Item2` and return an integer:

Result < 0 if `Item1` comes before `Item2`

Result = 0 if `Item1` is at the same level as `Item2`

Result > 0 if `Item1` comes after `Item2`

`TComponentClass = Class of TComponent`

The `TComponentClass` type is used when constructing `TComponent` (330) descendant instances and when registering components.

`TComponentName = String`

Names of components are of type `TComponentName`. By specifying a different type, the Object inspector can handle this property differently than a standard string property.

```
TComponentState= Set of (csLoading,csReading,csWriting,csDestroying
,
                        csDesigning,csAncestor,csUpdating,csFixups
,
                        csFreeNotification,csInline,csDesignInstance
)
```

Table 4.6: Enumeration values for type

Value	Explanation
<code>csAncestor</code>	The component is being streamed as part of a frame (?)
<code>csDesigning</code>	The component is being designed in an IDE.
<code>csDesignInstance</code>	??
<code>csDestroying</code>	The component is being destroyed.
<code>csFixups</code>	The component's references to other components are being fixed.
<code>csFreeNotification</code>	Indicates whether the component has freenotifications
<code>csInline</code>	Component is part of a frame (?).
<code>csLoading</code>	The component is being loaded from the stream.
<code>csReading</code>	Properties are being read from the stream.
<code>csUpdating</code>	The component is being updated.
<code>csWriting</code>	Properties are being written to the stream.

The following values are possible:

csLoading The component (and all child components) are being loaded from a stream. This means that a `TReader` (394) instance is reading properties from this and child components from a stream and is applying the values found in the stream to the properties.

csReading The properties of this component are being read from a stream. This means that a `TReader` (394) instance is reading properties from this component from a stream and is applying the values.

csWriting The properties of this component are being written to a stream. This means that a `TWriter` (466) instance is writing properties from this component to a stream.

csDestroying The component is being destroyed.

csDesigning The component is being designed in an IDE.

csAncestor The component has a design ancestor. This is used to record differences between a component and its design ancestor. For example a form `TForm2` inherited from a form `TForm1`. `TForm1` and all its components are copied to `TForm2`. `TForm2` and all its inherited components have `csAncestor` set. Only differences between `TForm1` and `TForm2` are stored in the stream of `TForm2`. The child components of a frame put onto a form have `csAncestor` too.

csInline The component is a nested top level component. For example a frame on a form. The children of the frame do not have `csInline`, unless they are other frames.

csDesignInstance The component is designed (`csDesigning`) and is a root component, meaning it has no owner (`Owner=nil`).

csFixups The component's references to other components are being fixed. While reading a component from stream, it can happen that the stream contains a component reference property with a name of a component that was not yet created and read from the stream. Such properties are saved, and the missing references are resolved when the complete stream was read. This resolving step is called fixing up references, and the `csFixups` flag is set during this step.

csFreeNotification This flag indicates that the component has free notifications registered with `TComponent.FreeNotification` (334)

```
TComponentStyle= Set of (csInheritable,csCheckPropAvail,csSubComponent
,
                        csTransient)
```

Table 4.7: Enumeration values for type

Value	Explanation
<code>csCheckPropAvail</code>	??
<code>csInheritable</code>	The component can be on inherited forms.
<code>csSubComponent</code>	Subcomponent - streamed as part of the owning component
<code>csTransient</code>	Transient component

Describes the style of the component.

```
TCreateComponentEvent = procedure(Reader: TReader;
  ComponentClass: TComponentClass;
  var Component: TComponent) of object
```

Event handler type, occurs when a component instance must be created when a component is read from a stream.

```
TDataModuleClass = Class of TDataModule
```

`TDataModuleClass` defines the class pointer for `TDataModule` (344).

`TDuplicates = Types.TDuplicates`

Type to describe what to do with duplicate values in a `TStringlist` (424).

`TExceptionClass = Class of Exception`

`TExceptionClass` is the class pointer for the `Exception` (1623) class, defined in the `SysUtils` (1442) unit.

`TFilerFlag = (ffInherited, ffChildPos, ffInline)`

Table 4.8: Enumeration values for type `TFilerFlag`

Value	Explanation
<code>ffChildPos</code>	The position of the child on it's parent is included.
<code>ffInherited</code>	Stored object is an inherited object.
<code>ffInline</code>	Used for frames.

The `TFiler` class uses this enumeration type to decide whether the streamed object was streamed as part of an inherited form or not.

`TFilerFlags = Set of TFilerFlag`

Set of `TFilerFlag` (238)

```
TFindAncestorEvent = procedure(Writer: TWriter; Component: TComponent
;
                                const Name: string;
    var Ancestor: TComponent;
    var RootAncestor: TComponent) of object
```

Event that occurs w

```
TFindComponentClassEvent = procedure(Reader: TReader;
    const ClassName: string;
    var ComponentClass: TComponentClass)
of object
```

Event handler type, occurs when a component class pointer must be found when reading a component from a stream.

`TFindGlobalComponent = function(const Name: string) : TComponent`

`TFindGlobalComponent` is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

The variable `FindGlobalComponent` (253) is a callback of type `TFindGlobalComponent`. It can be set by the IDE when an unknown reference is found, to offer the designer to redirect the link to a new component.

```
TFindMethodEvent = procedure(Reader: TReader; const MethodName: string
;
                                var Address: CodePointer;
var Error: Boolean) of object
```

If a `TReader` (394) instance needs to locate a method and it doesn't find it in the streamed form, then the `OnFindMethod` (405) event handler will be called, if one is installed. This event can be assigned in order to use different locating methods. If a method is found, then its address should be returned in `Address`. The `Error` should be set to `True` if the reader should raise an exception after the event was handled. If it is set to `False` no exception will be raised, even if no method was found. On entry, `Error` will be set to `True`.

```
TFPObservedOperation = (ooChange, ooFree, ooAddItem, ooDeleteItem, ooCustom
)
```

Table 4.9: Enumeration values for type `TFPObservedOperation`

Value	Explanation
<code>ooAddItem</code>	An item is added to the observed object (generally a list).
<code>ooChange</code>	The observed object has changed.
<code>ooCustom</code>	Custom event.
<code>ooDeleteItem</code>	An item is deleted from the observed object (generally a list).
<code>ooFree</code>	The observed object is being freed.

`TFPObservedOperation` enumerates the possible operations that can be reported to an observer. Which of these operations is reported depends on the implementation of the observed object.

```
TGetChildProc = procedure(Child: TComponent) of object
```

Callback used when obtaining child components.

```
TGetStrProc = procedure(const S: string) of object
```

This event is used as a callback to retrieve string values. It is used, among other things, to pass along string properties in property editors.

```
THandle = System.THandle
```

This type is used as the handle for `THandleStream` (360) stream descendants

```
THelpContext = -MaxLongint..MaxLongint
```

Range type to specify help contexts.

```
THelpEvent = function(Command: Word; Data: LongInt;
var CallHelp: Boolean) : Boolean of object
```

This event is used for display of online help.

```
THelpType = (htKeyword, htContext)
```


Table 4.10: Enumeration values for type THelpType

Value	Explanation
htContext	Help type: Context ID help.
htKeyword	Help type: Keyword help

Enumeration type specifying the kind of help requested.

```
TIdentMapEntry = record
  Value : Integer;
  Name : string;
end
```

TIdentMapEntry is used internally by the [IdentToInt \(255\)](#) and [IntToIdent \(256\)](#) calls to store the mapping between the identifiers and the integers they represent.

```
TIdentToInt = function(const Ident: string; var Int: LongInt) :
  Boolean
```

TIdentToInt is a callback used to look up identifiers (Ident) and return an integer value corresponding to this identifier (Int). The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIdentToInt should be specified when an integer is registered using the [RegisterIntegerConsts \(261\)](#) call.

```
TInitComponentHandler = function(Instance: TComponent;
  RootAncestor: TClass) : Boolean
```

TInitComponentHandler is a callback type. It is used in the [InitInheritedComponent \(256\)](#) call to initialize a component. Callbacks of this type are registered with the [RegisterInitComponentHandler \(261\)](#) call.

```
TIntToIdent = function(Int: LongInt; var Ident: string) : Boolean
```

TIntToIdent is a callback used to look up integers (Ident) and return an identifier (Ident) that can be used to represent this integer value in an IDE. The callback should return True if a value corresponding to integer Ident was found, False if not.

A callback of type TIntToIdent should be specified when an integer is registered using the [RegisterIntegerConsts \(261\)](#) call.

```
TLeftRight = taLeftJustify..taRightJustify
```

TLeftRight is a subrange type based on the [TAlignment \(234\)](#) enumerated type. It contains only the left and right alignment constants.

```
TListAssignOp = (laCopy, laAnd, laOr, laXor, laSrcUnique, laDestUnique
  )
```

Table 4.11: Enumeration values for type TListAssignOp

Value	Explanation
laAnd	Remove all elements not first second list
laCopy	Clear list and copy all strings from second list.
laDestUnique	Keep all elements that exists only in list2
laOr	Add all elements from second (and optional third) list, eliminate duplicates
laSrcUnique	Just keep all elements that exist only in source list
laXor	Remove elements in second lists, Add all elements from second list not in first list

This type determines what operation TList.Assign (376) or TFPList.assign (356) performs.

```
TListCallback = Types.TListCallback
```

TListCallback is the method callback prototype for the function that is passed to the TFPList.ForEachCall (357) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TListNotification = (lnAdded, lnExtracted, lnDeleted)
```

Table 4.12: Enumeration values for type TListNotification

Value	Explanation
lnAdded	List change notification: Element added to the list.
lnDeleted	List change notification: Element deleted from the list.
lnExtracted	List change notification: Element extracted from the list.

Kind of list notification event.

```
TListSortCompare = function(Item1: Pointer; Item2: Pointer) :  
    Integer
```

Callback type for the list sort algorithm.

```
TListStaticCallback = Types.TListStaticCallback
```

TListCallback is the procedural callback prototype for the function that is passed to the TFPList.ForEachCall (357) call. The data argument will be filled with all the pointers in the list (one per call) and the arg argument is the Arg argument passed to the ForEachCall call.

```
TNotifyCallBack = procedure(Sender: TObject; AData: Pointer)
```

TNotifyCallBack is used to notify about thread termination when using static callbacks. When called, the Sender will contain the thread which is terminating, and AData is the AData parameter passed to TThread.ExecuteInThread (454).

```
TNotifyEvent = procedure(Sender: TObject) of object
```

Most event handlers are implemented as a property of type `TNotifyEvent`. When this is set to a certain method of a class, when the event occurs, the method will be called, and the class that generated the event will pass itself along as the `Sender` argument.

`TObjectTextEncoding = (oteDFM, oteLFM)`

Table 4.13: Enumeration values for type `TObjectTextEncoding`

Value	Explanation
<code>oteDFM</code>	Characters are in DFM (Delphi) format: widechar encoded.
<code>oteLFM</code>	Characters are in LFM format: UTF-8 encoded.

`TObjectTextEncoding` is an enumerated type which denotes the encoding of non ascii characters in an object stream file. It is needed for correct encoding when reading string values in the text stream.

`TOperation = (opInsert, opRemove)`

Table 4.14: Enumeration values for type `TOperation`

Value	Explanation
<code>opInsert</code>	A new component is being inserted in the child component list.
<code>opRemove</code>	A component is being removed from the child component list.

Operation of which a component is notified.

`TPersistentClass = Class of TPersistent`

`TPersistentClass` is the class reference type for the `TPersistent` (390) class.

`TPoint = Types.TPoint`

This record describes a coordinate. It is used to handle the `Top` (330) and `Left` (330) properties of `TComponent` (330).

`X` represents the X-Coordinate of the point described by the record. `Y` represents the Y-Coordinate of the point described by the record.

`TPointerList = Array[0..MaxListSize-1] of Pointer`

Type for an Array of pointers.

```

TPropertyNotFoundEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  var PropName: string;
  IsPath: Boolean;
  var
    Handled: Boolean;
    var Skip: Boolean
  ) of object

```

`TPropertyNotFoundEvent` is the prototype for the `TReader.OnPropertyNotFound` (404) event. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Handled` should be set to `True` if the handler redirected the unknown property successfully, and `Skip` should be set to `True` if the value should be skipped. `IsPath` determines whether the property refers to a sub-property.

```
TReadComponentsProc = procedure(Component: TComponent) of object
```

Callback type when reading a component from a stream

```
TReaderError = procedure(Reader: TReader; const Message: string;
    var Handled: Boolean) of object
```

Event handler type, called when an error occurs during the streaming.

```
TReaderProc = procedure(Reader: TReader) of object
```

The `TReaderProc` reader procedure is a callback procedure which will be used by a `TPersistent` (390) descendant to read user properties from a stream during the streaming process. The `Reader` argument is the writer object which can be used read properties from the stream.

```
TReadWriteStringPropertyEvent = procedure(Sender: TObject;
    const Instance: TPersistent;
    PropInfo: PPropInfo;
    var Content: string) of
    object
```

`TReadWriteStringPropertyEvent` is the prototype for the `TReader.OnReadStringProperty` (406) event handler. `Reader` is the sender of the event, `Instance` is the instance that is being streamed. `PropInfo` is a pointer to the RTTI information for the property being read. `Content` is the string as it was read from the stream.

```
TRect = Types.TRect
```

`TRect` describes a rectangle in space with its upper-left (in `(Top,Left>)`) and lower-right (in `(Bottom,Right)`) corners.

```
TReferenceNameEvent = procedure(Reader: TReader; var Name: string
    )
                                of object
```

Occurs when a named object needs to be looked up.

```
TSeekOrigin = (soBeginning, soCurrent, soEnd)
```

Table 4.15: Enumeration values for type `TSeekOrigin`

Value	Explanation
<code>soBeginning</code>	Offset is interpreted relative to the start of the stream.
<code>soCurrent</code>	Offset is interpreted relative to the current position in the stream.
<code>soEnd</code>	Offset is interpreted relative to the end of the stream.

Specifies the origin of the `TStream.Seek` (411) method.

```
TSetMethodPropertyEvent = procedure(Reader: TReader;
  Instance: TPersistent;
  PropInfo: PPropInfo;
  const TheMethodName: string;
  var Handled: Boolean) of object
```

TSetMethodPropertyEvent is the prototype for the TReader.OnSetMethodProperty (405) event. Reader is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being read, and TheMethodName is the name of the method that the property should be set to. Handled should be set to True if the handler set the property successfully.

```
TSetNameEvent = procedure(Reader: TReader; Component: TComponent;
  var Name: string) of object
```

Occurs when the reader needs to set a component's name.

```
TShiftState = Set of TShiftStateEnum
```

This type is used when describing a shortcut key or when describing what special keys are pressed on a keyboard when a key event is generated.

The set contains the special keys that can be used in combination with a 'normal' key.

```
TShiftStateEnum = (ssShift, ssAlt, ssCtrl, ssLeft, ssRight, ssMiddle,
  ssDouble, ssMeta, ssSuper, ssHyper, ssAltGr, ssCaps
  , ssNum,
  ssScroll, ssTriple, ssQuad, ssExtra1, ssExtra2
  )
```

Table 4.16: Enumeration values for type TShiftStateEnum

Value	Explanation
ssAlt	Alt key pressed
ssAltGr	Alt-GR key pressed.
ssCaps	Caps lock key pressed
ssCtrl	Ctrl key pressed
ssDouble	Double mouse click.
ssExtra1	Extra key 1
ssExtra2	Extra key 2
ssHyper	Hyper key pressed.
ssLeft	Left mouse button pressed.
ssMeta	Meta key pressed.
ssMiddle	Middle mouse button pressed.
ssNum	Num lock key pressed
ssQuad	Quadruple mouse click
ssRight	Right mouse button pressed.
ssScroll	Scroll lock key pressed
ssShift	Shift key pressed
ssSuper	Super key pressed.
ssTriple	Triple mouse click

Keyboard/Mouse shift state enumerator

```
TShortCut = (Word) .. (Word)
```

Enumeration type to identify shortcut key combinations.

```
TSmallPoint = record
  x : SmallInt;
  y : SmallInt;
end
```

Same as TPoint (242), only the X and Y ranges are limited to 2-byte integers instead of 4-byte integers.

```
TStreamOwnership = (soReference, soOwned)
```

Table 4.17: Enumeration values for type TStreamOwnership

Value	Explanation
soOwned	Stream is owned; it will be freed when the adapter is freed.
soReference	Stream is referenced only, it is not freed by the adapter

The ownership of a streamadapter determines what happens with the stream on which a TStreamAdapter (419) acts, when the adapter is freed.

```
TStreamProc = procedure(Stream: TStream) of object
```

Procedure type used in streaming.

```
TStringItem = record
  FString : string;
  FObject : TObject;
end
```

The TStringItem is used to store the string and object items in a TStringList (424) string list instance. It should never be used directly.

```
TStringItemList = Array[0..MaxListSize] of TStringItem
```

This declaration is provided for Delphi compatibility, it is not used in Free Pascal.

```
TStringListSortCompare = function(List: TStringList; Index1: Integer
;
                                Index2: Integer) : Integer
```

Callback type used in stringlist compares.

```
TStringsSortStyle = (sslNone, sslUser, sslAuto)
```

Table 4.18: Enumeration values for type TStringsSortStyle

Value	Explanation
sslAuto	The TStrings instance keeps the strings sorted.
sslNone	The strings are not sorted
sslUser	The strings are kept sorted by the user.

TStringsSortStyle is the type used in the TStringList.SortStyle (429) property, and describes how the strings are sorted when the TStringList.Sorted (427) property is True. It has the following values:

sslNone The strings are not sorted

sslUser The strings are kept sorted by the user.

sslAuto The TStrings instance keeps the strings sorted.

TStringsSortStyles = Set of TStringsSortStyle

TStringsSortStyles is the set type for enumeration TStringsSortStyle (246).

TSynchronizeProcVar = procedure

Synchronize callback type

TThreadExecuteCallBack = procedure (AData: Pointer)

TThreadExecuteCallBack is the signature of the static procedure to be used when executing something in a thread using TThread.ExecuteInThread (454) when no status reporting is required.

TThreadExecuteHandler = TThreadMethod

TThreadExecuteHandler is the signature of the method to be used when executing something in a thread using TThread.ExecuteInThread (454) when no status reporting is required.

```
TThreadExecuteStatusCallBack = procedure (AData: Pointer;
  ReportStatus: TThreadReportStatus
)
```

TThreadExecuteStatusCallBack is the signature of a procedure to be used when executing something in a thread using TThread.ExecuteInThread (454) when status reporting is required.

On entry in the method, AData is the AData parameter passed to TThread.ExecuteInThread (454). ReportStatus is passed to the method, and the threaded procedure can call ReportStatus at various stages to report about the status of the method: The status will be reported to the main thread using TThread.synchronize (451), so calls to ReportStatus will be blocked as long as the status was not reported.

```
TThreadExecuteStatusHandler = procedure
  (ReportStatus: TThreadReportStatus)
  of object
```

`TThreadExecuteStatusHandler` is the signature of the method to be used when executing something in a thread using `TThread.ExecuteInThread` (454) when status reporting is required.

On entry in the method, `ReportStatus` is passed to the method, and the method can call `ReportStatus` at various stages to report about the status of the method: The status will be reported to the main thread using `TThread.synchronize` (451), and calls `ReportStatus` will be blocked as long as the status was not reported.

```
TThreadMethod = procedure of object
```

Procedure variable used when synchronizing threads.

```
TThreadPriority = (tpIdle, tpLowest, tpLower, tpNormal, tpHigher, tpHighest
,
                    tpTimeCritical)
```

Table 4.19: Enumeration values for type `TThreadPriority`

Value	Explanation
<code>tpHigher</code>	Thread runs at high priority
<code>tpHighest</code>	Thread runs at highest possible priority.
<code>tpIdle</code>	Thread only runs when other processes are idle.
<code>tpLower</code>	Thread runs at a lower priority.
<code>tpLowest</code>	Thread runs at the lowest priority.
<code>tpNormal</code>	Thread runs at normal process priority.
<code>tpTimeCritical</code>	Thread runs at realtime priority.

Enumeration specifying the priority at which a thread runs.

```
TThreadReportStatus = procedure(const status: string) of object
```

`TThreadReportStatus` is the callback prototype for the `TThread.ExecuteInThread` (454) method. This callback is used to report thread status to the main thread: the `Status` string can be used to report the status of thread execution.

```
TThreadStatusNotifyCallBack = procedure(Sender: TThread;
    AData: Pointer;
    const status: string)
```

`TThreadStatusNotifyCallBack` is the signature of the callback to be provided when executing a static procedure in a thread using `TThread.ExecuteInThread` (454) when status reporting is required.

This callback will be called in the main thread. When called, it has the thread whose status is reported in `Sender`, `AData` is the `AData` parameter passed to `TThread.ExecuteInThread` (454). Finally, the status message in `ReportStatus` is passed to the callback.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using `TThread.synchronize` (451).

```
TThreadStatusNotifyEvent = procedure(Sender: TThread;
    const status: string) of object
```


`TThreadStatusNotifyEvent` is the signature of the method to be provided when executing something in a thread using `TThread.ExecuteInThread` (454) when status reporting is required.

This event handler will be called in the main thread. When called, it has the thread whose status is reported in `Sender`, and the status message in `ReportStatus` is passed to the method.

Note that the thread reporting its status is blocked while the callback is being handled: The status is be reported to the main thread using `TThread.synchronize` (451).

```
TValueType = (vaNull, vaList, vaInt8, vaInt16, vaInt32, vaExtended, vaString
,
    vaIdent, vaFalse, vaTrue, vaBinary, vaSet, vaLString, vaNil
,
    vaCollection, vaSingle, vaCurrency, vaDate, vaWString
, vaInt64,
    vaUTF8String, vaUString, vaQWord)
```

Table 4.20: Enumeration values for type `TValueType`

Value	Explanation
<code>vaBinary</code>	Binary data follows.
<code>vaCollection</code>	Collection follows
<code>vaCurrency</code>	Currency value follows
<code>vaDate</code>	Date value follows
<code>vaExtended</code>	Extended value.
<code>vaFalse</code>	Boolean False value.
<code>vaIdent</code>	Identifier.
<code>vaInt16</code>	Integer value, 16 bits long.
<code>vaInt32</code>	Integer value, 32 bits long.
<code>vaInt64</code>	Integer value, 64 bits long.
<code>vaInt8</code>	Integer value, 8 bits long.
<code>vaList</code>	Identifies the start of a list of values
<code>vaLString</code>	Ansistring data follows.
<code>vaNil</code>	Nil pointer.
<code>vaNull</code>	Empty value. Ends a list.
<code>vaQWord</code>	QWord (64-bit word) value
<code>vaSet</code>	Set data follows.
<code>vaSingle</code>	Single type follows.
<code>vaString</code>	String value.
<code>vaTrue</code>	Boolean True value.
<code>vaUString</code>	UnicodeString value
<code>vaUTF8String</code>	UTF8 encoded unicode string.
<code>vaWString</code>	Widestring value follows.

Enumerated type used to identify the kind of streamed property

```
TWriteMethodPropertyEvent = procedure(Writer: TWriter;
    Instance: TPersistent;
    PropInfo: PPropInfo;
    const MethodValue: TMethod;
    const DefMethodValue: TMethod;
    var Handled: Boolean) of object
```

TWriteMethodPropertyEvent is the prototype for the TWriter.OnWriteMethodProperty (473) event. Writer is the sender of the event, Instance is the instance that is being streamed. PropInfo is a pointer to the RTTI information for the property being written, and MethodValue is the value of the method that the property was set to. DefMethodCodeValue is set to the default value of the property (Nil or the parent value). Handled should be set to True if the handler set the property successfully.

TWriterProc = procedure(Writer: TWriter) of object

The TWriterProc writer procedure is a callback procedure which will be used by a TPersistent (390) descendant to write user properties from a stream during the streaming process. The Writer argument is the writer object which can be used write properties to the stream.

4.3.3 Variables

AddDataModule : procedure(DataModule: TDataModule) of object

AddDataModule can be set by an IDE or a streaming mechanism to receive notification when a new instance of a TDataModule (344) descendant is created.

ApplicationHandleException : procedure(Sender: TObject) of object

ApplicationHandleException can be set by an application object to handle any exceptions that may occur when a TDataModule (344) is created.

ApplicationShowException : procedure(E: Exception) of object

Unused.

CreateVCLComObjectProc : procedure(Component: TComponent) = Nil

CreateVCLComObjectProc is called by TComponent if it needs to create a IVCLComObject interface for itself (when the ComObject property is read). It passes itself as the Component parameter.

GlobalNameSpace : IReadWriteSync

An interface protecting the global namespace. Used when reading/writing to the global namespace list during streaming of forms.

MainThreadID : TThreadID

ID of main thread. Unused at this point.

RegisterComponentsProc : procedure(const Page: string;
ComponentClasses: Array of TComponentClass)

RegisterComponentsProc can be set by an IDE to be notified when new components are being registered. Application programmers should never have to set RegisterComponentsProc

RegisterNoIconProc : procedure(ComponentClasses: Array of TComponentClass
)

`RegisterNoIconProc` can be set by an IDE to be notified when new components are being registered, and which do not need an Icon in the component palette. Application programmers should never have to set `RegisterComponentsProc`

`RemoveDataModule` : procedure(`DataModule`: `TDataModule`) of object

`RemoveDataModule` can be set by an IDE or a streaming mechanism to receive notification when an instance of a `TDataModule` (344) descendant is freed.

`WakeMainThread` : `TNotifyEvent` = Nil

`WakeMainThread` is a handler, which, when set, is called by the `TThread.Synchronize` (451) routine to signal the main thread that a synchronization routine is waiting in the queue.

This handler is by default empty. An actual implementation depends on the main program logic (usually an event loop) and must be provided by the event loop logic: the event loop will normally call `CheckSynchronize` (251) at regular intervals. The `WakeMainThread` can make sure this happens as soon as possible.

While this handle should alert the main program thread that a thread is waiting for synchronization, the call is executed by the thread, and should therefore NOT synchronize the thread, but should somehow signal the main thread that a thread is waiting for synchronization. For example, by sending a message.

4.4 Procedures and functions

4.4.1 ActivateClassGroup

Synopsis: Activates a class group

Declaration: function `ActivateClassGroup`(`AClass`: `TPersistentClass`) : `TPersistentClass`

Visibility: default

Description: `ActivateClassGroup` activates the group of classes to which `AClass` belongs. The function returns the class that was last used to activate the class group.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

Errors: If `AClass` does not belong to a class group, an exception is raised.

See also: `StartClassGroup` (263), `GroupDescendantsWith` (231), `ClassGroupOf` (252)

4.4.2 BeginGlobalLoading

Synopsis: Not yet implemented

Declaration: procedure `BeginGlobalLoading`

Visibility: default

Description: Not yet implemented

4.4.3 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex (BinValue: PChar; HexValue: PChar;
BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size $2 * \text{BufSize}$.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `HexToBin` ([255](#))

4.4.4 Bounds

Synopsis: Returns a `TRect` structure with the bounding rect of the given location and size.

Declaration: `function Bounds (ALeft: Integer; ATop: Integer; AWidth: Integer;
AHeight: Integer) : TRect`

Visibility: default

Description: `Bounds` returns a `TRect` ([243](#)) record with the given origin (`ALeft`, `ATop`) and dimensions (`AWidth`, `AHeight`) filled in. The bottom-right corner is calculated by adding `AWidth` to `ALeft` and `AHeight` to `ATop`. As a result, a rectangle with width/height set to 0 is exactly 1 pixel.

See also: `Rect` ([259](#))

4.4.5 CheckSynchronize

Synopsis: Check whether there are any synchronize calls in the synchronize queue.

Declaration: `function CheckSynchronize (timeout: LongInt) : Boolean`

Visibility: default

Description: `CheckSynchronize` should be called regularly by the main application thread to handle any `TThread.Synchronize` ([451](#)) calls that may be waiting for execution by the main thread. If any such calls are waiting for execution by the main thread, they are executed at once, in the order that they were scheduled.

The function returns `True` if any `Synchronize` method was executed.

`TimeOut` is the maximum amount of time (in milliseconds) that the `CheckSynchronize` routine will wait for synchronisation requests to appear in the queue.

Calling this routine more often will ensure that synchronize requests are handled faster.

This routine may not be called from any thread other than the main thread, as it will execute the waiting requests.

Threads may call the `WakeMainThread` ([250](#)) to signal the main thread that the synchronisation queue contains items, and thus speed up the execution of the synchronize calls.

See also: `TThread.Synchronize` ([451](#)), `WakeMainThread` ([250](#))

4.4.6 ClassGroupOf

Synopsis: Returns the class group to which an instance or class belongs

Declaration: `function ClassGroupOf(AClass: TPersistentClass) : TPersistentClass`
`function ClassGroupOf(Instance: TPersistent) : TPersistentClass`

Visibility: default

Description: `ClassGroupOf` returns the class group to which `AClass` or `Instance` belongs.

Errors: The result is `Nil` if no matching class group is found.

See also: `StartClassGroup` ([263](#)), `ActivateClassGroup` ([250](#)), `GroupDescendantsWith` ([231](#))

4.4.7 CollectionsEqual

Synopsis: Returns `True` if two collections are equal.

Declaration: `function CollectionsEqual(C1: TCollection; C2: TCollection) : Boolean`
`function CollectionsEqual(C1: TCollection; C2: TCollection;`
`Owner1: TComponent; Owner2: TComponent)`
`: Boolean`

Visibility: default

Description: `CollectionsEqual` is not yet implemented. It simply returns `False`

4.4.8 EndGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure EndGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.9 ExtractStrings

Synopsis: Split a string in different words.

Declaration: `function ExtractStrings(Separators: TSysCharSet;`
`WhiteSpace: TSysCharSet; Content: PChar;`
`Strings: TStrings; AddEmptyStrings: Boolean)`
`: Integer`

Visibility: default

Description: `ExtractStrings` splits `Content` (a null-terminated string) into words, and adds the words to the `Strings` stringlist. The words are separated by `Separators` and any characters in `whitespace` are stripped from the strings. The space and CR/LF characters are always considered `whitespace`.

Errors: No length checking is performed on `Content`. If no null-termination character is present, an access violation may occur. Likewise, if `Strings` is not valid, an access violation may occur.

4.4.10 FindClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function FindClass(const AClassName: string) : TPersistentClass`

Visibility: default

Description: `FindClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, an exception is raised.

The `GetClass` (254) function does not raise an exception when it does not find the class, but returns a `Nil` pointer instead.

See also: `RegisterClass` (260), `GetClass` (254)

4.4.11 FindGlobalComponent

Synopsis: Callback used when a component must be found.

Declaration: `function FindGlobalComponent(const Name: string) : TComponent`

Visibility: default

Description: `FindGlobalComponent` is a callback of type `TFindGlobalComponent` (238). It can be set by the IDE when an unknown reference is found, to offer the user to redirect the link to a new component.

It is a callback used to find a component in a global scope. It is used when the streaming system needs to find a component which is not part of the component which is currently being streamed. It should return the component with name `Name`, or `Nil` if none is found.

See also: `TFindGlobalComponent` (238)

4.4.12 FindIdentToInt

Synopsis: Return the string to integer converter for an integer type

Declaration: `function FindIdentToInt(AIntegerType: Pointer) : TIdentToInt`

Visibility: default

Description: `FindIdentToInt` returns the handler that handles the conversion of a string representation to an integer that can be used in component streaming, when `IdentToInt` (255) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

4.4.13 FindIntToIdent

Synopsis: Return the integer to string converter for an integer type

Declaration: `function FindIntToIdent(AIntegerType: Pointer) : TIntToIdent`

Visibility: default

Description: `FindIntToIdent` returns the handler that handles the conversion of an integer to a string representation that can be used in component streaming, when `IntToIdent` (256) is called.

Errors: `Nil` is returned if no handler is registered for the given type.

See also: `IntToIdent` (256), `TIntToIdent` (240), `FindIdentToInt` (253)

4.4.14 FindNestedComponent

Synopsis: Finds the component with name path starting at the indicated root component.

Declaration: `function FindNestedComponent (Root: TComponent; APath: string;
CStyle: Boolean) : TComponent`

Visibility: default

Description: `FindNestedComponent` will descend through the list of owned components (starting at `Root`) and will return the component whose name path matches `NamePath`. As a path separator the characters `.` (dot), `-` (dash) and `>` (greater than) can be used

See also: `GlobalFixupReferences` ([255](#))

4.4.15 GetClass

Synopsis: Returns the class pointer of a class with given name.

Declaration: `function GetClass (const AClassName: string) : TPersistentClass`

Visibility: default

Description: `GetClass` searches for the class named `ClassName` in the list of registered classes and returns a class pointer to the definition. If no class with the given name could be found, `Nil` is returned.

The `FindClass` ([253](#)) function will raise an exception if it does not find the class.

See also: `RegisterClass` ([260](#)), `GetClass` ([254](#))

4.4.16 GetFixupInstanceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component, whose reference contains `ReferenceRootName`

Declaration: `procedure GetFixupInstanceNames (Root: TComponent;
const ReferenceRootName: string;
Names: TStrings)`

Visibility: default

Description: `GetFixupInstanceNames` examines the list of unresolved references and returns the names of classes that contain unresolved references to the `Root` component in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupReferenceNames` ([254](#)), `GlobalFixupReferences` ([255](#))

4.4.17 GetFixupReferenceNames

Synopsis: Returns the names of elements that need to be resolved for the `root` component.

Declaration: `procedure GetFixupReferenceNames (Root: TComponent; Names: TStrings)`

Visibility: default

Description: `GetFixupReferenceNames` examines the list of unresolved references and returns the names of properties that must be resolved for the component `Root` in the list `Names`. The list is not cleared prior to filling it.

See also: `GetFixupInstanceNames` ([254](#)), `GlobalFixupReferences` ([255](#))

4.4.18 GlobalFixupReferences

Synopsis: Called to resolve unresolved references after forms are loaded.

Declaration: `procedure GlobalFixupReferences`

Visibility: default

Description: `GlobalFixupReferences` runs over the list of unresolved references and tries to resolve them. This routine should under normal circumstances not be called in an application programmer's code. It is called automatically by the streaming system after a component has been instantiated and its properties read from a stream. It will attempt to resolve references to other global components.

See also: `GetFixupReferenceNames` (254), `GetFixupInstanceNames` (254)

4.4.19 GroupDescendentsWith

Synopsis: Provided for Delphi compatibility

Declaration: `procedure GroupDescendentsWith(AClass: TPersistentClass;
AClassGroup: TPersistentClass)`

Visibility: default

Description: `GroupDescendentsWith` exists for Delphi compatibility, it doesn't actually do anything in Free Pascal.

See also: `RegisterClasses` (260)

4.4.20 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer)
: Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` (251)

4.4.21 IdentToInt

Synopsis: Looks up an integer value in a integer-to-identifier map list.

Declaration: `function IdentToInt(const Ident: string; out Int: LongInt;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IdentToInt` searches `Map` for an entry whose `Name` field matches `Ident` and returns the corresponding integer value in `Int`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: `TIdentToInt` (240), `TIntToIdent` (240), `IntToIdent` (256), `TIdentMapEntry` (240)

4.4.22 InitComponentRes

Synopsis: Provided for Delphi compatibility only

Declaration: `function InitComponentRes(const ResName: string; Instance: TComponent)
: Boolean`

Visibility: default

Description: This function is provided for Delphi compatibility. It always returns `false`.

See also: [ReadComponentRes \(258\)](#)

4.4.23 InitInheritedComponent

Synopsis: Initializes a component descending from `RootAncestor`

Declaration: `function InitInheritedComponent(Instance: TComponent;
RootAncestor: TClass) : Boolean`

Visibility: default

Description: `InitInheritedComponent` should be called from a constructor to read properties of the component `Instance` from the streaming system. The `RootAncestor` class is the root class from which `Instance` is a descendant. This must be one of `TDatamodule`, `TCustomForm` or `TFrame`. The function returns `True` if the properties were successfully read from a stream or `False` if some error occurred.

See also: [ReadComponentRes \(258\)](#), [ReadComponentResEx \(259\)](#), [ReadComponentResFile \(259\)](#)

4.4.24 IntToIdent

Synopsis: Looks up an identifier for an integer value in a identifier-to-integer map list.

Declaration: `function IntToIdent(Int: LongInt; var Ident: string;
const Map: Array of TIdentMapEntry) : Boolean`

Visibility: default

Description: `IntToIdent` searches `Map` for an entry whose `Value` field matches `Int` and returns the corresponding identifier in `Ident`. If a match was found, the function returns `True`, otherwise, `False` is returned.

See also: [TIdentToInt \(240\)](#), [TintToIdent \(240\)](#), [IdentToInt \(255\)](#), [TIdentMapEntry \(240\)](#)

4.4.25 InvalidPoint

Synopsis: Check whether a point is invalid.

Declaration: `function InvalidPoint(X: Integer; Y: Integer) : Boolean
function InvalidPoint(const At: TPoint) : Boolean
function InvalidPoint(const At: TSmallPoint) : Boolean`

Visibility: default

Description: `InvalidPoint` returns `True` if the `X` and `Y` coordinates (of the `TPoint` or `TSmallPoint` records, if one of these versions is used) are `-1`.

See also: [TPoint \(242\)](#), [TSmallPoint \(245\)](#), [PointsEqual \(258\)](#)

4.4.26 LineStart

Synopsis: Finds the start of a line in `Buffer` before `BufPos`.

Declaration: `function LineStart(Buffer: PChar; BufPos: PChar) : PChar`

Visibility: default

Description: `LineStart` reversely scans `Buffer` starting at `BufPos` for a linefeed character. It returns a pointer at the linefeed character.

4.4.27 NotifyGlobalLoading

Synopsis: Not yet implemented.

Declaration: `procedure NotifyGlobalLoading`

Visibility: default

Description: Not yet implemented.

4.4.28 ObjectBinaryToText

Synopsis: Converts an object stream from a binary to a text format.

Declaration: `procedure ObjectBinaryToText(Input: TStream; Output: TStream;
Encoding: TObjectTextEncoding)
procedure ObjectBinaryToText(Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectBinaryToText` reads an object stream in binary format from `Input` and writes the object stream in text format to `Output`. No components are instantiated during the process, this is a pure conversion routine.

See also: `ObjectTextToBinary` ([257](#))

4.4.29 ObjectResourceToText

Synopsis: Converts an object stream from a (windows) resource to a text format.

Declaration: `procedure ObjectResourceToText(Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectResourceToText` reads the resource header from the `Input` stream and then passes the streams to `ObjectBinaryToText` ([257](#))

See also: `ObjectBinaryToText` ([257](#)), `ObjectTextToResource` ([258](#))

4.4.30 ObjectTextToBinary

Synopsis: Converts an object stream from a text to a binary format.

Declaration: `procedure ObjectTextToBinary(Input: TStream; Output: TStream)`

Visibility: default

Description: Converts an object stream from a text to a binary format.

4.4.31 ObjectTextToResource

Synopsis: Converts an object stream from a text to a (windows) resource format.

Declaration: `procedure ObjectTextToResource (Input: TStream; Output: TStream)`

Visibility: default

Description: `ObjectTextToResource` reads an object stream in text format from `Input` and writes a resource stream to `Output`.

Note that for the current implementation of this method in Free Pascal, the output stream should support positioning. (e.g. it should not be a pipe)

See also: `ObjectBinaryToText` (257), `ObjectResourceToText` (257)

4.4.32 Point

Synopsis: Returns a `TPoint` record with the given coordinates.

Declaration: `function Point (AX: Integer; AY: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` (242) record with the given coordinates `AX` and `AY` filled in.

See also: `TPoint` (242), `SmallPoint` (263), `Rect` (259), `Bounds` (251)

4.4.33 PointsEqual

Synopsis: Check whether two `TPoint` variables are equal.

Declaration: `function PointsEqual (const P1: TPoint; const P2: TPoint) : Boolean`
`function PointsEqual (const P1: TSmallPoint; const P2: TSmallPoint)`
`: Boolean`

Visibility: default

Description: `PointsEqual` compares the `P1` and `P2` points (of type `TPoint` (242) or `TSmallPoint` (245)) and returns `True` if the X and Y coordinates of the points are equal, or `False` otherwise.

See also: `TPoint` (242), `TSmallPoint` (245), `InvalidPoint` (256)

4.4.34 ReadComponentRes

Synopsis: Read component properties from a resource in the current module

Declaration: `function ReadComponentRes (const ResName: string; Instance: TComponent)`
`: TComponent`

Visibility: default

Description: `ReadComponentRes` will read the component's properties from the resource `ResName` in the current module (always program module). It returns `Nil` if the resource was not found. It returns `Instance` if the resource was found and successfully applied to the component.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentResEx` (259)

4.4.35 ReadComponentResEx

Synopsis: Read component properties from a resource in the specified module

Declaration: `function ReadComponentResEx(HInstance: THandle; const ResName: string)
: TComponent`

Visibility: default

Description: `ReadComponentRes` will locate the resource `ResName` in instance `HInstance` (the current program, normally). It returns `Nil` if the resource was not found. It returns an instantiated component with all properties found in the stream, applied. This requires that the component is registered using `registerclass`.

Errors: The function may raise an exception if the stream contains wrong data.

See also: `ReadComponentRes` ([258](#))

4.4.36 ReadComponentResFile

Synopsis: Read component properties from a specified resource file

Declaration: `function ReadComponentResFile(const FileName: string;
Instance: TComponent) : TComponent`

Visibility: default

Description: `ReadComponentResFile` starts reading properties for `Instance` from the file `FileName`. It creates a filestream from `FileName` and then calls the `TStream.ReadComponentRes` ([413](#)) method to read the state of the component from the stream.

See also: `TStream.ReadComponentRes` ([413](#)), `WriteComponentResFile` ([264](#))

4.4.37 Rect

Synopsis: Returns a `TRect` record with the given coordinates.

Declaration: `function Rect(ALeft: Integer; ATop: Integer; ARight: Integer;
ABottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a `TRect` ([243](#)) record with the given top-left (`ALeft`, `ATop`) and bottom-right (`ABottom`, `ARight`) corners filled in.

No checking is done to see whether the coordinates are valid.

See also: `TRect` ([243](#)), `Point` ([258](#)), `SmallPoint` ([263](#)), `Bounds` ([251](#))

4.4.38 RedirectFixupReferences

Synopsis: Redirects references under the `root` object from `OldRootName` to `NewRootName`

Declaration: `procedure RedirectFixupReferences(Root: TComponent;
const OldRootName: string;
const NewRootName: string)`

Visibility: default

Description: `RedirectFixupReferences` examines the list of unresolved references and replaces references to a root object named `OldRootName` with references to root object `NewRootName`.

An application programmer should never need to call `RedirectFixupReferences`. This function can be used by an IDE to support redirection of broken component links.

See also: `RemoveFixupReferences` ([262](#))

4.4.39 RegisterClass

Synopsis: Registers a class with the streaming system.

Declaration: `procedure RegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `RegisterClass` registers the class `AClass` in the streaming system. After the class has been registered, it can be read from a stream when a reference to this class is encountered.

See also: `RegisterClasses` ([260](#)), `RegisterClassAlias` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.40 RegisterClassAlias

Synopsis: Registers a class alias with the streaming system.

Declaration: `procedure RegisterClassAlias (AClass: TPersistentClass;
const Alias: string)`

Visibility: default

Description: `RegisterClassAlias` registers a class alias in the streaming system. If a reference to a class `Alias` is encountered in a stream, then an instance of the class `AClass` will be created instead by the streaming code.

See also: `RegisterClass` ([260](#)), `RegisterClasses` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.41 RegisterClasses

Synopsis: Registers multiple classes with the streaming system.

Declaration: `procedure RegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `RegisterClasses` registers the specified classes `AClass` in the streaming system. After the classes have been registered, they can be read from a stream when a reference to this class is encountered.

See also: `RegisterClass` ([260](#)), `RegisterClassAlias` ([260](#)), `RegisterComponents` ([260](#)), `UnregisterClass` ([263](#))

4.4.42 RegisterComponents

Synopsis: Registers components for the component palette.

Declaration: `procedure RegisterComponents (const Page: string;
ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterComponents` registers the component on the appropriate component page. The component pages can be used by an IDE to display the known components so an application programmer may pick and use the components in his programs.

`RegisterComponents` inserts the component class in the correct component page. If the `RegisterComponentsProc` procedure is set, this is called as well. Note that this behaviour is different from Delphi's behaviour where an exception will be raised if the procedural variable is not set.

See also: `RegisterClass` (260), `RegisterNoIcon` (262)

4.4.43 RegisterFindGlobalComponentProc

Synopsis: Register a component searching handler

Declaration: `procedure RegisterFindGlobalComponentProc`
`(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `RegisterFindGlobalComponentProc` registers a global component search callback `AFindGlobalComponent`. When `FindGlobalComponent` (253) is called, then this callback will be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (253), `UnRegisterFindGlobalComponentProc` (264)

4.4.44 RegisterInitComponentHandler

Synopsis: Register a component initialization handler

Declaration: `procedure RegisterInitComponentHandler(ComponentClass: TComponentClass;`
`Handler: TInitComponentHandler)`

Visibility: default

Description: `RegisterInitComponentHandler` registers a component initialization handler `Handler` for the component `ComponentClass`. This handler will be used to initialize descendants of `ComponentClass` in the `InitInheritedComponent` (256) call.

See also: `InitInheritedComponent` (256), `TInitComponentHandler` (240)

4.4.45 RegisterIntegerConsts

Synopsis: Registers some integer-to-identifier mappings.

Declaration: `procedure RegisterIntegerConsts(IntegerType: Pointer;`
`IdentToIntFn: TIdentToInt;`
`IntToIdentFn: TIntToIdent)`

Visibility: default

Description: `RegisterIntegerConsts` registers a pair of callbacks to be used when an integer of type `IntegerType` must be mapped to an identifier (using `IntToIdentFn`) or when an identifier must be mapped to an integer (using `IdentToIntFn`).

Component programmers can use `RegisterIntegerConsts` to associate a series of identifier strings with integer values for a property. A necessary condition is that the property should have a

separate type declared using the `type integer` syntax. If a type of integer is defined in this way, an IDE can show symbolic names for the values of these properties.

The `IntegerType` should be a pointer to the type information of the integer type. The `IntToIdentFn` and `IdentToIntFn` are two callbacks that will be used when converting between the identifier and integer value and vice versa. The functions `IdentToInt` (255) and `IntToIdent` (256) can be used to implement these callback functions.

See also: `TIdentToInt` (240), `TIntToIdent` (240), `IdentToInt` (255), `IntToIdent` (256)

4.4.46 RegisterNoIcon

Synopsis: Registers components that have no icon on the component palette.

Declaration: `procedure RegisterNoIcon(ComponentClasses: Array of TComponentClass)`

Visibility: default

Description: `RegisterNoIcon` performs the same function as `RegisterComponents` (260) except that it calls `RegisterNoIconProc` (250) instead of `RegisterComponentsProc` (249)

See also: `RegisterNoIconProc` (250), `RegisterComponents` (260)

4.4.47 RegisterNonActiveX

Synopsis: Register non-activex component.

Declaration: `procedure RegisterNonActiveX
(ComponentClasses: Array of TComponentClass;
AxRegType: TActiveXRegType)`

Visibility: default

Description: Not yet implemented in Free Pascal

4.4.48 RemoveFixupReferences

Synopsis: Removes references to rootname from the fixup list.

Declaration: `procedure RemoveFixupReferences(Root: TComponent;
const RootName: string)`

Visibility: default

Description: `RemoveFixupReferences` examines the list of unresolved references and removes references to a root object pointing at `Root` or a root component named `RootName`.

An application programmer should never need to call `RemoveFixupReferences`. This function can be used by an IDE to support removal of broken component links.

See also: `RedirectFixupReferences` (259)

4.4.49 RemoveFixups

Synopsis: Removes Instance from the fixup list.

Declaration: `procedure RemoveFixups (Instance: TPersistent)`

Visibility: default

Description: `RemoveFixups` removes all entries for component Instance from the list of unresolved references.

See also: `RedirectFixupReferences` (259), `RemoveFixupReferences` (262)

4.4.50 SmallPoint

Synopsis: Returns a `TSmallPoint` record with the given coordinates.

Declaration: `function SmallPoint (AX: SmallInt; AY: SmallInt) : TSmallPoint`

Visibility: default

Description: `SmallPoint` returns a `TSmallPoint` (245) record with the given coordinates AX and AY filled in.

See also: `TSmallPoint` (245), `Point` (258), `Rect` (259), `Bounds` (251)

4.4.51 StartClassGroup

Synopsis: Start new class group.

Declaration: `procedure StartClassGroup (AClass: TPersistentClass)`

Visibility: default

Description: `StartClassGroup` starts a new class group and adds AClass to it.

The class registration and streaming mechanism allows to organize the classes in groups. This allows an IDE to form groups of classes, which can be enabled or disabled. It is not needed at Run-Time.

See also: `GroupDescendantsWith` (231), `ActivateClassGroup` (250), `ClassGroupOf` (252)

4.4.52 UnRegisterClass

Synopsis: Unregisters a class from the streaming system.

Declaration: `procedure UnRegisterClass (AClass: TPersistentClass)`

Visibility: default

Description: `UnregisterClass` removes the class AClass from the class definitions in the streaming system.

See also: `UnRegisterClasses` (263), `UnRegisterModuleClasses` (264), `RegisterClass` (260)

4.4.53 UnRegisterClasses

Synopsis: Unregisters multiple classes from the streaming system.

Declaration: `procedure UnRegisterClasses (AClasses: Array of TPersistentClass)`

Visibility: default

Description: `UnregisterClasses` removes the classes in AClasses from the class definitions in the streaming system.

4.4.54 UnregisterFindGlobalComponentProc

Synopsis: Remove a previously registered component searching handler.

Declaration: `procedure UnregisterFindGlobalComponentProc`
`(AFindGlobalComponent: TFindGlobalComponent)`

Visibility: default

Description: `UnRegisterFindGlobalComponentProc` unregisters the previously registered global component search callback `AFindGlobalComponent`. After this call, when `FindGlobalComponent` (253) is called, then this callback will be no longer be used to search for the component.

Errors: None.

See also: `FindGlobalComponent` (253), `RegisterFindGlobalComponentProc` (261)

4.4.55 UnRegisterModuleClasses

Synopsis: Unregisters classes registered by module.

Declaration: `procedure UnRegisterModuleClasses (Module: HMODULE)`

Visibility: default

Description: `UnRegisterModuleClasses` unregisters all classes which reside in the module `Module`. For each registered class, the definition pointer is checked to see whether it resides in the module, and if it does, the definition is removed.

See also: `UnRegisterClass` (263), `UnRegisterClasses` (263), `RegisterClasses` (260)

4.4.56 WriteComponentResFile

Synopsis: Write component properties to a specified resource file

Declaration: `procedure WriteComponentResFile (const FileName: string;`
`Instance: TComponent)`

Visibility: default

Description: `WriteComponentResFile` starts writing properties of `Instance` to the file `FileName`. It creates a filestream from `FileName` and then calls `TStream.WriteComponentRes` (414) method to write the state of the component to the stream.

See also: `TStream.WriteComponentRes` (414), `ReadComponentResFile` (259)

4.5 EBitsError

4.5.1 Description

When an index of a bit in a `TBits` (313) is out of the valid range (0 to `Count-1`) then a `EBitsError` exception is raised.

4.6 EClassNotFound

4.6.1 Description

When the streaming system needs to create a component, it looks for the class pointer (VMT) in the list of registered classes by its name. If this name is not found, then an `EClassNotFound` is raised.

See also: `EFileError` ([265](#))

4.7 EComponentError

4.7.1 Description

When an error occurs during the registration of a component, or when naming a component, then a `EComponentError` is raised. Possible causes are:

1. An name with an illegal character was assigned to a component.
2. A component with the same name and owner already exists.
3. The component registration system isn't set up properly.

See also: `TComponent` ([330](#)), `TComponent.Name` ([340](#))

4.8 EFCreateError

4.8.1 Description

When the operating system reports an error during creation of a new file in the Filestream Constructor ([350](#)), a `EFCreateError` is raised.

See also: `EStreamError` ([267](#)), `EFOpenError` ([265](#))

4.9 EFileError

4.9.1 Description

This class serves as an ancestor class for exceptions that are raised when an error occurs during component streaming. A `EFileError` exception is raised when a class is registered twice.

See also: `EStreamError` ([267](#)), `EReadError` ([267](#))

4.10 EFOpenError

4.10.1 Description

When the operating system reports an error during the opening of a file in the Filestream Constructor ([350](#)), a `EFOpenError` is raised.

See also: `EStreamError` ([267](#)), `EFCreateError` ([265](#))

4.11 EInvalidImage

4.11.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.12 EInvalidOperation

4.12.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.13 EListError

4.13.1 Description

If an error occurs in one of the `TList` (370) or `TStrings` (429) methods, then a `EListError` exception is raised. This can occur in one of the following cases:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. An attempt was made to reduce the capacity of the list below the current element count.
4. An attempt was made to set the list count to a negative value.
5. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
6. An attempt was made to move an item to a position outside the list's bounds.

See also: `TList` (370), `TStrings` (429)

4.14 EMethodNotFound

4.14.1 Description

This exception is no longer used in the streaming system. This error is replaced by a `EReadError` (267).

See also: `EFileError` (265), `EReadError` (267)

4.15 EObserver

4.15.1 Description

`EObserver` is an error that is raised when an object is registered as an observer, and it does not implement the `IFPObserver` (271) interface.

See also: `IFPObserver` (271), `IFPObserver.FPOAttachObserver` (270)

4.16 EOutOfResources

4.16.1 Description

This exception is not used in Free Pascal, it is defined for Delphi compatibility purposes only.

4.17 EParserError

4.17.1 Description

When an error occurs during the parsing of a stream, an `EParserError` is raised. Usually this indicates that an invalid token was found on the input stream, or the token read from the stream wasn't the expected token.

See also: `TParser` ([383](#))

4.18 EReadError

4.18.1 Description

If an error occurs when reading from a stream, a `EReadError` exception is raised. Possible causes for this are:

1. Not enough data is available when reading from a stream
2. The stream containing a component's data contains invalid data. this will occur only when reading a component from a stream.

See also: `EFileError` ([265](#)), `EWriteError` ([268](#))

4.19 EResNotFound

4.19.1 Description

This exception is not used by Free Pascal but is provided for Delphi compatibility.

4.20 EStreamError

4.20.1 Description

An `EStreamError` is raised when an error occurs during reading from or writing to a stream: Possible causes are

1. Not enough data is available in the stream.
2. Trying to seek beyond the beginning or end of the stream.
3. Trying to set the capacity of a memory stream and no memory is available.
4. Trying to write to a read-only stream, such as a resource stream.
5. Trying to read from a write-only stream.

See also: `EFCREATEError` ([265](#))

4.21 TStringListError

4.21.1 Description

When an error occurs in one of the methods of `TStrings` (429) then an `EStringListError` is raised. This can have one of the following causes:

1. There is not enough memory to expand the list.
2. The list tried to grow beyond its maximal capacity.
3. A non-existent element of the list was referenced. (i.e. the list index was out of bounds)
4. An attempt was made to add a duplicate entry to a `TStringList` (424) when `TStringList.Duplicates` (427) is `False`.

See also: `TStrings` (429), `TStringList` (424)

4.22 EThread

4.22.1 Description

Thread error exception.

4.23 EThreadDestroyCalled

4.23.1 Description

Exception raised when a thread is destroyed illegally.

4.24 EThreadExternalException

4.24.1 Description

`EThreadExternalException` is raised by for example `TThread.CheckTerminated` (452) and `TThread.SetReturnValue` (452) when the thread was not created by the Free Pascal program, but by an external code base (for example a DLL, or the calling application in a DLL).

See also: `TThread.CheckTerminated` (452), `TThread.SetReturnValue` (452)

4.25 EWriteError

4.25.1 Description

If an error occurs when writing to a stream, a `EWriteError` exception is raised. Possible causes for this are:

1. The stream doesn't allow writing.
2. An error occurred when writing a property to a stream.

See also: `EFileError` (265), `EReadError` (267)

4.26 IDesignerNotify

4.26.1 Description

`IDesignerNotify` is an interface that can be used to communicate changes to a designer mechanism. It offers functionality for detecting changes, and notifications when the component is destroyed.

4.26.2 Method overview

Page	Method	Description
269	<code>Modified</code>	Notify that the component is modified.
269	<code>Notification</code>	Notification of owner changes

4.26.3 IDesignerNotify.Modified

Synopsis: Notify that the component is modified.

Declaration: `procedure Modified`

Visibility: `default`

Description: `Modified` can be used to notify a designer of changes, indicating that components should be streamed.

4.26.4 IDesignerNotify.Notification

Synopsis: Notification of owner changes

Declaration: `procedure Notification(AnObject: TPersistent; Operation: TOperation)`

Visibility: `default`

Description: `Notification` is the interface counterpart of `TComponent.Notification` ([332](#)) which is used to communicate adds to the components.

See also: `TComponent.Notification` ([332](#))

4.27 IFPObserved

4.27.1 Description

`IFPObserved` is an interface which can be implemented in objects that must be observable. Objects that wish to observe the object can register themselves with the `FPOAttachObserver` ([231](#)) call, and must be detached using the `FPODetachObserver` ([231](#)) call.

This interface is not reference counted, so care must be taken that the `ooFree` message is sent with `FPONotifyObservers` ([231](#)) when the object is freed.

See also: `FPONotifyObservers` ([231](#))

4.27.2 Method overview

Page	Method	Description
270	FPOAttachObserver	Attach a new observer to the object
270	FPODetachObserver	Remove an observer from the list of observers.
270	FPONotifyObservers	Notify all observers

4.27.3 IFPObserved.FPOAttachObserver

Synopsis: Attach a new observer to the object

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: default

Description: `FPOAttachObserver` must be called with an object instance `AObserver` that implements the `IFPObserver` ([271](#)) interface. The `FPOObservedChanged` ([271](#)) method of the interface will be called whenever `FPONotifyObservers` ([231](#)) is used to notify observers of a change. Objects implementing this interface should check that `AObserver` actually implements the `IFPObserver` ([271](#)) interface.

Do not make assumptions on how the interface behaves if `FPOAttachObserver` is called more than once with the same interface. It may add the object to the list of observers unconditionally (in which case it will be notified twice) or it may check that it is not yet in the list.

Errors: If `AObserver` does not implement the `IFPObserver` ([271](#)) interface, an `EObserver` ([266](#)) exception must be raised. No other errors should be raised, other than a possible out of memory error.

See also: `IFPObserver` ([271](#)), `FPOObservedChanged` ([271](#)), `FPONotifyObservers` ([231](#))

4.27.4 IFPObserved.FPODetachObserver

Synopsis: Remove an observer from the list of observers.

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: default

Description: `FPODetachObserver` removes the `AObserver` object from the list of observers. If it was not in the list, then this is silently accepted. Once removed, it will no longer receive notifications when `FPOObservedChanged` ([271](#)) is called.

If the object was added more than once using `FPOAttachObserver` ([231](#)), then it depends on the implementor of the interface whether or `FPODetachObserver` must be called an equal number of times.

See also: `IFPObserver` ([271](#)), `FPOObservedChanged` ([271](#)), `FPONotifyObservers` ([231](#)), `FPOAttachObserver` ([231](#))

4.27.5 IFPObserved.FPONotifyObservers

Synopsis: Notify all observers

Declaration: `procedure FPONotifyObservers(ASender: TObject;
AOperation: TFPObservedOperation;
Data: Pointer)`

Visibility: default

Description: `FPONotifyObservers` notifies all observers of the object that a change has occurred. It calls `FPOObservedChanged` (271) on the `IFPObserver` (271) interface of all attached objects, and passes on `ASender` (normally this is `Self`), `AOperation` and `Data`. What `Data` is, depends on the implementor of the interface.

There is no guaranteed order in which the change notifications are delivered to the observers. This is an implementation-specific detail, which should not be relied upon in any way.

See also: `IFPObserver` (271), `FPOObservedChanged` (271), `FPODetachObserver` (231), `FPOAttachObserver` (231)

4.28 IFPObserver

4.28.1 Description

`IFPObserver` is the interface an object must implement if it wishes to receive change notifications from another object. The presence of this interface will be checked when the object registers itself using `IFPObserver.FPOAttachObserver` (271). The change notifications arrive because the `FPOObservedChanged` (231) method is called by the observed object.

See also: `IFPObserved` (269), `FPOAttachObserver` (270)

4.28.2 Method overview

Page	Method	Description
271	<code>FPOObservedChanged</code>	Entry point for change notifications

4.28.3 IFPObserver.FPOObservedChanged

Synopsis: Entry point for change notifications

Declaration: `procedure FPOObservedChanged(ASender: TObject;
Operation: TFPObservedOperation;
Data: Pointer)`

Visibility: default

Description: `FPOObservedChanged` is the method that is called by an observed object (`IFPObserved` (269)) when it calls `FPONotifyObservers` (270). The `Sender` is the object under observation, the `Operation` and `Data` are the parameters used in the call to `FPONotifyObservers`.

See also: `IFPObserved` (269), `FPONotifyObservers` (270)

4.29 IInterfaceComponentReference

4.29.1 Description

`IInterfaceComponentReference` is an interface to return the component that implements a given interface. It is implemented by `TComponent` (330).

See also: `TComponent` (330)

4.29.2 Method overview

Page	Method	Description
272	<code>GetComponent</code>	Return component instance

4.29.3 `IInterfaceComponentReference.GetComponent`

Synopsis: Return component instance

Declaration: `function GetComponent : TComponent`

Visibility: default

Description: `GetComponent` returns the component instance.

Errors: None.

See also: `TComponent` ([330](#))

4.30 `IInterfaceList`

4.30.1 Description

`IInterfaceList` is an interface for maintaining a list of interfaces, strongly resembling the standard `TList` ([370](#)) class. It offers the same list of public methods as `TList`, with the exception that it uses interfaces instead of pointers.

All interfaces in the list should descend from `IUnknown`.

More detailed descriptions of how the various methods behave can be found in the `TList` reference.

See also: `TList` ([370](#))

4.30.2 Method overview

Page	Method	Description
275	<code>Add</code>	Add an interface to the list
274	<code>Clear</code>	Clear the list
274	<code>Delete</code>	Remove an interface from the list
275	<code>Exchange</code>	Exchange 2 interfaces in the list
275	<code>First</code>	Return the first non-empty interface in the list.
273	<code>Get</code>	Retrieve an interface pointer from the list.
273	<code>GetCapacity</code>	Return the capacity of the list.
273	<code>GetCount</code>	Return the current number of elements in the list.
275	<code>IndexOf</code>	Return the index of an interface.
275	<code>Insert</code>	Insert an interface in the list.
276	<code>Last</code>	Returns the last non-nil interface in the list.
276	<code>Lock</code>	Lock the list
273	<code>Put</code>	Write an item to the list
276	<code>Remove</code>	Remove an interface from the list
274	<code>SetCapacity</code>	Set the capacity of the list
274	<code>SetCount</code>	Set the number of items in the list
276	<code>Unlock</code>	Unlock the list.

4.30.3 Property overview

Page	Properties	Access	Description
276	Capacity	rw	Capacity of the list
277	Count	rw	Current number of elements in the list.
277	Items	rw	Provides Index-based, sequential, access to the interfaces in the list.

4.30.4 IInterfaceList.Get

Synopsis: Retrieve an interface pointer from the list.

Declaration: `function Get(i: Integer) : IUnknown`

Visibility: default

Description: `Get` returns the interface pointer at position `i` in the list. It serves as the `Read` method for the `Items` ([277](#)) property.

See also: `IInterfaceList.Items` ([277](#)), `TList.Items` ([377](#))

4.30.5 IInterfaceList.GetCapacity

Synopsis: Return the capacity of the list.

Declaration: `function GetCapacity : Integer`

Visibility: default

Description: `GetCapacity` returns the current capacity of the list. It serves as the `Read` method for the `Capacity` ([276](#)) property.

See also: `IInterfaceList.Capacity` ([276](#)), `TList.Capacity` ([377](#))

4.30.6 IInterfaceList.GetCount

Synopsis: Return the current number of elements in the list.

Declaration: `function GetCount : Integer`

Visibility: default

Description: It serves as the `Read` method for the `Count` ([277](#)) property.

See also: `IInterfaceList.Count` ([277](#)), `TList.Count` ([377](#))

4.30.7 IInterfaceList.Put

Synopsis: Write an item to the list

Declaration: `procedure Put(i: Integer; item: IUnknown)`

Visibility: default

Description: `Put` writes the interface `Item` at position `I` in the list. It servers as the `Write` method for the `Items` ([277](#)) property.

See also: `IInterfaceList.Items` ([277](#)), `TList.Items` ([377](#))

4.30.8 **InterfaceList.SetCapacity**

Synopsis: Set the capacity of the list

Declaration: `procedure SetCapacity(NewCapacity: Integer)`

Visibility: default

Description: `SetCapacity` sets the capacity of the list to `NewCapacity`. It serves as the `Write` method for the `Capacity` (276) property.

See also: `InterfaceList.Capacity` (276), `TList.Capacity` (377)

4.30.9 **InterfaceList.SetCount**

Synopsis: Set the number of items in the list

Declaration: `procedure SetCount(NewCount: Integer)`

Visibility: default

Description: `SetCount` sets the count of the list to `NewCount`. It serves as the `Write` method for the `Capacity` (276)

See also: `InterfaceList.Count` (277), `TList.Count` (377)

4.30.10 **InterfaceList.Clear**

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: default

Description: `Clear` removes all interfaces from the list. All interfaces in the list will be cleared (i.e. their reference count will decrease with 1)

See also: `TList.Clear` (373)

4.30.11 **InterfaceList.Delete**

Synopsis: Remove an interface from the list

Declaration: `procedure Delete(index: Integer)`

Visibility: default

Description: `Delete` removes the interface at position `Index` from the list. It does this by explicitly clearing the interface and then removing the slot.

See also: `TList.Clear` (373), `InterfaceList.Add` (275), `InterfaceList.Delete` (274), `InterfaceList.Insert` (275)

4.30.12 **IInterfaceList.Exchange**

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: default

Description: `Exchange` exchanges 2 interfaces in the list at locations `index1` and `Index2`.

See also: `TList.Exchange` (373), `IInterfaceList.Add` (275), `IInterfaceList.Delete` (274), `IInterfaceList.Insert` (275)

4.30.13 **IInterfaceList.First**

Synopsis: Return the first non-empty interface in the list.

Declaration: `function First : IUnknown`

Visibility: default

Description: `First` returns the first non-empty interface in the list.

See also: `TList.First` (374), `IInterfaceList.IndexOf` (275), `IInterfaceList.Last` (276)

4.30.14 **IInterfaceList.IndexOf**

Synopsis: Return the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: default

Description: `IndexOf` returns the location in the list of the interface `Item`. If there is no such interface in the list, then -1 is returned.

See also: `TList.IndexOf` (375), `IInterfaceList.First` (275), `IInterfaceList.Last` (276)

4.30.15 **IInterfaceList.Add**

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: default

Description: `Add` adds the interface `Item` to the list, and returns the position at which it has been added.

See also: `TList.Add` (372), `IInterfaceList.Insert` (275), `IInterfaceList.Delete` (274)

4.30.16 **IInterfaceList.Insert**

Synopsis: Insert an interface in the list.

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: default

Description: `Insert` inserts the interface `Item` in the list, at position `I`, shifting all items one position.

See also: `TList.Insert` (375), `IInterfaceList.Add` (275), `IInterfaceList.Delete` (274)

4.30.17 **IInterfaceList.Last**

Synopsis: Returns the last non-nil interface in the list.

Declaration: `function Last : IUnknown`

Visibility: default

Description: `Last` returns the last non-empty interface in the list.

See also: `TList.Last` ([375](#)), `IInterfaceList.First` ([275](#)), `IInterfaceList.IndexOf` ([275](#))

4.30.18 **IInterfaceList.Remove**

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: default

Description: `Remove` searches for the first occurrence of `Item` in the list and deletes it.

See also: `TList.Remove` ([376](#)), `IInterfaceList.Delete` ([274](#)), `IInterfaceList.IndexOf` ([275](#))

4.30.19 **IInterfaceList.Lock**

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: default

Description: `Lock` locks the list. After a call to lock, the object list can only be accessed by the current thread, until `UnLock` ([276](#)) is called.

See also: `TInterfaceList.Lock` ([367](#)), `IInterfaceList.Unlock` ([276](#))

4.30.20 **IInterfaceList.Unlock**

Synopsis: Unlock the list.

Declaration: `procedure Unlock`

Visibility: default

Description: `Unlock` unlocks a locked list. After a call to `UnLock`, other threads are again able to access the list.

See also: `TInterfaceList.UnLock` ([367](#)), `IInterfaceList.Lock` ([276](#))

4.30.21 **IInterfaceList.Capacity**

Synopsis: Capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: default

Access: Read,Write

Description: `Capacity` is the maximum number of elements the list can hold without needing to reallocate memory for the list. It can be set to improve speed when adding a lot of items to the list.

See also: `TList.Capacity` ([377](#)), `IInterfaceList.Count` ([277](#))

4.30.22 IInterfaceList.Count

Synopsis: Current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: default

Access: Read,Write

Description: `Count` is the current number of elements in the list. Setting it to a larger number will allocate empty slots. Setting it to a smaller number will clear any interfaces that fall outside the new border.

See also: `IInterfaceList.Capacity` ([276](#)), `TList.Count` ([377](#))

4.30.23 IInterfaceList.Items

Synopsis: Provides Index-based, sequential, access to the interfaces in the list.

Declaration: `Property Items[index: Integer]: IUnknown; default`

Visibility: default

Access: Read,Write

Description: `Items` is the default property of the interface list and provides index-based array access to the interfaces in the list. Allowed values for `Index` include 0 to `Count-1`

See also: `IInterfaceList.Count` ([277](#)), `TList.Items` ([377](#))

4.31 IStreamPersist

4.31.1 Description

`IStreamPersist` defines an interface for object persistence streaming to a stream. Any class implementing this interface is expected to be able to save or load it's state from or to a stream.

See also: `TPersistent` ([390](#)), `TComponent` ([330](#)), `TStream` ([409](#))

4.31.2 Method overview

Page	Method	Description
278	<code>LoadFromStream</code>	Load persistent data from stream.
278	<code>SaveToStream</code>	Save persistent data to stream.

4.31.3 IStreamPersist.LoadFromStream

Synopsis: Load persistent data from stream.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: default

Description: `LoadFromStream` is the method called when the object should load it's state from the stream `stream`. It should be able to read the data which was written using the `SaveToStream` method.

See also: [TPersistent \(390\)](#), [TComponent \(330\)](#), [TStream \(409\)](#), [IStreamPersist.SaveToStream \(278\)](#)

4.31.4 IStreamPersist.SaveToStream

Synopsis: Save persistent data to stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: default

Description: `SaveFromStream` is the method called when the object should load it's state from the stream `stream`. The data written by this method should be readable by the `LoadFromStream` method.

See also: [TPersistent \(390\)](#), [TComponent \(330\)](#), [TStream \(409\)](#), [IStreamPersist.LoadFromStream \(278\)](#)

4.32 IStringsAdapter

4.32.1 Description

Is not yet supported in Free Pascal.

See also: [TStrings \(429\)](#)

4.32.2 Method overview

Page	Method	Description
278	<code>ReferenceStrings</code>	Add a reference to the indicated strings.
278	<code>ReleaseStrings</code>	Release the reference to the strings.

4.32.3 IStringsAdapter.ReferenceStrings

Synopsis: Add a reference to the indicated strings.

Declaration: `procedure ReferenceStrings(S: TStrings)`

Visibility: default

4.32.4 IStringsAdapter.ReleaseStrings

Synopsis: Release the reference to the strings.

Declaration: `procedure ReleaseStrings`

Visibility: default

4.33 IVCLComObject

4.33.1 Description

IVCLComObject is used by TComponent to implement the IUnknown interface used by COM automation servers. Partially, it is the translation to pascal of the IDispatch interface definition by Microsoft. If TComponent needs to return an IUnknown interface, it creates a IVCLComObject interface instead.

See also: TComponent.VCLComObject ([340](#))

4.33.2 Method overview

Page	Method	Description
280	FreeOnRelease	Is called by TComponent.FreeOnRelease
280	GetIDsOfNames	The IDispatch:GetIDsOfNames call for automation servers.
279	GetTypeInfo	The IDispatch:GetTypeInfo call for automation servers
279	GetTypeInfoCount	The IDispatch:GetTypeInfoCount call for automation servers
280	Invoke	The IDispatch:Invoke call for automation servers.
280	SafeCallException	This method can be invoked if an exception occurs during Invoke

4.33.3 IVCLComObject.GetTypeInfoCount

Synopsis: The IDispatch:GetTypeInfoCount call for automation servers

Declaration: `function GetTypeInfoCount(out Count: Integer) : HRESULT`

Visibility: default

Description: GetTypeInfoCount must return in Count either 0 or 1 to indicate that it provides type information (1) or not (0).

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfo ([279](#))

4.33.4 IVCLComObject.GetTypeInfo

Synopsis: The IDispatch:GetTypeInfo call for automation servers

Declaration: `function GetTypeInfo(Index: Integer; LocaleID: Integer; out TypeInfo) : HRESULT`

Visibility: default

Description: GetTypeInfo must return the Index-th entry in the type information of the component in TypeInfo. The LocaleID argument can be used to indicate the locale of the caller, as different type information can be returned depending on the locale.

Errors: On error, a nonzero (different from S_OK) return value must be returned.

See also: IVCLComObject.GetTypeInfoCount ([279](#))

4.33.5 IVCLComObject.GetIDsOfNames

Synopsis: The `IDispatch::GetIDsOfNames` call for automation servers.

Declaration: `function GetIDsOfNames(const IID: TGuid; Names: Pointer;
NameCount: Integer; LocaleID: Integer;
DispIDs: Pointer) : HRESULT`

Visibility: default

Description: `GetIDsOfNames` must return in `DispIDs` the dispatch Ids for the `NameCount` names of the methods listed in `Names`. The `LocaleID` indicates the locale of the caller.

Errors: On error, a nonzero (different from `S_OK`) return value must be returned.

See also: `IVCLComObject.Invoke` ([280](#))

4.33.6 IVCLComObject.Invoke

Synopsis: The `IDispatch::Invoke` call for automation servers.

Declaration: `function Invoke(DispID: Integer; const IID: TGuid; LocaleID: Integer;
Flags: Word; var Params; VarResult: Pointer;
ExcepInfo: Pointer; ArgErr: Pointer) : HRESULT`

Visibility: default

Description: `Invoke` must invoke the method designated by `DispID`. `IID` can be ignored. `LocaleID` is used by the caller to indicate the locale it is using. The `Flags` argument describes the context in which `Invoke` is called: a method, or property getter/setter. The `Params` argument contains the parameters to the call. The result should be in `VarResult`. On error, `ExcepInfo` and `ArgError` should be filled.

The function should return 0 (`S_OK`) if all went well.

See also: `IVCLComObject.GetIDsOfNames` ([280](#))

4.33.7 IVCLComObject.SafeCallException

Synopsis: This method can be invoked if an exception occurs during `Invoke`

Declaration: `function SafeCallException(ExceptObject: TObject;
ExceptAddr: CodePointer) : HRESULT`

Visibility: default

Description: `SafeCallException` is called to handle an exception during invocation of the `Invoke` method. The `TObject` implementation of this method returns `E_UNEXPECTED`.

See also: `IVCLComObject.Invoke` ([280](#))

4.33.8 IVCLComObject.FreeOnRelease

Synopsis: Is called by `TComponent.FreeOnRelease`

Declaration: `procedure FreeOnRelease`

Visibility: default

Description: `FreeOnRelease` is called by `TComponent.FreeOnRelease` (334) for the `IVCLComObject` interface implemented by `TComponent`.

See also: `TComponent.FreeOnRelease` (334)

4.34 TAbstractObjectReader

4.34.1 Description

The Free Pascal streaming mechanism, while compatible with Delphi's mechanism, differs from it in the sense that the streaming mechanism uses a driver class when streaming components. The `TAbstractObjectReader` class is the base driver class for reading property values from streams. It consists entirely of abstract methods, which must be implemented by descendant classes.

Different streaming mechanisms can be implemented by making a descendant from `TAbstractObjectReader`. The `TBinaryObjectReader` (300) class is such a descendant class, which streams data in binary (Delphi compatible) format.

All methods described in this class, must be implemented by descendant classes.

See also: `TBinaryObjectReader` (300)

4.34.2 Method overview

Page	Method	Description
282	<code>BeginComponent</code>	Marks the reading of a new component.
283	<code>BeginProperty</code>	Marks the reading of a property value.
282	<code>BeginRootComponent</code>	Starts the reading of the root component.
281	<code>NextValue</code>	Returns the type of the next value in the stream.
283	<code>Read</code>	Read raw data from stream
283	<code>ReadBinary</code>	Read binary data from the stream.
284	<code>ReadCurrency</code>	Read a currency value from the stream.
284	<code>ReadDate</code>	Read a date value from the stream.
283	<code>ReadFloat</code>	Read a float value from the stream.
284	<code>ReadIdent</code>	Read an identifier from the stream.
285	<code>ReadInt16</code>	Read a 16-bit integer from the stream.
286	<code>ReadInt32</code>	Read a 32-bit integer from the stream.
286	<code>ReadInt64</code>	Read a 64-bit integer from the stream.
285	<code>ReadInt8</code>	Read an 8-bit integer from the stream.
286	<code>ReadSet</code>	Reads a set from the stream.
287	<code>ReadSignature</code>	Read resource signature
284	<code>ReadSingle</code>	Read a single (real-type) value from the stream.
287	<code>ReadStr</code>	Read a shortstring from the stream
287	<code>ReadString</code>	Read a string of type <code>StringType</code> from the stream.
288	<code>ReadUnicodeString</code>	Read a unicode string value
282	<code>ReadValue</code>	Reads the type of the next value.
288	<code>ReadWideString</code>	Read a widestring value from the stream.
288	<code>SkipComponent</code>	Skip till the end of the component.
288	<code>SkipValue</code>	Skip the current value.

4.34.3 TAbstractObjectReader.NextValue

Synopsis: Returns the type of the next value in the stream.

Declaration: `function NextValue : TValueType; Virtual; Abstract`

Visibility: public

Description: This function should return the type of the next value in the stream, but should not read the actual value, i.e. the stream position should not be altered by this method. This is used to 'peek' in the stream what value is next.

See also: `TAbstractObjectReader.ReadValue` ([282](#))

4.34.4 TAbstractObjectReader.ReadValue

Synopsis: Reads the type of the next value.

Declaration: `function ReadValue : TValueType; Virtual; Abstract`

Visibility: public

Description: This function returns the type of the next value in the stream and reads it. i.e. after the call to this method, the stream is positioned to read the value of the type returned by this function.

See also: `TAbstractObjectReader.ReadValue` ([282](#))

4.34.5 TAbstractObjectReader.BeginRootComponent

Synopsis: Starts the reading of the root component.

Declaration: `procedure BeginRootComponent; Virtual; Abstract`

Visibility: public

Description: This function can be used to initialize the driver class for reading a component. It is called once at the beginning of the read process, and is immediately followed by a call to `BeginComponent` ([282](#)).

See also: `TAbstractObjectReader.BeginComponent` ([282](#))

4.34.6 TAbstractObjectReader.BeginComponent

Synopsis: Marks the reading of a new component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Virtual; Abstract`

Visibility: public

Description: This method is called when the streaming process wants to start reading a new component.

Descendant classes should override this method to read the start of a component new component definition and return the needed arguments. `Flags` should be filled with any flags that were found at the component definition, as well as `AChildPos`. The `CompClassName` should be filled with the class name of the streamed component, and the `CompName` argument should be filled with the name of the component.

`AChildPos` is used to change the ordering in which components appear below their parent component when streaming descendant forms.

See also: `TAbstractObjectReader.BeginRootComponent` ([282](#)), `TAbstractObjectReader.BeginProperty` ([283](#))

4.34.7 TAbstractObjectReader.BeginProperty

Synopsis: Marks the reading of a property value.

Declaration: `function BeginProperty : string; Virtual; Abstract`

Visibility: public

Description: `BeginProperty` is called by the streaming system when it wants to read a new property. The return value of the function is the name of the property which can be read from the stream.

See also: `TAbstractObjectReader.BeginComponent` ([282](#))

4.34.8 TAbstractObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TBinaryObjectReader.Read` ([303](#)), `TReader.Read` ([398](#))

4.34.9 TAbstractObjectReader.ReadBinary

Synopsis: Read binary data from the stream.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Virtual; Abstract`

Visibility: public

Description: `ReadBinary` is called when binary data should be read from the stream (i.e. after `ReadValue` ([282](#)) returned a valuetype of `vaBinary`). The data should be stored in the `DestData` memory stream by descendant classes.

See also: `TAbstractObjectReader.ReadFloat` ([283](#)), `TAbstractObjectReader.ReadDate` ([284](#)), `TAbstractObjectReader.ReadSingle` ([284](#)), `TAbstractObjectReader.ReadIdent` ([284](#)), `TAbstractObjectReader.ReadInt8` ([285](#)), `TAbstractObjectReader.ReadInt16` ([285](#)), `TAbstractObjectReader.ReadInt32` ([286](#)), `TAbstractObjectReader.ReadInt64` ([286](#)), `TAbstractObjectReader.ReadSet` ([286](#)), `TAbstractObjectReader.ReadStr` ([287](#)), `TAbstractObjectReader.ReadString` ([287](#))

4.34.10 TAbstractObjectReader.ReadFloat

Synopsis: Read a float value from the stream.

Declaration: `function ReadFloat : Extended; Virtual; Abstract`

Visibility: public

Description: `ReadFloat` is called by the streaming system when it wants to read a float from the stream (i.e. after `ReadValue` ([282](#)) returned a valuetype of `vaExtended`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` ([283](#)), `TAbstractObjectReader.ReadDate` ([284](#)), `TAbstractObjectReader.ReadSingle` ([284](#)), `TAbstractObjectReader.ReadIdent` ([284](#)), `TAbstractObjectReader.ReadInt8` ([285](#)), `TAbstractObjectReader.ReadInt16` ([285](#)), `TAbstractObjectReader.ReadInt32` ([286](#)), `TAbstractObjectReader.ReadInt64` ([286](#)), `TAbstractObjectReader.ReadSet` ([286](#)), `TAbstractObjectReader.ReadStr` ([287](#)), `TAbstractObjectReader.ReadString` ([287](#))

4.34.11 TAbstractObjectReader.ReadSingle

Synopsis: Read a single (real-type) value from the stream.

Declaration: `function ReadSingle : Single; Virtual; Abstract`

Visibility: public

Description: `ReadSingle` is called by the streaming system when it wants to read a single-type float from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaSingle`). The return value should be the value of the float.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (286), `TabstractObjectReader.ReadString` (287), `TabstractObjectReader.ReadString` (287)

4.34.12 TAbstractObjectReader.ReadDate

Synopsis: Read a date value from the stream.

Declaration: `function ReadDate : TDateTime; Virtual; Abstract`

Visibility: public

Description: `ReadDate` is called by the streaming system when it wants to read a date/time value from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaDate`). The return value should be the date/time value. (This value can be stored as a float, since `TDateTime` is nothing but a float.)

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (286), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (287)

4.34.13 TAbstractObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Virtual; Abstract`

Visibility: public

Description: `ReadCurrency` is called when a currency-typed value should be read from the stream. This abstract method should be overridden by descendant classes, and should return the currency value read from the stream.

See also: `TAbstractObjectWriter.WriteCurrency` (292)

4.34.14 TAbstractObjectReader.ReadIdent

Synopsis: Read an identifier from the stream.

Declaration: `function ReadIdent(ValueType: TValueType) : string; Virtual; Abstract`

Visibility: public

Description: `ReadIdent` is called by the streaming system if it expects to read an identifier of type `ValueType` from the stream after a call to `ReadValue` (282) returned `vaIdent`. The identifier should be returned as a string. Note that in some cases the identifier does not actually have to be in the stream. The following table indicates which identifiers must actually be read:

Table 4.21:

ValueType	Expected value
<code>vaIdent</code>	Read from stream.
<code>vaNil</code>	'Nil'. This does not have to be read from the stream.
<code>vaFalse</code>	'False'. This does not have to be read from the stream.
<code>vaTrue</code>	'True'. This does not have to be read from the stream.
<code>vaNull</code>	'Null'. This does not have to be read from the stream.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (286), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (287)

4.34.15 TAbstractObjectReader.ReadInt8

Synopsis: Read an 8-bit integer from the stream.

Declaration: `function ReadInt8 : ShortInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt8` is called by the streaming process if it expects to read an integer value with a size of 8 bits (1 byte) from the stream (i.e. after `ReadValue` (282) returned a `valuetype` of `vaInt8`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 1 byte.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TabstractObjectReader.ReadSet` (286), `TabstractObjectReader.ReadStr` (287), `TabstractObjectReader.ReadString` (287)

4.34.16 TAbstractObjectReader.ReadInt16

Synopsis: Read a 16-bit integer from the stream.

Declaration: `function ReadInt16 : SmallInt; Virtual; Abstract`

Visibility: `public`

Description: `ReadInt16` is called by the streaming process if it expects to read an integer value with a size of 16 bits (2 bytes) from the stream (i.e. after `ReadValue` (282) returned a `valuetype` of `vaInt16`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 2 bytes.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (286), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (287)

4.34.17 `TAbstractObjectReader.ReadInt32`

Synopsis: Read a 32-bit integer from the stream.

Declaration: `function ReadInt32 : LongInt; Virtual; Abstract`

Visibility: public

Description: `ReadInt32` is called by the streaming process if it expects to read an integer value with a size of 32 bits (4 bytes) from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaInt32`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 4 bytes.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (286), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (287)

4.34.18 `TAbstractObjectReader.ReadInt64`

Synopsis: Read a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64; Virtual; Abstract`

Visibility: public

Description: `ReadInt64` is called by the streaming process if it expects to read an `int64` value with a size of 64 bits (8 bytes) from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaInt64`). The return value is the value of the integer. Note that the size of the value in the stream does not actually have to be 8 bytes.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadSet` (286), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (287)

4.34.19 `TAbstractObjectReader.ReadSet`

Synopsis: Reads a set from the stream.

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Virtual; Abstract`

Visibility: public

Description: This method is called by the streaming system if it expects to read a set from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaSet`). The return value is the contents of the set, encoded in a bitmask the following way:

For each (enumerated) value in the set, the bit corresponding to the ordinal value of the enumerated value should be set. i.e. as `1 shl ord(value)`.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadStr` (287), `TAbstractObjectReader.ReadString` (287)

4.34.20 TAbstractObjectReader.ReadSignature

Synopsis: Read resource signature

Declaration: `procedure ReadSignature; Virtual; Abstract`

Visibility: public

Description: `ReadSignature` reads the streaming signature from a stream. This method does nothing. It must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectWriter.WriteSignature` (290), `TBinaryObjectReader.ReadSignature` (305)

4.34.21 TAbstractObjectReader.ReadStr

Synopsis: Read a shortstring from the stream

Declaration: `function ReadStr : string; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (286), `TAbstractObjectReader.ReadStr` (287)

4.34.22 TAbstractObjectReader.ReadString

Synopsis: Read a string of type `StringType` from the stream.

Declaration: `function ReadString(StringType: TValueType) : string; Virtual; Abstract`

Visibility: public

Description: `ReadStr` is called by the streaming system if it expects to read a string from the stream (i.e. after `ReadValue` (282) returned a valuetype of `vaLString`, `vaWstring` or `vaString`). The return value is the string.

See also: `TAbstractObjectReader.ReadFloat` (283), `TAbstractObjectReader.ReadDate` (284), `TAbstractObjectReader.ReadSingle` (284), `TAbstractObjectReader.ReadIdent` (284), `TAbstractObjectReader.ReadInt8` (285), `TAbstractObjectReader.ReadInt16` (285), `TAbstractObjectReader.ReadInt32` (286), `TAbstractObjectReader.ReadInt64` (286), `TAbstractObjectReader.ReadSet` (286), `TAbstractObjectReader.ReadStr` (287)

4.34.23 TAbstractObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Virtual; Abstract`

Visibility: public

Description: `ReadWideString` is called when a widestring-typed value should be read from the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectWriter.WriteWideString` ([293](#))

4.34.24 TAbstractObjectReader.ReadUnicodeString

Synopsis: Read a unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Virtual; Abstract`

Visibility: public

Description: `ReadUnicodeString` should read a `UnicodeString` value from the stream. (indicated by the `vaUString` value type).

Descendant classes should override this method to actually read a `UnicodeString` value.

See also: `TBinaryObjectWriter.WriteUnicodeString` ([312](#)), `TAbstractObjectReader.ReadWideString` ([288](#))

4.34.25 TAbstractObjectReader.SkipComponent

Synopsis: Skip till the end of the component.

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean); Virtual
; Abstract`

Visibility: public

Description: This method is used to skip the entire declaration of a component in the stream. Each descendant of `TAbstractObjectReader` should implement this in a way which is optimal for the implemented stream format.

See also: `TAbstractObjectReader.BeginComponent` ([282](#)), `TAbstractObjectReader.SkipValue` ([288](#))

4.34.26 TAbstractObjectReader.SkipValue

Synopsis: Skip the current value.

Declaration: `procedure SkipValue; Virtual; Abstract`

Visibility: public

Description: `SkipValue` should be used when skipping a value in the stream; The method should determine the type of the value which should be skipped by itself, if this is necessary.

See also: `TAbstractObjectReader.SkipComponent` ([288](#))

4.35 TAbstractObjectWriter

4.35.1 Description

Abstract driver class for writing component data.

4.35.2 Method overview

Page	Method	Description
289	BeginCollection	Start writing a collection.
289	BeginComponent	Start writing a component
290	BeginList	Start writing a list.
290	BeginProperty	Start writing a property
290	EndList	Mark the end of a list.
290	EndProperty	Marks the end of writing of a property.
291	Write	Write raw data to stream
291	WriteBinary	Writes binary data to the stream.
291	WriteBoolean	Writes a boolean value to the stream.
292	WriteCurrency	Write a currency value to the stream
292	WriteDate	Writes a date type to the stream.
291	WriteFloat	Writes a float value to the stream.
292	WriteIdent	Writes an identifier to the stream.
292	WriteInteger	Writes an integer value to the stream
293	WriteMethodName	Writes a methodname to the stream.
293	WriteSet	Writes a set value to the stream.
290	WriteSignature	Write stream signature to the stream
291	WriteSingle	Writes a single-type real value to the stream.
293	WriteString	Writes a string value to the stream.
292	WriteUInt64	Write an unsigned 64-bit integer
294	WriteUnicodeString	Write a unicode string to the stream.
293	WriteVariant	Write a variant to the stream
293	WriteWideString	Write a widestring value to the stream

4.35.3 TAbstractObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Virtual; Abstract`

Visibility: `public`

Description: Start writing a collection.

4.35.4 TAbstractObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent (Component: TComponent; Flags: TFileFlags;
ChildPos: Integer); Virtual; Abstract`

Visibility: `public`

Description: Start writing a component

4.35.5 TAbstractObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Virtual; Abstract`

Visibility: public

Description: `WriteSignature` writes the streaming signature to a stream. This method does nothing, it must be implemented by descendents that have a signature header in the stream. (such as binary streams)

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.35.6 TAbstractObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Virtual; Abstract`

Visibility: public

Description: Start writing a list.

4.35.7 TAbstractObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Virtual; Abstract`

Visibility: public

Description: Mark the end of a list.

4.35.8 TAbstractObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Virtual; Abstract`

Visibility: public

Description: Start writing a property

4.35.9 TAbstractObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Virtual; Abstract`

Visibility: public

Description: Marks the end of writing of a property.

4.35.10 TAbstractObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([310](#)), `TWriter.Write` ([468](#))

4.35.11 TAbstractObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Virtual; Abstract`

Visibility: public

Description: Writes binary data to the stream.

4.35.12 TAbstractObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Virtual; Abstract`

Visibility: public

Description: Writes a boolean value to the stream.

4.35.13 TAbstractObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Virtual; Abstract`

Visibility: public

Description: Writes a float value to the stream.

4.35.14 TAbstractObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Virtual; Abstract`

Visibility: public

Description: Writes a single-type real value to the stream.

4.35.15 TAbstractObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Virtual; Abstract`

Visibility: `public`

Description: Writes a date type to the stream.

4.35.16 TAbstractObjectWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency); Virtual; Abstract`

Visibility: `public`

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadCurrency` ([284](#))

4.35.17 TAbstractObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Virtual; Abstract`

Visibility: `public`

Description: Writes an identifier to the stream.

4.35.18 TAbstractObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream

Declaration: `procedure WriteInteger(Value: Int64); Virtual; Abstract`

Visibility: `public`

Description: Writes an integer value to the stream

4.35.19 TAbstractObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Virtual; Abstract`

Visibility: `public`

Description: `WriteUInt64` must be overridden by descendant classes to write a 64-bit unsigned `Value` (value type `QWord`) to the stream.

Errors: None.

See also: `TBinaryObjectWriter.WriteUInt64` ([311](#))

4.35.20 TAbstractObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const Value: Variant); Virtual; Abstract`

Visibility: public

Description: `WriteVariant` must be overridden by descendant classes to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types.

See also: `TBinaryObjectWriter.WriteVariant` ([312](#))

4.35.21 TAbstractObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Virtual; Abstract`

Visibility: public

Description: Writes a methodname to the stream.

4.35.22 TAbstractObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Virtual
; Abstract`

Visibility: public

Description: Writes a set value to the stream.

4.35.23 TAbstractObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Virtual; Abstract`

Visibility: public

Description: Writes a string value to the stream.

4.35.24 TAbstractObjectWriter.WriteWideString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString); Virtual; Abstract`

Visibility: public

Description: `WriteCurrency` is called when a currency-typed value should be written to the stream. This abstract method should be overridden by descendant classes.

See also: `TAbstractObjectReader.ReadWideString` ([288](#))

4.35.25 TAbstractObjectWriter.WriteUnicodeString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Virtual
; Abstract`

Visibility: public

Description: `WriteUnicodeString` must be overridden by descendant classes to write a unicodestring (valuetype `vaUString`) value to the stream.

See also: `TBinaryObjectWriter.WriteUnicodeString` (312)

4.36 TBasicAction

4.36.1 Description

`TBasicAction` implements a basic action class from which all actions are derived. It introduces all basic methods of an action, and implements functionality to maintain a list of clients, i.e. components that are connected with this action.

Do not create instances of `TBasicAction`. Instead, create a descendant class and create an instance of this class instead.

See also: `TBasicActionLink` (298), `TComponent` (330)

4.36.2 Method overview

Page	Method	Description
294	Create	Creates a new instance of a <code>TBasicAction</code> (294) class.
295	Destroy	Destroys the action.
296	Execute	Triggers the <code>OnExecute</code> (297) event
296	ExecuteTarget	Executes the action on the <code>Target</code> object
295	HandlesTarget	Determines whether <code>Target</code> can be handled by this action
296	RegisterChanges	Registers a new client with the action.
296	UnRegisterChanges	Unregisters a client from the list of clients
297	Update	Triggers the <code>OnUpdate</code> (298) event
295	UpdateTarget	Notify client controls when the action updates itself.

4.36.3 Property overview

Page	Properties	Access	Description
297	ActionComponent	rw	Returns the component that initiated the action.
297	OnExecute	rw	Event triggered when the action executes.
298	OnUpdate	rw	Event triggered when the application is idle.

4.36.4 TBasicAction.Create

Synopsis: Creates a new instance of a `TBasicAction` ([294](#)) class.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: public

Description: `Create` calls the inherited constructor, and then initializes the list of clients controls (or action lists).

Under normal circumstances it should not be necessary to create a `TBasicAction` descendant manually, actions are created in an IDE.

See also: `Destroy` ([295](#)), `AssignClient` ([294](#))

4.36.5 `TBasicAction.Destroy`

Synopsis: Destroys the action.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` cleans up the list of client controls and then calls the inherited destructor.

An application programmer should not call `Destroy` directly; Instead `Free` should be called, if it needs to be called at all. Normally the controlling class (e.g. a `TActionList`) will destroy the action.

4.36.6 `TBasicAction.HandlesTarget`

Synopsis: Determines whether `Target` can be handled by this action

Declaration: `function HandlesTarget(Target: TObject) : Boolean; Virtual`

Visibility: `public`

Description: `HandlesTarget` returns `True` if `Target` is a valid client for this action and if so, if it is in a suitable state to execute the action. An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

In `TBasicAction` this method is empty; descendant classes should override this method to implement appropriate checks.

See also: `UpdateTarget` ([295](#)), `ExecuteTarget` ([296](#))

4.36.7 `TBasicAction.UpdateTarget`

Synopsis: Notify client controls when the action updates itself.

Declaration: `procedure UpdateTarget(Target: TObject); Virtual`

Visibility: `public`

Description: `UpdateTarget` should update the client control specified by `Target` when the action updates itself. In `TBasicAction`, the implementation of `UpdateTarget` is empty. Descendant classes should override and implement `UpdateTarget` to actually update the `Target` object.

An application programmer should never need to call `HandlesTarget` directly, it will be called by the action itself when needed.

See also: `HandlesTarget` ([295](#)), `ExecuteTarget` ([296](#))

4.36.8 TBasicAction.ExecuteTarget

Synopsis: Executes the action on the `Target` object

Declaration: `procedure ExecuteTarget (Target: TObject); Virtual`

Visibility: `public`

Description: `ExecuteTarget` performs the action on the `Target` object. In `TBasicAction` this method does nothing. Descendant classes should implement the action to be performed. For instance an action to post data in a dataset could call the `Post` method of the dataset.

An application programmer should never call `ExecuteTarget` directly.

See also: `HandlesTarget` (295), `UpdateTarget` (296), `Execute` (296)

4.36.9 TBasicAction.Execute

Synopsis: Triggers the `OnExecute` (297) event

Declaration: `function Execute : Boolean; Dynamic`

Visibility: `public`

Description: `Execute` triggers the `OnExecute` event, if one is assigned. It returns `True` if the event handler was called, `False` otherwise.

4.36.10 TBasicAction.RegisterChanges

Synopsis: Registers a new client with the action.

Declaration: `procedure RegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `RegisterChanges` adds `Value` to the list of clients.

See also: `UnregisterChanges` (296)

4.36.11 TBasicAction.UnRegisterChanges

Synopsis: Unregisters a client from the list of clients

Declaration: `procedure UnRegisterChanges (Value: TBasicActionLink)`

Visibility: `public`

Description: `UnregisterChanges` removes `Value` from the list of clients. This is called for instance when the action is destroyed, or when the client is assigned a new action.

See also: `UnregisterChanges` (296), `Destroy` (295)

4.36.12 TBasicAction.Update

Synopsis: Triggers the OnUpdate ([298](#)) event

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` triggers the `OnUpdate` event, if one is assigned. It returns `True` if the event was triggered, or `False` if no event was assigned.

Application programmers should never run `Update` directly. The `Update` method is called automatically by the action mechanism; Normally this is in the Idle time of an application. An application programmer should assign the `OnUpdate` ([298](#)) event, and perform any checks in that handler.

See also: `OnUpdate` ([298](#)), `Execute` ([296](#)), `UpdateTarget` ([295](#))

4.36.13 TBasicAction.ActionComponent

Synopsis: Returns the component that initiated the action.

Declaration: `Property ActionComponent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: `ActionComponent` is set to the component that caused the action to execute, e.g. a `toolbutton` or a menu item. The property is set just before the action executes, and is reset to `nil` after the action was executed.

See also: `Execute` ([296](#)), `OnExecute` ([297](#))

4.36.14 TBasicAction.OnExecute

Synopsis: Event triggered when the action executes.

Declaration: `Property OnExecute : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnExecute` is the event triggered when the action is activated (executed). The event is triggered e.g. when the user clicks e.g. on a menu item or a button associated to the action. The application programmer should provide a `OnExecute` event handler to execute whatever code is necessary when the button is pressed or the menu item is chosen.

Note that assigning an `OnExecute` handler will result in the `Execute` ([296](#)) method returning a `True` value. Predefined actions (such as dataset actions) will check the result of `Execute` and will not perform their normal task if the `OnExecute` handler was called.

See also: `Execute` ([296](#)), `OnUpdate` ([298](#))

4.36.15 TBasicAction.OnUpdate

Synopsis: Event triggered when the application is idle.

Declaration: `Property OnUpdate : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnUpdate` is the event triggered when the application is idle, and the action is being updated. The `OnUpdate` event can be used to set the state of the action, for instance disable it if the action cannot be executed at this point in time.

See also: [Update \(297\)](#), [OnExecute \(297\)](#)

4.37 TBasicActionLink

4.37.1 Description

`TBasicActionLink` links an Action to its clients. With each client for an action, a `TBasicActionLink` class is instantiated to handle the communication between the action and the client. It passes events between the action and its clients, and thus presents the action with a uniform interface to the clients.

An application programmer should never use a `TBasicActionLink` instance directly; They are created automatically when an action is associated with a component. Component programmers should create specialized descendants of `TBasicActionLink` which communicate changes in the action to the component.

See also: [TBasicAction \(294\)](#)

4.37.2 Method overview

Page	Method	Description
298	Create	Creates a new instance of the <code>TBasicActionLink</code> class
299	Destroy	Destroys the <code>TBasicActionLink</code> instance.
299	Execute	Calls the action's <code>Execute</code> method.
299	Update	Calls the action's <code>Update</code> method

4.37.3 Property overview

Page	Properties	Access	Description
300	Action	rw	The action to which the link was assigned.
300	OnChange	rw	Event handler triggered when the action's properties change

4.37.4 TBasicActionLink.Create

Synopsis: Creates a new instance of the `TBasicActionLink` class

Declaration: `constructor Create(AClient: TObject); Virtual`

Visibility: `public`

Description: `Create` creates a new instance of a `TBasicActionLink` and assigns `AClient` as the client of the link.

Application programmers should never instantiate `TBasicActionLink` classes directly. An instance is created automatically when an action is assigned to a control (client).

Component programmers can override the `create` constructor to initialize further properties.

See also: `Destroy` ([299](#))

4.37.5 `TBasicActionLink.Destroy`

Synopsis: Destroys the `TBasicActionLink` instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` unregisters the `TBasicActionLink` with the action, and then calls the inherited destructor.

Application programmers should never call `Destroy` directly. If a link should be destroyed at all, the `Free` method should be called instead.

See also: `Create` ([298](#))

4.37.6 `TBasicActionLink.Execute`

Synopsis: Calls the action's `Execute` method.

Declaration: `function Execute(AComponent: TComponent) : Boolean; Virtual`

Visibility: `public`

Description: `Execute` sets the `ActionComponent` ([297](#)) property of the associated `Action` ([300](#)) to `AComponent` and then calls the `Action`'s `execute` ([296](#)) method. After the action has executed, the `ActionComponent` property is cleared again.

The return value of the function is the return value of the `Action`'s `execute` method.

Application programmers should never call `Execute` directly. This method will be called automatically when the associated control is activated. (e.g. a button is clicked on)

Component programmers should call `Execute` whenever the action should be activated.

See also: `Action` ([300](#)), `TBasicAction.ActionComponent` ([297](#)), `TBasicAction.Execute` ([296](#)), `TBasicAction.onExecute` ([297](#))

4.37.7 `TBasicActionLink.Update`

Synopsis: Calls the action's `Update` method

Declaration: `function Update : Boolean; Virtual`

Visibility: `public`

Description: `Update` calls the associated `Action`'s `Update` ([297](#)) method.

Component programmers can override the `Update` method to provide additional processing when the `Update` method occurs.

4.37.8 TBasicActionLink.Action

Synopsis: The action to which the link was assigned.

Declaration: `Property Action : TBasicAction`

Visibility: `public`

Access: `Read, Write`

Description: `Action` represents the Action (294) which was assigned to the client. Setting this property will unregister the client at the old action (if one existed) and registers the client at the new action.

See also: `TBasicAction` (294)

4.37.9 TBasicActionLink.OnChange

Synopsis: Event handler triggered when the action's properties change

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read, Write`

Description: `OnChange` is the event triggered when the action's properties change.

Application programmers should never need to assign this event. Component programmers can assign this event to have a client control reflect any changes in an Action's properties.

See also: `Change` (298), `TBasicAction.Change` (294)

4.38 TBinaryObjectReader

4.38.1 Description

The `TBinaryObjectReader` class reads component data stored in binary form in a file. For this, it overrides or implements all abstract methods from `TAbstractObjectReader` (281). No new functionality is added by this class, it is a driver class for the streaming system.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (414) call should be used.

See also: `TAbstractObjectReader` (281), `TBinaryObjectWriter` (307)

4.38.2 Method overview

Page	Method	Description
302	<code>BeginComponent</code>	Start reading a component.
303	<code>BeginProperty</code>	Start reading a property.
302	<code>BeginRootComponent</code>	Start reading the root component.
301	<code>Create</code>	Creates a new binary data reader instance.
301	<code>Destroy</code>	Destroys the binary data reader.
302	<code>NextValue</code>	Return the type of the next value.
303	<code>Read</code>	Read raw data from stream
303	<code>ReadBinary</code>	Start reading a binary value.
304	<code>ReadCurrency</code>	Read a currency value from the stream.
304	<code>ReadDate</code>	Read a date.
303	<code>ReadFloat</code>	Read a float value
304	<code>ReadIdent</code>	Read an identifier
304	<code>ReadInt16</code>	Read a 16-bits integer.
305	<code>ReadInt32</code>	Read a 32-bits integer.
305	<code>ReadInt64</code>	Read a 64-bits integer.
304	<code>ReadInt8</code>	Read an 8-bits integer.
305	<code>ReadSet</code>	Read a set
305	<code>ReadSignature</code>	Reads the filer signature
303	<code>ReadSingle</code>	Read a single-size float value
306	<code>ReadStr</code>	Read a short string
306	<code>ReadString</code>	Read a string
306	<code>ReadUnicodeString</code>	Read a unicode string value
302	<code>ReadValue</code>	Read the next value in the stream
306	<code>ReadWideString</code>	Read a widestring value from the stream.
307	<code>SkipComponent</code>	Skip a component's data
307	<code>SkipValue</code>	Skip a value's data

4.38.3 TBinaryObjectReader.Create

Synopsis: Creates a new binary data reader instance.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new binary component data reader. The `Stream` stream is the stream from which data will be read. The `BufSize` argument is the size of the internal buffer that will be used by the reader. This can be used to optimize the reading process.

See also: `TAbstractObjectReader` ([281](#))

4.38.4 TBinaryObjectReader.Destroy

Synopsis: Destroys the binary data reader.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the buffer allocated when the instance was created. It also positions the stream on the last used position in the stream (the buffering may cause the reader to read more bytes than were actually used.)

See also: `TBinaryObjectReader.Create` ([301](#))

4.38.5 TBinaryObjectReader.NextValue

Synopsis: Return the type of the next value.

Declaration: `function NextValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` returns the type of the next value in a binary stream, but does not read the value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.6 TBinaryObjectReader.ReadValue

Synopsis: Read the next value in the stream

Declaration: `function ReadValue : TValueType; Override`

Visibility: `public`

Description: `NextValue` reads the next value in a binary stream and returns the type of the read value.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.7 TBinaryObjectReader.BeginRootComponent

Synopsis: Start reading the root component.

Declaration: `procedure BeginRootComponent; Override`

Visibility: `public`

Description: `BeginRootComponent` starts reading the root component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.8 TBinaryObjectReader.BeginComponent

Synopsis: Start reading a component.

Declaration: `procedure BeginComponent (var Flags: TFileFlags;
var AChildPos: Integer;
var CompClassName: string; var CompName: string)
; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.9 TBinaryObjectReader.BeginProperty

Synopsis: Start reading a property.

Declaration: `function BeginProperty : string; Override`

Visibility: `public`

Description: This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.10 TBinaryObjectReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Override`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([283](#)), `TReader.Read` ([398](#))

4.38.11 TBinaryObjectReader.ReadBinary

Synopsis: Start reading a binary value.

Declaration: `procedure ReadBinary(const DestData: TMemoryStream); Override`

Visibility: `public`

Description: `ReadBinary` reads a binary value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.12 TBinaryObjectReader.ReadFloat

Synopsis: Read a float value

Declaration: `function ReadFloat : Extended; Override`

Visibility: `public`

Description: `ReadFloat` reads a float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.13 TBinaryObjectReader.ReadSingle

Synopsis: Read a single-size float value

Declaration: `function ReadSingle : Single; Override`

Visibility: `public`

Description: `ReadSingle` reads a single-sized float value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.14 TBinaryObjectReader.ReadDate

Synopsis: Read a date.

Declaration: `function ReadDate : TDateTime; Override`

Visibility: `public`

Description: `ReadDate` reads a date value from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.15 TBinaryObjectReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency; Override`

Visibility: `public`

Description: `var>ReadCurrency` reads a currency-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([281](#)).

See also: `TAbstractObjectReader.ReadCurrency` ([284](#)), `TBinaryObjectWriter.WriteCurrency` ([311](#))

4.38.16 TBinaryObjectReader.ReadIdent

Synopsis: Read an identifier

Declaration: `function ReadIdent(ValueType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadIdent` reads an identifier from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.17 TBinaryObjectReader.ReadInt8

Synopsis: Read an 8-bits integer.

Declaration: `function ReadInt8 : ShortInt; Override`

Visibility: `public`

Description: `Read8Int` reads an 8-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.18 TBinaryObjectReader.ReadInt16

Synopsis: Read a 16-bits integer.

Declaration: `function ReadInt16 : SmallInt; Override`

Visibility: `public`

Description: `Read16Int` reads a 16-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.19 `TBinaryObjectReader.ReadInt32`

Synopsis: Read a 32-bits integer.

Declaration: `function ReadInt32 : LongInt; Override`

Visibility: `public`

Description: `Read32Int` reads a 32-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.20 `TBinaryObjectReader.ReadInt64`

Synopsis: Read a 64-bits integer.

Declaration: `function ReadInt64 : Int64; Override`

Visibility: `public`

Description: `Read64Int` reads a 64-bits signed integer from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.21 `TBinaryObjectReader.ReadSet`

Synopsis: Read a set

Declaration: `function ReadSet (EnumType: Pointer) : Integer; Override`

Visibility: `public`

Description: `ReadSet` reads a set from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.22 `TBinaryObjectReader.ReadSignature`

Synopsis: Reads the filer signature

Declaration: `procedure ReadSignature; Override`

Visibility: `public`

Description: `ReadSignature` is overridden by `TBinaryObjectReader` to read the signature (TPF0) from binary streams.

Errors: If the stream does not start with the correct signature, an `EReadError` ([267](#)) exception is raised.

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TAbstractObjectWriter.WriteSignature` ([290](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.38.23 TBinaryObjectReader.ReadStr

Synopsis: Read a short string

Declaration: `function ReadStr : string; Override`

Visibility: `public`

Description: `ReadStr` reads a short string from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.24 TBinaryObjectReader.ReadString

Synopsis: Read a string

Declaration: `function ReadString(StringType: TValueType) : string; Override`

Visibility: `public`

Description: `ReadStr` reads a string of type `StringType` from a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#))

4.38.25 TBinaryObjectReader.ReadWideString

Synopsis: Read a widestring value from the stream.

Declaration: `function ReadWideString : WideString; Override`

Visibility: `public`

Description: `var>ReadWideString` reads a widestring-typed value from a binary stream. It is the implementation of the method introduced in `TAbstractObjectReader` ([281](#)).

See also: `TAbstractObjectReader.ReadWideString` ([288](#)), `TBinaryObjectWriter.WriteWideString` ([312](#))

4.38.26 TBinaryObjectReader.ReadUnicodeString

Synopsis: Read a unicode string value

Declaration: `function ReadUnicodeString : UnicodeString; Override`

Visibility: `public`

Description: `ReadUnicodeString` is overridden by `TBinaryObjectReader` to read a `UnicodeString` value from the binary stream.

See also: `TAbstractObjectReader.ReadUnicodeString` ([288](#))

4.38.27 TBinaryObjectReader.SkipComponent

Synopsis: Skip a component's data

Declaration: `procedure SkipComponent (SkipComponentInfos: Boolean);` Override

Visibility: public

Description: `SkipComponent` skips the data of a component in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#)).

4.38.28 TBinaryObjectReader.SkipValue

Synopsis: Skip a value's data

Declaration: `procedure SkipValue;` Override

Visibility: public

Description: `SkipComponent` skips the data of the next value in a binary stream.

This method is simply the implementation for a binary stream of the abstract method introduced in `TAbstractObjectReader` ([281](#)).

4.39 TBinaryObjectWriter

4.39.1 Description

Driver class which stores component data in binary form.

4.39.2 Method overview

Page	Method	Description
309	BeginCollection	Start writing a collection.
309	BeginComponent	Start writing a component
309	BeginList	Start writing a list.
309	BeginProperty	Start writing a property
308	Create	Creates a new instance of a binary object writer.
308	Destroy	Destroys an instance of the binary object writer.
309	EndList	Mark the end of a list.
309	EndProperty	Marks the end of writing of a property.
310	Write	Write raw data to stream
310	WriteBinary	Writes binary data to the stream.
310	WriteBoolean	Writes a boolean value to the stream.
311	WriteCurrency	Write a currency-valued type to a stream
310	WriteDate	Writes a date type to the stream.
310	WriteFloat	Writes a float value to the stream.
311	WriteIdent	Writes an identifier to the stream.
311	WriteInteger	Writes an integer value to the stream.
311	WriteMethodName	Writes a methodname to the stream.
311	WriteSet	Writes a set value to the stream.
308	WriteSignature	Write stream signature to the stream
310	WriteSingle	Writes a single-type real value to the stream.
312	WriteStr	Write a string to the binary stream
312	WriteString	Writes a string value to the stream.
311	WriteUInt64	Write an unsigned 64-bit integer
312	WriteUnicodeString	Write a unicode string to the stream.
312	WriteVariant	Write a variant to the stream
312	WriteWideString	Write a widestring-valued type to a stream

4.39.3 TBinaryObjectWriter.Create

Synopsis: Creates a new instance of a binary object writer.

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new instance of a binary object writer.

4.39.4 TBinaryObjectWriter.Destroy

Synopsis: Destroys an instance of the binary object writer.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys an instance of the binary object writer.

4.39.5 TBinaryObjectWriter.WriteSignature

Synopsis: Write stream signature to the stream

Declaration: `procedure WriteSignature; Override`

Visibility: public

Description: `WriteSignature` is overridden by `TBinaryObjectWriter` to write the signature (TPF0) to binary streams.

See also: `TAbstractObjectWriter.WriteSignature` (290), `TAbstractObjectReader.ReadSignature` (287), `TBinaryObjectReader.ReadSignature` (305)

4.39.6 TBinaryObjectWriter.BeginCollection

Synopsis: Start writing a collection.

Declaration: `procedure BeginCollection; Override`

Visibility: public

4.39.7 TBinaryObjectWriter.BeginComponent

Synopsis: Start writing a component

Declaration: `procedure BeginComponent(Component: TComponent; Flags: TFileFlags; ChildPos: Integer); Override`

Visibility: public

4.39.8 TBinaryObjectWriter.BeginList

Synopsis: Start writing a list.

Declaration: `procedure BeginList; Override`

Visibility: public

4.39.9 TBinaryObjectWriter.EndList

Synopsis: Mark the end of a list.

Declaration: `procedure EndList; Override`

Visibility: public

4.39.10 TBinaryObjectWriter.BeginProperty

Synopsis: Start writing a property

Declaration: `procedure BeginProperty(const PropName: string); Override`

Visibility: public

4.39.11 TBinaryObjectWriter.EndProperty

Synopsis: Marks the end of writing of a property.

Declaration: `procedure EndProperty; Override`

Visibility: public

4.39.12 TBinaryObjectWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Override`

Visibility: public

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectWriter.Write` ([291](#)), `TWriter.Write` ([468](#))

4.39.13 TBinaryObjectWriter.WriteBinary

Synopsis: Writes binary data to the stream.

Declaration: `procedure WriteBinary(const Buffer; Count: LongInt); Override`

Visibility: public

4.39.14 TBinaryObjectWriter.WriteBoolean

Synopsis: Writes a boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean); Override`

Visibility: public

4.39.15 TBinaryObjectWriter.WriteFloat

Synopsis: Writes a float value to the stream.

Declaration: `procedure WriteFloat(const Value: Extended); Override`

Visibility: public

4.39.16 TBinaryObjectWriter.WriteSingle

Synopsis: Writes a single-type real value to the stream.

Declaration: `procedure WriteSingle(const Value: Single); Override`

Visibility: public

4.39.17 TBinaryObjectWriter.WriteDate

Synopsis: Writes a date type to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime); Override`

Visibility: public

4.39.18 TBinaryObjectWriter.WriteCurrency

Synopsis: Write a currency-valued type to a stream

Declaration: `procedure WriteCurrency(const Value: Currency); Override`

Visibility: public

Description: `WriteCurrency` writes a currency-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (289).

See also: `TAbstractObjectWriter.WriteCurrency` (292)

4.39.19 TBinaryObjectWriter.WriteIdent

Synopsis: Writes an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string); Override`

Visibility: public

4.39.20 TBinaryObjectWriter.WriteInteger

Synopsis: Writes an integer value to the stream.

Declaration: `procedure WriteInteger(Value: Int64); Override`

Visibility: public

4.39.21 TBinaryObjectWriter.WriteUInt64

Synopsis: Write an unsigned 64-bit integer

Declaration: `procedure WriteUInt64(Value: QWord); Override`

Visibility: public

Description: `WriteUInt64` is overridden by `TBinaryObjectWriter` to write an unsigned 64-bit integer (QWord) to the stream. It tries to use the smallest possible storage for the value that is passed. (largest valuetype will be `vaQWord`).

See also: `TAbstractObjectWriter.WriteUInt64` (292)

4.39.22 TBinaryObjectWriter.WriteMethodName

Synopsis: Writes a methodname to the stream.

Declaration: `procedure WriteMethodName(const Name: string); Override`

Visibility: public

4.39.23 TBinaryObjectWriter.WriteSet

Synopsis: Writes a set value to the stream.

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer); Override`

Visibility: public

4.39.24 TBinaryObjectWriter.WriteString

Synopsis: Write a string to the binary stream

Declaration: `procedure WriteStr(const Value: string)`

Visibility: `public`

Description: `WriteStr` writes a string value to the binary stream. It is exposed so it can be used in `DefineProperties`.

4.39.25 TBinaryObjectWriter.WriteString

Synopsis: Writes a string value to the stream.

Declaration: `procedure WriteString(const Value: string); Override`

Visibility: `public`

4.39.26 TBinaryObjectWriter.WriteString

Synopsis: Write a widestring-valued type to a stream

Declaration: `procedure WriteWideString(const Value: WideString); Override`

Visibility: `public`

Description: `WriteWideString` writes a widestring-typed value to a binary stream. It is the implementation of the method introduced in `TAbstractObjectWriter` (289).

See also: `TAbstractObjectWriter.WriteString` (293)

4.39.27 TBinaryObjectWriter.WriteString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString); Override`

Visibility: `public`

Description: `WriteUnicodeString` is overridden `TBinaryObjectWriter` to write a unicodestring (valuetype `vaUString`) value to the stream. It simply writes the character length and then all widecharacters.

See also: `TAbstractObjectWriter.WriteString` (294)

4.39.28 TBinaryObjectWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant); Override`

Visibility: `public`

Description: `WriteVariant` is overridden by `TBinaryObjectWriter` to write a simple variant type to the stream. `WriteVariant` does not write arrays types or complex types. Only null, integer (ordinal) float and string types are written.

Errors: If a non-supported type is written, then an `EWriteError` exception is.

4.40 TBits

4.40.1 Description

`TBits` can be used to store collections of bits in an indexed array. This is especially useful for storing collections of booleans: Normally the size of a boolean is the size of the smallest enumerated type, i.e. 1 byte. Since a bit can take 2 values it can be used to store a boolean as well. Since `TBits` can store 8 bits in a byte, it takes 8 times less space to store an array of booleans in a `TBits` class then it would take to store them in a conventional array.

`TBits` introduces methods to store and retrieve bit values, apply masks, and search for bits.

4.40.2 Method overview

Page	Method	Description
315	<code>AndBits</code>	Performs an <code>and</code> operation on the bits.
314	<code>Clear</code>	Clears a particular bit.
315	<code>Clearall</code>	Clears all bits in the array.
313	<code>Create</code>	Creates a new bits collection.
314	<code>Destroy</code>	Destroys a bit collection
317	<code>Equals</code>	Determines whether the bits of 2 arrays are equal.
317	<code>FindFirstBit</code>	Find first bit with a particular value
318	<code>FindNextBit</code>	Searches the next bit with a particular value.
318	<code>FindPrevBit</code>	Searches the previous bit with a particular value.
316	<code>Get</code>	Retrieve the value of a particular bit
314	<code>GetFSIZE</code>	Returns the number of records used to store the bits.
316	<code>Grow</code>	Expands the bits array to the requested size.
316	<code>NotBits</code>	Performs a <code>not</code> operation on the bits.
318	<code>OpenBit</code>	Returns the position of the first bit that is set to <code>False</code> .
315	<code>OrBits</code>	Performs an <code>or</code> operation on the bits.
317	<code>SetIndex</code>	Sets the start position for <code>FindNextBit</code> (318) and <code>FindPrevBit</code> (318)
314	<code>SetOn</code>	Turn a particular bit on.
315	<code>XorBits</code>	Performs a <code>xor</code> operation on the bits.

4.40.3 Property overview

Page	Properties	Access	Description
319	<code>Bits</code>	<code>rw</code>	Access to all bits in the array.
319	<code>Size</code>	<code>rw</code>	Current size of the array of bits.

4.40.4 TBits.Create

Synopsis: Creates a new bits collection.

Declaration: `constructor Create(TheSize: LongInt); Virtual`

Visibility: `public`

Description: `Create` creates a new bit collection with initial size `TheSize`. The size of the collection can be changed later on.

All bits are initially set to zero.

See also: `Destroy` ([314](#))

4.40.5 TBits.Destroy

Synopsis: Destroys a bit collection

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys a previously created bit collection and releases all memory used to store the bit collection.

`Destroy` should never be called directly, `Free` should be used instead.

Errors: None.

See also: [Create \(313\)](#)

4.40.6 TBits.GetFSize

Synopsis: Returns the number of records used to store the bits.

Declaration: `function GetFSize : LongInt`

Visibility: `public`

Description: `GetFSize` returns the number of records used to store the current number of bits.

Errors: None.

See also: [Size \(319\)](#)

4.40.7 TBits.SetOn

Synopsis: Turn a particular bit on.

Declaration: `procedure SetOn(Bit: LongInt)`

Visibility: `public`

Description: `SetOn` turns on the bit at position `bit`, i.e. sets it to 1. If `bit` is at a position bigger than the current size, the collection is expanded to the required size using [Grow \(316\)](#).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an [EBitsError \(264\)](#) exception is raised.

See also: [Bits \(319\)](#), [Clear \(314\)](#)

4.40.8 TBits.Clear

Synopsis: Clears a particular bit.

Declaration: `procedure Clear(Bit: LongInt)`

Visibility: `public`

Description: `Clear` clears the bit at position `bit`. If the array `bit` is at a position bigger than the current size, the collection is expanded to the required size using [Grow \(316\)](#).

Errors: If `bit` is larger than the maximum allowed bits array size or is negative, an [EBitsError \(264\)](#) exception is raised.

See also: [Bits \(319\)](#), [seton \(314\)](#)

4.40.9 TBits.Clearall

Synopsis: Clears all bits in the array.

Declaration: `procedure Clearall`

Visibility: `public`

Description: `ClearAll` clears all bits in the array, i.e. sets them to zero. `ClearAll` works faster than clearing all individual bits, since it uses the packed nature of the bits.

Errors: None.

See also: [Bits \(319\)](#), [clear \(314\)](#)

4.40.10 TBits.AndBits

Synopsis: Performs an `and` operation on the bits.

Declaration: `procedure AndBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `and` operation on the bits in the array with the bits of array `BitSet`. If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are cleared.

Errors: None.

See also: [ClearAll \(315\)](#), [OrBits \(315\)](#), [XOrBits \(315\)](#), [NotBits \(316\)](#)

4.40.11 TBits.OrBits

Synopsis: Performs an `or` operation on the bits.

Declaration: `procedure OrBits(BitSet: TBits)`

Visibility: `public`

Description: `andbits` performs an `or` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `or` operation is performed.

Errors: None.

See also: [ClearAll \(315\)](#), [andBits \(315\)](#), [XOrBits \(315\)](#), [NotBits \(316\)](#)

4.40.12 TBits.XorBits

Synopsis: Performs a `xor` operation on the bits.

Declaration: `procedure XorBits(BitSet: TBits)`

Visibility: `public`

Description: `XorBits` performs a `xor` operation on the bits in the array with the bits of array `BitSet`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

If the current array contains less bits than `BitSet` then it is grown to the size of `BitSet` before the `xor` operation is performed.

Errors: None.

See also: `ClearAll` (315), `andBits` (315), `OrBits` (315), `NotBits` (316)

4.40.13 TBits.NotBits

Synopsis: Performs a `not` operation on the bits.

Declaration: `procedure NotBits(BitSet: TBits)`

Visibility: `public`

Description: `NotBits` performs a `not` operation on the bits in the array with the bits of array `Bitset`.

If `BitSet` contains less bits than the current array, then all bits which have no counterpart in `BitSet` are left untouched.

Errors: None.

See also: `ClearAll` (315), `andBits` (315), `OrBits` (315), `XOrBits` (315)

4.40.14 TBits.Get

Synopsis: Retrieve the value of a particular bit

Declaration: `function Get(Bit: LongInt) : Boolean`

Visibility: `public`

Description: `Get` returns `True` if the bit at position `bit` is set, or `False` if it is not set.

Errors: If `bit` is not a valid bit index then an `EBitsError` (264) exception is raised.

See also: `Bits` (319), `FindFirstBit` (317), `seton` (314)

4.40.15 TBits.Grow

Synopsis: Expands the bits array to the requested size.

Declaration: `procedure Grow(NBit: LongInt)`

Visibility: `public`

Description: `Grow` expands the bit array so it can at least contain `nbit` bits. If `nbit` is less than the current size, nothing happens.

Errors: If there is not enough memory to complete the operation, then an `EBitsError` (264) is raised.

See also: `Size` (319)

4.40.16 TBits.Equals

Synopsis: Determines whether the bits of 2 arrays are equal.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`
`function Equals(BitSet: TBits) : Boolean; Overload`

Visibility: public

Description: `equals` returns `True` if all the bits in `BitSet` are the same as the ones in the current `BitSet`; if not, `False` is returned.

If the sizes of the two `BitSets` are different, the arrays are still reported equal when all the bits in the larger set, which are not present in the smaller set, are zero.

Errors: None.

See also: `ClearAll` (315), `andBits` (315), `OrBits` (315), `XOrBits` (315)

4.40.17 TBits.SetIndex

Synopsis: Sets the start position for `FindNextBit` (318) and `FindPrevBit` (318)

Declaration: `procedure SetIndex(Index: LongInt)`

Visibility: public

Description: `SetIndex` sets the search start position for `FindNextBit` (318) and `FindPrevBit` (318) to `Index`. This means that these calls will start searching from position `Index`.

This mechanism provides an alternative to `FindFirstBit` (317) which can also be used to position for the `FindNextBit` and `FindPrevBit` calls.

Errors: None.

See also: `FindNextBit` (318), `FindPrevBit` (318), `FindFirstBit` (317), `OpenBit` (318)

4.40.18 TBits.FindFirstBit

Synopsis: Find first bit with a particular value

Declaration: `function FindFirstBit(State: Boolean) : LongInt`

Visibility: public

Description: `FindFirstBit` searches for the first bit with value `State`. It returns the position of this bit, or `-1` if no such bit was found.

The search starts at position 0 in the array. If the first search returned a positive result, the found position is saved, and the `FindNextBit` (318) and `FindPrevBit` (318) will use this position to resume the search. To start a search from a certain position, the start position can be set with the `SetIndex` (317) instead.

Errors: None.

See also: `FindNextBit` (318), `FindPrevBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.19 TBits.FindNextBit

Synopsis: Searches the next bit with a particular value.

Declaration: `function FindNextBit : LongInt`

Visibility: `public`

Description: `FindNextBit` resumes a previously started search. It searches for the next bit with the value specified in the `FindFirstBit` (317). The search is done towards the end of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (317).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `FindFirstBit` (317), `FindPrevBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.20 TBits.FindPrevBit

Synopsis: Searches the previous bit with a particular value.

Declaration: `function FindPrevBit : LongInt`

Visibility: `public`

Description: `FindPrevBit` resumes a previously started search. It searches for the previous bit with the value specified in the `FindFirstBit` (317). The search is done towards the beginning of the array and starts at the position last reported by one of the `Find` calls or at the position set with `SetIndex` (317).

If another bit with the same value is found, its position is returned. If no more bits with the same value are present in the array, `-1` is returned.

Errors: None.

See also: `FindFirstBit` (317), `FindNextBit` (318), `OpenBit` (318), `SetIndex` (317)

4.40.21 TBits.OpenBit

Synopsis: Returns the position of the first bit that is set to `False`.

Declaration: `function OpenBit : LongInt`

Visibility: `public`

Description: `OpenBit` returns the position of the first bit whose value is `0` (`False`), or `-1` if no open bit was found. This call is equivalent to `FindFirstBit(False)`, except that it doesn't set the position for the next searches.

Errors: None.

See also: `FindNextBit` (317), `FindPrevBit` (318), `FindFirstBit` (317), `SetIndex` (317)

4.40.22 TBits.Bits

Synopsis: Access to all bits in the array.

Declaration: `Property Bits[Bit: LongInt]: Boolean; default`

Visibility: public

Access: Read,Write

Description: `Bits` allows indexed access to all of the bits in the array. It gives `True` if the bit is 1, `False` otherwise; Assigning to this property will set, respectively clear the bit.

Errors: If an index is specified which is out of the allowed range then an `EBitsError` (264) exception is raised.

See also: `Size` (319)

4.40.23 TBits.Size

Synopsis: Current size of the array of bits.

Declaration: `Property Size : LongInt`

Visibility: public

Access: Read,Write

Description: `Size` is the current size of the bit array. Setting this property will adjust the size; this is equivalent to calling `Grow(Value-1)`

Errors: If an invalid size (negative or too large) is specified, a `EBitsError` (264) exception is raised.

See also: `Bits` (319)

4.41 TBytesStream

4.41.1 Description

`TBytesStream` is a stream that uses an array of byte (`TBytes` (231)) to keep the stream data. it overrides the `TMemoryStream` (379) memory allocation routine to use the array of bytes. The array of bytes is exposed through the `Bytes` (231) property.

See also: `TBytes` (231), `TMemoryStream` (379), `Bytes` (231)

4.41.2 Method overview

Page	Method	Description
320	Create	Create a new instance of the stream, initializing it with an array of bytes

4.41.3 Property overview

Page	Properties	Access	Description
320	Bytes	r	The stream data as an array of bytes.

4.41.4 TBytesStream.Create

Synopsis: Create a new instance of the stream, initializing it with an array of bytes

Declaration: `constructor Create(const ABytes: TBytes);` Overload

Visibility: `public`

Description: `Create` creates a new instance and initializes the memory with the data in `ABytes`.

See also: [TBytes \(231\)](#), [TMemoryStream \(379\)](#), [Bytes \(231\)](#)

4.41.5 TBytesStream.Bytes

Synopsis: The stream data as an array of bytes.

Declaration: `Property Bytes : TBytes`

Visibility: `public`

Access: `Read`

Description: `Bytes` provides byte-sized access to the array of bytes that represent the stream data. As a pointer value, it equals `TCustomMemoryStream.Memory (344)`, meaning that `Memory` points to the first byte in the array.

See also: [TBytes \(231\)](#), [TMemoryStream \(379\)](#), [TCustomMemoryStream.Memory \(344\)](#)

4.42 TCollection

4.42.1 Description

`TCollection` implements functionality to manage a collection of named objects. Each of these objects needs to be a descendant of the `TCollectionItem (328)` class. Exactly which type of object is managed can be seen from the `TCollection.ItemClass (326)` property.

Normally, no `TCollection` is created directly. Instead, a descendants of `TCollection` and `TCollectionItem (328)` are created as a pair.

See also: [TCollectionItem \(328\)](#)

4.42.2 Method overview

Page	Method	Description
322	Add	Creates and adds a new item to the collection.
322	Assign	Assigns one collection to another.
322	BeginUpdate	Start an update batch.
323	Clear	Removes all items from the collection.
321	Create	Creates a new collection.
323	Delete	Delete an item from the collection.
321	Destroy	Destroys the collection and frees all the objects it manages.
323	EndUpdate	Ends an update batch.
325	Exchange	Exchange 2 items in the collection
324	FindItemID	Searches for an Item in the collection, based on its TCollectionItem.ID (329) property.
324	GetEnumerator	Create an IEnumerator instance
324	GetNamePath	Overrides TPersistent.GetNamePath (392) to return a proper pathname.
324	Insert	Insert an item in the collection.
322	Owner	Owner of the collection.
325	Sort	Sort the items in the collection

4.42.3 Property overview

Page	Properties	Access	Description
325	Count	r	Number of items in the collection.
326	ItemClass	r	Class pointer for each item in the collection.
326	Items	rw	Indexed array of items in the collection.

4.42.4 TCollection.Create

Synopsis: Creates a new collection.

Declaration: constructor Create(AItemClass: TCollectionItemClass)

Visibility: public

Description: Create instantiates a new instance of the TCollection class which will manage objects of class AItemClass. It creates the list used to hold all objects, and stores the AItemClass for the adding of new objects to the collection.

See also: TCollection.ItemClass ([326](#)), TCollection.Destroy ([321](#))

4.42.5 TCollection.Destroy

Synopsis: Destroys the collection and frees all the objects it manages.

Declaration: destructor Destroy; Override

Visibility: public

Description: Destroy first clears the collection, and then frees all memory allocated to this instance.

Don't call Destroy directly, call Free instead.

See also: TCollection.Create ([321](#))

4.42.6 TCollection.Owner

Synopsis: Owner of the collection.

Declaration: `function Owner : TPersistent`

Visibility: `public`

Description: `Owner` returns a reference to the owner of the collection. This property is required by the object inspector to be able to show the collection.

4.42.7 TCollection.Add

Synopsis: Creates and adds a new item to the collection.

Declaration: `function Add : TCollectionItem`

Visibility: `public`

Description: `Add` instantiates a new item of class `TCollection.ItemClass` (326) and adds it to the list. The newly created object is returned.

See also: `TCollection.ItemClass` (326), `TCollection.Clear` (323)

4.42.8 TCollection.Assign

Synopsis: Assigns one collection to another.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` assigns the contents of one collection to another. It does this by clearing the items list, and adding as much elements as there are in the `Source` collection; it assigns to each created element the contents of it's counterpart in the `Source` element.

Two collections cannot be assigned to each other if instances of the `ItemClass` classes cannot be assigned to each other.

Errors: If the objects in the collections cannot be assigned to one another, then an `EConvertError` is raised.

See also: `TPersistent.Assign` (391), `TCollectionItem` (328)

4.42.9 TCollection.BeginUpdate

Synopsis: Start an update batch.

Declaration: `procedure BeginUpdate; Virtual`

Visibility: `public`

Description: `BeginUpdate` is called at the beginning of a batch update. It raises the update count with 1.

Call `BeginUpdate` at the beginning of a series of operations that will change the state of the collection. This will avoid the call to `TCollection.Update` (320) for each operation. At the end of the operations, a corresponding call to `EndUpdate` must be made. It is best to do this in the context of a `Try ... finally` block:

```

With MyCollection Do
  try
    BeginUpdate;
    // Some Lengthy operations
  finally
    EndUpdate;
  end;

```

This insures that the number of calls to `BeginUpdate` always matches the number of calls to `TCollection.EndUpdate` (323), even in case of an exception.

See also: `TCollection.EndUpdate` (323), `TCollection.Changed` (320), `TCollection.Update` (320)

4.42.10 TCollection.Clear

Synopsis: Removes all items from the collection.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` will clear the collection, i.e. each item in the collection is destroyed and removed from memory. After a call to `Clear`, `Count` is zero.

See also: `TCollection.Add` (322), `TCollectionItem.Destroy` (328), `TCollection.Destroy` (321)

4.42.11 TCollection.EndUpdate

Synopsis: Ends an update batch.

Declaration: `procedure EndUpdate; Virtual`

Visibility: `public`

Description: `EndUpdate` signals the end of a series of operations that change the state of the collection, possibly triggering an update event. It does this by decreasing the update count with 1 and calling `TCollection.Changed` (320) it should always be used in conjunction with `TCollection.BeginUpdate` (322), preferably in the `Finally` section of a `Try ... Finally` block.

See also: `TCollection.BeginUpdate` (322), `TCollection.Changed` (320), `TCollection.Update` (320)

4.42.12 TCollection.Delete

Synopsis: Delete an item from the collection.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at (zero based) position `Index` from the collection. This will result in a `cnDeleted` notification.

Errors: If an invalid index is specified, an `EListError` exception is raised.

See also: `TCollection.Items` (326), `TCollection.Insert` (324), `TCollection.Clear` (323)

4.42.13 TCollection.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TCollectionEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1425) interface for `TCollection`. It creates a `TCollectionEnumerator` (326) instance and returns its `IEnumerator` (1426) interface.

See also: `TCollectionEnumerator` (326), `IEnumerator` (1426), `IEnumerable` (1425)

4.42.14 TCollection.GetNamePath

Synopsis: Overrides `TPersistent.GetNamePath` (392) to return a proper pathname.

Declaration: `function GetNamePath : string; Override`

Visibility: public

Description: `GetNamePath` returns the name path for this collection. If the following conditions are satisfied:

1. There is an owner object.
2. The owner object returns a non-empty name path.
3. The `TCollection.Propname` (320) property is not empty

collection has an owner and the owning object has a name, then the function returns the owner name, followed by the propname. If one of the conditions is not satisfied, then the classname is returned.

See also: `TCollection.GetOwner` (320), `TCollection.Propname` (320)

4.42.15 TCollection.Insert

Synopsis: Insert an item in the collection.

Declaration: `function Insert(Index: Integer) : TCollectionItem`

Visibility: public

Description: `Insert` creates a new item instance and inserts it in the collection at position `Index`, and returns the new instance.

In contrast, `TCollection.Add` (322) adds a new item at the end.

Errors: None.

See also: `TCollection.Add` (322), `TCollection.Delete` (323), `TCollection.Items` (326)

4.42.16 TCollection.FindItemID

Synopsis: Searches for an Item in the collection, based on its `TCollectionItem.ID` (329) property.

Declaration: `function FindItemID(ID: Integer) : TCollectionItem`

Visibility: public

Description: `FindItemID` searches through the collection for the item that has a value of `ID` for its `TCollectionItem.ID` (329) property, and returns the found item. If no such item is found in the collection, `Nil` is returned.

The routine performs a linear search, so this can be slow on very large collections.

See also: `TCollection.Items` (326), `TCollectionItem.ID` (329)

4.42.17 TCollection.Exchange

Synopsis: Exchange 2 items in the collection

Declaration: `procedure Exchange(const Index1: Integer; const index2: Integer)`

Visibility: public

Description: `Exchange` exchanges the items at indexes `Index1` and `Index2` in the collection.

Errors: If one of the two indexes is invalid (less than zero or larger than the number of items) an `EListError` exception is raised.

See also: `Items` (326), `TCollectionItem.Index` (330)

4.42.18 TCollection.Sort

Synopsis: Sort the items in the collection

Declaration: `procedure Sort(const Compare: TCollectionSortCompare)`

Visibility: public

Description: `Sort` sorts the items in the collection, and uses the `Compare` procedure to compare 2 items in the collection. It is more efficient to use this method than to perform the sort manually, because the list items are manipulated directly.

For more information on how the `Compare` function should behave, see the `TCollectionSortCompare` (236) type.

See also: `TCollectionSortCompare` (236)

4.42.19 TCollection.Count

Synopsis: Number of items in the collection.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` contains the number of items in the collection.

Remark: The items in the collection are identified by their `TCollectionItem.Index` (330) property, which is a zero-based index, meaning that it can take values between 0 and `Count-1`, borders included.

See also: `TCollectionItem.Index` (330), `TCollection.Items` (326)

4.42.20 TCollection.ItemClass

Synopsis: Class pointer for each item in the collection.

Declaration: `Property ItemClass : TCollectionItemClass`

Visibility: public

Access: Read

Description: `ItemClass` is the class pointer with which each new item in the collection is created. It is the value that was passed to the collection's constructor when it was created, and does not change during the lifetime of the collection.

See also: `TCollectionItem` (328), `TCollection.Items` (326)

4.42.21 TCollection.Items

Synopsis: Indexed array of items in the collection.

Declaration: `Property Items[Index: Integer]: TCollectionItem`

Visibility: public

Access: Read, Write

Description: `Items` provides indexed access to the items in the collection. Since the array is zero-based, `Index` should be an integer between 0 and `Count-1`.

It is possible to set or retrieve an element in the array. When setting an element of the array, the object that is assigned should be compatible with the class of the objects in the collection, as given by the `TCollection.ItemClass` (326) property.

Adding an element to the array can be done with the `TCollection.Add` (322) method. The array can be cleared with the `TCollection.Clear` (323) method. Removing an element of the array should be done by freeing that element.

See also: `TCollection.Count` (325), `TCollection.ItemClass` (326), `TCollection.Clear` (323), `TCollection.Add` (322)

4.43 TCollectionEnumerator

4.43.1 Description

`TCollectionEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TCollection` (320) class, so the `TCollection` class can be used in a `for ... in` loop. It is returned by the `TCollection.GetEnumerator` (324) method of `TCollection`.

See also: `TCollection` (320), `TCollection.GetEnumerator` (324), `#rtl.system.IEnumerator` (1426)

4.43.2 Method overview

Page	Method	Description
327	Create	Initialize a new instance of <code>TCollectionEnumerator</code>
327	GetCurrent	Return the current pointer in the list
327	MoveNext	Move the position of the enumerator to the next position in the collection.

4.43.3 Property overview

Page	Properties	Access	Description
327	Current	r	Current pointer in the list

4.43.4 TCollectionEnumerator.Create

Synopsis: Initialize a new instance of `TCollectionEnumerator`

Declaration: `constructor Create (ACollection: TCollection)`

Visibility: `public`

Description: `Create` initializes a new instance of `TCollectionEnumerator` and keeps a reference to the collection `ACollection` that will be enumerated.

See also: `TCollection` ([320](#))

4.43.5 TCollectionEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TCollectionItem`

Visibility: `public`

Description: `GetCurrent` returns the current `TCollectionItem` ([328](#)) instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([327](#)), `TCollectionItem` ([328](#))

4.43.6 TCollectionEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the collection.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the collection, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([327](#))

4.43.7 TCollectionEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TCollectionItem`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([327](#)) as a property.

See also: `GetCurrent` ([327](#))

4.44 TCollectionItem

4.44.1 Description

TCollectionItem and TCollection (320) form a pair of base classes that manage a collection of named objects. The TCollectionItem is the named object that is managed, it represents one item in the collection. An item in the collection is represented by three properties: TCollectionItem.DisplayName (330), TCollection.Index (320) and TCollectionItem.ID (329).

A TCollectionItem object is never created directly. To manage a set of named items, it is necessary to make a descendant of TCollectionItem to which needed properties and methods are added. This descendant can then be managed with a TCollection (320) class. The managing collection will create and destroy its items by itself, it should therefore never be necessary to create TCollectionItem descendants manually.

See also: TCollection (320)

4.44.2 Method overview

Page	Method	Description
328	Create	Creates a new instance of this collection item.
328	Destroy	Destroys this collection item.
329	GetNamePath	Returns the namepath of this collection item.

4.44.3 Property overview

Page	Properties	Access	Description
329	Collection	rw	Pointer to the collection managing this item.
330	DisplayName	rw	Name of the item, displayed in the object inspector.
329	ID	r	Initial index of this item.
330	Index	rw	Index of the item in its managing collection TCollection.Items (326) property.

4.44.4 TCollectionItem.Create

Synopsis: Creates a new instance of this collection item.

Declaration: `constructor Create(ACollection: TCollection); Virtual`

Visibility: public

Description: Create instantiates a new item in a TCollection (320). It is called by the TCollection.Add (322) function and should under normal circumstances never be called directly. called

See also: TCollectionItem.Destroy (328)

4.44.5 TCollectionItem.Destroy

Synopsis: Destroys this collection item.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` removes the item from the managing collection and Destroys the item instance.

This is the only way to remove items from a collection;

See also: `TCollectionItem.Create` (328)

4.44.6 `TCollectionItem.GetNamePath`

Synopsis: Returns the namepath of this collection item.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` overrides the `TPersistent.GetNamePath` (392) method to return the name of the managing collection and appends its `TCollectionItem.Index` (330) property.

See also: `TCollectionItem.Collection` (329), `TPersistent.GetNamePath` (392), `TCollectionItem.Index` (330)

4.44.7 `TCollectionItem.Collection`

Synopsis: Pointer to the collection managing this item.

Declaration: `Property Collection : TCollection`

Visibility: `public`

Access: `Read,Write`

Description: `Collection` points to the collection managing this item. This property can be set to point to a new collection. If this is done, the old collection will be notified that the item should no longer be managed, and the new collection is notified that it should manage this item as well.

See also: `TCollection` (320)

4.44.8 `TCollectionItem.ID`

Synopsis: Initial index of this item.

Declaration: `Property ID : Integer`

Visibility: `public`

Access: `Read`

Description: `ID` is the initial value of `TCollectionItem.Index` (330); it doesn't change after the index changes. It can be used to uniquely identify the item. The `ID` property doesn't change as items are added and removed from the collection.

While the `TCollectionItem.Index` (330) property forms a continuous series, `ID` does not. If items are removed from the collection, their `ID` is not used again, leaving gaps. Only when the collection is initially created, the `ID` and `Index` properties will be equal.

See also: `TCollection.Items` (326), `TCollectionItem.Index` (330)

4.44.9 TCollectionItem.Index

Synopsis: Index of the item in its managing collection `TCollection.Items` (326) property.

Declaration: `Property Index : Integer`

Visibility: public

Access: Read,Write

Description: `Index` is the current index of the item in its managing collection's `TCollection.Items` (326) property. This property may change as items are added and removed from the collection.

The index of an item is zero-based, i.e. the first item has index zero. The last item has index `Count-1` where `Count` is the number of items in the collection.

The `Index` property of the items in a collection form a continuous series ranging from 0 to `Count-1`. The `TCollectionItem.ID` (329) property does not form a continuous series, but can also be used to identify an item.

See also: `TCollectionItem.ID` (329), `TCollection.Items` (326)

4.44.10 TCollectionItem.DisplayName

Synopsis: Name of the item, displayed in the object inspector.

Declaration: `Property DisplayName : string`

Visibility: public

Access: Read,Write

Description: `DisplayName` contains the name of this item as shown in the object inspector. For `TCollectionItem` this returns always the class name of the managing collection, followed by the index of the item.

`TCollectionItem` does not implement any functionality to store the `DisplayName` property. The property can be set, but this will have no effect other than that the managing collection is notified of a change. The actual displayname will remain unchanged. To store the `DisplayName` property, `TCollectionItem` descendants should override the `TCollectionItem.SetDisplayName` (328) and `TCollectionItem.GetDisplayName` (328) to add storage functionality.

See also: `TCollectionItem.Index` (330), `TCollectionItem.ID` (329), `TCollectionItem.GetDisplayName` (328), `TCollectionItem.SetDisplayName` (328)

4.45 TComponent

4.45.1 Description

`TComponent` is the base class for any set of classes that needs owner-owned functionality, and which needs support for property streaming. All classes that should be handled by an IDE (Integrated Development Environment) must descend from `TComponent`, as it includes all support for streaming all its published properties.

Components can 'own' other components. `TComponent` introduces methods for enumerating the child components. It also allows to name the owned components with a unique name. Furthermore, functionality for sending notifications when a component is removed from the list or removed from memory altogether is also introduced in `TComponent`.

`TComponent` introduces a form of automatic memory management: When a component is destroyed, all its child components will be destroyed first.

4.45.2 Interfaces overview

Page	Interfaces	Description
271	IInterfaceComponentReference	Interface for checking component references
1428	IUnknown	Basic interface for all COM-based interfaces

4.45.3 Method overview

Page	Method	Description
333	BeforeDestruction	Overrides standard BeforeDestruction.
332	Create	Creates a new instance of the component.
333	Destroy	Destroys the instance of the component.
333	DestroyComponents	Destroy child components.
333	Destroying	Called when the component is being destroyed
334	ExecuteAction	Standard action execution method.
334	FindComponent	Finds and returns the named component in the owned components.
334	FreeNotification	Ask the component to notify called when it is being destroyed.
334	FreeOnRelease	Part of the IVCLComObject interface.
335	GetEnumerator	Create an IEnumerator instance
335	GetNamePath	Returns the name path of this component.
335	GetParentComponent	Returns the parent component.
335	HasParent	Does the component have a parent ?
336	InsertComponent	Insert the given component in the list of owned components.
337	IsImplementorOf	Checks if the current component is the implementor of the interface
332	Notification	Called by components that are freed and which received a FreeNotification.
337	ReferenceInterface	Interface implementation of Notification
336	RemoveComponent	Remove the given component from the list of owned components.
334	RemoveFreeNotification	Remove a component from the Free Notification list.
336	SafeCallException	Part of the IVCLComObject Interface.
336	SetSubComponent	Sets the csSubComponent style.
337	UpdateAction	Updates the state of an action.
332	WriteState	Writes the component to a stream.

4.45.4 Property overview

Page	Properties	Access	Description
337	ComObject	r	Interface reference implemented by the component
338	ComponentCount	r	Count of owned components
338	ComponentIndex	rw	Index of component in it's owner's list.
338	Components	r	Indexed list (zero-based) of all owned components.
338	ComponentState	r	Current component's state.
339	ComponentStyle	r	Current component's style.
339	DesignInfo	rw	Information for IDE designer.
340	Name	rws	Name of the component.
339	Owner	r	Owner of this component.
340	Tag	rw	Tag value of the component.
340	VCLComObject	rw	Not implemented.

4.45.5 TComponent.Notification

Synopsis: Called by components that are freed and which received a FreeNotification.

Declaration: `procedure Notification(AComponent: TComponent; Operation: TOperation)
; Virtual`

Visibility: protected

Description: `Notification` is called whenever a child component is destroyed, inserted or removed from the list of owned component. Components that were requested to send a notification when they are freed ((with `FreeNotification` (334)) will also call `Notification` when they are freed.

The `AComponent` parameter specifies which component sends the notification, and `Operation` specifies whether the component is being inserted into or removed from the child component list, or whether it is being destroyed.

Descendants of `TComponent` can use `FreeNotification` (334) to request notification of the destruction of another object. By overriding the `Notification` method, they can do special processing (typically, set a reference to this component to `Nil`) when this component is destroyed. The `Notification` method is called quite often in the streaming process, so speed should be a consideration when overriding this method.

See also: `TOperation` (242), `TComponent.FreeNotification` (334), `TComponent.RemoveFreeNotification` (334)

4.45.6 TComponent.WriteState

Synopsis: Writes the component to a stream.

Declaration: `procedure WriteState(Writer: TWriter); Virtual`

Visibility: public

Description: `WriteState` writes the component's current state to a stream through the writer (466) object `writer`. Values for all published properties of the component can be written to the stream. Normally there is no need to call `WriteState` directly. The streaming system calls `WriteState` itself.

The `TComponent` (330) implementation of `WriteState` simply calls `TWriter.WriteData` (466). Descendant classes can, however, override `WriteState` to provide additional processing of stream data.

See also: `ReadState` (330), `TStream.WriteComponent` (414), `TWriter.WriteData` (466)

4.45.7 TComponent.Create

Synopsis: Creates a new instance of the component.

Declaration: `constructor Create(AOwner: TComponent); Virtual`

Visibility: public

Description: `Create` creates a new instance of a `TComponent` class. If `AOwner` is not `Nil`, the new component attempts to insert itself in the list of owned components of the owner.

See also: `Insert` (330), `Owner` (339)

4.45.8 TComponent.Destroy

Synopsis: Destroys the instance of the component.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` sends a `opRemove` notification to all components in the free-notification list. After that, all owned components are destroyed by calling `DestroyComponents` (333) (and hence removed from the list of owned components). When this is done, the component removes itself from its owner's child component list. After that, the parent's destroy method is called.

See also: Notification (332), Owner (339), `DestroyComponents` (333), Components (338)

4.45.9 TComponent.BeforeDestruction

Synopsis: Overrides standard `BeforeDestruction`.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` is overridden by `TComponent` to set the `csDestroying` flag in `TComponent.ComponentState` (338)

See also: `TComponent.ComponentState` (338)

4.45.10 TComponent.DestroyComponents

Synopsis: Destroy child components.

Declaration: `procedure DestroyComponents`

Visibility: `public`

Description: `DestroyComponents` calls the destructor of all owned components, till no more components are left in the Components (338) array.

Calling the destructor of an owned component has as the effect that the component will remove itself from the list of owned components, if nothing has disrupted the sequence of destructors.

Errors: If an overridden 'destroy' method does not call it's inherited destructor or raises an exception, it's `TComponent.Destroy` (333) destructor will not be called, which may result in an endless loop.

See also: `Destroy` (333), Components (338)

4.45.11 TComponent.Destroying

Synopsis: Called when the component is being destroyed

Declaration: `procedure Destroying`

Visibility: `public`

Description: `Destroying` sets the `csDestroying` flag in the component's state (330) property, and does the same for all owned components.

It is not necessary to call `Destroying` directly, the destructor `Destroy` (333) does this automatically.

See also: State (330), `Destroy` (333)

4.45.12 TComponent.ExecuteAction

Synopsis: Standard action execution method.

Declaration: `function ExecuteAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: public

Description: `ExecuteAction` checks whether `Action` handles the current component, and if yes, calls the `ExecuteAction` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: `TBasicAction` (294), `TBasicAction.ExecuteAction` (294), `TBasicAction.HandlesTarget` (295), `TComponent.UpdateAction` (337)

4.45.13 TComponent.FindComponent

Synopsis: Finds and returns the named component in the owned components.

Declaration: `function FindComponent(const AName: string) : TComponent`

Visibility: public

Description: `FindComponent` searches the component with name `AName` in the list of owned components. If `AName` is empty, then `Nil` is returned.

See also: `Components` (338), `Name` (340)

4.45.14 TComponent.FreeNotification

Synopsis: Ask the component to notify called when it is being destroyed.

Declaration: `procedure FreeNotification(AComponent: TComponent)`

Visibility: public

Description: `FreeNotification` inserts `AComponent` in the freenotification list. When the component is destroyed, the `Notification` (332) method is called for all components in the freenotification list.

See also: `Components` (338), `Notification` (332), `TComponent.RemoveFreeNotification` (334)

4.45.15 TComponent.RemoveFreeNotification

Synopsis: Remove a component from the Free Notification list.

Declaration: `procedure RemoveFreeNotification(AComponent: TComponent)`

Visibility: public

Description: `RemoveFreeNotification` removes `AComponent` from the freenotification list.

See also: `TComponent.FreeNotification` (334)

4.45.16 TComponent.FreeOnRelease

Synopsis: Part of the `IVCLComObject` interface.

Declaration: `procedure FreeOnRelease`

Visibility: public

Description: Provided for Delphi compatibility, but is not yet implemented.

4.45.17 TComponent.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TComponentEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1425) interface for `TComponent`. It creates a `TComponentEnumerator` (341) instance and returns its `IEnumerator` (1426) interface. The enumerator enumerates all child components of the component instance.

See also: `TComponentEnumerator` (341), `IEnumerator` (1426), `IEnumerable` (1425)

4.45.18 TComponent.GetNamePath

Synopsis: Returns the name path of this component.

Declaration: `function GetNamePath : string; Override`

Visibility: `public`

Description: `GetNamePath` returns the name of the component as it will be shown in the object inspector. `TComponent` overrides `GetNamePath` so it returns the `Name` (340) property of the component.

See also: `Name` (340), `TPersistent.GetNamePath` (392)

4.45.19 TComponent.GetParentComponent

Synopsis: Returns the parent component.

Declaration: `function GetParentComponent : TComponent; Dynamic`

Visibility: `public`

Description: `GetParentComponent` can be implemented to return the parent component of this component. The implementation of this method in `TComponent` always returns `Nil`. Descendant classes must override this method to return the visual parent of the component.

See also: `HasParent` (335), `Owner` (339)

4.45.20 TComponent.HasParent

Synopsis: Does the component have a parent ?

Declaration: `function HasParent : Boolean; Dynamic`

Visibility: `public`

Description: `HasParent` can be implemented to return whether the parent of the component exists. The implementation of this method in `TComponent` always returns `False`, and should be overridden by descendant classes to return `True` when a parent is available. If `HasParent` returns `True`, then `GetParentComponent` (335) will return the parent component.

See also: `HasParent` (335), `Owner` (339)

4.45.21 TComponent.InsertComponent

Synopsis: Insert the given component in the list of owned components.

Declaration: `procedure InsertComponent (AComponent : TComponent)`

Visibility: `public`

Description: `InsertComponent` attempts to insert `AComponent` in the list with owned components. It first calls `ValidateComponent` (330) to see whether the component can be inserted. It then checks whether there are no name conflicts by calling `ValidateRename` (330). If neither of these checks have raised an exception the component is inserted, and notified of the insert.

See also: `RemoveComponent` (336), `Insert` (330), `ValidateContainer` (330), `ValidateRename` (330), `Notification` (332)

4.45.22 TComponent.RemoveComponent

Synopsis: Remove the given component from the list of owned components.

Declaration: `procedure RemoveComponent (AComponent : TComponent)`

Visibility: `public`

Description: `RemoveComponent` will send an `opRemove` notification to `AComponent` and will then proceed to remove `AComponent` from the list of owned components.

See also: `InsertComponent` (336), `Remove` (330), `ValidateRename` (330), `Notification` (332)

4.45.23 TComponent.SafeCallException

Synopsis: Part of the `IVCLComObject` Interface.

Declaration: `function SafeCallException (ExceptObject : TObject;
 ExceptAddr : CodePointer) : HRESULT; Override`

Visibility: `public`

Description: Provided for Delphi compatibility, but not implemented.

4.45.24 TComponent.SetSubComponent

Synopsis: Sets the `csSubComponent` style.

Declaration: `procedure SetSubComponent (ASubComponent : Boolean)`

Visibility: `public`

Description: `SetSubComponent` includes `csSubComponent` in the `ComponentStyle` (339) property if `ASubComponent` is `True`, and excludes it again if `ASubComponent` is `False`.

See also: `TComponent.ComponentStyle` (339)

4.45.25 TComponent.UpdateAction

Synopsis: Updates the state of an action.

Declaration: `function UpdateAction(Action: TBasicAction) : Boolean; Dynamic`

Visibility: public

Description: `UpdateAction` checks whether `Action` handles the current component, and if yes, calls the `UpdateTarget` method, passing itself as a parameter. The function returns `True` if the action handles the current component.

See also: [TBasicAction \(294\)](#), [TBasicAction.UpdateTarget \(295\)](#), [TBasicAction.HandlesTarget \(295\)](#), [TBasicAction.ExecuteAction \(294\)](#)

4.45.26 TComponent.IsImplementorOf

Synopsis: Checks if the current component is the implementor of the interface

Declaration: `function IsImplementorOf(const Intf: IInterface) : Boolean`

Visibility: public

Description: `IsImplementorOf` returns `True` if the current component implements the given interface. The interface should descend from [IInterfaceComponentReference \(271\)](#) and the `GetComponent` method should return the current instance.

See also: [IInterfaceComponentReference \(271\)](#)

4.45.27 TComponent.ReferenceInterface

Synopsis: Interface implementation of Notification

Declaration: `procedure ReferenceInterface(const intf: IInterface; op: TOperation)`

Visibility: public

Description: `ReferenceInterface` can be used to notify an interface of a component operation: it is the equivalent of the `TComponent.Notification (332)` method of `TComponent` for interfaces. If the interface implements [IInterfaceComponentReference \(271\)](#), then the component that implements the interface is notified of the given operation `Op`.

Errors: None.

See also: [TComponent.Notification \(332\)](#), [IInterfaceComponentReference \(271\)](#)

4.45.28 TComponent.ComObject

Synopsis: Interface reference implemented by the component

Declaration: `Property ComObject : IUnknown`

Visibility: public

Access: Read

Description: `ComObject` returns the COM interface represented by the component. If the component does not represent a COM interface, reading this property will raise an [EComponentError \(265\)](#).

See also: [EComponentError \(265\)](#)

4.45.29 TComponent.Components

Synopsis: Indexed list (zero-based) of all owned components.

Declaration: `Property Components[Index: Integer]: TComponent`

Visibility: public

Access: Read

Description: `Components` provides indexed access to the list of owned components. `Index` can range from 0 to `ComponentCount-1` (338).

See also: `ComponentCount` (338), `Owner` (339)

4.45.30 TComponent.ComponentCount

Synopsis: Count of owned components

Declaration: `Property ComponentCount : Integer`

Visibility: public

Access: Read

Description: `ComponentCount` returns the number of components that the current component owns. It can be used to determine the valid index range in the `Component` (338) array.

See also: `Components` (338), `Owner` (339)

4.45.31 TComponent.ComponentIndex

Synopsis: Index of component in it's owner's list.

Declaration: `Property ComponentIndex : Integer`

Visibility: public

Access: Read, Write

Description: `ComponentIndex` is the index of the current component in its owner's list of components. If the component has no owner, the value of this property is -1.

See also: `Components` (338), `ComponentCount` (338), `Owner` (339)

4.45.32 TComponent.ComponentState

Synopsis: Current component's state.

Declaration: `Property ComponentState : TComponentState`

Visibility: public

Access: Read

Description: `ComponentState` indicates the current state of the component. It is a set of flags which indicate the various stages in the lifetime of a component. The following values can occur in this set:

Table 4.22: Component states

Flag	Meaning
<code>csLoading</code>	The component is being loaded from stream
<code>csReading</code>	Component properties are being read from stream.
<code>csWriting</code>	Component properties are being written to stream.
<code>csDestroying</code>	The component or one of its owners is being destroyed.
<code>csAncestor</code>	The component is being streamed as part of a frame
<code>csUpdating</code>	The component is being updated
<code>csFixups</code>	References to other components are being resolved
<code>csFreeNotification</code>	The component has free notifications.
<code>csInline</code>	The component is being loaded as part of a frame
<code>csDesignInstance</code>	? not used.

The component state is set by various actions such as reading it from stream, destroying it etc.

See also: [SetAncestor \(330\)](#), [SetDesigning \(330\)](#), [SetInline \(330\)](#), [SetDesignInstance \(330\)](#), [Updating \(330\)](#), [Updated \(330\)](#), [Loaded \(330\)](#)

4.45.33 TComponent.ComponentStyle

Synopsis: Current component's style.

Declaration: `Property ComponentStyle : TComponentStyle`

Visibility: public

Access: Read

Description: Current component's style.

4.45.34 TComponent.DesignInfo

Synopsis: Information for IDE designer.

Declaration: `Property DesignInfo : LongInt`

Visibility: public

Access: Read, Write

Description: `DesignInformation` can be used by an IDE to store design information in the component. It should not be used by an application programmer.

See also: [Tag \(340\)](#)

4.45.35 TComponent.Owner

Synopsis: Owner of this component.

Declaration: `Property Owner : TComponent`

Visibility: public

Access: Read

Description: `Owner` returns the owner of this component. The owner cannot be set except by explicitly inserting the component in another component's owned components list using that component's `InsertComponent` (336) method, or by removing the component from it's owner's owned component list using the `RemoveComponent` (336) method.

See also: Components (338), `InsertComponent` (336), `RemoveComponent` (336)

4.45.36 TComponent.VCLComObject

Synopsis: Not implemented.

Declaration: `Property VCLComObject : Pointer`

Visibility: public

Access: Read,Write

Description: `VCLComObject` is not yet implemented in Free Pascal.

4.45.37 TComponent.Name

Synopsis: Name of the component.

Declaration: `Property Name : TComponentName`

Visibility: published

Access: Read,Write

Description: `Name` is the name of the component. This name should be a valid identifier, i.e. must start with a letter or underscore, and can contain only letters, numbers and the underscore character. When attempting to set the name of a component, the name will be checked for validity. Furthermore, when a component is owned by another component, the name must be either empty or must be unique among the child component names.

By "letters", 7-bit letters are meant.

Errors: Attempting to set the name to an invalid value will result in an exception being raised.

See also: `ValidateRename` (330), `Owner` (339)

4.45.38 TComponent.Tag

Synopsis: Tag value of the component.

Declaration: `Property Tag : PtrInt`

Visibility: published

Access: Read,Write

Description: `Tag` can be used to store an integer value in the component. This value is streamed together with all other published properties. It can be used for instance to quickly identify a component in an event handler.

See also: `Name` (340)

4.46 TComponentEnumerator

4.46.1 Description

`TComponentEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TComponent` (330) class, so the `TComponent` class can be used in a `for ... in` loop over the `TComponent.Components` (338) child components of the component. It is returned by the `TComponent.GetEnumerator` (335) method of `TComponent`.

See also: `TComponent` (330), `TComponent.GetEnumerator` (335), `#rtl.system.IEnumerator` (1426)

4.46.2 Method overview

Page	Method	Description
341	<code>Create</code>	Initialize a new instance of <code>TComponentEnumerator</code>
341	<code>GetCurrent</code>	Return the current pointer in the list
342	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.46.3 Property overview

Page	Properties	Access	Description
342	<code>Current</code>	<code>r</code>	Current pointer in the list

4.46.4 TComponentEnumerator.Create

Synopsis: Initialize a new instance of `TComponentEnumerator`

Declaration: `constructor Create (AComponent: TComponent)`

Visibility: `public`

Description: `Create` initializes a new instance of `TComponentEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TComponent` (330)

4.46.5 TComponentEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : TComponent`

Visibility: `public`

Description: `GetCurrent` returns the current `TComponent` (330) child component instance in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (342), `TComponent.Components` (338)

4.46.6 TComponentEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next child in the components child components, and returns `True` if this succeeded, or `False` if the pointer is past the last child in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([341](#))

4.46.7 TComponentEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : TComponent`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([341](#)) as a property.

See also: `GetCurrent` ([341](#))

4.47 TCustomMemoryStream

4.47.1 Description

`TCustomMemoryStream` is the parent class for streams that stored their data in memory. It introduces all needed functions to handle reading from and navigating through the memory, and introduces a `Memory` ([344](#)) property which points to the memory area where the stream data is kept.

The only thing which `TCustomMemoryStream` does not do is obtain memory to store data when writing data or the writing of data. This functionality is implemented in descendant streams such as `TMemoryStream` ([379](#)). The reason for this approach is that this way it is possible to create e.g. read-only descendants of `TCustomMemoryStream` that point to a fixed part in memory which can be read from, but not written to.

Remark: Since `TCustomMemoryStream` is an abstract class, do not create instances of `TMemoryStream` directly. Instead, create instances of descendants such as `TMemoryStream` ([379](#)).

See also: `TMemoryStream` ([379](#)), `TStream` ([409](#))

4.47.2 Method overview

Page	Method	Description
343	<code>Read</code>	Reads <code>Count</code> bytes from the stream into <code>buffer</code> .
344	<code>SaveToFile</code>	Writes the contents of the stream to a file.
343	<code>SaveToStream</code>	Writes the contents of the memory stream to another stream.
343	<code>Seek</code>	Sets a new position in the stream.

4.47.3 Property overview

Page	Properties	Access	Description
344	Memory	r	Pointer to the data kept in the memory stream.

4.47.4 TCustomMemoryStream.Read

Synopsis: Reads `Count` bytes from the stream into `buffer`.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` reads `Count` bytes from the stream into the memory pointed to by `buffer`. It returns the number of bytes actually read.

This method overrides the `TStream.Read` (410) method of `TStream` (409). It will read as much bytes as are still available in the memory area pointer to by `Memory` (344). After the bytes are read, the internal stream position is updated.

See also: `TCustomMemoryStream.Memory` (344), `TStream.Read` (410)

4.47.5 TCustomMemoryStream.Seek

Synopsis: Sets a new position in the stream.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: `public`

Description: `Seek` overrides the abstract `TStream.Seek` (411) method. It simply updates the internal stream position, and returns the new position.

Errors: No checking is done whether the new position is still a valid position, i.e. whether the position is still within the range `0..Size`. Attempting a seek outside the valid memory range of the stream may result in an exception at the next read or write operation.

See also: `TStream.Position` (418), `TStream.Size` (419), `TCustomMemoryStream.Memory` (344)

4.47.6 TCustomMemoryStream.SaveToStream

Synopsis: Writes the contents of the memory stream to another stream.

Declaration: `procedure SaveToStream(Stream: TStream)`

Visibility: `public`

Description: `SaveToStream` writes the contents of the memory stream to `Stream`. The content of `Stream` is not cleared first. The current position of the memory stream is not changed by this action.

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Seek(0, soFromBeginning);
Stream.CopyFrom(Self, Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToStream` writes the contents of the memory as one big block.

Errors: If an error occurs when writing to `Stream` an `EStreamError` (267) exception will be raised.

See also: `TCustomMemoryStream.SaveToFile` (344), `TStream.CopyFrom` (413)

4.47.7 TCustomMemoryStream.SaveToFile

Synopsis: Writes the contents of the stream to a file.

Declaration: `procedure SaveToFile(const FileName: string)`

Visibility: public

Description: `SaveToFile` writes the contents of the stream to a file with name `FileName`. It simply creates a filestream and writes the contents of the memorystream to this file stream using `TCustomMemoryStream.SaveToStream` (343).

Remark: This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Stream:=TFileStream.Create(fmCreate,FileName);
Seek(0,soFromBeginning);
Stream.CopyFrom(Self,Size);
```

because the `CopyFrom` method copies the contents in blocks, while `SaveToFile` writes the contents of the memory as one big block.

Errors: If an error occurs when creating or writing to the file, an `EStreamError` (267) exception may occur.

See also: `TCustomMemoryStream.SaveToStream` (343), `TFileStream` (350), `TStream.CopyFrom` (413)

4.47.8 TCustomMemoryStream.Memory

Synopsis: Pointer to the data kept in the memory stream.

Declaration: `Property Memory : Pointer`

Visibility: public

Access: Read

Description: `Memory` points to the memory area where stream keeps it's data. The property is read-only, so the pointer cannot be set this way.

Remark: Do not write to the memory pointed to by `Memory`, since the memory content may be read-only, and thus writing to it may cause errors.

See also: `TStream.Size` (419)

4.48 TDataModule

4.48.1 Description

`TDataModule` is a container for non-visual objects which can be used in an IDE to group non-visual objects which can be used by various other containers (forms) in a project. Notably, data access components are typically stored on a datamodule. Web components and services can also be implemented as descendants of datamodules.

`TDataModule` introduces some events which make it easier to program, and provides the needed streaming capabilities for persistent storage.

An IDE will typically allow to create a descendant of `TDataModule` which contains non-visual components in it's published property list.

See also: `TDataModule.OnCreate` (347)

4.48.2 Method overview

Page	Method	Description
346	AfterConstruction	Overrides standard TObject (1432) behaviour.
346	BeforeDestruction	
345	Create	Create a new instance of a TDataModule.
345	CreateNew	
346	Destroy	Destroys the TDataModule instance.

4.48.3 Property overview

Page	Properties	Access	Description
346	DesignOffset	rw	Position property needed for manipulation in an IDE.
347	DesignPPI	rw	
347	DesignSize	rw	Size property needed for manipulation in an IDE.
348	OldCreateOrder	rw	Determines when OnCreate and OnDestroy are triggered.
347	OnCreate	rw	Event handler, called when the datamodule is created.
347	OnDestroy	rw	Event handler, called when the datamodule is destroyed.

4.48.4 TDataModule.Create

Synopsis: Create a new instance of a TDataModule.

Declaration: `constructor Create(AOwner: TComponent); Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TDataModule` and calls `TDataModule.CreateNew` ([345](#)). After that it reads the published properties from a stream using `InitInheritedComponent` ([256](#)) if a descendant class is instantiated. If the `OldCreateOrder` ([348](#)) property is `True`, the `TDataModule.OnCreate` ([347](#)) event is called.

Errors: An exception can be raised during the streaming operation.

See also: `TDataModule.CreateNew` ([345](#))

4.48.5 TDataModule.CreateNew

Synopsis:

Declaration: `constructor CreateNew(AOwner: TComponent)`
`constructor CreateNew(AOwner: TComponent; CreateMode: Integer); Virtual`

Visibility: `public`

Description: `CreateNew` creates a new instance of the class, but bypasses the streaming mechanism. The `CreateMode` parameter (by default zero) is not used in `TDataModule`. If the `AddDataModule` ([249](#)) handler is set, then it is called, with the newly created instance as an argument.

See also: `TDataModule.Create` ([345](#)), `AddDataModule` ([249](#)), `TDataModule.OnCreate` ([347](#))

4.48.6 TDataModule.Destroy

Synopsis: Destroys the TDataModule instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the TDataModule instance. If the `OldCreateOrder` (348) property is `True` the `OnDestroy` (347) event handler is called prior to destroying the data module.

Before calling the inherited `destroy`, the `RemoveDataModule` (250) handler is called if it is set, and `Self` is passed as a parameter.

Errors: An event can be raised during the `OnDestroy` event handler.

See also: `TDataModule.OnDestroy` (347), `RemoveDataModule` (250)

4.48.7 TDataModule.AfterConstruction

Synopsis: Overrides standard TObject (1432) behaviour.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` calls the `OnCreate` (347) handler if the `OldCreateOrder` (348) property is `False`.

See also: `TDataModule.OldCreateOrder` (348), `TDataModule.OnCreate` (347)

4.48.8 TDataModule.BeforeDestruction

Synopsis:

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `BeforeDestruction` calls the `OnDestroy` (347) handler if the `OldCreateOrder` (348) property is `False`.

See also: `TDataModule.OldCreateOrder` (348), `TDataModule.OnDestroy` (347)

4.48.9 TDataModule.DesignOffset

Synopsis: Position property needed for manipulation in an IDE.

Declaration: `Property DesignOffset : TPoint`

Visibility: `public`

Access: `Read, Write`

Description: `DesignOffset` is the position of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignSize` (347)

4.48.10 TDataModule.DesignSize

Synopsis: Size property needed for manipulation in an IDE.

Declaration: `Property DesignSize : TPoint`

Visibility: `public`

Access: `Read,Write`

Description: `DesignSize` is the size of the datamodule when displayed in an IDE. It is streamed to the form file, and should not be used at run-time.

See also: `TDataModule.DesignOffset` ([346](#))

4.48.11 TDataModule.DesignPPI

Declaration: `Property DesignPPI : Integer`

Visibility: `public`

Access: `Read,Write`

4.48.12 TDataModule.OnCreate

Synopsis: Event handler, called when the datamodule is created.

Declaration: `Property OnCreate : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnCreate` event is triggered when the datamodule is created and streamed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([348](#)) property.

See also: `TDataModule.Create` ([345](#)), `TDataModule.CreateNew` ([345](#)), `TDataModule.OldCreateOrder` ([348](#))

4.48.13 TDataModule.OnDestroy

Synopsis: Event handler, called when the datamodule is destroyed.

Declaration: `Property OnDestroy : TNotifyEvent`

Visibility: `published`

Access: `Read,Write`

Description: The `OnDestroy` event is triggered when the datamodule is destroyed. The exact moment of triggering is dependent on the value of the `OldCreateOrder` ([348](#)) property.

See also: `TDataModule.Destroy` ([346](#)), `TDataModule.OnCreate` ([347](#)), `TDataModule.Create` ([345](#)), `TDataModule.CreateNew` ([345](#)), `TDataModule.OldCreateOrder` ([348](#))

4.48.14 TDataModule.OldCreateOrder

Synopsis: Determines when `OnCreate` and `OnDestroy` are triggered.

Declaration: `Property OldCreateOrder : Boolean`

Visibility: `published`

Access: `Read, Write`

Description: `OldCreateOrder` determines when exactly the `OnCreate` (347) and `OnDestroy` (347) event handlers are called.

If set to `True`, then the `OnCreate` event handler is called after the data module was streamed. If it is set to `False`, then the handler is called prior to the streaming process.

If set to `True`, then the `OnDestroy` event handler is called before the data module is removed from the streaming system. If it is set to `False`, then the handler is called after the data module was removed from the streaming process.

See also: `TDataModule.OnDestroy` (347), `TDataModule.OnCreate` (347), `TDataModule.Destroy` (346), `TDataModule.Create` (345), `TDataModule.CreateNew` (345), `TDataModule.OldCreateOrder` (348)

4.49 TFiler

4.49.1 Description

Class responsible for streaming of components.

4.49.2 Method overview

Page	Method	Description
349	<code>DefineBinaryProperty</code>	
348	<code>DefineProperty</code>	

4.49.3 Property overview

Page	Properties	Access	Description
349	<code>Ancestor</code>	<code>rw</code>	Ancestor component from which an inherited component is streamed.
350	<code>IgnoreChildren</code>	<code>rw</code>	Determines whether children will be streamed as well.
349	<code>LookupRoot</code>	<code>r</code>	Component used to look up ancestor components.
349	<code>Root</code>	<code>rw</code>	The root component is the initial component which is being streamed.

4.49.4 TFiler.DefineProperty

Synopsis:

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc; WriteData: TWriterProc; HasData: Boolean); Virtual; Abstract`

Visibility: `public`

Description:

4.49.5 TFiler.DefineBinaryProperty

Synopsis:

Declaration: `procedure DefineBinaryProperty(const Name: string;
 ReadData: TStreamProc;
 WriteData: TStreamProc; HasData: Boolean)
 ; Virtual; Abstract`

Visibility: public

Description:

4.49.6 TFiler.Root

Synopsis: The root component is the initial component which is being streamed.

Declaration: `Property Root : TComponent`

Visibility: public

Access: Read,Write

Description: The streaming process will stream a component and all the components which it owns. The `Root` component is the component which is initially streamed.

See also: `LookupRoot` ([349](#))

4.49.7 TFiler.LookupRoot

Synopsis: Component used to look up ancestor components.

Declaration: `Property LookupRoot : TComponent`

Visibility: public

Access: Read

Description: When comparing inherited component's values against parent values, the values are compared with the component in `LookupRoot`. Initially, it is set to `Root` ([349](#)).

See also: `Root` ([349](#))

4.49.8 TFiler.Ancestor

Synopsis: Ancestor component from which an inherited component is streamed.

Declaration: `Property Ancestor : TPersistent`

Visibility: public

Access: Read,Write

Description: When streaming a component, this is the parent component. Only properties that differ from the parent's property value will be streamed.

See also: `Root` ([349](#)), `LookupRoot` ([349](#))

4.49.9 TFiler.IgnoreChildren

Synopsis: Determines whether children will be streamed as well.

```
Declaration: Property IgnoreChildren : Boolean
```

Visibility: public

Access: Read, Write

Description: By default, all children (i.e. owned objects) will also be streamed when streaming a component. This property can be used to prevent owned objects from being streamed.

4.50 TFileStream

4.50.1 Description

TFileStream is a TStream (409) descendant that stores or reads its data from a named file in the filesystem of the operating system.

To this end, it overrides some of the methods in `TStream` and implements them for the case of files on disk, and it adds the `FileName` (351) property to the list of public properties.

See also: [TFileStream.Create \(350\)](#), [TStream \(409\)](#)

4.50.2 Method overview

Page	Method	Description
350	Create	Creates a file stream.
351	Destroy	Destroys the file stream.

4.50.3 Property overview

Page	Properties	Access	Description
351	FileName	r	The filename of the stream.

4.50.4 TFileStream.Create

Synopsis: Creates a file stream.

```
Declaration: constructor Create(const AFileName: string; Mode: Word)
              constructor Create(const AFileName: string; Mode: Word;
                                Rights: Cardinal)
```

Visibility: public

Description: `Create` creates a new instance of a `TFileStream` class. It opens the file `AFileName` with mode `Mode`, which can have one of the following values:

Table 4.23:

fmCreate	TFileStream.Create (350) creates a new file if needed.
fmOpenRead	TFileStream.Create (350) opens a file with read-only access.
fmOpenWrite	TFileStream.Create (350) opens a file with write-only access.
fmOpenReadWrite	TFileStream.Create (350) opens a file with read-write access.

These constants (except `fmCreate`) can be OR-ed with the following to specify how sharing and file locking is supposed to be handled:

Table 4.24:

<code>fmShareCompat</code>	Open file in DOS share-compatibility mode
<code>fmShareExclusive</code>	Lock file for exclusive use
<code>fmShareDenyWrite</code>	Lock file so other processes can only read.
<code>fmShareDenyRead</code>	Lock file so other processes cannot read.
<code>fmShareDenyNone</code>	Do not lock file.

Note that sharing is advisory on Unix-like platforms.

After the file has been opened in the requested mode and a handle has been obtained from the operating system, the inherited constructor is called.

Errors: If the file could not be opened in the requested mode, an `EFOpenError` (265) exception is raised.

See also: `TStream` (409), `TFileStream.FileName` (351), `THandleStream.Create` (361)

4.50.5 TFileStream.Destroy

Synopsis: Destroys the file stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` closes the file (causing possible buffered data to be written to disk) and then calls the inherited destructor.

Do not call `destroy` directly, instead call the `Free` method. `Destroy` does not check whether `Self` is `nil`, while `Free` does.

See also: `TFileStream.Create` (350)

4.50.6 TFileStream.FileName

Synopsis: The filename of the stream.

Declaration: `Property FileName : string`

Visibility: `public`

Access: `Read`

Description: `FileName` is the name of the file that the stream reads from or writes to. It is the name as passed in the constructor of the stream; it cannot be changed. To write to another file, the stream must be freed and created again with the new filename.

See also: `TFileStream.Create` (350)

4.51 TFPList

4.51.1 Description

`TFPList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. Contrary to `TList` (370), `TFPList` has no notification mechanism. If no notification mechanism is used, it is better to use `TFPList` instead of `TList`, as the performance of `TFPList` is much higher.

To manage collections of strings, it is better to use a `TStrings` (429) descendant such as `TStringList` (424). To manage general objects, a `TCollection` (320) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` (429), `TCollection` (320)

4.51.2 Method overview

Page	Method	Description
353	Add	Adds a new pointer to the list.
353	AddList	Add all pointers from another list
356	Assign	Assign performs the given operation on the list.
353	Clear	Clears the pointer list.
353	Delete	Removes a pointer from the list.
352	Destroy	Destroys the list and releases the memory used to store the list elements.
354	Error	Raises an <code>EListError</code> (266) exception.
354	Exchange	Exchanges two pointers in the list.
354	Expand	Increases the capacity of the list if needed.
354	Extract	Remove the first occurrence of a pointer from the list.
355	First	Returns the first non-nil pointer in the list.
357	ForEachCall	Call a procedure or method for each pointer in the list.
355	GetEnumerator	Create an <code>IEnumerator</code> instance
355	IndexOf	Returns the index of a given pointer.
355	IndexOfItem	Search an item in the list
356	Insert	Inserts a new pointer in the list at a given position.
356	Last	Returns the last non-nil pointer in the list.
356	Move	Moves a pointer from one position in the list to another.
357	Pack	Removes <code>Nil</code> pointers from the list and frees unused memory.
357	Remove	Removes a value from the list.
357	Sort	Sorts the pointers in the list.

4.51.3 Property overview

Page	Properties	Access	Description
358	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
358	Count	rw	Current number of pointers in the list.
358	Items	rw	Provides access to the pointers in the list.
359	List	r	Memory array where pointers are stored.

4.51.4 TFPList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.51.5 TFPList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TFPList)`

Visibility: `public`

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TFPList.Assign` (356), `TList.AddList` (372)

4.51.6 TFPList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Expand` (354) method.

To insert a pointer at a certain position in the list, use the `Insert` (356) method instead.

See also: `Delete` (353), `Grow` (370), `Insert` (356)

4.51.7 TFPList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` (352)

4.51.8 TFPList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete (Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.51.9 TFPList.Error

Synopsis: Raises an `EListError` (266) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: public

Description: `Error` raises an `EListError` (266) exception, with a message formatted with `Msg` and `Data`.

4.51.10 TFPList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: public

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` (266) exception will be raised.

4.51.11 TFPList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TFPList`

Visibility: public

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` (358)

4.51.12 TFPList.Extract

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(Item: Pointer) : Pointer`

Visibility: public

Description: `Extract` searches for the first occurrence of `Item` in the list and deletes it from the list. If `Item` was found, it's value is returned. If `Item` was not found, `Nil` is returned.

See also: `TFPList.Delete` (353)

4.51.13 TFPList.First

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: public

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([356](#))

4.51.14 TFPList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TFPListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1425](#)) interface for `TFPList`. It creates a `TFPListEnumerator` ([359](#)) instance and returns its `IEnumerator` ([1426](#)) interface.

See also: `TFPListEnumerator` ([359](#)), `IEnumerator` ([1426](#)), `IEnumerable` ([1425](#))

4.51.15 TFPList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.51.16 TFPList.IndexOfItem

Synopsis: Search an item in the list

Declaration: `function IndexOfItem(Item: Pointer; Direction: TDirection) : Integer`

Visibility: public

Description: `IndexOfItem` has the same function as the `IndexOf` ([231](#)) function: it searches for `Item` in the list, and returns the index of the first found matching pointer. If none is found, -1 is returned.

In difference with the `IndexOf` function, it accepts a parameter `Direction` indicating the search direction: from the beginning of the list till the end of the list, or from the end of the list till the beginning. The `IndexOf` function starts at the beginning of the list. The search direction is only important if the item can appear multiple times in the list.

See also: `TFPList.TDirection` ([??](#)), `TFPList.IndexOf` ([355](#))

4.51.17 TFPList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert (Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` (266) exception is raised.

See also: `Add` (353), `Delete` (353)

4.51.18 TFPList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: public

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` (355)

4.51.19 TFPList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` (266) exception is raised.

See also: `Exchange` (354)

4.51.20 TFPList.Assign

Synopsis: `Assign` performs the given operation on the list.

Declaration: `procedure Assign (ListA: TFPList; AOperator: TListAssignOp;
ListB: TFPList)`

Visibility: public

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` (241) type.

See also: `TFPList.Add` (353), `TFPList.Clear` (353)

4.51.21 TFPList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` ([353](#)), `IndexOf` ([355](#)), `Insert` ([356](#))

4.51.22 TFPList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TFPList.Clear` ([353](#))

4.51.23 TFPList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort(Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.51.24 TFPList.ForEachCall

Synopsis: Call a procedure or method for each pointer in the list.

Declaration: `procedure ForEachCall(proc2call: TListCallback; arg: pointer)`
`procedure ForEachCall(proc2call: TListStaticCallback; arg: pointer)`

Visibility: public

Description: `ForEachCall` iterates over all pointers in the list and calls `proc2call`, passing it the pointer and the additional `arg` data pointer. `Proc2Call` can be a method or a static procedure.

Errors: None.

See also: `TListStaticCallback` ([241](#)), `TListCallback` ([241](#))

4.51.25 `TFPList.Capacity`

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` ([353](#)) or `insert` ([356](#)), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` ([352](#)), `Count` ([358](#))

4.51.26 `TFPList.Count`

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.51.27 `TFPList.Items`

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` is used to access the pointers in the list. It is the default property of the `TFPList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.51.28 TFPList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: `Read`

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.52 TFPListEnumerator

4.52.1 Description

`TFPListEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TFPList` (352) class, so the `TFPList` class can be used in a `for ... in` loop. It is returned by the `TFPList.GetEnumerator` (355) method of `TFPList`.

See also: `TFPList` (352), `TFPList.GetEnumerator` (355), `#rtl.system.IEnumerator` (1426)

4.52.2 Method overview

Page	Method	Description
359	<code>Create</code>	Initialize a new instance of <code>TFPListEnumerator</code>
359	<code>GetCurrent</code>	Return the current pointer in the list
360	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.52.3 Property overview

Page	Properties	Access	Description
360	<code>Current</code>	<code>r</code>	Current pointer in the list

4.52.4 TFPListEnumerator.Create

Synopsis: Initialize a new instance of `TFPListEnumerator`

Declaration: `constructor Create(AList: TFPList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TFPListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TFPList` (352)

4.52.5 TFPListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` ([360](#))

4.52.6 `TFPListEnumerator.MoveNext`

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([359](#))

4.52.7 `TFPListEnumerator.Current`

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` ([359](#)) as a property.

See also: `GetCurrent` ([359](#))

4.53 `THandleStream`

4.53.1 Description

`THandleStream` is an abstract descendant of the `TStream` ([409](#)) class that provides methods for a stream to handle all reading and writing to and from a handle, provided by the underlying OS. To this end, it overrides the `Read` ([361](#)) and `Write` ([361](#)) methods of `TStream`.

Remark:

- `THandleStream` does not obtain a handle from the OS by itself, it just handles reading and writing to such a handle by wrapping the system calls for reading and writing; Descendant classes should obtain a handle from the OS by themselves and pass it on in the inherited constructor.
- Contrary to Delphi, no seek is implemented for `THandleStream`, since pipes and sockets do not support this. The seek is implemented in descendant methods that support it.

See also: `TStream` ([409](#)), `TFileStream` ([350](#))

4.53.2 Method overview

Page	Method	Description
361	Create	Create a handlestream from an OS Handle.
361	Read	Overrides standard read method.
362	Seek	Overrides the Seek method.
361	Write	Overrides standard write method.

4.53.3 Property overview

Page	Properties	Access	Description
362	Handle	r	The OS handle of the stream.

4.53.4 THandleStream.Create

Synopsis: Create a handlestream from an OS Handle.

Declaration: `constructor Create(AHandle: THandle)`

Visibility: `public`

Description: `Create` creates a new instance of a `THandleStream` class. It stores `AHandle` in an internal variable and then calls the inherited constructor.

See also: `TStream` ([409](#))

4.53.5 THandleStream.Read

Synopsis: Overrides standard read method.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` overrides the `Read` ([410](#)) method of `TStream`. It uses the `Handle` ([362](#)) property to read the `Count` bytes into `Buffer`

If no error occurs while reading, the number of bytes actually read will be returned.

Errors: If the operating system reports an error while reading from the handle, -1 is returned.

See also: `TStream.Read` ([410](#)), `THandleStream.Write` ([361](#)), `THandleStream.Handle` ([362](#))

4.53.6 THandleStream.Write

Synopsis: Overrides standard write method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `Write` ([411](#)) method of `TStream`. It uses the `Handle` ([362](#)) property to write the `Count` bytes from `Buffer`.

If no error occurs while writing, the number of bytes actually written will be returned.

Errors: If the operating system reports an error while writing to the handle, 0 is returned.

See also: `TStream.Read` ([410](#)), `THandleStream.Write` ([361](#)), `THandleStream.Handle` ([362](#))

4.53.7 THandleStream.Seek

Synopsis: Overrides the Seek method.

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64; Override`

Visibility: public

Description: `seek` uses the `FileSeek` (1526) method to position the stream on the desired position. Note that handle stream descendants (notably pipes) can override the method to prevent the seek.

4.53.8 THandleStream.Handle

Synopsis: The OS handle of the stream.

Declaration: `Property Handle : THandle`

Visibility: public

Access: Read

Description: `Handle` represents the Operating system handle to which reading and writing is done. The handle can be read only, i.e. it cannot be set after the `THandleStream` instance was created. It should be passed to the constructor `THandleStream.Create` (361)

See also: `THandleStream` (360), `THandleStream.Create` (361)

4.54 TInterfacedPersistent

4.54.1 Description

`TInterfacedPersistent` is a direct descendant of `TPersistent` (390) which implements the `#rtl.system.IInterface` (1223) interface. In particular, it implements the `QueryInterface` as a public method.

See also: `IInterface` (1223)

4.54.2 Interfaces overview

Page	Interfaces	Description
1223	<code>IInterface</code>	Basic interface for all COM based interfaces

4.54.3 Method overview

Page	Method	Description
363	<code>AfterConstruction</code>	Overrides the standard <code>AfterConstruction</code> method.
362	<code>QueryInterface</code>	Implementation of <code>IInterface.QueryInterface</code>

4.54.4 TInterfacedPersistent.QueryInterface

Synopsis: Implementation of `IInterface.QueryInterface`

Declaration: `function QueryInterface(const IID: TGuid; out Obj) : HRESULT; Virtual`

Visibility: public

Description: `QueryInterface` simply calls `GetInterface` using the specified `IID`, and returns the correct values.

See also: `TObject.GetInterface` ([1439](#))

4.54.5 TInterfacedPersistent.AfterConstruction

Synopsis: Overrides the standard `AfterConstruction` method.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: `AfterConstruction` is overridden to do some extra interface housekeeping: a reference to the `IInterface` interface of the owning class is obtained (if it exists).

4.55 TInterfaceList

4.55.1 Description

`TInterfaceList` is a standard implementation of the `IInterfaceList` ([272](#)) interface. It uses a `TThreadList` ([464](#)) instance to store the list of interfaces.

See also: `IInterfaceList` ([272](#)), `TList` ([370](#))

4.55.2 Interfaces overview

Page	Interfaces	Description
272	<code>IInterfaceList</code>	Interface for maintaining a list of interfaces.

4.55.3 Method overview

Page	Method	Description
366	<code>Add</code>	Add an interface to the list
364	<code>Clear</code>	Removes all interfaces from the list.
364	<code>Create</code>	Create a new instance of <code>TInterfaceList</code>
364	<code>Delete</code>	Delete an interface from the list.
364	<code>Destroy</code>	Destroys the list of interfaces
365	<code>Exchange</code>	Exchange 2 interfaces in the list
367	<code>Expand</code>	Expands the list
365	<code>First</code>	Returns the first non- <code>Nil</code> element in the list.
365	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
365	<code>IndexOf</code>	Returns the index of an interface.
366	<code>Insert</code>	Insert an interface to the list
366	<code>Last</code>	Returns the last non- <code>Nil</code> element in the list.
367	<code>Lock</code>	Lock the list
366	<code>Remove</code>	Remove an interface from the list
367	<code>Unlock</code>	UnLocks a locked list

4.55.4 Property overview

Page	Properties	Access	Description
367	Capacity	rw	The current capacity of the list.
368	Count	rw	The current number of elements in the list.
368	Items	rw	Array-based access to the list's items.

4.55.5 TInterfaceList.Create

Synopsis: Create a new instance of `TInterfaceList`

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` creates a new instance of the `TInterfaceList` class. It sets up the internal structures needed to store the list of interfaces.

See also: `Destroy` ([364](#))

4.55.6 TInterfaceList.Destroy

Synopsis: Destroys the list of interfaces

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` first calls `Clear` ([364](#)) and then frees the `TInterfaceList` instance from memory.

Note that the `Clear` method decreases the reference count of all interfaces.

See also: `Create` ([364](#)), `Clear` ([364](#))

4.55.7 TInterfaceList.Clear

Synopsis: Removes all interfaces from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` is the implementation of the `IInterfaceList.Clear` ([274](#)) method. It removes all interfaces from the list. It does this by setting each element in the list to `Nil`, in this way the reference count of each interface in the list is decreased.

See also: `IInterfaceList.Clear` ([274](#)), `Add` ([366](#)), `Destroy` ([364](#)), `TList.Clear` ([373](#)), `TFPList.Clear` ([353](#))

4.55.8 TInterfaceList.Delete

Synopsis: Delete an interface from the list.

Declaration: `procedure Delete(index: Integer)`

Visibility: `public`

Description: `Delete` is the implementation of the `IInterfaceList.Delete` ([274](#)) method. It clears the slot first and then removes the element from the list.

See also: `IInterfaceList.Delete` ([274](#)), `TInterfaceList.Remove` ([366](#)), `TInterfaceList.Add` ([366](#)), `TList.Delete` ([373](#)), `TFPList.Delete` ([353](#))

4.55.9 TInterfaceList.Exchange

Synopsis: Exchange 2 interfaces in the list

Declaration: `procedure Exchange(index1: Integer; index2: Integer)`

Visibility: public

Description: `Exchange` is the implementation of the `IInterfaceList.Exchange` (275) method. It exchanges the position of 2 interfaces in the list.

See also: `IInterfaceList.Exchange` (275), `TInterfaceList.Delete` (364), `TInterfaceList.Add` (366), `TList.Exchange` (373), `TFPList.Exchange` (354)

4.55.10 TInterfaceList.First

Synopsis: Returns the first non-`Nil` element in the list.

Declaration: `function First : IUnknown`

Visibility: public

Description: `First` is the implementation of the `IInterfaceList.First` (275) method. It returns the first non-`Nil` element from the list.

See also: `IInterfaceList.First` (275), `TList.First` (374)

4.55.11 TInterfaceList.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TInterfaceListEnumerator`

Visibility: public

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1425) interface for `TInterfaceList`. It creates a `TInterfaceListEnumerator` (368) instance and returns it's `IEnumerator` (1426) interface. The enumerator enumerates all interfaces in the list.

See also: `TInterfaceListEnumerator` (368), `IEnumerator` (1426), `IEnumerable` (1425)

4.55.12 TInterfaceList.IndexOf

Synopsis: Returns the index of an interface.

Declaration: `function IndexOf(item: IUnknown) : Integer`

Visibility: public

Description: `IndexOf` is the implementation of the `IInterfaceList.IndexOf` (275) method. It returns the zero-based index in the list of the indicated interface, or -1 if the index is not in the list.

See also: `IInterfaceList.IndexOf` (275), `TList.IndexOf` (375)

4.55.13 TInterfaceList.Add

Synopsis: Add an interface to the list

Declaration: `function Add(item: IUnknown) : Integer`

Visibility: public

Description: `Add` is the implementation of the `IInterfaceList.Add` (275) method. It adds an interface to the list, and returns the location of the new element in the list. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Add` (275), `TInterfaceList.Delete` (364), `TInterfaceList.Insert` (366), `TList.Add` (372), `TFPList.Add` (353)

4.55.14 TInterfaceList.Insert

Synopsis: Insert an interface to the list

Declaration: `procedure Insert(i: Integer; item: IUnknown)`

Visibility: public

Description: `Insert` is the implementation of the `IInterfaceList.Insert` (275) method. It inserts an interface in the list at the indicated position. This operation will increment the reference count of the interface.

See also: `IInterfaceList.Insert` (275), `TInterfaceList.Delete` (364), `TInterfaceList.Add` (366), `TList.Insert` (375), `TFPList.Insert` (356)

4.55.15 TInterfaceList.Last

Synopsis: Returns the last non-`Nil` element in the list.

Declaration: `function Last : IUnknown`

Visibility: public

Description: `Last` is the implementation of the `IInterfaceList.Last` (276) method. It returns the last non-`Nil` element from the list.

See also: `IInterfaceList.Last` (276), `TInterfaceList.First` (365), `TList.Last` (375), `TFPList.Last` (356)

4.55.16 TInterfaceList.Remove

Synopsis: Remove an interface from the list

Declaration: `function Remove(item: IUnknown) : Integer`

Visibility: public

Description: `Remove` is the implementation of the `IInterfaceList.Remove` (276) method. It removes the first occurrence of the interface from the list.

See also: `IInterfaceList.Remove` (276), `TInterfaceList.Delete` (364), `TInterfaceList.IndexOf` (365), `TList.Remove` (376), `TFPList.Remove` (357)

4.55.17 TInterfaceList.Lock

Synopsis: Lock the list

Declaration: `procedure Lock`

Visibility: `public`

Description: `Lock` locks the list. It is the implementation of the `IInterfaceList.Lock` (276) method. It limits access to the list to the current thread.

See also: `IInterfaceList.Lock` (276), `TInterfaceList.Unlock` (367), `TThreadList.LockList` (465)

4.55.18 TInterfaceList.Unlock

Synopsis: UnLocks a locked list

Declaration: `procedure Unlock`

Visibility: `public`

Description: `Unlock` unlocks the list. It is the implementation of the `IInterfaceList.Unlock` (276) method. After a call to unlock, the current thread releases the list for manipulation by other threads.

See also: `IInterfaceList.Unlock` (276), `TInterfaceList.Lock` (367), `TThreadList.UnlockList` (466)

4.55.19 TInterfaceList.Expand

Synopsis: Expands the list

Declaration: `function Expand : TInterfaceList`

Visibility: `public`

Description: `Expand` calls the `expand` method from the internally used list. It returns itself.

See also: `TList.Expand` (373)

4.55.20 TInterfaceList.Capacity

Synopsis: The current capacity of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the number of elements that the list can contain without needing to allocate more memory.

See also: `IInterfaceList.Capacity` (276), `TInterfaceList.Count` (368), `TList.Capacity` (377), `TFPList.Capacity` (358)

4.55.21 TInterfaceList.Count

Synopsis: The current number of elements in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read, Write`

Description: `Count` is the number of elements in the list. This can include `Nil` elements. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`.

See also: `IInterfaceList.Count` (277), `TInterfaceList.Items` (368), `TInterfaceList.Capacity` (367), `TList.Count` (377), `TFPList.Count` (358)

4.55.22 TInterfaceList.Items

Synopsis: Array-based access to the list's items.

Declaration: `Property Items[Index: Integer]: IUnknown; default`

Visibility: `public`

Access: `Read, Write`

Description: `Items` provides indexed access to the elements in the list. Note that the elements are zero-based, and thus are indexed from 0 to `Count-1`. The items are read-write. It is not possible to add elements to the list by accessing an element with index larger or equal to `Count` (368).

See also: `IInterfaceList.Items` (277), `TInterfaceList.Count` (368), `TList.Items` (377), `TFPList.Items` (358)

4.56 TInterfaceListEnumerator

4.56.1 Description

`TInterfaceListEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TInterfaceList` (363) class, so the `TInterfaceList` class can be used in a `for ... in` loop over the `TInterfaceList.Components` (363) child components of the component. It is returned by the `TInterfaceList.GetEnumerator` (365) method of `TInterfaceList`.

See also: `TInterfaceList` (363), `TInterfaceList.GetEnumerator` (365), `#rtl.system.IEnumerator` (1426)

4.56.2 Method overview

Page	Method	Description
369	<code>Create</code>	Initialize a new instance of <code>TInterfaceListEnumerator</code>
369	<code>GetCurrent</code>	Return the current pointer in the list
369	<code>MoveNext</code>	Move the position of the enumerator to the next position in the children of the component.

4.56.3 Property overview

Page	Properties	Access	Description
369	<code>Current</code>	<code>r</code>	Current pointer in the list

4.56.4 TInterfaceListEnumerator.Create

Synopsis: Initialize a new instance of `TInterfaceListEnumerator`

Declaration: `constructor Create (AList: TInterfaceList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TInterfaceListEnumerator` and keeps a reference to the component `AComponent` that will be enumerated.

See also: `TInterfaceList` (363)

4.56.5 TInterfaceListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : IUnknown`

Visibility: `public`

Description: `GetCurrent` returns the current interface in the `TInterfaceList` (363) list.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (369), `TInterfaceList.Components` (363)

4.56.6 TInterfaceListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the children of the component.

Declaration: `function MoveNext : Boolean`

Visibility: `public`

Description: `MoveNext` puts the pointer on the next interface in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last interface in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` (369)

4.56.7 TInterfaceListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : IUnknown`

Visibility: `public`

Access: `Read`

Description: `Current` redefines `GetCurrent` (369) as a property.

See also: `GetCurrent` (369)

4.57 TList

4.57.1 Description

`TList` is a class that can be used to manage collections of pointers. It introduces methods and properties to store the pointers, search in the list of pointers, sort them. It manages its memory by itself, no intervention for that is needed. It has an event notification mechanism which allows to notify of list changes. This slows down some of `TList` mechanisms, and if no notification is used, `TFPList` (352) may be used instead.

To manage collections of strings, it is better to use a `TStrings` (429) descendant such as `TStringList` (424). To manage general objects, a `TCollection` (320) class exists, from which a descendant can be made to manage collections of various kinds.

See also: `TStrings` (429), `TCollection` (320)

4.57.2 Interfaces overview

Page	Interfaces	Description
269	<code>IFPObserved</code>	Interface implemented by an object that can be observed.

4.57.3 Method overview

Page	Method	Description
372	<code>Add</code>	Adds a new pointer to the list.
372	<code>AddList</code>	Add all pointers from another list
376	<code>Assign</code>	Copy the contents of other lists.
373	<code>Clear</code>	Clears the pointer list.
371	<code>Create</code>	Class to manage collections of pointers.
373	<code>Delete</code>	Removes a pointer from the list.
371	<code>Destroy</code>	Destroys the list and releases the memory used to store the list elements.
373	<code>Error</code>	Raises an <code>EListError</code> (266) exception.
373	<code>Exchange</code>	Exchanges two pointers in the list.
373	<code>Expand</code>	Increases the capacity of the list if needed.
374	<code>Extract</code>	Remove the first occurrence of a pointer from the list.
374	<code>First</code>	Returns the first non-nil pointer in the list.
371	<code>FPOAttachObserver</code>	Add an observer to the list of observers
371	<code>FPODetachObserver</code>	Remove an observer from the list of observers
372	<code>FPONotifyObservers</code>	Notify observers of changes in the list
374	<code>GetEnumerator</code>	Create an <code>IEnumerator</code> instance
375	<code>IndexOf</code>	Returns the index of a given pointer.
375	<code>Insert</code>	Inserts a new pointer in the list at a given position.
375	<code>Last</code>	Returns the last non-nil pointer in the list.
375	<code>Move</code>	Moves a pointer from one position in the list to another.
376	<code>Pack</code>	Removes <code>Nil</code> pointers from the list and frees unused memory.
376	<code>Remove</code>	Removes a value from the list.
376	<code>Sort</code>	Sorts the pointers in the list.

4.57.4 Property overview

Page	Properties	Access	Description
377	Capacity	rw	Current capacity (i.e. number of pointers that can be stored) of the list.
377	Count	rw	Current number of pointers in the list.
377	Items	rw	Provides access to the pointers in the list.
377	List	r	Memory array where pointers are stored.

4.57.5 TList.Create

Synopsis: Class to manage collections of pointers.

Declaration: `constructor Create`

Visibility: `public`

Description: `TList.Create` creates a new instance of `TList`. It clears the list and prepares it for use.

See also: `TList` ([370](#)), `TList.Destroy` ([371](#))

4.57.6 TList.Destroy

Synopsis: Destroys the list and releases the memory used to store the list elements.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` destroys the list and releases the memory used to store the list elements. The elements themselves are in no way touched, i.e. any memory they point to must be explicitly released before calling the destructor.

4.57.7 TList.FPOAttachObserver

Synopsis: Add an observer to the list of observers

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` ([269](#)) interface in `TList`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserver` ([271](#)) interface.

See also: `IFPObserver` ([271](#)), `IFPObserved.FPOAttachObserver` ([270](#)), `IFPObserved` ([269](#))

4.57.8 TList.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TList`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (269), `IFPObserved.FPODetachObserver` (270), `IFPObserver` (271)

4.57.9 TList.FPONotifyObservers

Synopsis: Notify observers of changes in the list

Declaration: `procedure FPONotifyObservers (ASender: TObject;
 AOperation: TFPObservedOperation;
 Data: Pointer)`

Visibility: public

Description: `FPONotifyObservers` is called to notify observers of changes in the list. The following notifications are sent:

ooAddItem when a pointer is added. `Data` is the pointer that is added.

ooDeleteItem when a pointer is deleted or extracted. `Data` is the pointer that is deleted or extracted.

ooChange called when 2 pointers are exchanged.

ooFreeCalled when the list is freed.

See also: `FPODetachObserver` (231), `FPOAttachObserver` (231), `Add` (231), `Exchange` (231), `Delete` (231), `Extract` (231)

4.57.10 TList.AddList

Synopsis: Add all pointers from another list

Declaration: `procedure AddList (AList: TList)`

Visibility: public

Description: `AddList` adds all pointers from `AList` to the list. If a pointer is already present, it is added a second time.

See also: `TList.Assign` (376), `TFPList.AddList` (353)

4.57.11 TList.Add

Synopsis: Adds a new pointer to the list.

Declaration: `function Add (Item: Pointer) : Integer`

Visibility: public

Description: `Add` adds a new pointer to the list after the last pointer (i.e. at position `Count`, thus increasing the item count with 1. If the list is at full capacity, the capacity of the list is expanded, using the `Grow` (370) method.

To insert a pointer at a certain position in the list, use the `Insert` (375) method instead.

See also: `Delete` (373), `Grow` (370), `Insert` (375)

4.57.12 TList.Clear

Synopsis: Clears the pointer list.

Declaration: `procedure Clear; Virtual`

Visibility: `public`

Description: `Clear` removes all pointers from the list, and sets the capacity to 0, thus freeing any memory allocated to maintain the list.

See also: `Destroy` ([371](#))

4.57.13 TList.Delete

Synopsis: Removes a pointer from the list.

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` removes the pointer at position `Index` from the list, shifting all following pointers one position up (or to the left).

The memory the pointer is pointing to is *not* deallocated.

4.57.14 TList.Error

Synopsis: Raises an `EListError` ([266](#)) exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt); Virtual`

Visibility: `public`

Description: `Error` raises an `EListError` ([266](#)) exception, with a message formatted with `Msg` and `Data`.

4.57.15 TList.Exchange

Synopsis: Exchanges two pointers in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer)`

Visibility: `public`

Description: `Exchange` exchanges the pointers at positions `Index1` and `Index2`. Both pointers must be within the current range of the list, or an `EListError` ([266](#)) exception will be raised.

4.57.16 TList.Expand

Synopsis: Increases the capacity of the list if needed.

Declaration: `function Expand : TList`

Visibility: `public`

Description: `Expand` increases the capacity of the list if the current element count matches the current list capacity.

The capacity is increased according to the following algorithm:

- 1.If the capacity is less than 3, the capacity is increased with 4.
- 2.If the capacity is larger than 3 and less than 8, the capacity is increased with 8.
- 3.If the capacity is larger than 8, the capacity is increased with 16.

The return value is `Self`.

See also: `Capacity` ([377](#))

4.57.17 `TList.Extract`

Synopsis: Remove the first occurrence of a pointer from the list.

Declaration: `function Extract(item: Pointer) : Pointer`

Visibility: `public`

Description: `Extract` searched for an occurrence of `item`, and if a match is found, the match is deleted from the list. If no match is found, nothing is deleted. If `Item` was found, the result is `Item`. If `Item` was not found, the result is `Nil`. A `lnExtracted` notification event is triggered if an element is extracted from the list.

See also: `TList.Delete` ([373](#)), `TList.IndexOf` ([375](#)), `TList.Remove` ([376](#))

4.57.18 `TList.First`

Synopsis: Returns the first non-nil pointer in the list.

Declaration: `function First : Pointer`

Visibility: `public`

Description: `First` returns the value of the first non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `Last` ([375](#))

4.57.19 `TList.GetEnumerator`

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TListEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` ([1425](#)) interface for `TList`. It creates a `TListEnumerator` ([378](#)) instance and returns it's `IEnumerator` ([1426](#)) interface.

See also: `TListEnumerator` ([378](#)), `IEnumerator` ([1426](#)), `IEnumerable` ([1425](#))

4.57.20 TList.IndexOf

Synopsis: Returns the index of a given pointer.

Declaration: `function IndexOf(Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches for the pointer `Item` in the list of pointers, and returns the index of the pointer, if found.

If no pointer with the value `Item` was found, -1 is returned.

4.57.21 TList.Insert

Synopsis: Inserts a new pointer in the list at a given position.

Declaration: `procedure Insert(Index: Integer; Item: Pointer)`

Visibility: public

Description: `Insert` inserts pointer `Item` at position `Index` in the list. All pointers starting from `Index` are shifted to the right.

If `Index` is not a valid position, then a `EListError` (266) exception is raised.

See also: `Add` (372), `Delete` (373)

4.57.22 TList.Last

Synopsis: Returns the last non-nil pointer in the list.

Declaration: `function Last : Pointer`

Visibility: public

Description: `Last` returns the value of the last non-nil pointer in the list.

If there are no pointers in the list or all pointers equal `Nil`, then `Nil` is returned.

See also: `First` (374)

4.57.23 TList.Move

Synopsis: Moves a pointer from one position in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the pointer at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

If `CurIndex` or `NewIndex` are not inside the valid range of indices, an `EListError` (266) exception is raised.

See also: `Exchange` (373)

4.57.24 TList.Assign

Synopsis: Copy the contents of other lists.

Declaration: `procedure Assign(ListA: TList; AOperator: TListAssignOp; ListB: TList)`

Visibility: public

Description: `Assign` can be used to merge or assign lists. It is an extended version of the usual `TPersistent.Assign` mechanism. The arguments `ListA` and `ListB` are used as sources of pointers to add or remove elements from the current list, depending on the operation `AOperation`. The available operations are documented in the `TListAssignOp` (241) type.

See also: `TList.Clear` (373)

4.57.25 TList.Remove

Synopsis: Removes a value from the list.

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: public

Description: `Remove` searches `Item` in the list, and, if it finds it, deletes the item from the list. Only the first occurrence of `Item` is removed.

See also: `Delete` (373), `IndexOf` (375), `Insert` (375)

4.57.26 TList.Pack

Synopsis: Removes `Nil` pointers from the list and frees unused memory.

Declaration: `procedure Pack`

Visibility: public

Description: `Pack` removes all `nil` pointers from the list. The capacity of the list is then set to the number of pointers in the list. This method can be used to free unused memory if the list has grown to very large sizes and has a lot of unneeded `nil` pointers in it.

See also: `TList.Clear` (373)

4.57.27 TList.Sort

Synopsis: Sorts the pointers in the list.

Declaration: `procedure Sort(Compare: TListSortCompare)`

Visibility: public

Description: `Sort` sorts the pointers in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first pointer is assumed to be 'less' than the second and will be moved before the second in the list.
- If the function result is positive, the first pointer is assumed to be 'greater than' the second and will be moved after the second in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

4.57.28 TList.Capacity

Synopsis: Current capacity (i.e. number of pointers that can be stored) of the list.

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: Read,Write

Description: `Capacity` contains the number of pointers the list can store before it starts to grow.

If a new pointer is added to the list using `add` (372) or `insert` (375), and there is not enough memory to store the new pointer, then the list will try to allocate more memory to store the new pointer. Since this is a time consuming operation, it is important that this operation be performed as little as possible. If it is known how many pointers there will be before filling the list, it is a good idea to set the capacity first before filling. This ensures that the list doesn't need to grow, and will speed up filling the list.

See also: `SetCapacity` (370), `Count` (377)

4.57.29 TList.Count

Synopsis: Current number of pointers in the list.

Declaration: `Property Count : Integer`

Visibility: `public`

Access: Read,Write

Description: `Count` is the current number of (possibly `Nil`) pointers in the list. Since the list is zero-based, the index of the largest pointer is `Count-1`.

4.57.30 TList.Items

Synopsis: Provides access to the pointers in the list.

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: Read,Write

Description: `Items` is used to access the pointers in the list. It is the default property of the `TList` class, so it can be omitted.

The list is zero-based, so `Index` must be in the range 0 to `Count-1`.

4.57.31 TList.List

Synopsis: Memory array where pointers are stored.

Declaration: `Property List : PPointerList`

Visibility: `public`

Access: Read

Description: `List` points to the memory space where the pointers are stored. This can be used to quickly copy the list of pointers to another location.

4.58 TListEnumerator

4.58.1 Description

`TListEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TList` (370) class, so the `TList` class can be used in a `for ... in` loop. It is returned by the `TList.GetEnumerator` (374) method of `TList`.

See also: `TList` (370), `TList.GetEnumerator` (374), `#rtl.system.IEnumerator` (1426)

4.58.2 Method overview

Page	Method	Description
378	<code>Create</code>	Initialize a new instance of <code>TListEnumerator</code>
378	<code>GetCurrent</code>	Return the current pointer in the list
378	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.58.3 Property overview

Page	Properties	Access	Description
379	<code>Current</code>	<code>r</code>	Current pointer in the list

4.58.4 TListEnumerator.Create

Synopsis: Initialize a new instance of `TListEnumerator`

Declaration: `constructor Create (AList: TList)`

Visibility: `public`

Description: `Create` initializes a new instance of `TListEnumerator` and keeps a reference to the list `AList` that will be enumerated.

See also: `TList` (370)

4.58.5 TListEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : Pointer`

Visibility: `public`

Description: `GetCurrent` returns the current pointer in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (378)

4.58.6 TListEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the list, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([378](#))

4.58.7 TListEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : Pointer`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` ([378](#)) as a property.

See also: `GetCurrent` ([378](#))

4.59 TMemoryStream

4.59.1 Description

`TMemoryStream` is a `TStream` ([409](#)) descendant that stores its data in memory. It descends directly from `TCustomMemoryStream` ([342](#)) and implements the necessary to allocate and de-allocate memory directly from the heap. It implements the `Write` ([381](#)) method which is missing in `TCustomMemoryStream`.

`TMemoryStream` also introduces methods to load the contents of another stream or a file into the memory stream.

It is not necessary to do any memory management manually, as the stream will allocate or de-allocate memory as needed. When the stream is freed, all allocated memory will be freed as well.

See also: `TCustomMemoryStream` ([342](#)), `TStream` ([409](#))

4.59.2 Method overview

Page	Method	Description
380	<code>Clear</code>	Zeroes the position, capacity and size of the stream.
379	<code>Destroy</code>	Frees any allocated memory and destroys the memory stream.
380	<code>LoadFromFile</code>	Loads the contents of a file into memory.
380	<code>LoadFromStream</code>	Loads the contents of a stream into memory.
381	<code>SetSize</code>	Sets the size for the memory stream.
381	<code>Write</code>	Writes data to the stream's memory.

4.59.3 TMemoryStream.Destroy

Synopsis: Frees any allocated memory and destroys the memory stream.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` clears the memory stream, thus in effect freeing any memory allocated for it, and then frees the memory stream.

4.59.4 TMemoryStream.Clear

Synopsis: Zeroes the position, capacity and size of the stream.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` sets the position and size to 0, and sets the capacity of the stream to 0, thus freeing all memory allocated for the stream.

See also: `TStream.Size` (419), `TStream.Position` (418), `TCustomMemoryStream.Memory` (344)

4.59.5 TMemoryStream.LoadFromStream

Synopsis: Loads the contents of a stream into memory.

Declaration: `procedure LoadFromStream(Stream: TStream)`

Visibility: `public`

Description: `LoadFromStream` loads the contents of `Stream` into the memorybuffer of the stream. Any previous contents of the memory stream are overwritten. Memory is allocated as needed.

Remark: The `LoadFromStream` uses the `Size` (419) property of `Stream` to determine how much memory must be allocated. Some streams do not allow the stream size to be determined, so care must be taken when using this method.

This method will work much faster than the use of the `TStream.CopyFrom` (413) method:

```
Seek(0, soFromBeginning);
CopyFrom(Stream, Stream.Size);
```

because the `CopyFrom` method copies the contents in blocks, while `LoadFromStream` reads the contents of the stream as one big block.

Errors: If an error occurs when reading from the stream, an `EStreamError` (267) may occur.

See also: `TStream.CopyFrom` (413), `TMemoryStream.LoadFromFile` (380)

4.59.6 TMemoryStream.LoadFromFile

Synopsis: Loads the contents of a file into memory.

Declaration: `procedure LoadFromFile(const FileName: string)`

Visibility: `public`

Description: `LoadFromFile` loads the contents of the file with name `FileName` into the memory stream. The current contents of the memory stream is replaced by the contents of the file. Memory is allocated as needed.

The `LoadFromFile` method simply creates a filestream and then calls the `TMemoryStream.LoadFromStream` (380) method.

See also: `TMemoryStream.LoadFromStream` (380)

4.59.7 TMemoryStream.SetSize

Synopsis: Sets the size for the memory stream.

Declaration: `procedure SetSize(const NewSize: Int64); Override`

Visibility: `public`

Description: `SetSize` sets the size of the memory stream to `NewSize`. This will set the capacity of the stream to `NewSize` and correct the current position in the stream when needed.

See also: `TStream.Position` ([418](#)), `TStream.Size` ([419](#))

4.59.8 TMemoryStream.Write

Synopsis: Writes data to the stream's memory.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` writes `Count` bytes from `Buffer` to the stream's memory, starting at the current position in the stream. If more memory is needed than currently allocated, more memory will be allocated. Any contents in the memory stream at the current position will be overwritten. The function returns the number of bytes actually written (which should under normal circumstances always equal `Count`).

This method overrides the `TStream.Write` ([411](#)) method.

Errors: If no more memory could be allocated, then an exception will be raised.

See also: `TCustomMemoryStream.Read` ([343](#))

4.60 TOwnedCollection

4.60.1 Description

`TOwnedCollection` automatically maintains owner information, so it can be displayed in an IDE. Collections that should be displayed in an IDE should descend from `TOwnedCollection` or must implement a `GetOwner` function.

See also: `TCollection` ([320](#))

4.60.2 Method overview

Page	Method	Description
381	<code>Create</code>	Create a new <code>TOwnerCollection</code> instance.

4.60.3 TOwnedCollection.Create

Synopsis: Create a new `TOwnerCollection` instance.

Declaration: `constructor Create(AOwner: TPersistent;
 AItemClass: TCollectionItemClass)`

Visibility: `public`

Description: `Create` creates a new instance of `TOwnedCollection` and stores the `AOwner` references. It will the value returned in the `TCollection.Owner` (322) property of the collection. The `ItemClass` class reference is passed on to the inherited constructor, and will be used to create new instances in the `Insert` (324) and `Add` (322) methods.

See also: `TCollection.Create` (321), `TCollection.Owner` (322)

4.61 TOwnerStream

4.61.1 Description

`TOwnerStream` can be used when creating stream chains such as when using encryption and compression streams. It keeps a reference to the source stream and will automatically free the source stream when ready (if the `SourceOwner` (383) property is set to `True`).

See also: `TStream` (409), `TOwnerStream.Source` (383), `TOwnerStream.SourceOwner` (383)

4.61.2 Method overview

Page	Method	Description
382	<code>Create</code>	Create a new instance of <code>TOwnerStream</code> .
382	<code>Destroy</code>	Destroys the <code>TOwnerStream</code> instance and the source stream.

4.61.3 Property overview

Page	Properties	Access	Description
383	<code>Source</code>	<code>r</code>	Reference to the source stream.
383	<code>SourceOwner</code>	<code>rw</code>	Indicates whether the ownerstream owns it's source

4.61.4 TOwnerStream.Create

Synopsis: Create a new instance of `TOwnerStream`.

Declaration: `constructor Create (ASource: TStream)`

Visibility: `public`

Description: `Create` instantiates a new instance of `TOwnerStream` and stores the reference to `AStream`. If `SourceOwner` is `True`, the source stream will also be freed when the instance is destroyed.

See also: `TOwnerStream.Destroy` (382), `TOwnerStream.Source` (383), `TOwnerStream.SourceOwner` (383)

4.61.5 TOwnerStream.Destroy

Synopsis: Destroys the `TOwnerStream` instance and the source stream.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` frees the source stream if the `SourceOwner` property is `True`.

See also: `TOwnerStream.Create` (382), `TOwnerStream.Source` (383), `TOwnerStream.SourceOwner` (383)

4.61.6 TOwnerStream.Source

Synopsis: Reference to the source stream.

Declaration: `Property Source : TStream`

Visibility: `public`

Access: `Read`

Description: `Source` is the source stream. It should be used by descendant streams to access the source stream to read from or write to.

Do not free the `Source` reference directly if `SourceOwner` is `True`. In that case the owner stream instance will free the source stream itself.

See also: `TOwnerStream.Create` ([382](#))

4.61.7 TOwnerStream.SourceOwner

Synopsis: Indicates whether the ownerstream owns it's source

Declaration: `Property SourceOwner : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `SourceOwner` indicates whether the `TOwnerStream` owns it's `Source` stream or not. If this property is `True` then the `Source` stream is freed when the `TOwnerStream` instance is freed.

See also: `TOwnerStream.Source` ([383](#)), `TOwnerStream.Destroy` ([382](#))

4.62 TParser

4.62.1 Description

This class breaks a stream of text data in tokens. Its primary use is to help reading the contents of a form file (usually a file with `dfm`, `xfm` or `lfm` extension), and for this reason it isn't suitable to be used as a general parser.

The parser is always positioned on a certain token, whose type is stored in the `Token` ([389](#)) property. Various methods are provided to obtain the token value in the desired format.

To advance to the next token, invoke `NextToken` ([386](#)) method.

See also: `TParser.Token` ([389](#)), `TParser.NextToken` ([386](#))

4.62.2 Method overview

Page	Method	Description
385	<code>CheckToken</code>	Checks whether the token is of the given type.
385	<code>CheckTokenSymbol</code>	Checks whether the token equals the given symbol
384	<code>Create</code>	Creates a new parser instance.
384	<code>Destroy</code>	Destroys the parser instance.
385	<code>Error</code>	Raises an <code>EParserError</code> (267) exception with the given message
385	<code>ErrorFmt</code>	Raises an <code>EParserError</code> (267) exception and formats the message.
385	<code>ErrorStr</code>	Raises an <code>EParserError</code> (267) exception with the given message
386	<code>HexToBinary</code>	Writes hexadecimal data to a stream.
386	<code>NextToken</code>	Reads the next token and returns its type.
386	<code>SourcePos</code>	Returns the current position in the stream.
387	<code>TokenComponentIdent</code>	Returns the path of a subcomponent starting from the current token.
387	<code>TokenFloat</code>	Returns the current token as a float.
387	<code>TokenInt</code>	Returns the current token as an integer.
388	<code>TokenString</code>	Returns the current token as a string.
388	<code>TokenSymbolIs</code>	Returns <code>True</code> if the token equals the given symbol.
388	<code>TokenWideString</code>	Returns the current token as a widestring

4.62.3 Property overview

Page	Properties	Access	Description
389	<code>FloatType</code>	<code>r</code>	The type of a float token.
389	<code>SourceLine</code>	<code>r</code>	Current source line number.
389	<code>Token</code>	<code>r</code>	The type of the current token.

4.62.4 TParser.Create

Synopsis: Creates a new parser instance.

Declaration: `constructor Create(Stream: TStream)`

Visibility: `public`

Description: `Create` creates a new `TParser` instance, using `Stream` as the stream to read data from, and reads the first token from the stream.

Errors: If an error occurs while parsing the first token, an `EParserError` ([267](#)) exception is raised.

See also: `TParser.NextToken` ([386](#)), `TParser.Token` ([389](#))

4.62.5 TParser.Destroy

Synopsis: Destroys the parser instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the parser instance.

Errors: None.

4.62.6 TParser.CheckToken

Synopsis: Checks whether the token if of the given type.

Declaration: `procedure CheckToken(T: Char)`

Visibility: public

Description: Checks whether the token if of the given type.

Errors: If current token isn't of type T, an EParserError (267) exception is raised.

See also: TParser.Token (389)

4.62.7 TParser.CheckTokenSymbol

Synopsis: Checks whether the token equals the given symbol

Declaration: `procedure CheckTokenSymbol(const S: string)`

Visibility: public

Description: `CheckTokenSymbol` performs a case-insensitive comparison of current token value with S.

Current token must be of type `toSymbol` (233), otherwise an EParserError (267) exception is raised.

Errors: If the comparison fails, or current token isn't a symbol, an EParserError (267) exception is raised.

See also: TParser.TokenSymbolIs (388), `toSymbol` (233)

4.62.8 TParser.Error

Synopsis: Raises an EParserError (267) exception with the given message

Declaration: `procedure Error(const Ident: string)`

Visibility: public

Description: Raises an EParserError (267) exception with the given message

4.62.9 TParser.ErrorFmt

Synopsis: Raises an EParserError (267) exception and formats the message.

Declaration: `procedure ErrorFmt(const Ident: string; const Args: Array of const)`

Visibility: public

Description: Raises an EParserError (267) exception and formats the message.

4.62.10 TParser.ErrorStr

Synopsis: Raises an EParserError (267) exception with the given message

Declaration: `procedure ErrorStr(const Message: string)`

Visibility: public

Description: Raises an EParserError (267) exception with the given message

4.62.11 TParser.HexToBinary

Synopsis: Writes hexadecimal data to a stream.

Declaration: `procedure HexToBinary(Stream: TStream)`

Visibility: public

Description: `HexToBinary` reads a sequence of hexadecimal characters from the input stream and converts them to a sequence of bytes which is written to `Stream`. Each byte is represented by two contiguous hexadecimal characters.

Whitespace is allowed between hexadecimal characters if it doesn't appear between two characters that form the same byte.

`HexToBinary` stops when the first non-hexadecimal and non-whitespace character is found, or the end of the input stream is reached.

Remark: This method begins reading after the current token: that is, current token, even if it's a valid hexadecimal value, isn't included.

Errors: If a single hexadecimal character is found, an `EParseError` (267) exception is raised.

4.62.12 TParser.NextToken

Synopsis: Reads the next token and returns its type.

Declaration: `function NextToken : Char`

Visibility: public

Description: `NextToken` parses the next token in the stream and returns its type. The type of the token can also be retrieved later reading `Token` (389) property.

If the end of the stream is reached, `toEOF` (233) is returned.

For details about token types, see `TParser.Token` (389)

Errors: If an error occurs while parsing the token, an `EParseError` (267) exception is raised.

See also: `TParser.Token` (389)

4.62.13 TParser.SourcePos

Synopsis: Returns the current position in the stream.

Declaration: `function SourcePos : LongInt`

Visibility: public

Description: This is not the character position relative to the current source line, but the byte offset from the beginning of the stream.

Errors: None.

See also: `TParser.SourceLine` (389)

4.62.14 TParser.TokenComponentIdent

Synopsis: Returns the path of a subcomponent starting from the current token.

Declaration: `function TokenComponentIdent : string`

Visibility: public

Description: If current token is `toSymbol` (233), `TokenComponentIdent` tries to find subcomponent names separated by a dot (.). The returned string is the longest subcomponent path found. If there are no subcomponents, current symbol is returned.

Remark: After this method has been called, subsequent calls to `TokenString` (388) or `TokenWideString` (388) return the same value returned by `TokenComponentIdent`.

Example

If source stream contains `a.b.c` and `TParser` is positioned on the first token (`a`), this method returns `a.b.c`.

Errors: If `Token` (389) isn't `toSymbol` (233), or no valid symbol is found after a dot, an `EParserError` (267) exception is raised.

See also: `TParser.NextToken` (386), `TParser.Token` (389), `TParser.TokenString` (388), `TParser.TokenWideString` (388), `toSymbol` (233)

4.62.15 TParser.TokenFloat

Synopsis: Returns the current token as a float.

Declaration: `function TokenFloat : Extended`

Visibility: public

Description: If current token type is `toFloat` (233), this method returns the token value as a float.

To specify a negative number, no space must exist between unary minus and number.

Floating point numbers can be postfixed with a character that specifies the floating point type. See `FloatType` (389) for further information.

Remark: In the input stream the decimal separator, if present, must be a dot (.).

Errors: If `Token` (389) isn't `toFloat` (233), an `EParserError` (267) exception is raised.

See also: `TParser.FloatType` (389), `TParser.NextToken` (386), `TParser.Token` (389), `toFloat` (233)

4.62.16 TParser.TokenInt

Synopsis: Returns the current token as an integer.

Declaration: `function TokenInt : Int64`

Visibility: public

Description: If current token type is `toInteger` (233), this method returns the token value as an integer.

In the input stream an integer can be an hexadecimal (prefixed by ' \$ ' character) or decimal number. Decimal numbers can be prefixed by an unary minus: if this is the case, no space must exist between minus and number.

Errors: If `Token` (389) isn't `toInteger` (233), an `EConvertError` (231) exception is raised.

See also: `TParser.NextToken` (386), `TParser.Token` (389), `toInteger` (233)

4.62.17 TParser.TokenString

Synopsis: Returns the current token as a string.

Declaration: `function TokenString : string`

Visibility: public

Description: If current token type is `toString` (233) or `toWString` (233), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token type isn't a string, a string containing the token representation in the input stream is returned, without any conversion: hexadecimal integers are returned with the leading \$, and floating point suffixes like `s`, `c` or `d` are kept. For tokens whose type isn't a special type, return value of `TokenString` equals `Token` (389).

Remark: If `Token` (389) is `toWString` (233), `TokenWideString` (388) should be used instead.

Errors: None.

See also: `TParser.NextToken` (386), `TParser.TokenWideString` (388), `TParser.Token` (389), `toString` (233), `toWString` (233)

4.62.18 TParser.TokenWideString

Synopsis: Returns the current token as a widestring

Declaration: `function TokenWideString : WideString`

Visibility: public

Description: If current token type is `toWString` (233), this method returns the contents of the string. That is, enclosing quotes are removed, embedded quotes are unescaped and control strings are converted to the appropriate sequence of characters.

If current token isn't a widestring, `TokenWideString` behaviour is the same as `TokenString` (388).

Errors: None.

See also: `TParser.NextToken` (386), `TokenString` (388), `TParser.Token` (389), `toWString` (233)

4.62.19 TParser.TokenSymbols

Synopsis: Returns `True` if the token equals the given symbol.

Declaration: `function TokenSymbolIs(const S: string) : Boolean`

Visibility: public

Description: `TokenSymbolIs` performs a case-insensitive comparison of current token value with `S`.

If current token isn't of type `toSymbol` (233), or comparison fails, `False` is returned.

Errors: None.

See also: `TParser.CheckTokenSymbol` (385), `TParser.Token` (389)

4.62.20 TParser.FloatType

Synopsis: The type of a float token.

Declaration: `Property FloatType : Char`

Visibility: `public`

Access: `Read`

Description: Floating point numbers can be postfixed with a character specifying the type of floating point value. When specified, this property holds the character postfixed to the number.

It can be one of the following values:

Table 4.25:

<code>s</code> or <code>S</code>	Value is a single.
<code>c</code> or <code>C</code>	Value is a currency.
<code>d</code> or <code>D</code>	Value is a date.

If `Token` (389) isn't `toFloat` (233) or one of the above characters wasn't specified, `FloatType` is the null character (zero).

See also: `TParser.NextToken` (386), `TParser.Token` (389), `TParser.TokenFloat` (387), `toFloat` (233)

4.62.21 TParser.SourceLine

Synopsis: Current source line number.

Declaration: `Property SourceLine : Integer`

Visibility: `public`

Access: `Read`

Description: Current source line number.

See also: `TParser.SourcePos` (386)

4.62.22 TParser.Token

Synopsis: The type of the current token.

Declaration: `Property Token : Char`

Visibility: `public`

Access: `Read`

Description: This property holds the type of the current token. When `Token` isn't one of the special token types (whose value can be retrieved with specific methods) it is the character representing the current token.

Special token types:

Table 4.26:

toEOF (233)	Value returned by <code>TParser.Token (389)</code> when the end of the input stream was reached.
toSymbol (233)	Value returned by <code>TParser.Token (389)</code> when a symbol was found in the input stream.
toString (233)	Value returned by <code>TParser.Token (389)</code> when a string was found in the input stream.
toInteger (233)	Value returned by <code>TParser.Token (389)</code> when an integer was found in the input stream.
toFloat (233)	Value returned by <code>TParser.Token (389)</code> when a floating point value was found in the input stream.
toWString (233)	Value returned by <code>TParser.Token (389)</code> when a wistring was found in the input stream.

To advance to the next token, use `NextToken (386)` method.

See also: `TParser.CheckToken (385)`, `TParser.NextToken (386)`, `TParser.TokenComponentIdent (387)`, `TParser.TokenFloat (387)`, `TParser.TokenInt (387)`, `TParser.TokenString (388)`, `TParser.TokenWideString (388)`

4.63 TPersistent

4.63.1 Description

`TPersistent` is the basic class for the streaming system. Since it is compiled in the `{ $M+ }` state, the compiler generates RTTI (Run-Time Type Information) for it and all classes that descend from it. This information can be used to stream all properties of classes.

It also introduces functionality to assign the contents of 2 classes to each other.

`TPersistent` implements the `IFPObserved (269)` interface for the benefit of descendant classes, but does not call `IFPObserved.FPONotifyObservers (270)`. Descendants such as `TStrings (429)` and `TCollection (320)` and `TCollectionItem (328)` do use it.

See also: `TComponent (330)`, `IFPObserved (269)`, `TStrings (429)`, `TCollection (320)`, `TCollectionItem (328)`

4.63.2 Interfaces overview

Page	Interfaces	Description
269	<code>IFPObserved</code>	Interface implemented by an object that can be observed.

4.63.3 Method overview

Page	Method	Description
391	<code>Assign</code>	Assign the contents of one class to another.
390	<code>Destroy</code>	Destroys the <code>TPersistent</code> instance.
391	<code>FPOAttachObserver</code>	Add an observer to the list of observers.
392	<code>FPODetachObserver</code>	Remove an observer from the list of observers
392	<code>FPONotifyObservers</code>	Notify observers of changes.
392	<code>GetNamePath</code>	Returns a string that can be used to identify the class instance.

4.63.4 TPersistent.Destroy

Synopsis: Destroys the `TPersistent` instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` disposes of the persistent object. This method should never be called directly. Instead the `Free` method should be used.

4.63.5 TPersistent.Assign

Synopsis: Assign the contents of one class to another.

Declaration: `procedure Assign(Source: TPersistent); Virtual`

Visibility: public

Description: `Assign` copies the contents of `Source` to `Self`, if the classes of the destination and source classes are compatible.

The `TPersistent` implementation of `Assign` does nothing but calling the `AssignTo` (390) method of source. This means that if the destination class does not know how to assign the contents of the source class, the source class instance is asked to assign itself to the destination class. This means that it is necessary to implement only one of the two methods so that two classes can be assigned to one another.

Remark: In general, a statement of the form

```
Destination:=Source;
```

(where `Destination` and `Source` are classes) does not achieve the same as a statement of the form

```
Destination.Assign(Source);
```

After the former statement, both `Source` and `Destination` will point to the same object. The latter statement will copy the *contents* of the `Source` class to the `Destination` class.

See also: `AssignTo` (390)

4.63.6 TPersistent.FPOAttachObserver

Synopsis: Add an observer to the list of observers.

Declaration: `procedure FPOAttachObserver(AObserver: TObject)`

Visibility: public

Description: `FPOAttachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TPersistent`. It adds a new observer to the list of observers. Calling this multiple times will add the observed object multiple times to the list.

Errors: An `EObserver` exception may be raised if `AObject` does not implement the `IFPObserver` (271) interface.

See also: `IFPObserver` (271), `IFPObserved.FPOAttachObserver` (270), `IFPObserved` (269)

4.63.7 TPersistent.FPODetachObserver

Synopsis: Remove an observer from the list of observers

Declaration: `procedure FPODetachObserver(AObserver: TObject)`

Visibility: `public`

Description: `FPODetachObserver` is part of the implementation of the `IFPObserved` (269) interface in `TPersistent`. It removes the first found instance of the observer from the list of observers.

See also: `IFPObserved` (269), `IFPObserved.FPODetachObserver` (270), `IFPObserver` (271)

4.63.8 TPersistent.FPONotifyObservers

Synopsis: Notify observers of changes.

Declaration: `procedure FPONotifyObservers(ASender: TObject;
AOperation: TFPObservedOperation;
Data: Pointer)`

Visibility: `public`

Description: `FPONotifyObservers` can be called to notify observers of changes in the object. This method simply passes on the parameters that it receives to all attached `IFPObserver` (271) interfaces.

`TPersistent` does not call `FPONotifyObservers`. It is implemented for the benefit of descendant classes.

See also: `IFPObserved` (269), `IFPObserved.FPONotifyObservers` (270), `IFPObserver` (271)

4.63.9 TPersistent.GetNamePath

Synopsis: Returns a string that can be used to identify the class instance.

Declaration: `function GetNamePath : string; Virtual`

Visibility: `public`

Description: `GetNamePath` returns a string that can be used to identify the class instance. This can be used to display a name for this instance in a Object designer.

`GetNamePath` constructs a name by recursively prepending the `Classname` of the Owner instance to the `Classname` of this instance, separated by a dot.

See also: `TPersistent.GetOwner` (390)

4.64 TProxyStream

4.64.1 Description

`TProxyStream` is a proxy class for the `#rtl.types.IStream` (1756) interface. It implements all stream methods by relaying them to the `IStream` interface.

See also: `#rtl.types.IStream` (1756), `TStreamAdapter` (419)

4.64.2 Method overview

Page	Method	Description
393	Check	Check errors
393	Create	Create a new instance of the <code>TProxyStream</code> class.
393	Read	
393	Seek	
393	Write	

4.64.3 TProxyStream.Create

Synopsis: Create a new instance of the `TProxyStream` class.

Declaration: `constructor Create(const Stream: IStream)`

Visibility: `public`

Description: `Create` initializes a new instance of the `TProxyStream` class. It saves `var stream` for use in the other methods.

See also: `#rtl.types.IStream` ([1756](#))

4.64.4 TProxyStream.Read

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

4.64.5 TProxyStream.Write

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

4.64.6 TProxyStream.Seek

Declaration: `function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64
; Override`

Visibility: `public`

4.64.7 TProxyStream.Check

Synopsis: Check errors

Declaration: `procedure Check(err: Integer); Virtual`

Visibility: `public`

Description: `Check` will check the result of the `IStream` interface. This method must be overridden by descendant classes to return interface-specific errors.

See also: `#rtl.types.IStream` ([1756](#))

4.65 TReader

4.65.1 Description

The `TReader` class is a reader class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectReader` (281) to do the actual reading of data. The interface of the `TReader` class should be identical to the interface in Delphi.

Note that the `TReader` design is such that it can read a single component from a stream. It will read all children of this component, but it is not designed to read multiple components in succession from one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.ReadComponent` (413) call should be used.

See also: `TFile` (348), `TWriter` (466), `TAbstractObjectReader` (281)

4.65.2 Method overview

Page	Method	Description
396	BeginReferences	Initializes the component referencing mechanism.
397	CheckValue	Raises an exception if the next value in the stream is not of type Value
403	CopyValue	Copy a value to a writer.
396	Create	Creates a new reader class
397	DefineBinaryProperty	Reads a user-defined binary property from the stream.
397	DefineProperty	Reads a user-defined property from the stream.
396	Destroy	Destroys a reader class.
397	EndOfList	Returns true if the stream contains an end-of-list marker.
397	EndReferences	Finalizes the component referencing mechanism.
398	FixupReferences	Tries to resolve all unresolved component references.
398	NextValue	Returns the type of the next value.
398	Read	Read raw data from stream
398	ReadBoolean	Reads a boolean from the stream.
398	ReadChar	Reads a character from the stream.
399	ReadCollection	Reads a collection from the stream.
399	ReadComponent	Starts reading a component from the stream.
399	ReadComponents	Starts reading child components from the stream.
400	ReadCurrency	Read a currency value from the stream.
400	ReadDate	Reads a date from the stream
400	ReadFloat	Reads a float from the stream.
400	ReadIdent	Reads an identifier from the stream.
401	ReadInt64	Reads a 64-bit integer from the stream.
401	ReadInteger	Reads an integer from the stream
401	ReadListBegin	Checks for the beginning of a list.
401	ReadListEnd	Checks for the end of a list.
402	ReadRootComponent	Starts reading a root component.
401	ReadSet	Read a set value from the stream
402	ReadSignature	Read stream signature from the stream
400	ReadSingle	Reads a single-type real from the stream.
402	ReadString	Reads a string from the stream.
399	ReadUnicodeChar	Read unicode character
403	ReadUnicodeString	Read a UnicodeString value from the stream
403	ReadValue	Reads the next value type from the stream.
402	ReadVariant	Read a variant from the stream
399	ReadWideChar	Read widechar from the stream
403	ReadWideString	Read a WideString value from the stream.

4.65.3 Property overview

Page	Properties	Access	Description
403	Driver	r	The driver in use for streaming the data.
405	OnAncestorNotFound	rw	Handler called when the ancestor component cannot be found.
406	OnCreateComponent	rw	Handler called when a component needs to be created.
404	OnError	rw	Handler called when an error occurs.
406	OnFindComponentClass	rw	Handler called when a component class reference needs to be found.
405	OnFindMethod	rw	Handler to find or change a method address.
404	OnPropertyNotFound	rw	Handler for treating missing properties.
406	OnReadStringProperty	rw	Handler for translating strings when read from the stream.
405	OnReferenceName	rw	Handler called when another component is referenced.
405	OnSetMethodProperty	rw	Handler for setting method properties.
405	OnSetName	rw	Handler called when setting a component name.
404	Owner	rw	Owner of the component being read
404	Parent	rw	Parent of the component being read.

4.65.4 TReader.Create

Synopsis: Creates a new reader class

Declaration: `constructor Create(Stream: TStream; BufSize: Integer)`

Visibility: `public`

Description: Creates a new reader class

4.65.5 TReader.Destroy

Synopsis: Destroys a reader class.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys a reader class.

4.65.6 TReader.BeginReferences

Synopsis: Initializes the component referencing mechanism.

Declaration: `procedure BeginReferences`

Visibility: `public`

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method initializes up that system.

4.65.7 TReader.CheckValue

Synopsis: Raises an exception if the next value in the stream is not of type Value

Declaration: `procedure CheckValue(Value: TValueType)`

Visibility: public

Description: Raises an exception if the next value in the stream is not of type Value

4.65.8 TReader.DefineProperty

Synopsis: Reads a user-defined property from the stream.

Declaration: `procedure DefineProperty(const Name: string; AReadData: TReaderProc;
WriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined property from the stream.

4.65.9 TReader.DefineBinaryProperty

Synopsis: Reads a user-defined binary property from the stream.

Declaration: `procedure DefineBinaryProperty(const Name: string;
AReadData: TStreamProc;
WriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: public

Description: Reads a user-defined binary property from the stream.

4.65.10 TReader.EndOfList

Synopsis: Returns true if the stream contains an end-of-list marker.

Declaration: `function EndOfList : Boolean`

Visibility: public

Description: Returns true if the stream contains an end-of-list marker.

4.65.11 TReader.EndReferences

Synopsis: Finalizes the component referencing mechanism.

Declaration: `procedure EndReferences`

Visibility: public

Description: When streaming components, the streaming mechanism keeps a list of existing components that can be referenced to. This method cleans up that system.

4.65.12 TReader.FixupReferences

Synopsis: Tries to resolve all unresolved component references.

Declaration: `procedure FixupReferences`

Visibility: `public`

Description: Tries to resolve all unresolved component references.

4.65.13 TReader.NextValue

Synopsis: Returns the type of the next value.

Declaration: `function NextValue : TValueType`

Visibility: `public`

Description: Returns the type of the next value.

4.65.14 TReader.Read

Synopsis: Read raw data from stream

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: `public`

Description: `Read` is introduced for Delphi compatibility to read raw data from the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TAbstractObjectReader.Read` ([283](#)), `TBinaryObjectReader.Read` ([303](#))

4.65.15 TReader.ReadBoolean

Synopsis: Reads a boolean from the stream.

Declaration: `function ReadBoolean : Boolean`

Visibility: `public`

Description: Reads a boolean from the stream.

4.65.16 TReader.ReadChar

Synopsis: Reads a character from the stream.

Declaration: `function ReadChar : Char`

Visibility: `public`

Description: Reads a character from the stream.

4.65.17 TReader.ReadWideChar

Synopsis: Read widechar from the stream

Declaration: `function ReadWideChar : WideChar`

Visibility: public

Description: `TReader.ReadWideChar` reads a widechar from the stream. This actually reads a widestring and returns the first character.

See also: `TReader.ReadWideString` ([403](#)), `TWriter.WriteWideChar` ([469](#))

4.65.18 TReader.ReadUnicodeChar

Synopsis: Read unicode character

Declaration: `function ReadUnicodeChar : UnicodeChar`

Visibility: public

Description: `ReadUnicodeChar` reads a single unicode character from the stream. It does this by reading a `UnicodeString` string from the stream and returning the first character.

Errors: If the string has a length different from 1, an `EReadError` exception will occur.

See also: `TReader.ReadUnicodeString` ([403](#))

4.65.19 TReader.ReadCollection

Synopsis: Reads a collection from the stream.

Declaration: `procedure ReadCollection(Collection: TCollection)`

Visibility: public

Description: Reads a collection from the stream.

4.65.20 TReader.ReadComponent

Synopsis: Starts reading a component from the stream.

Declaration: `function ReadComponent(Component: TComponent) : TComponent`

Visibility: public

Description: Starts reading a component from the stream.

4.65.21 TReader.ReadComponents

Synopsis: Starts reading child components from the stream.

Declaration: `procedure ReadComponents(AOwner: TComponent; AParent: TComponent;
Proc: TReadComponentsProc)`

Visibility: public

Description: Starts reading child components from the stream.

4.65.22 TReader.ReadFloat

Synopsis: Reads a float from the stream.

Declaration: `function ReadFloat : Extended`

Visibility: `public`

Description: Reads a float from the stream.

4.65.23 TReader.ReadSingle

Synopsis: Reads a single-type real from the stream.

Declaration: `function ReadSingle : Single`

Visibility: `public`

Description: Reads a single-type real from the stream.

4.65.24 TReader.ReadDate

Synopsis: Reads a date from the stream

Declaration: `function ReadDate : TDateTime`

Visibility: `public`

Description: Reads a date from the stream

4.65.25 TReader.ReadCurrency

Synopsis: Read a currency value from the stream.

Declaration: `function ReadCurrency : Currency`

Visibility: `public`

Description: `ReadCurrency` reads a currency typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteCurrency` ([470](#))

4.65.26 TReader.ReadIdent

Synopsis: Reads an identifier from the stream.

Declaration: `function ReadIdent : string`

Visibility: `public`

Description: Reads an identifier from the stream.

4.65.27 TReader.ReadInteger

Synopsis: Reads an integer from the stream

Declaration: `function ReadInteger : LongInt`

Visibility: `public`

Description: Reads an integer from the stream

4.65.28 TReader.ReadInt64

Synopsis: Reads a 64-bit integer from the stream.

Declaration: `function ReadInt64 : Int64`

Visibility: `public`

Description: Reads a 64-bit integer from the stream.

4.65.29 TReader.ReadSet

Synopsis: Read a set value from the stream

Declaration: `function ReadSet (EnumType: Pointer) : Integer`

Visibility: `public`

Description: `ReadSet` reads a set of elements with type `EnumType` and returns them as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be read with this function.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TWriter.WriteSet` ([471](#))

4.65.30 TReader.ReadListBegin

Synopsis: Checks for the beginning of a list.

Declaration: `procedure ReadListBegin`

Visibility: `public`

Description: Checks for the beginning of a list.

4.65.31 TReader.ReadListEnd

Synopsis: Checks for the end of a list.

Declaration: `procedure ReadListEnd`

Visibility: `public`

Description: Checks for the end of a list.

4.65.32 TReader.ReadRootComponent

Synopsis: Starts reading a root component.

Declaration: `function ReadRootComponent (ARoot: TComponent) : TComponent`

Visibility: `public`

Description: Starts reading a root component.

4.65.33 TReader.ReadVariant

Synopsis: Read a variant from the stream

Declaration: `function ReadVariant : Variant`

Visibility: `public`

Description: `ReadVariant` reads the next value from the stream and returns it as a variant. No variant array can be read from the stream, only single values.

Errors: If no variant manager is installed, the function will raise an `EReadError` exception. If the next value is not a simple value, again an `EReadError` exception is raised. exception is

See also: `TBinaryObjectWriter.WriteVariant` ([312](#))

4.65.34 TReader.ReadSignature

Synopsis: Read stream signature from the stream

Declaration: `procedure ReadSignature`

Visibility: `public`

Description: `ReadSignature` is called when starting to read a root component from a stream. Some streams contain a signature (header) to detect whether the stream contains correct data.

Errors: If the stream does not start with the correct signature, an `EReadError` ([267](#)) exception will be raised.

See also: `TAbstractObjectReader.ReadSignature` ([287](#)), `TAbstractObjectWriter.WriteSignature` ([290](#))

4.65.35 TReader.ReadString

Synopsis: Reads a string from the stream.

Declaration: `function ReadString : string`

Visibility: `public`

Description: Reads a string from the stream.

4.65.36 TReader.ReadWideString

Synopsis: Read a WideString value from the stream.

Declaration: `function ReadWideString : WideString`

Visibility: public

Description: `ReadWideString` reads a `WideString` typed value from the stream and returns the result. This method does nothing except call the driver method of the driver being used.

See also: `TWriter.WriteString` ([472](#))

4.65.37 TReader.ReadUnicodeString

Synopsis: Read a UnicodeString value from the stream

Declaration: `function ReadUnicodeString : UnicodeString`

Visibility: public

Description: `ReadUnicodeString` reads a `UnicodeString` string from the stream. The stream can contain a string from any type, it will be converted to `UnicodeString`.

See also: `TAbstractObjectReader.ReadUnicodeString` ([288](#)), `TWriter.WriteUnicodeString` ([472](#))

4.65.38 TReader.ReadValue

Synopsis: Reads the next value type from the stream.

Declaration: `function ReadValue : TValueType`

Visibility: public

Description: Reads the next value type from the stream.

4.65.39 TReader.CopyValue

Synopsis: Copy a value to a writer.

Declaration: `procedure CopyValue (Writer: TWriter)`

Visibility: public

Description: `CopyValue` reads the next value from the reader stream, and writes it to the passed `Writer`.

4.65.40 TReader.Driver

Synopsis: The driver in use for streaming the data.

Declaration: `Property Driver : TAbstractObjectReader`

Visibility: public

Access: Read

Description: The driver in use for streaming the data.

4.65.41 TReader.Owner

Synopsis: Owner of the component being read

Declaration: `Property Owner : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Owner of the component being read

4.65.42 TReader.Parent

Synopsis: Parent of the component being read.

Declaration: `Property Parent : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Parent of the component being read.

4.65.43 TReader.OnError

Synopsis: Handler called when an error occurs.

Declaration: `Property OnError : TReaderError`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when an error occurs.

4.65.44 TReader.OnPropertyNotFound

Synopsis: Handler for treating missing properties.

Declaration: `Property OnPropertyNotFound : TPropertyNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnPropertyNotFound` can be used to take appropriate action when a property is read from a stream and no such property is found in the RTTI information of the Instance that is being read from the stream. It can be set at runtime, or at design time by an IDE.

For more information about the meaning of the various arguments to the event handler, see `TPropertyNotFoundEvent` ([243](#)).

See also: `TPropertyNotFoundEvent` ([243](#)), `TReader.OnSetMethodProperty` ([405](#)), `TReader.OnReadStringProperty` ([406](#))

4.65.45 TReader.OnFindMethod

Synopsis: Handler to find or change a method address.

Declaration: `Property OnFindMethod : TFindMethodEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler to find or change a method address.

4.65.46 TReader.OnSetMethodProperty

Synopsis: Handler for setting method properties.

Declaration: `Property OnSetMethodProperty : TSetMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnSetMethodProperty` can be set to handle the setting of method properties. This handler can be used by an IDE to prevent methods from actually being assigned when an object is being streamed in the designer.

See also: `TReader.OnReadStringProperty` ([406](#)), `TReader.OnPropertyNotFound` ([404](#))

4.65.47 TReader.OnSetName

Synopsis: Handler called when setting a component name.

Declaration: `Property OnSetName : TSetNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when setting a component name.

4.65.48 TReader.OnReferenceName

Synopsis: Handler called when another component is referenced.

Declaration: `Property OnReferenceName : TReferenceNameEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when another component is referenced.

4.65.49 TReader.OnAncestorNotFound

Synopsis: Handler called when the ancestor component cannot be found.

Declaration: `Property OnAncestorNotFound : TAncestorNotFoundEvent`

Visibility: `public`

Access: `Read,Write`

Description: Handler called when the ancestor component cannot be found.

4.65.50 TReader.OnCreateComponent

Synopsis: Handler called when a component needs to be created.

Declaration: Property OnCreateComponent : TCreateComponentEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component needs to be created.

4.65.51 TReader.OnFindComponentClass

Synopsis: Handler called when a component class reference needs to be found.

Declaration: Property OnFindComponentClass : TFindComponentClassEvent

Visibility: public

Access: Read,Write

Description: Handler called when a component class reference needs to be found.

4.65.52 TReader.OnReadStringProperty

Synopsis: Handler for translating strings when read from the stream.

Declaration: Property OnReadStringProperty : TReadWriteStringPropertyEvent

Visibility: public

Access: Read,Write

Description: OnReadStringProperty is called whenever a string property is read from the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is loaded. See TReadWriteStringPropertyEvent (243) for a description of the various parameters.

See also: TReader.OnPropertyNotFound (404), TReader.OnSetMethodProperty (405), TReadWriteStringPropertyEvent (243)

4.66 TRecall

4.66.1 Description

TRecall is a helper class used to copy published properties of a class (the reference object) in another class (the storage object). The reference object and storage object must be assignable to each other.

The TRecall can be used to store the state of a persistent class, and restore it at a later time.

When a TRecall object is created, it gets passed a reference instance and a storage instance. It immediately stores the properties of the reference object in the storage object.

The Store (407) method can be called throughout the lifetime of the reference object to update the stored properties.

When the TRecall instance is destroyed then the properties are copied from the storage object to the reference object. The storage object is freed automatically.

If the properties should not be copied back from the storage to the reference object, the Forget (408) can be called.

See also: `TRecall.Create` (407), `TRecall.Destroy` (407), `TRecall.Forget` (408), `TRecall.Store` (407), `TPersistent.Assign` (391)

4.66.2 Method overview

Page	Method	Description
407	Create	Creates a new instance of <code>TRecall</code> .
407	Destroy	Copies the stored properties to the reference object and destroys the <code>TRecall</code> instance.
408	Forget	Clear the reference property.
407	Store	Assigns the reference instance to the storage instance.

4.66.3 Property overview

Page	Properties	Access	Description
408	Reference	r	The reference object.

4.66.4 TRecall.Create

Synopsis: Creates a new instance of `TRecall`.

Declaration: `constructor Create(AStorage: TPersistent; AReference: TPersistent)`

Visibility: public

Description: `Create` creates a new instance of `TRecall` and initializes the Reference and Storage instances. It calls `Store` (407) to assign the reference object properties to the storage instance.

See also: `TRecall.Store` (407), `TRecall.Destroy` (407)

4.66.5 TRecall.Destroy

Synopsis: Copies the stored properties to the reference object and destroys the `TRecall` instance.

Declaration: `destructor Destroy; Override`

Visibility: public

Description: `Destroy` assigns the storage instance to the reference instance, if the latter is still valid. After this, it frees the storage and calls the inherited `destroy`.

Errors: `Destroy` does not check whether the reference (408) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (408) to clear the reference instance.

See also: `TRecall.Store` (407), `TRecall.Forget` (408)

4.66.6 TRecall.Store

Synopsis: Assigns the reference instance to the storage instance.

Declaration: `procedure Store`

Visibility: public

Description: `Store` assigns the reference instance to the storage instance. This will only work if the two classes can be assigned to each other.

This method can be used to refresh the storage.

Errors: `Store` does not check whether the reference (408) instance is still valid. If the reference pointer was invalidated, call `TRecall.Forget` (408) to clear the reference instance.

4.66.7 TRecall.Forget

Synopsis: Clear the reference property.

Declaration: `procedure Forget`

Visibility: `public`

Description: `Forget` sets the `Reference` (408) property to `Nil`. When the `TRecall` instance is destroyed, the reference instance will not be restored.

Note that after a call to `Forget`, a call to `Store` (407) has no effect.

Errors: None.

See also: `TRecall.Reference` (408), `TRecall.Store` (407), `TRecall.Destroy` (407)

4.66.8 TRecall.Reference

Synopsis: The reference object.

Declaration: `Property Reference : TPersistent`

Visibility: `public`

Access: `Read`

Description: `Reference` is the instance of the reference object. Do not free the reference directly. Call `Forget` (408) to clear the reference and then free the reference object.

See also: `TRecall.Forget` (408)

4.67 TResourceStream

4.67.1 Description

Stream that reads its data from a resource object.

4.67.2 Method overview

Page	Method	Description
409	<code>Create</code>	Creates a new instance of a resource stream.
409	<code>CreateFromID</code>	Creates a new instance of a resource stream with a resource
409	<code>Destroy</code>	Destroys the instance of the resource stream.

4.67.3 TResourceStream.Create

Synopsis: Creates a new instance of a resource stream.

Declaration: constructor `Create(Instance: TFPResourceHMODULE; const ResName: string; ResType: PChar)`

Visibility: public

Description: Creates a new instance of a resource stream.

4.67.4 TResourceStream.CreateFromID

Synopsis: Creates a new instance of a resource stream with a resource

Declaration: constructor `CreateFromID(Instance: TFPResourceHMODULE; ResID: Integer; ResType: PChar)`

Visibility: public

Description: The resource is loaded from the loaded module (identified by the handle `Instance`), identifier `ResID` and type `ResType`.

4.67.5 TResourceStream.Destroy

Synopsis: Destroys the instance of the resource stream.

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Destroys the instance of the resource stream.

4.68 TStream

4.68.1 Description

`TStream` is the base class for all streaming classes. It defines methods for reading (410), writing (411) from and to streams, as well as functions to determine the size of the stream as well as the current position of the stream.

Descendant classes such as `TMemoryStream` (379) or `TFileStream` (350) then override these methods to write streams to memory or file.

See also: `TMemoryStream` (379), `TFileStream` (350), `TStringStream` (447)

4.68.2 Method overview

Page	Method	Description
413	<code>CopyFrom</code>	Copy data from one stream to another
415	<code>FixupResourceHeader</code>	Not implemented in FPC
410	<code>Read</code>	Reads data from the stream to a buffer and returns the number of bytes read.
417	<code>ReadAnsiString</code>	Read an ansistring from the stream and return its value.
412	<code>ReadBuffer</code>	Reads data from the stream to a buffer
415	<code>ReadByte</code>	Read a byte from the stream and return its value.
413	<code>ReadComponent</code>	Reads component data from a stream
413	<code>ReadComponentRes</code>	Reads component data and resource header from a stream
416	<code>ReadDWord</code>	Read a DWord from the stream and return its value.
416	<code>ReadQWord</code>	Read a QWord value from the stream and return its value
415	<code>ReadResHeader</code>	Read a resource header from the stream.
416	<code>ReadWord</code>	Read a word from the stream and return its value.
411	<code>Seek</code>	Sets the current position in the stream
411	<code>Write</code>	Writes data from a buffer to the stream and returns the number of bytes written.
418	<code>WriteAnsiString</code>	Write an ansistring to the stream.
412	<code>WriteBuffer</code>	Writes data from a buffer to the stream
417	<code>WriteByte</code>	Write a byte to the stream.
414	<code>WriteComponent</code>	Write component data to the stream
414	<code>WriteComponentRes</code>	Write resource header and component data to a stream
414	<code>WriteDescendent</code>	Write descendent of a component
414	<code>WriteDescendentRes</code>	Write descendent of a component as resource
417	<code>WriteDWord</code>	Write a DWord to the stream.
418	<code>WriteQWord</code>	Write a QWord value to the stream
415	<code>WriteResourceHeader</code>	Write resource header to the stream
417	<code>WriteWord</code>	Write a word to the stream.

4.68.3 Property overview

Page	Properties	Access	Description
418	<code>Position</code>	<code>rw</code>	The current position in the stream.
419	<code>Size</code>	<code>rw</code>	The current size of the stream.

4.68.4 TStream.Read

Synopsis: Reads data from the stream to a buffer and returns the number of bytes read.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Virtual`

Visibility: `public`

Description: `Read` attempts to read `Count` from the stream to `Buffer` and returns the number of bytes actually read.

This method should be used when the number of bytes is not determined. If a specific number of bytes is expected, use `TStream.ReadBuffer` ([412](#)) instead.

As implemented in `TStream`, `Read` does nothing but raises an `EStreamError` ([267](#)) exception to indicate that reading is not supported. Descendant classes that allow reading must override this method to do the actual reading.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow reading from the stream, an exception is raised.

See also: [TStream.Write \(411\)](#), [TStream.ReadBuffer \(412\)](#)

4.68.5 TStream.Write

Synopsis: Writes data from a buffer to the stream and returns the number of bytes written.

```
Declaration: function Write(const Buffer; Count: LongInt) : LongInt; Virtual
```

Visibility: public

Description: *Write* attempts to write `Count` bytes from `Buffer` to the stream. It returns the actual number of bytes written to the stream.

This method should be used when the number of bytes that should be written is not determined. If a specific number of bytes should be written, use `TStream.WriteBuffer` (412) instead.

As implemented in `TStream`, `Write` does nothing but raises `EStreamError` (267) exception to indicate that writing is not supported. Descendant classes that allow writing must override this method to do the actual writing.

Descendant classes should (if they don't explicitly raise an exception) return a positive value (≥ 0), where zero indicates an error.

Errors: In case a descendant class does not allow writing to the stream, an exception is raised.

See also: [TStream.Read \(410\)](#), [TStream.WriteBuffer \(412\)](#)

4.68.6 TStream.Seek

Synopsis: Sets the current position in the stream

```
Declaration: function Seek(Offset: LongInt; Origin: Word) : LongInt; Virtual
                ; Overload
function Seek(const Offset: Int64; Origin: TSeekOrigin) : Int64
                ; Virtual; Overload
```

Visibility: public

Description: *Seek* sets the position of the stream to *Offset* bytes from *Origin*. There is a 32-bit variant of this function and a 64-bit variant. The difference can be made by choosing the correct *Offset* parameter: the integer-typed parameter selects the 32-bit variant, the parameter of type *TSeekOrigin* (243) selects the 64-bit variant of the function.

The `Origin` parameter for the 32-bit version can have one of the following values:

Table 4.27:

Constant	Meaning
<code>soFromBeginning</code>	Set the position relative to the start of the stream.
<code>soFromCurrent</code>	Set the position relative to the current position in the stream.
<code>soFromEnd</code>	Set the position relative to the end of the stream.

These values are defined in the SysUtils (231) unit.

The `Origin` parameter for the 64-bit version has one of the following values:

Table 4.28:

Value	Meaning
soBeginning	Offset is interpreted relative to the start of the stream.
soCurrent	Offset is interpreted relative to the current position in the stream.
soEnd	Offset is interpreted relative to the end of the stream.

Offset should be negative when the origin is SoFromEnd (soEnd). It should be positive for soFromBeginning and can have both signs for soFromCurrent

This is an abstract method, which must be overridden by descendant classes. They may choose not to implement this method for all values of Origin and Offset.

Remark: Internally, all calls are re-routed to the 64-bit version of the call. When creating a descendant of TStream, the 64-bit version of the call should be overridden.

Errors: An exception may be raised if this method is called with an invalid pair of Offset,Origin values. e.g. a negative offset for soFromBeginning (or soBeginning).

See also: TStream.Position (418)

4.68.7 TStream.ReadBuffer

Synopsis: Reads data from the stream to a buffer

Declaration: `procedure ReadBuffer (var Buffer; Count: LongInt)`

Visibility: public

Description: ReadBuffer reads Count bytes of the stream into Buffer. If the stream does not contain Count bytes, then an exception is raised.

ReadBuffer should be used to read in a fixed number of bytes, such as when reading structures or the content of variables. If the number of bytes is not determined, use TStream.Read (410) instead. ReadBuffer uses Read internally to do the actual reading.

Errors: If the stream does not allow to read Count bytes, then an exception is raised.

See also: TStream.Read (410), TStream.WriteBuffer (412)

4.68.8 TStream.WriteBuffer

Synopsis: Writes data from a buffer to the stream

Declaration: `procedure WriteBuffer (const Buffer; Count: LongInt)`

Visibility: public

Description: WriteBuffer writes Count bytes to the stream from Buffer. If the stream does not allow Count bytes to be written, then an exception is raised.

WriteBuffer should be used to write a fixed number of bytes, such as when writing structures or the content of variables. If the number of bytes is not determined, use TStream.Write (411) instead. WriteBuffer uses Write internally to do the actual writing.

Errors: If the stream does not allow to write Count bytes, then an exception is raised.

See also: TStream.Write (411), TStream.ReadBuffer (412)

4.68.9 TStream.CopyFrom

Synopsis: Copy data from one stream to another

Declaration: `function CopyFrom(Source: TStream; Count: Int64) : Int64`

Visibility: public

Description: `CopyFrom` reads `Count` bytes from `Source` and writes them to the current stream. This updates the current position in the stream. After the action is completed, the number of bytes copied is returned. If `Count` is zero, then the whole contents of the `Source` stream is copied. It is positioned on the first byte of data, and `Size` bytes are copied. Note that this cannot be used with streams that do not allow seeking or do not allow determining the size of the stream.

This can be used to quickly copy data from one stream to another or to copy the whole contents of the stream.

See also: `TStream.Read` (410), `TStream.Write` (411)

4.68.10 TStream.ReadComponent

Synopsis: Reads component data from a stream

Declaration: `function ReadComponent(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponent` reads a component state from the stream and transfers this state to `Instance`. If `Instance` is nil, then it is created first based on the type stored in the stream. `ReadComponent` returns the component as it is read from the stream.

`ReadComponent` simply creates a `TReader` (394) object and calls its `ReadRootComponent` (402) method.

Errors: If an error occurs during the reading of the component, an `EFileError` (265) exception is raised.

See also: `TStream.WriteComponent` (414), `TStream.ReadComponentRes` (413), `TReader.ReadRootComponent` (402)

4.68.11 TStream.ReadComponentRes

Synopsis: Reads component data and resource header from a stream

Declaration: `function ReadComponentRes(Instance: TComponent) : TComponent`

Visibility: public

Description: `ReadComponentRes` reads a resource header from the stream, and then calls `ReadComponent` (413) to read the component state from the stream into `Instance`.

This method is usually called by the global streaming method when instantiating forms and datamodules as created by an IDE. It should be used mainly on Windows, to store components in Windows resources.

Errors: If an error occurs during the reading of the component, an `EFileError` (265) exception is raised.

See also: `TStream.ReadComponent` (413), `TStream.WriteComponentRes` (414)

4.68.12 TStream.WriteComponent

Synopsis: Write component data to the stream

Declaration: `procedure WriteComponent (Instance: TComponent)`

Visibility: public

Description: `WriteComponent` writes the published properties of `Instance` to the stream, so they can later be read with `TStream.ReadComponent` (413). This method is intended to be used by an IDE, to preserve the state of a form or datamodule as designed in the IDE.

`WriteComponent` simply calls `WriteDescendant` (409) with `Nil` ancestor.

See also: `TStream.ReadComponent` (413), `TStream.WriteComponentRes` (414)

4.68.13 TStream.WriteComponentRes

Synopsis: Write resource header and component data to a stream

Declaration: `procedure WriteComponentRes (const ResName: string; Instance: TComponent)`

Visibility: public

Description: `WriteComponentRes` writes a `ResName` resource header to the stream and then calls `WriteComponent` (414) to write the published properties of `Instance` to the stream.

This method is intended for use by an IDE that can use it to store forms or datamodules as designed in a Windows resource stream.

See also: `TStream.WriteComponent` (414), `TStream.ReadComponentRes` (413)

4.68.14 TStream.WriteDescendent

Synopsis: Write descendent of a component

Declaration: `procedure WriteDescendent (Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendent` will create a `TWriter` (466) writer class and write `Instance` as a descendent of `Ancestor` using the writer. This is used to create diff streams: only the properties where `Instance` differs from `Ancestor` are written to the stream.

See also: `TWriter.WriteDescendent` (469)

4.68.15 TStream.WriteDescendentRes

Synopsis: Write descendent of a component as resource

Declaration: `procedure WriteDescendentRes (const ResName: string;
Instance: TComponent; Ancestor: TComponent)`

Visibility: public

Description: `WriteDescendentRes` calls `WriteDescendent` as a resource stream.

See also: `TWriter.WriteDescendent` (469)

4.68.16 TStream.WriteResourceHeader

Synopsis: Write resource header to the stream

Declaration: `procedure WriteResourceHeader(const ResName: string;
var FixupInfo: LongInt)`

Visibility: public

Description: `WriteResourceHeader` writes a resource-file header for a resource called `ResName`. It returns in `FixupInfo` the argument that should be passed on to `TStream.FixupResourceHeader` (415).

`WriteResourceHeader` should not be used directly. It is called by the `TStream.WriteComponentRes` (414) and `TStream.WriteDescendantRes` (409) methods.

See also: `TStream.FixupResourceHeader` (415), `TStream.WriteComponentRes` (414), `TStream.WriteDescendantRes` (409)

4.68.17 TStream.FixupResourceHeader

Synopsis: Not implemented in FPC

Declaration: `procedure FixupResourceHeader(FixupInfo: LongInt)`

Visibility: public

Description: `FixupResourceHeader` is used to write the size of the resource after a component was written to stream. The size is determined from the current position, and it is written at position `FixupInfo`. After that the current position is restored.

`FixupResourceHeader` should never be called directly; it is handled by the streaming system.

See also: `TStream.WriteResourceHeader` (415), `TStream.WriteComponentRes` (414), `TStream.WriteDescendantRes` (409)

4.68.18 TStream.ReadResHeader

Synopsis: Read a resource header from the stream.

Declaration: `procedure ReadResHeader`

Visibility: public

Description: `ReadResourceHeader` reads a resource file header from the stream. It positions the stream just beyond the header.

`ReadResourceHeader` should not be called directly, it is called by the streaming system when needed.

Errors: If the resource header is invalid an `EInvalidImage` (266) exception is raised.

See also: `TStream.ReadComponentRes` (413), `EInvalidImage` (266)

4.68.19 TStream.ReadByte

Synopsis: Read a byte from the stream and return its value.

Declaration: `function ReadByte : Byte`

Visibility: public

Description: `ReadByte` reads one byte from the stream and returns its value.

Errors: If the byte cannot be read, a `EStreamError` (267) exception will be raised. This is a utility function which simply calls the `Read` (410) function.

See also: `TStream.Read` (410), `TStream.WriteByte` (417), `TStream.ReadWord` (416), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.20 `TStream.ReadWord`

Synopsis: Read a word from the stream and return its value.

Declaration: `function ReadWord : Word`

Visibility: `public`

Description: `ReadWord` reads one `Word` (i.e. 2 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (410) function.

Errors: If the word cannot be read, a `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteWord` (417), `TStream.ReadByte` (415), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.21 `TStream.ReadDWord`

Synopsis: Read a `DWord` from the stream and return its value.

Declaration: `function ReadDWord : Cardinal`

Visibility: `public`

Description: `ReadDWord` reads one `DWord` (i.e. 4 bytes) from the stream and returns its value. This is a utility function which simply calls the `Read` (410) function.

Errors: If the `DWord` cannot be read, a `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteDWord` (417), `TStream.ReadByte` (415), `TStream.ReadWord` (416), `TStream.ReadAnsiString` (417)

4.68.22 `TStream.ReadQWord`

Synopsis: Read a `QWord` value from the stream and return its value

Declaration: `function ReadQWord : QWord`

Visibility: `public`

Description: `ReadQWord` reads a `QWord` value (8 bytes) from the stream and returns its value.

Errors: If not enough bytes are available on the stream, an `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteByte` (417), `TStream.ReadWord` (416), `TStream.ReadDWord` (416), `TStream.ReadAnsiString` (417)

4.68.23 TStream.ReadAnsiString

Synopsis: Read an ansistring from the stream and return its value.

Declaration: `function ReadAnsiString : string`

Visibility: `public`

Description: `ReadAnsiString` reads an ansistring from the stream and returns its value. This is a utility function which simply calls the read function several times. The Ansistring should be stored as 4 bytes (a DWord) representing the length of the string, and then the string value itself. The `WriteAnsiString` (418) function writes an ansistring in such a format.

Errors: If the `AnsiString` cannot be read, an `EStreamError` (267) exception will be raised.

See also: `TStream.Read` (410), `TStream.WriteAnsiString` (418), `TStream.ReadByte` (415), `TStream.ReadWord` (416), `TStream.ReadDWord` (416)

4.68.24 TStream.WriteByte

Synopsis: Write a byte to the stream.

Declaration: `procedure WriteByte(b: Byte)`

Visibility: `public`

Description: `WriteByte` writes the byte `B` to the stream. This is a utility function which simply calls the `Write` (411) function. The byte can be read from the stream using the `ReadByte` (415) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadByte` (415), `TStream.WriteWord` (417), `TStream.WriteDWord` (417), `TStream.WriteAnsiString` (418)

4.68.25 TStream.WriteWord

Synopsis: Write a word to the stream.

Declaration: `procedure WriteWord(w: Word)`

Visibility: `public`

Description: `WriteWord` writes the word `W` (i.e. 2 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The word can be read from the stream using the `ReadWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadWord` (416), `TStream.WriteByte` (417), `TStream.WriteDWord` (417), `TStream.WriteAnsiString` (418)

4.68.26 TStream.WriteDWord

Synopsis: Write a DWord to the stream.

Declaration: `procedure WriteDWord(d: Cardinal)`

Visibility: `public`

Description: `WriteDWord` writes the `DWord D` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The `DWord` can be read from the stream using the `ReadDWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadDWord` (416), `TStream.WriteByte` (417), `TStream.WriteWord` (417), `TStream.WriteString` (418)

4.68.27 TStream.WriteQWord

Synopsis: Write a `QWord` value to the stream

Declaration: `procedure WriteQWord(q: QWord)`

Visibility: `public`

Description: `WriteQWord` writes the word `W` (i.e. 8 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The word can be read from the stream using the `ReadQWord` (416) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadByte` (415), `TStream.WriteWord` (417), `TStream.WriteDWord` (417), `TStream.WriteString` (418)

4.68.28 TStream.WriteString

Synopsis: Write an ansistring to the stream.

Declaration: `procedure WriteAnsiString(const S: string)`

Visibility: `public`

Description: `WriteAnsiString` writes the `AnsiString S` (i.e. 4 bytes) to the stream. This is a utility function which simply calls the `Write` (411) function. The ansistring is written as a 4 byte length specifier, followed by the ansistring's content. The ansistring can be read from the stream using the `ReadAnsiString` (417) function.

Errors: If an error occurs when attempting to write, an `EStreamError` (267) exception will be raised.

See also: `TStream.Write` (411), `TStream.ReadAnsiString` (417), `TStream.WriteByte` (417), `TStream.WriteWord` (417), `TStream.WriteDWord` (417)

4.68.29 TStream.Position

Synopsis: The current position in the stream.

Declaration: `Property Position : Int64`

Visibility: `public`

Access: `Read, Write`

Description: `Position` can be read to determine the current position in the stream. It can be written to set the (absolute) position in the stream. The position is zero-based, so to set the position at the beginning of the stream, the position must be set to zero.

Remark: Not all `TStream` descendants support setting the position in the stream, so this should be used with care.

Errors: Some descendants may raise an `EStreamError` (267) exception if they do not support setting the stream position.

See also: `TStream.Size` (419), `TStream.Seek` (411)

4.68.30 TStream.Size

Synopsis: The current size of the stream.

Declaration: `Property Size : Int64`

Visibility: `public`

Access: `Read,Write`

Description: `Size` can be read to determine the stream size or to set the stream size.

Remark: Not all descendants of `TStream` support getting or setting the stream size; they may raise an exception if the `Size` property is read or set.

See also: `TStream.Position` (418), `TStream.Seek` (411)

4.69 TStreamAdapter

4.69.1 Description

Implements `IStream` for `TStream` (409) descendants

4.69.2 Interfaces overview

Page	Interfaces	Description
1756	<code>IStream</code>	COM stream abstraction

4.69.3 Method overview

Page	Method	Description
423	<code>Clone</code>	Clone the stream
422	<code>Commit</code>	Commit data to the stream
421	<code>CopyTo</code>	Copy data to destination stream
420	<code>Create</code>	Create a new instance of <code>TStreamAdapter</code>
420	<code>Destroy</code>	Free the <code>TStreamAdapter</code> instance
422	<code>LockRegion</code>	Lock a region of the stream
420	<code>Read</code>	Read from the stream.
422	<code>Revert</code>	Revert operations on the stream
421	<code>Seek</code>	Set the stream position
421	<code>SetSize</code>	Set the stream size
423	<code>Stat</code>	Return statistical data about the stream
422	<code>UnlockRegion</code>	Unlock a region of the stream
420	<code>Write</code>	Write to the stream

4.69.4 Property overview

Page	Properties	Access	Description
423	Stream	r	Stream on which adaptor works
423	StreamOwnership	rw	Determines what happens with the stream when the adaptor is freed

4.69.5 TStreamAdapter.Create

Synopsis: Create a new instance of `TStreamAdapter`

Declaration: constructor `Create(Stream: TStream; Ownership: TStreamOwnership)`

Visibility: public

Description: `Create` creates a new instance of `TStreamAdapter`. It initializes `TStreamAdapter.Stream` ([423](#)) with `Stream` and initializes `StreamOwnership` ([423](#)) with `Ownership`.

`TStreamAdapter` is an abstract class: descendants must be created that implement the actual functionality.

See also: `StreamOwnership` ([423](#)), `TStreamAdapter.Stream` ([423](#))

4.69.6 TStreamAdapter.Destroy

Synopsis: Free the `TStreamAdapter` instance

Declaration: destructor `Destroy`; Override

Visibility: public

Description: Explicitly free the `TStreamAdapter` instance. Normally, this is done automatically if a reference to the `IStream` interface is freed.

4.69.7 TStreamAdapter.Read

Synopsis: Read from the stream.

Declaration: function `Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Read` implements `#rtl.types.ISequentialStream.Read` ([1755](#)) by reading from the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Read` ([1755](#))

4.69.8 TStreamAdapter.Write

Synopsis: Write to the stream

Declaration: function `Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`
; Virtual

Visibility: public

Description: `Write` implements `#rtl.types.ISequentialStream.Write` (1756) by writing to the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.ISequentialStream.Write` (1756)

4.69.9 TStreamAdapter.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: LargeUInt; dwOrigin: LongInt;
out libNewPosition: LargeUInt) : HRESULT; Virtual`

Visibility: public

Description: `Seek` implements `#rtl.types.IStream.Seek` (1756) by setting the position of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Seek` (1756)

4.69.10 TStreamAdapter.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUInt) : HRESULT; Virtual`

Visibility: public

Description: `SetSize` implements `#rtl.types.IStream.SetSize` (1756) by setting the size of the stream specified at creation.

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.SetSize` (1756)

4.69.11 TStreamAdapter.CopyTo

Synopsis: Copy data to destination stream

Declaration: `function CopyTo(stm: IStream; cb: LargeUInt; out cbRead: LargeUInt;
out cbWritten: LargeUInt) : HRESULT; Virtual`

Visibility: public

Description: `CopyTo` implements `#rtl.types.IStream.CopyTo` (1757).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

4.69.12 TStreamAdapter.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `Commit` implements `#rtl.types.IStream.Commit` ([1757](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Commit` ([1757](#))

4.69.13 TStreamAdapter.Revert

Synopsis: Revert operations on the stream

Declaration: `function Revert : HRESULT; Virtual`

Visibility: public

Description: `Revert` implements `#rtl.types.IStream.Revert` ([1757](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Revert` ([1757](#))

4.69.14 TStreamAdapter.LockRegion

Synopsis: Lock a region of the stream

Declaration: `function LockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `LockRegion` implements `#rtl.types.IStream.LockRegion` ([1757](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.LockRegion` ([1757](#))

4.69.15 TStreamAdapter.UnlockRegion

Synopsis: Unlock a region of the stream

Declaration: `function UnlockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: LongInt) : HRESULT; Virtual`

Visibility: public

Description: `UnLockRegion` implements `#rtl.types.IStream.UnLockRegion` ([1758](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.UnLockRegion` ([1758](#))

4.69.16 TStreamAdapter.Stat

Synopsis: Return statistical data about the stream

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: LongInt) : HRESULT
; Virtual`

Visibility: public

Description: `Stat` implements `#rtl.types.IStream.Stat` ([1758](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Stat` ([1758](#))

4.69.17 TStreamAdapter.Clone

Synopsis: Clone the stream

Declaration: `function Clone(out stm: IStream) : HRESULT; Virtual`

Visibility: public

Description: `Clone` implements `#rtl.types.IStream.Clone` ([1758](#)).

Errors: This function must be overridden and will raise a `runerror 217` when called directly.

See also: `#rtl.types.IStream.Clone` ([1758](#))

4.69.18 TStreamAdapter.Stream

Synopsis: Stream on which adaptor works

Declaration: `Property Stream : TStream`

Visibility: public

Access: Read

Description: This is the stream on which the adaptor works. It was specified at creation.

4.69.19 TStreamAdapter.StreamOwnership

Synopsis: Determines what happens with the stream when the adaptor is freed

Declaration: `Property StreamOwnership : TStreamOwnership`

Visibility: public

Access: Read, Write

Description: `StreamOwnership` determines what happens when the adaptor

4.70 TStringList

4.70.1 Description

`TStringList` is a descendant class of `TStrings` (429) that implements all of the abstract methods introduced there. It also introduces some additional methods:

- Sort the list, or keep the list sorted at all times
- Special handling of duplicates in sorted lists
- Notification of changes in the list

See also: `TStrings` (429), `TStringList.Duplicates` (427), `TStringList.Sorted` (427)

4.70.2 Method overview

Page	Method	Description
425	Add	Implements the <code>TStrings.Add</code> (431) function.
425	Clear	Implements the <code>TStrings.Clear</code> (433) function.
427	CustomSort	Sort the stringlist using a custom sort algorithm
425	Delete	Implements the <code>TStrings.Delete</code> (434) function.
424	Destroy	Destroys the stringlist.
425	Exchange	Implements the <code>TStrings.Exchange</code> (435) function.
426	Find	Locates the index for a given string in sorted lists.
426	IndexOf	Overrides the <code>TStrings.IndexOf</code> (435) property.
426	Insert	Overrides the <code>TStrings.Insert</code> (436) method.
426	Sort	Sorts the strings in the list.

4.70.3 Property overview

Page	Properties	Access	Description
428	CaseSensitive	rw	Indicates whether comparing strings happens in a case sensitive manner.
427	Duplicates	rw	Describes the behaviour of a sorted list with respect to duplicate strings.
428	OnChange	rw	Event triggered after the list was modified.
428	OnChanging	rw	Event triggered when the list is about to be modified.
429	OwnsObjects	rw	Determines whether the stringlist owns it's objects or not.
427	Sorted	rw	Determines whether the list is sorted or not.
429	SortStyle	rw	Sort style for strings

4.70.4 TStringList.Destroy

Synopsis: Destroys the stringlist.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears the stringlist, release all memory allocated for the storage of the strings, and then calls the inherited `destroy` method.

Remark: Any objects associated to strings in the list will *not* be destroyed; it is the responsibility of the caller to destroy all objects associated with strings in the list.

4.70.5 TStringList.Add

Synopsis: Implements the TStrings.Add (431) function.

Declaration: `function Add(const S: string) : Integer; Override`

Visibility: public

Description: Add will add S to the list. If the list is sorted and the string S is already present in the list and TStringList.Duplicates (427) is dupError then an EStringListError (268) exception is raised. If Duplicates is set to dupIgnore then the return value is the index of the previous entry.

If the list is sorted, new strings will not necessarily be added to the end of the list, rather they will be inserted at their alphabetical position.

Errors: If the list is sorted and the string S is already present in the list and TStringList.Duplicates (427) is dupError then an EStringListError (268) exception is raised.

See also: TStringList.Insert (426), TStringList.Duplicates (427)

4.70.6 TStringList.Clear

Synopsis: Implements the TStrings.Clear (433) function.

Declaration: `procedure Clear; Override`

Visibility: public

Description: Implements the TStrings.Clear (433) function.

4.70.7 TStringList.Delete

Synopsis: Implements the TStrings.Delete (434) function.

Declaration: `procedure Delete(Index: Integer); Override`

Visibility: public

Description: Implements the TStrings.Delete (434) function.

4.70.8 TStringList.Exchange

Synopsis: Implements the TStrings.Exchange (435) function.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Override`

Visibility: public

Description: Exchange will exchange two items in the list as described in TStrings.Exchange (435).

Remark: Exchange will not check whether the list is sorted or not; if Exchange is called on a sorted list and the strings are not identical, the sort order of the list will be destroyed.

See also: TStringList.Sorted (427), TStrings.Exchange (435)

4.70.9 TStringList.Find

Synopsis: Locates the index for a given string in sorted lists.

Declaration: `function Find(const S: string; out Index: Integer) : Boolean; Virtual`

Visibility: public

Description: `Find` returns `True` if the string `S` is present in the list. Upon exit, the `Index` parameter will contain the position of the string in the list. If the string is not found, the function will return `False` and `Index` will contain the position where the string will be inserted if it is added to the list.

Remark:

1. Use this method only on sorted lists. For unsorted lists, use `TStringList.IndexOf` (426) instead.
2. `Find` uses a binary search method to locate the string

4.70.10 TStringList.IndexOf

Synopsis: Overrides the `TStrings.IndexOf` (435) property.

Declaration: `function IndexOf(const S: string) : Integer; Override`

Visibility: public

Description: `IndexOf` overrides the ancestor method `TStrings.indexOf` (435). It tries to optimize the search by executing a binary search if the list is sorted. The function returns the position of `S` if it is found in the list, or -1 if the string is not found in the list.

See also: `TStrings.IndexOf` (435), `TStringList.Find` (426)

4.70.11 TStringList.Insert

Synopsis: Overrides the `TStrings.Insert` (436) method.

Declaration: `procedure Insert(Index: Integer; const S: string); Override`

Visibility: public

Description: `Insert` will insert the string `S` at position `Index` in the list. If the list is sorted, an `EStringListError` (268) exception will be raised instead. `Index` is a zero-based position.

Errors: If `Index` contains an invalid value (less than zero or larger than `Count`, or the list is sorted, an `EStringListError` (268) exception will be raised.

See also: `TStringList.Add` (425), `TStrings.Insert` (436), `TStrings.InsertObject` (437)

4.70.12 TStringList.Sort

Synopsis: Sorts the strings in the list.

Declaration: `procedure Sort; Virtual`

Visibility: public

Description: `Sort` will sort the strings in the list using the quicksort algorithm. If the list has its `TStringList.Sorted` (427) property set to `True` then nothing will be done.

See also: `TStringList.Sorted` (427)

4.70.13 TStringList.CustomSort

Synopsis: Sort the stringlist using a custom sort algorithm

Declaration: `procedure CustomSort (CompareFn: TStringListSortCompare); Virtual`

Visibility: public

Description: `CustomSort` sorts the stringlist with a custom comparison function. The function should compare 2 elements in the list, and return a negative number if the first item is before the second. It should return 0 if the elements are equal, and a positive result indicates that the second elements should be before the first.

See also: `TStringList.Sorted` (427), `TStringList.Sort` (426)

4.70.14 TStringList.Duplicates

Synopsis: Describes the behaviour of a sorted list with respect to duplicate strings.

Declaration: `Property Duplicates : TDuplicates`

Visibility: public

Access: Read,Write

Description: `Duplicates` describes what to do in case a duplicate value is added to the list:

Table 4.29:

<code>dupIgnore</code>	Duplicate values will not be added to the list, but no error will be triggered.
<code>dupError</code>	If an attempt is made to add a duplicate value to the list, an <code>EStringListError</code> (268) exception is raised.
<code>dupAccept</code>	Duplicate values can be added to the list.

If the stringlist is not sorted, the `Duplicates` setting is ignored.

4.70.15 TStringList.Sorted

Synopsis: Determines whether the list is sorted or not.

Declaration: `Property Sorted : Boolean`

Visibility: public

Access: Read,Write

Description: `Sorted` can be set to `True` in order to cause the list of strings to be sorted. Further additions to the list will be inserted at the correct position so the list remains sorted at all times. Setting the property to `False` has no immediate effect, but will allow strings to be inserted at any position.

Remark:

1. When `Sorted` is `True`, `TStringList.Insert` (426) cannot be used. For sorted lists, `TStringList.Add` (425) should be used instead.
2. If `Sorted` is `True`, the `TStringList.Duplicates` (427) setting has effect. This setting is ignored when `Sorted` is `False`.

See also: `TStringList.Sort` (426), `TStringList.Duplicates` (427), `TStringList.Add` (425), `TstringList.Insert` (426)

4.70.16 TStringList.CaseSensitive

Synopsis: Indicates whether comparing strings happens in a case sensitive manner.

Declaration: `Property CaseSensitive : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `CaseSensitive` indicates how string values are compared: When `True` this happens case sensitively, and when `False`, case must match.

This property influences [IndexOf \(435\)](#), [Find \(426\)](#), [IndexOfName \(436\)](#) and [Sort \(426\)](#).

See also: [IndexOf \(435\)](#), [Find \(426\)](#), [IndexOfName \(436\)](#), [Sort \(426\)](#)

4.70.17 TStringList.OnChange

Synopsis: Event triggered after the list was modified.

Declaration: `Property OnChange : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChange` can be assigned to respond to changes that have occurred in the list. The handler is called whenever strings are added, moved, modified or deleted from the list.

The `OnChange` event is triggered after the modification took place. When the modification is about to happen, an `TStringList.OnChanging (428)` event occurs.

See also: `TStringList.OnChanging (428)`

4.70.18 TStringList.OnChanging

Synopsis: Event triggered when the list is about to be modified.

Declaration: `Property OnChanging : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnChanging` can be assigned to respond to changes that will occurred in the list. The handler is called whenever strings will be added, moved, modified or deleted from the list.

The `Onchanging` event is triggered before the modification will take place. When the modification has happened, an `TStringList.OnChange (428)` event occurs.

See also: `TStringList.OnChange (428)`

4.70.19 TStringList.OwnsObjects

Synopsis: Determines whether the stringlist owns it's objects or not.

Declaration: `Property OwnsObjects : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `OwnsObjects` can be set to `true` to let the stringlist instance own the objects in the list: if an element is removed from the list, the associated object (if there is any) will be freed as well. The same is true if the list is cleared or destroyed.

See also: `TStrings.Objects` ([444](#))

4.70.20 TStringList.SortStyle

Synopsis: Sort style for strings

Declaration: `Property SortStyle : TStringsSortStyle`

Visibility: `public`

Access: `Read,Write`

Description: `SortStyle` sets the sort style for the `TStringList` instance. Setting it to `sslAuto` will keep the list sorted automatically at all times.

`Find` ([426](#)) (and hence `IndexOf` ([435](#))) will use a binary search if `SortStyle` differs from `sslNone`. if `SortStyle` is `sslNone`, then it will raise an exception.

See also: `TStringsSortStyle` ([246](#)), `TStrings.Sorted` ([429](#))

4.71 TStrings

4.71.1 Description

`TStrings` implements an abstract class to manage an array of strings. It introduces methods to set and retrieve strings in the array, searching for a particular string, concatenating the strings and so on. It also allows an arbitrary object to be associated with each string.

It also introduces methods to manage a series of `name=value` settings, as found in many configuration files.

An instance of `TStrings` is never created directly, instead a descendant class such as `TStringList` ([424](#)) should be created. This is because `TStrings` is an abstract class which does not implement all methods; `TStrings` also doesn't store any strings, this is the functionality introduced in descendants such as `TStringList` ([424](#)).

`TStrings` implements the `IFPObserved` ([269](#)) interface: when the stringlist is changed, a `ooChanged` notification is sent to all observers.

See also: `TStringList` ([424](#)), `IFPObserved` ([269](#))

4.71.2 Method overview

Page	Method	Description
431	Add	Add a string to the list
431	AddObject	Add a string and associated object to the list.
432	AddStrings	Add contents of another stringlist to this list.
432	AddText	Add text to the string list.
432	Append	Add a string to the list.
433	Assign	Assign the contents of another stringlist to this one.
433	BeginUpdate	Mark the beginning of an update batch.
433	Clear	Removes all strings and associated objects from the list.
434	Delete	Delete a string from the list.
431	Destroy	Frees all strings and objects, and removes the list from memory.
434	EndUpdate	Mark the end of an update batch.
434	Equals	Compares the contents of two stringlists.
435	Exchange	Exchanges two strings in the list.
439	ExtractName	Extract the name part of a string
435	GetEnumerator	Create an <code>IEnumerator</code> instance
439	GetNameValue	Return both name and value of a name,value pair based on it's index.
435	GetText	Returns the contents as a <code>PChar</code>
435	IndexOf	Find a string in the list and return its position.
436	IndexOfName	Finds the index of a name in the name-value pairs.
436	IndexOfObject	Finds an object in the list and returns its index.
436	Insert	Insert a string in the list.
437	InsertObject	Insert a string and associated object in the list.
437	LoadFromFile	Load the contents of a file as a series of strings.
437	LoadFromStream	Load the contents of a stream as a series of strings.
437	Move	Move a string from one place in the list to another.
438	SaveToFile	Save the contents of the list to a file.
438	SaveToStream	Save the contents of the string to a stream.
439	SetText	Set the contents of the list from a <code>PChar</code> .

4.71.3 Property overview

Page	Properties	Access	Description
442	Capacity	rw	Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.
442	CommaText	rw	Contents of the list as a comma-separated string.
443	Count	r	Number of strings in the list.
440	DelimitedText	rw	Get or set all strings in the list in a delimited form.
440	Delimiter	rw	Delimiter character used in DelimitedText (440).
440	LineBreak	rw	LineBreak character to use
443	Names	r	Name parts of the name-value pairs in the list.
441	NameValueSeparator	rw	Value of the character used to separate name,value pairs
444	Objects	rw	Indexed access to the objects associated with the strings in the list.
441	QuoteChar	rw	Quote character used in DelimitedText (440).
445	SkipLastLineBreak	rw	Do not add a linebreak to the last item
441	StrictDelimiter	rw	Should only the delimiter character be considered a delimiter
444	Strings	rw	Indexed access to the strings in the list.
445	StringsAdapter	rw	Not implemented in Free Pascal.
445	Text	rw	Contents of the list as one big string.
439	TextLineBreakStyle	rw	Determines which line breaks to use in the Text (445) property
442	ValueFromIndex	rw	Return the value part of a string based on it's index.
444	Values	rw	Value parts of the name-value pairs in the list.

4.71.4 TStrings.Destroy

Synopsis: Frees all strings and objects, and removes the list from memory.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` is the destructor of `TStrings` it does nothing except calling the inherited destructor.

4.71.5 TStrings.Add

Synopsis: Add a string to the list

Declaration: `function Add(const S: string) : Integer; Virtual; Overload`
`function Add(const Fmt: string; const Args: Array of const) : Integer`
`; Overload`

Visibility: `public`

Description: `Add` adds `S` at the end of the list and returns the index of `S` in the list (which should equal `TStrings.Count` ([443](#)))

See also: `TStrings.Objects` ([444](#)), `TStrings.AddObject` ([431](#)), `TStrings.Insert` ([436](#)), `TStrings.Delete` ([434](#)), `TStrings.Strings` ([444](#)), `TStrings.Count` ([443](#))

4.71.6 TStrings.AddObject

Synopsis: Add a string and associated object to the list.

Declaration: `function AddObject(const S: string; AObject: TObject) : Integer
; Virtual; Overload
function AddObject(const Fmt: string; Args: Array of const;
AObject: TObject) : Integer; Overload`

Visibility: public

Description: `AddObject` adds `S` to the list of strings, and associates `AObject` with it. It returns the index of `S`.

Remark: An object added to the list is not automatically destroyed by the list of the list is destroyed or the string it is associated with is deleted. It is the responsibility of the application to destroy any objects associated with strings.

See also: `TStrings.Add` (431), `TStrings.Strings` (444), `TStrings.Objects` (444), `TStrings.InsertObject` (437)

4.71.7 TStrings.Append

Synopsis: Add a string to the list.

Declaration: `procedure Append(const S: string)`

Visibility: public

Description: `Append` does the same as `TStrings.Add` (431), only it does not return the index of the inserted string.

See also: `TStrings.Add` (431)

4.71.8 TStrings.AddStrings

Synopsis: Add contents of another stringlist to this list.

Declaration: `procedure AddStrings(TheStrings: TStrings); Virtual; Overload
procedure AddStrings(TheStrings: TStrings; ClearFirst: Boolean)
; Overload
procedure AddStrings(const TheStrings: Array of string); Virtual
; Overload
procedure AddStrings(const TheStrings: Array of string;
ClearFirst: Boolean); Overload`

Visibility: public

Description: `AddStrings` adds the contents of `TheStrings` to the stringlist. Any associated objects are added as well.

See also: `TStrings.Add` (431), `TStrings.Assign` (433)

4.71.9 TStrings.AddText

Synopsis: Add text to the string list.

Declaration: `procedure AddText(const S: string); Virtual`

Visibility: public

Description: `AddText` adds `S` to the strings. It is identical in function to setting `Text` (231) but does not clear the list of strings first: `S` is split into lines, and each line is added to the list.

See also: `TString.Text` (231)

4.71.10 TStrings.Assign

Synopsis: Assign the contents of another stringlist to this one.

Declaration: `procedure Assign(Source: TPersistent); Override`

Visibility: `public`

Description: `Assign` replaces the contents of the stringlist with the contents of `Source` if `Source` is also of type `TStrings`. Any associated objects are copied as well.

See also: `TStrings.Add` (431), `TStrings.AddStrings` (432), `TPersistent.Assign` (391)

4.71.11 TStrings.BeginUpdate

Synopsis: Mark the beginning of an update batch.

Declaration: `procedure BeginUpdate`

Visibility: `public`

Description: `BeginUpdate` increases the update count by one. It is advisable to call `BeginUpdate` before lengthy operations on the stringlist. At the end of these operation, `TStrings.EndUpdate` (434) should be called to mark the end of the operation. Descendant classes may use this information to perform optimizations. e.g. updating the screen only once after many strings were added to the list.

All `TStrings` methods that modify the string list call `BeginUpdate` before the actual operation, and call `endUpdate` when the operation is finished. Descendant classes should also call these methods when modifying the string list.

Remark: Always put the corresponding call to `TStrings.EndUpdate` (434) in the context of a `Finally` block, to ensure that the update count is always decreased at the end of the operation, even if an exception occurred:

```
With MyStrings do
  try
    BeginUpdate;
    // Some lengthy operation.
  finally
    EndUpdate
  end;
```

See also: `TStrings.EndUpdate` (434)

4.71.12 TStrings.Clear

Synopsis: Removes all strings and associated objects from the list.

Declaration: `procedure Clear; Virtual; Abstract`

Visibility: `public`

Description: `Clear` will remove all strings and their associated objects from the list. After a call to `clear`, `TStrings.Count` (443) is zero.

Since it is an abstract method, `TStrings` itself does not implement `Clear`. Descendant classes such as `TStringList` (424) implement this method.

See also: `TStrings.Objects` (444), `TStrings.Strings` (444), `TStrings.Delete` (434), `TStrings.Count` (443)

4.71.13 TStrings.Delete

Synopsis: Delete a string from the list.

Declaration: `procedure Delete(Index: Integer); Virtual; Abstract`

Visibility: public

Description: `Delete` deletes the string at position `Index` from the list. The associated object is also removed from the list, but not destroyed. `Index` is zero-based, and should be in the range 0 to `Count-1`.

Since it is an abstract method, `TStrings` itself does not implement `Delete`. Descendant classes such as `TStringList` (424) implement this method.

Errors: If `Index` is not in the allowed range, an `EStringListError` (268) is raised.

See also: `TStrings.Insert` (436), `TStrings.Objects` (444), `TStrings.Strings` (444), `TStrings.Clear` (433)

4.71.14 TStrings.EndUpdate

Synopsis: Mark the end of an update batch.

Declaration: `procedure EndUpdate`

Visibility: public

Description: `EndUpdate` should be called at the end of a lengthy operation on the stringlist, but only if there was a call to `BeginUpdate` before the operation was started. It is best to put the call to `EndUpdate` in the context of a `Finally` block, so it will be called even if an exception occurs.

For more information, see `TStrings.BeginUpdate` (433).

`TStrings` implements the `IFPObserved` (269) interface: when `EndUpdate` is called, a `ooChanged` notification is sent to all observers.

See also: `TStrings.BeginUpdate` (433), `IFPObserved` (269)

4.71.15 TStrings.Equals

Synopsis: Compares the contents of two stringlists.

Declaration: `function Equals(Obj: TObject) : Boolean; Override; Overload`
`function Equals(TheStrings: TStrings) : Boolean; Overload`

Visibility: public

Description: `Equals` compares the contents of the stringlist with the contents of `TheStrings`. If the contents match, i.e. the stringlist contain an equal amount of strings, and all strings match, then `True` is returned. If the number of strings in the lists is unequal, or they contain one or more different strings, `False` is returned.

Remark:

- 1.The strings are compared case-insensitively.
- 2.The associated objects are not compared

See also: `TStrings.Objects` (444), `TStrings.Strings` (444), `TStrings.Count` (443), `TStrings.Assign` (433)

4.71.16 TStrings.Exchange

Synopsis: Exchanges two strings in the list.

Declaration: `procedure Exchange(Index1: Integer; Index2: Integer); Virtual`

Visibility: `public`

Description: `Exchange` exchanges the strings at positions `Index1` and `Index2`. The associated objects are also exchanged.

Both indexes must be in the range of valid indexes, i.e. must have a value between 0 and `Count-1`.

Errors: If either `Index1` or `Index2` is not in the range of valid indexes, an `EStringListError` (268) exception is raised.

See also: `TStrings.Move` (437), `TStrings.Strings` (444), `TStrings.Count` (443)

4.71.17 TStrings.GetEnumerator

Synopsis: Create an `IEnumerator` instance

Declaration: `function GetEnumerator : TStringsEnumerator`

Visibility: `public`

Description: `GetEnumerator` is the implementation of the `IEnumerable` (1425) interface for `TStrings`. It creates a `TStringsEnumerator` (446) instance and returns its `IEnumerator` (1426) interface.

See also: `TStringsEnumerator` (446), `IEnumerator` (1426), `IEnumerable` (1425)

4.71.18 TStrings.GetText

Synopsis: Returns the contents as a `PChar`

Declaration: `function GetText : PChar; Virtual`

Visibility: `public`

Description: `GetText` allocates a memory buffer and compies the contents of the stringlist to this buffer as a series of strings, separated by an end-of-line marker. The buffer is zero terminated.

Remark: The caller is responsible for freeing the returned memory buffer.

4.71.19 TStrings.IndexOf

Synopsis: Find a string in the list and return its position.

Declaration: `function IndexOf(const S: string) : Integer; Virtual`

Visibility: `public`

Description: `IndexOf` searches the list for `S`. The search is case-insensitive. If a matching entry is found, its position is returned. if no matching string is found, `-1` is returned.

Remark:

1. Only the first occurrence of the string is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOfObject` (436), `TStrings.IndexOfName` (436), `TStrings.Strings` (444)

4.71.20 TStrings.IndexOfName

Synopsis: Finds the index of a name in the name-value pairs.

Declaration: `function IndexOfName(const Name: string) : Integer; Virtual`

Visibility: public

Description: `IndexOfName` searches in the list of strings for a name-value pair with name part `Name`. If such a pair is found, it returns the index of the pair in the stringlist. If no such pair is found, the function returns `-1`. The search is done case-insensitive.

Remark:

1. Only the first occurrence of a matching name-value pair is returned.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

See also: `TStrings.IndexOf` (435), `TStrings.IndexOfObject` (436), `TStrings.Strings` (444)

4.71.21 TStrings.IndexOfObject

Synopsis: Finds an object in the list and returns its index.

Declaration: `function IndexOfObject(AObject: TObject) : Integer; Virtual`

Visibility: public

Description: `IndexOfObject` searches through the list of strings till it find a string associated with `AObject`, and returns the index of this string. If no such string is found, `-1` is returned.

Remark:

1. Only the first occurrence of a string with associated object `AObject` is returned; if more strings in the list can be associated with `AObject`, they will not be found by this routine.
2. The returned position is zero-based, i.e. 0 indicates the first string in the list.

4.71.22 TStrings.Insert

Synopsis: Insert a string in the list.

Declaration: `procedure Insert(Index: Integer; const S: string); Virtual; Abstract`

Visibility: public

Description: `Insert` inserts the string `S` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Remark:

1. All methods that add strings to the list use `Insert` to add a string to the list.
2. If the string has an associated object, use `TStrings.InsertObject` (437) instead.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (268) exception is raised.

See also: `TStrings.Add` (431), `TStrings.InsertObject` (437), `TStrings.Append` (432), `TStrings.Delete` (434)

4.71.23 TStrings.InsertObject

Synopsis: Insert a string and associated object in the list.

Declaration: `procedure InsertObject(Index: Integer; const S: string;
AObject: TObject)`

Visibility: public

Description: `InsertObject` inserts the string `S` and its associated object `AObject` at position `Index` in the list. `Index` is a zero-based position, and can have values from 0 to `Count`. If `Index` equals `Count` then the string is appended to the list.

Errors: If `Index` is less than zero or larger than `Count` then an `EStringListError` (268) exception is raised.

See also: `TStrings.Insert` (436), `TStrings.AddObject` (431), `TStrings.Append` (432), `TStrings.Delete` (434)

4.71.24 TStrings.LoadFromFile

Synopsis: Load the contents of a file as a series of strings.

Declaration: `procedure LoadFromFile(const FileName: string); Virtual`

Visibility: public

Description: `LoadFromFile` loads the contents of a file into the stringlist. Each line in the file (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

`LoadFromFile` simply creates a file stream (350) with the given filename, and then executes `TStrings.LoadFromStream` (437); after that the file stream object is destroyed again.

See also: `TStrings.LoadFromStream` (437), `TStrings.SaveToFile` (438), `Tstrings.SaveToStream` (438)

4.71.25 TStrings.LoadFromStream

Synopsis: Load the contents of a stream as a series of strings.

Declaration: `procedure LoadFromStream(Stream: TStream); Virtual`

Visibility: public

Description: `LoadFromStream` loads the contents of `Stream` into the stringlist. Each line in the stream (as marked by the end-of-line marker of the particular OS the application runs on) becomes one string in the stringlist. This action replaces the contents of the stringlist, it does not append the strings to the current content.

See also: `TStrings.LoadFromFile` (437), `TStrings.SaveToFile` (438), `Tstrings.SaveToStream` (438)

4.71.26 TStrings.Move

Synopsis: Move a string from one place in the list to another.

Declaration: `procedure Move(CurIndex: Integer; NewIndex: Integer); Virtual`

Visibility: public

Description: `Move` moves the string at position `CurIndex` so it has position `NewIndex` after the move operation. The object associated to the string is also moved. `CurIndex` and `NewIndex` should be in the range of 0 to `Count-1`.

Remark: `NewIndex` is *not* the position in the stringlist before the move operation starts. The move operation

- 1.removes the string from position `CurIndex`
- 2.inserts the string at position `NewIndex`

This may not lead to the desired result if `NewIndex` is bigger than `CurIndex`. Consider the following example:

```
With MyStrings do
begin
  Clear;
  Add('String 0');
  Add('String 1');
  Add('String 2');
  Add('String 3');
  Add('String 4');
  Move(1,3);
end;
```

After the `Move` operation has completed, 'String 1' will be between 'String 3' and 'String 4'.

Errors: If either `CurIndex` or `NewIndex` is outside the allowed range, an `EStringListError` (268) is raised.

See also: `TStrings.Exchange` (435)

4.71.27 TStrings.SaveToFile

Synopsis: Save the contents of the list to a file.

Declaration: `procedure SaveToFile(const FileName: string); Virtual`

Visibility: `public`

Description: `SaveToFile` saves the contents of the stringlist to the file with name `FileName`. It writes the strings to the file, separated by end-of-line markers, so each line in the file will contain 1 string from the stringlist.

`SaveToFile` creates a file stream (350) with name `FileName`, calls `TStrings.SaveToStream` (438) and then destroys the file stream object.

Errors: An `EStreamError` (267) exception can be raised if the file `FileName` cannot be opened, or if it cannot be written to.

See also: `TStrings.SaveToStream` (438), `Tstrings.LoadFromStream` (437), `TStrings.LoadFromFile` (437)

4.71.28 TStrings.SaveToStream

Synopsis: Save the contents of the string to a stream.

Declaration: `procedure SaveToStream(Stream: TStream); Virtual`

Visibility: `public`

Description: `SaveToStream` saves the contents of the stringlist to `Stream`. It writes the strings to the stream, separated by end-of-line markers, so each 'line' in the stream will contain 1 string from the stringlist.

Errors: An `EStreamError` (267) exception can be raised if the stream cannot be written to.

See also: `TStrings.SaveToFile` (438), `Tstrings.LoadFromStream` (437), `TStrings.LoadFromFile` (437)

4.71.29 TStrings.SetText

Synopsis: Set the contents of the list from a `PChar`.

Declaration: `procedure SetText(TheText: PChar); Virtual`

Visibility: `public`

Description: `SetText` parses the contents of `TheText` and fills the stringlist based on the contents. It regards `TheText` as a series of strings, separated by end-of-line markers. Each of these strings is added to the stringlist.

See also: `TStrings.Text` (445)

4.71.30 TStrings.GetNameValue

Synopsis: Return both name and value of a name,value pair based on it's index.

Declaration: `procedure GetNameValue(Index: Integer; out AName: string;
out AValue: string)`

Visibility: `public`

Description: Return both name and value of a name,value pair based on it's index.

4.71.31 TStrings.ExtractName

Synopsis: Extract the name part of a string

Declaration: `function ExtractName(const S: string) : string`

Visibility: `public`

Description: `ExtractName` returns the name part (the part before the `NameValueSeparator` (441) character) of the string. If the character is not present, an empty string is returned. The resulting string is not trimmed, it can end or start with spaces.

See also: `NameValueSeparator` (441)

4.71.32 TStrings.TextLineBreakStyle

Synopsis: Determines which line breaks to use in the `Text` (445) property

Declaration: `Property TextLineBreakStyle : TTextLineBreakStyle`

Visibility: `public`

Access: `Read,Write`

Description: `TextLineBreakStyle` determines which linebreak style is used when constructing the `Text` property: the same rules are used as in the writing to text files:

tlbsLFLines are separated with a linefeed character #10.

tlbsCRLFLines are separated with a carriage-return/linefeed character pair: #13#10.

tlbsCRLLines are separated with a carriage-return character #13.

It has no effect when setting the text property.

See also: Text (445)

4.71.33 TStrings.Delimiter

Synopsis: Delimiter character used in DelimitedText (440).

Declaration: `Property Delimiter : Char`

Visibility: public

Access: Read,Write

Description: `Delimiter` is the delimiter character used to separate the different strings in the stringlist when they are read or set through the `DelimitedText` (440) property.

See also: `TStrings.DelimitedText` (440)

4.71.34 TStrings.DelimitedText

Synopsis: Get or set all strings in the list in a delimited form.

Declaration: `Property DelimitedText : string`

Visibility: public

Access: Read,Write

Description: `DelimitedText` returns all strings, properly quoted with `QuoteChar` (441) and separated by the `Delimiter` (440) character.

Strings are quoted if they contain a space or any character with ASCII value less than 32.

The `CommaText` (442) property is a special case of delimited text where the delimiter character is a comma and the quote character is a double quote.

If `StrictDelimiter` (441) is set to `True`, then no quoting is done (The `QuoteChar` property is disregarded completely): the returned text will contain the items in the stringlist, separated by the `Delimiter` character. When writing the `DelimitedText` property, the text will be split at all occurrences of the `Delimiter` character; however, when reading, the `QuoteChar` property will be taken into account.

See also: `TStrings.Delimiter` (440), `TStrings.Text` (445), `TStrings.QuoteChar` (441), `TStrings.CommaText` (442)

4.71.35 TStrings.LineBreak

Synopsis: LineBreak character to use

Declaration: `Property LineBreak : string`

Visibility: public

Access: Read,Write

Description: `LineBreak` is the character used to separate lines when reading or writing `TStrings.Text` (445), and it is also used when reading from file.

See also: `TStrings.Text` (445)

4.71.36 TStrings.StrictDelimiter

Synopsis: Should only the delimiter character be considered a delimiter

Declaration: `Property StrictDelimiter : Boolean`

Visibility: public

Access: Read,Write

Description: `StrictDelimiter` can be used to indicate that only the delimiter character should be considered a delimiter when setting `DelimitedText` (440): under normal circumstances, quotes and spaces are considered specially (see the `TStrings.CommaText` (442) property for more information).

When `StrictDelimiter` is set to `True` then only the `Delimiter` (440) character is considered when splitting the text in items: no quoting whatsoever is performed when writing the `DelimitedText` property. However, when reading the `DelimitedText` property, quoted strings are taken into account (so a quoted string can contain a delimiter that is treated as text instead of a delimiter).

See also: `DelimitedText` (440), `CommaText` (442), `Delimiter` (440)

4.71.37 TStrings QuoteChar

Synopsis: Quote character used in `DelimitedText` (440).

Declaration: `Property QuoteChar : Char`

Visibility: public

Access: Read,Write

Description: `QuoteChar` is the character used by the `DelimitedText` (440) property to quote strings that have a space or non-printing character in it.

4.71.38 TStrings.NameValueSeparator

Synopsis: Value of the character used to separate name,value pairs

Declaration: `Property NameValueSeparator : Char`

Visibility: public

Access: Read,Write

Description: `NameValueSeparator` is the character used to separate name,value pair. By default, this is the equal sign (=), resulting in `Name=Value` pairs.

It can be set to a colon for `Name : Value` pairs.

4.71.39 TStrings.ValueFromIndex

Synopsis: Return the value part of a string based on it's index.

Declaration: `Property ValueFromIndex[Index: Integer]: string`

Visibility: public

Access: Read,Write

Description: `ValueFromIndex` returns the value part of a string based on the string index. The value part are all characters in the string after the `NameValueSeparator` (441) character, or all characters if the `NameValueSeparator` character is not present.

4.71.40 TStrings.Capacity

Synopsis: Capacity of the list, i.e. number of strings that the list can currently hold before it tries to expand.

Declaration: `Property Capacity : Integer`

Visibility: public

Access: Read,Write

Description: `Capacity` is the number of strings that the list can hold before it tries to allocate more memory.

`TStrings` returns `TStrings.Count` (443) when read. Trying to set the capacity has no effect. Descendant classes such as `TStringList` (424) can override this property such that it actually sets the new capacity.

See also: `TStringList` (424), `TStrings.Count` (443)

4.71.41 TStrings.CommaText

Synopsis: Contents of the list as a comma-separated string.

Declaration: `Property CommaText : string`

Visibility: public

Access: Read,Write

Description: `CommaText` represents the stringlist as a single string, consisting of a comma-separated concatenation of the strings in the list. If one of the strings contains spaces, comma's or quotes it will be enclosed by double quotes. Any double quotes in a string will be doubled. For instance the following strings:

```
Comma,string
Quote"string
Space string
NormalSttring
```

is converted to

```
"Comma,string","Quote""String","Space string",NormalString
```

Conversely, when setting the `CommaText` property, the text will be parsed according to the rules outlined above, and the strings will be set accordingly. Note that spaces will in this context be regarded as string separators, unless the string as a whole is contained in double quotes. Spaces that occur next to a delimiter will be ignored. The following string:

```
"Comma,string" , "Quote"String",Space string,, NormalString
```

Will be converted to

```
Comma,String
Quote"String
Space
String
```

```
NormalString
```

This is a special case of the `TStrings.DelimitedText` (440) property where the quote character is always the double quote, and the delimiter is always the colon.

See also: `TStrings.Text` (445), `TStrings.SetText` (439)

4.71.42 TStrings.Count

Synopsis: Number of strings in the list.

Declaration: `Property Count : Integer`

Visibility: public

Access: Read

Description: `Count` is the current number of strings in the list. `TStrings` does not implement this property; descendant classes should override the property read handler to return the correct value.

Strings in the list are always uniquely identified by their `Index`; the index of a string is zero-based, i.e. it's supported range is 0 to `Count-1`. trying to access a string with an index larger than or equal to `Count` will result in an error. Code that iterates over the list in a stringlist should always take into account the zero-based character of the list index.

See also: `TStrings.Strings` (444), `TStrings.Objects` (444), `TStrings.Capacity` (442)

4.71.43 TStrings.Names

Synopsis: Name parts of the name-value pairs in the list.

Declaration: `Property Names[Index: Integer]: string`

Visibility: public

Access: Read

Description: `Names` provides indexed access to the names of the name-value pairs in the list. It returns the name part of the `Index`-th string in the list.

Remark: The index is not an index based on the number of name-value pairs in the list. It is the name part of the name-value pair a string `Index` in the list. If the string at position `Index` is not a name-value pair (i.e. does not contain the equal sign (=)), then an empty name is returned.

See also: `TStrings.Values` (444), `TStrings.IndexOfName` (436)

4.71.44 TStrings.Objects

Synopsis: Indexed access to the objects associated with the strings in the list.

Declaration: `Property Objects[Index: Integer]: TObject`

Visibility: public

Access: Read,Write

Description: `Objects` provides indexed access to the objects associated to the strings in the list. `Index` is a zero-based index and must be in the range of 0 to `Count-1`.

Setting the `objects` property will not free the previously associated object, if there was one. The caller is responsible for freeing the object that was previously associated to the string.

`TStrings` does not implement any storage for objects. Reading the `Objects` property will always return `Nil`. Setting the property will have no effect. It is the responsibility of the descendant classes to provide storage for the associated objects.

Errors: If an `Index` outside the valid range is specified, an `EStringListError` (268) exception will be raised.

See also: `TStrings.Strings` (444), `TStrings.IndexOfObject` (436), `TStrings.Names` (443), `TStrings.Values` (444)

4.71.45 TStrings.Values

Synopsis: Value parts of the name-value pairs in the list.

Declaration: `Property Values[Name: string]: string`

Visibility: public

Access: Read,Write

Description: `Values` represents the value parts of the name-value pairs in the list.

When reading this property, if there is a name-value pair in the list of strings that has name part `Name`, then the corresponding value is returned. If there is no such pair, an empty string is returned.

When writing this value, first it is checked whether there exists a name-value pair in the list with name `Name`. If such a pair is found, its value part is overwritten with the specified value. If no such pair is found, a new name-value pair is added with the specified `Name` and value.

Remark:

1. Names are compared case-insensitively.
2. Any character, including whitespace, up till the first equal (=) sign in a string is considered part of the name.

See also: `TStrings.Names` (443), `TStrings.Strings` (444), `TStrings.Objects` (444)

4.71.46 TStrings.Strings

Synopsis: Indexed access to the strings in the list.

Declaration: `Property Strings[Index: Integer]: string; default`

Visibility: public

Access: Read,Write

Description: `Strings` is the default property of `TStrings`. It provides indexed read-write access to the list of strings. Reading it will return the string at position `Index` in the list. Writing it will set the string at position `Index`.

`Index` is the position of the string in the list. It is zero-based, i.e. valid values range from 0 (the first string in the list) till `Count-1` (the last string in the list). When browsing through the strings in the list, this fact must be taken into account.

To access the objects associated with the strings in the list, use the `TStrings.Objects` (444) property. The name parts of name-value pairs can be accessed with the `TStrings.Names` (443) property, and the values can be set or read through the `TStrings.Values` (444) property.

Searching through the list can be done using the `TStrings.IndexOf` (435) method.

Errors: If `Index` is outside the allowed range, an `EStringListError` (268) exception is raised.

See also: `TStrings.Count` (443), `TStrings.Objects` (444), `TStrings.Names` (443), `TStrings.Values` (444), `TStrings.IndexOf` (435)

4.71.47 TStrings.Text

Synopsis: Contents of the list as one big string.

Declaration: `Property Text : string`

Visibility: public

Access: Read,Write

Description: `Text` returns, when read, the contents of the stringlist as one big string consisting of all strings in the list, separated by an end-of-line marker. When this property is set, the string will be cut into smaller strings, based on the positions of end-of-line markers in the string. Any previous content of the stringlist will be lost.

Remark: If any of the strings in the list contains an end-of-line marker, then the resulting string will appear to contain more strings than actually present in the list. To avoid this ambiguity, use the `TStrings.CommaText` (442) property instead.

See also: `TStrings.Strings` (444), `TStrings.Count` (443), `TStrings.CommaText` (442)

4.71.48 TStrings.StringsAdapter

Synopsis: Not implemented in Free Pascal.

Declaration: `Property StringsAdapter : IStringsAdapter`

Visibility: public

Access: Read,Write

Description: Not implemented in Free Pascal.

4.71.49 TStrings.SkipLastLineBreak

Synopsis: Do not add a linebreak to the last item

Declaration: `Property SkipLastLineBreak : Boolean`

Visibility: public

Access: Read,Write

Description: `SkipLastLineBreak` can be set to `True` to omit a linebreak character after the last string in the `TStrings.Text` (445). This also means when writing to file, that the file will not have a terminating linebreak character.

See also: `TStrings.LineBreak` (440), `TStrings.Text` (445)

4.72 TStringsEnumerator

4.72.1 Description

`TStringsEnumerator` implements the `#rtl.system.IEnumerator` (1426) interface for the `TStrings` (429) class, so the `TStrings` class can be used in a `for ... in` loop. It is returned by the `TStrings.GetEnumerator` (435) method of `TStrings`.

See also: `TStrings` (429), `TStrings.GetEnumerator` (435), `#rtl.system.IEnumerator` (1426)

4.72.2 Method overview

Page	Method	Description
446	<code>Create</code>	Initialize a new instance of <code>TStringsEnumerator</code>
446	<code>GetCurrent</code>	Return the current pointer in the list
447	<code>MoveNext</code>	Move the position of the enumerator to the next position in the list.

4.72.3 Property overview

Page	Properties	Access	Description
447	<code>Current</code>	<code>r</code>	Current pointer in the list

4.72.4 TStringsEnumerator.Create

Synopsis: Initialize a new instance of `TStringsEnumerator`

Declaration: `constructor Create(AStrings: TStrings)`

Visibility: `public`

Description: `Create` initializes a new instance of `TStringsEnumerator` and keeps a reference to the stringlist `AStrings` that will be enumerated.

See also: `TStrings` (429)

4.72.5 TStringsEnumerator.GetCurrent

Synopsis: Return the current pointer in the list

Declaration: `function GetCurrent : string`

Visibility: `public`

Description: `GetCurrent` returns the current string item in the enumerator.

Errors: No checking is done on the validity of the current position.

See also: `MoveNext` (447), `TStringItem` (245)

4.72.6 TStringsEnumerator.MoveNext

Synopsis: Move the position of the enumerator to the next position in the list.

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` puts the pointer on the next item in the stringlist, and returns `True` if this succeeded, or `False` if the pointer is past the last element in the list.

Errors: Note that if `False` is returned, calling `GetCurrent` will result in an exception.

See also: `GetCurrent` ([446](#))

4.72.7 TStringsEnumerator.Current

Synopsis: Current pointer in the list

Declaration: `Property Current : string`

Visibility: public

Access: Read

Description: `Current` redefines `GetCurrent` ([446](#)) as a property.

See also: `GetCurrent` ([446](#))

4.73 TStringStream

4.73.1 Description

`TStringStream` stores its data in an `ansistring`. The contents of this string is available as the `DataStream` ([449](#)) property. It also introduces some methods to read or write parts of the stringstream's data as a string.

The main purpose of a `TStringStream` is to be able to treat a string as a stream from which can be read.

See also: `TStream` ([409](#)), `TStringStream.DataStream` ([449](#)), `TStringStream.ReadString` ([448](#)), `TStringStream.WriteString` ([449](#))

4.73.2 Method overview

Page	Method	Description
448	<code>Create</code>	Creates a new stringstream and sets its initial content.
448	<code>Read</code>	Reads from the stream.
448	<code>ReadString</code>	Reads a string of length <code>Count</code>
448	<code>Seek</code>	Sets the position in the stream.
449	<code>Write</code>	<code>Write</code> overrides the <code>TStream.Write</code> (411) method.
449	<code>WriteString</code>	<code>WriteString</code> writes a string to the stream.

4.73.3 Property overview

Page	Properties	Access	Description
449	<code>DataStream</code>	<code>r</code>	Contains the contents of the stream in string form

4.73.4 TStringStream.Create

Synopsis: Creates a new stringstream and sets its initial content.

Declaration: `constructor Create(const AString: string)`

Visibility: `public`

Description: `Create` creates a new `TStringStream` instance and sets its initial content to `AString`. The position is still 0 but the size of the stream will equal the length of the string.

See also: `TStringStream.DataString` (449)

4.73.5 TStringStream.Read

Synopsis: Reads from the stream.

Declaration: `function Read(var Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Read` overrides the `Read` (410) from `TStream` (409). It tries to read `Count` bytes into `Buffer`. It returns the number of bytes actually read. The position of the stream is advanced with the number of bytes actually read; When the reading has reached the end of the `DataStream` (449), then the reading stops, i.e. it is not possible to read beyond the end of the `datastring`.

See also: `TStream.Read` (410), `TStringStream.Write` (449), `TStringStream.DataString` (449)

4.73.6 TStringStream.ReadString

Synopsis: Reads a string of length `Count`

Declaration: `function ReadString(Count: LongInt) : string`

Visibility: `public`

Description: `ReadString` reads `Count` bytes from the stream and returns the read bytes as a string. If less than `Count` bytes were available, the string has as many characters as bytes could be read.

The `ReadString` method is a wrapper around the `Read` (448) method. It does not do the same string as the `TStream.ReadAnsiString` (417) method, which first reads a length integer to determine the length of the string to be read.

See also: `TStringStream.Read` (448), `TStream.ReadAnsiString` (417)

4.73.7 TStringStream.Seek

Synopsis: Sets the position in the stream.

Declaration: `function Seek(Offset: LongInt; Origin: Word) : LongInt; Override`

Visibility: `public`

Description: `Seek` implements the abstract `Seek` (411) method.

4.73.8 TStringStream.Write

Synopsis: `Write` overrides the `TStream.Write` (411) method.

Declaration: `function Write(const Buffer; Count: LongInt) : LongInt; Override`

Visibility: `public`

Description: `Write` overrides the `TStream.Write` (411) method.

4.73.9 TStringStream.WriteString

Synopsis: `WriteString` writes a string to the stream.

Declaration: `procedure WriteString(const AString: string)`

Visibility: `public`

Description: `WriteString` writes a string to the stream.

4.73.10 TStringStream.DataString

Synopsis: Contains the contents of the stream in string form

Declaration: `Property DataString : string`

Visibility: `public`

Access: `Read`

Description: Contains the contents of the stream in string form

4.74 TTextWriter

4.74.1 Description

Not yet implemented.

4.75 TThread

4.75.1 Description

The `TThread` class encapsulates the native thread support of the operating system. To create a thread, declare a descendant of the `TThread` object and override the `Execute` (450) method. In this method, the `tthread`'s code should be executed. To run a thread, create an instance of the `tthread` descendant, and call its `execute` method.

It is also possible to simply execute a method or static procedure in a thread using the `TThread.ExecuteInThread` (454) class method.

See also: `EThread` (268), `TThread.Execute` (450), `TThread.ExecuteInThread` (454)

4.75.2 Method overview

Page	Method	Description
459	AfterConstruction	Code to be executed after construction but before execute.
452	CheckTerminated	Check if the current thread has finished executing.
451	Create	Creates a new thread.
452	CreateAnonymousThread	Execute code in an anonymous thread
451	Destroy	Destroys the thread object.
450	Execute	Execute method. Must be overridden in a descendant thread.
454	ExecuteInThread	Execute a method or static procedure in a thread
454	GetSystemTimes	Return CPU stats
454	GetTickCount	Return tick count (32-bit)
454	GetTickCount64	Return tick count (64-bit)
452	NameThreadForDebugging	Set a thread name
451	Queue	Queue a method for execution in the main thread
453	RemoveQueuedEvents	Remove methods scheduled for execution from queue
460	Resume	Resumes the thread's execution. Deprecated, see <code>TThread.Start</code>
452	SetReturnValue	Set return value of a thread
453	Sleep	Prevent thread execution
453	SpinWait	Prevent thread execution in a spin-wait loop
459	Start	Starts a thread that was created in a suspended state.
460	Suspend	Suspends the thread's execution.
451	Synchronize	Synchronizes the thread by executing the method in the main thread.
460	Terminate	Signals the thread it should terminate.
460	WaitFor	Waits for the thread to terminate and returns the exit status.
454	Yield	Yield execution to other threads

4.75.3 Property overview

Page	Properties	Access	Description
461	CurrentThread	r	Return current thread instance
462	ExternalThread	r	Is the thread instance an external thread ?
463	FatalException	r	Exception that occurred during thread execution
463	Finished	r	Has the thread finished executing
462	FreeOnTerminate	rw	Indicates whether the thread should free itself when it stops executing.
462	Handle	r	Returns the thread handle.
461	IsSingleProcessor	r	Is the current system single processor or not
463	OnTerminate	rw	Event called when the thread terminates.
462	Priority	rw	Returns the thread priority.
461	ProcessorCount	r	Return the processor count for this system
462	Suspended	rw	Indicates whether the thread is suspended.
463	ThreadID	r	Returns the thread ID.

4.75.4 TThread.Execute

Synopsis: Execute method. Must be overridden in a descendant thread.

Declaration: `procedure Execute; Virtual; Abstract`

Visibility: `protected`

Description: `Execute` is a method that must be overridden in descendant classes of the thread. It must contain the code that must execute in the thread. The `Execute` method is responsible for checking `Terminated` (231) at regular intervals: when it is set to `True` the execute method must exit.

See also: `Terminated` (231)

4.75.5 `TThread.Synchronize`

Synopsis: Synchronizes the thread by executing the method in the main thread.

Declaration: `procedure Synchronize(AMethod: TThreadMethod)`
`class procedure Synchronize(AThread: TThread; AMethod: TThreadMethod)`

Visibility: `protected`

Description: Synchronizes the thread by executing the method in the main thread.

4.75.6 `TThread.Queue`

Synopsis: Queue a method for execution in the main thread

Declaration: `procedure Queue(aMethod: TThreadMethod)`
`class procedure Queue(AThread: TThread; aMethod: TThreadMethod); Static`

Visibility: `protected`

Description: `Queue` schedules a method `aMethod` for execution in the main thread. In difference with `TThread.Synchronize` (451), `Queue` just posts the method for execution in a queue, and does not wait for it to be executed, so this call returns at once.

In the class procedure overloaded version of this call, the thread for which the method must be posted is the first argument. In the protected version of this call (used in the `tthread` instance), this argument is not there, and the thread instance is used.

When a thread finishes its execution, all its queued calls are removed from the queue list.

See also: `TThread.Synchronize` (451), `TThread.RemoveQueuedEvents` (453)

4.75.7 `TThread.Create`

Synopsis: Creates a new thread.

Declaration: `constructor Create(CreateSuspended: Boolean; const StackSize: SizeUInt)`

Visibility: `public`

Description: Creates a new thread.

4.75.8 `TThread.Destroy`

Synopsis: Destroys the thread object.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the thread object.

4.75.9 TThread.CreateAnonymousThread

Synopsis: Execute code in an anonymous thread

Declaration: `class function CreateAnonymousThread(aProc: TProcedure) : TThread
; Static`

Visibility: public

Description: `CreateAnonymousThread` will create an instance of a `TThread` descendant and calls `aProc` in this procedure. This can be used to quickly execute a method in another thread without having to explicitly declare a thread for such purposes. It returns the created `TThread` instance, which can be checked for termination etc.

Note that this method differs slightly from Delphi in that FPC does not yet support anonymous methods, so the signature of `aProc` differs slightly.

See also: `TThread.CheckTerminated` ([452](#))

4.75.10 TThread.NameThreadForDebugging

Synopsis: Set a thread name

Declaration: `class procedure NameThreadForDebugging(aThreadName: UnicodeString;
aThreadID: TThreadID); Static
class procedure NameThreadForDebugging(aThreadName: AnsiString;
aThreadID: TThreadID); Static`

Visibility: public

Description: `NameThreadForDebugging` sets the name of thread `aThreadID` to `aThreadName`. The thread name can be unicode or ansistring. This is mainly useful for debugging purposes, as thread names are more easily recognizable than IDs.

Note that this requires OS support. Currently this is not implemented for any FPC platform and is supported for Delphi compatibility only.

4.75.11 TThread.SetReturnValue

Synopsis: Set return value of a thread

Declaration: `class procedure SetReturnValue(aValue: Integer); Static`

Visibility: public

Description: `TThread.SetReturnValue` sets the return value of an internally created thread.

Errors: If the thread was not created by the FPC program, an `EThreadExternalException` ([268](#)) exception is raised.

See also: `EThreadExternalException` ([268](#)), `TThread.CheckTerminated` ([452](#))

4.75.12 TThread.CheckTerminated

Synopsis: Check if the current thread has finished executing.

Declaration: `class function CheckTerminated : Boolean; Static`

Visibility: public

Description: `TThread.CheckTerminated` can be used to check if the current thread has finished executing (i.e. `Execute` has finished). This can be called from methods in other classes where the current thread instance is not available.

Errors: If the thread was not created by the FPC program, an `EThreadExternalException` (268) exception is raised.

See also: [EThreadExternalException \(268\)](#), [TThread.SetReturnValue \(452\)](#)

4.75.13 TThread.RemoveQueuedEvents

Synopsis: Remove methods scheduled for execution from queue

```
Declaration: class procedure RemoveQueuedEvents(aThread: TThread;  
                                                aMethod: TThreadMethod); Static  
class procedure RemoveQueuedEvents(aMethod: TThreadMethod); Static  
class procedure RemoveQueuedEvents(aThread: TThread); Static
```

Visibility: public

Description: `RemoveQueuedEvents` removes methods from the list of methods waiting for execution in the main thread. If only `aThread` is specified, all methods scheduled for execution by that thread are removed. If only `aMethod` is specified, then all calls to that method are removed, regardless of the thread. If both arguments are specified, then all calls to the given method by the given thread are removed.

See also: [TThread.Synchronize \(451\)](#), [TThread.Queue \(451\)](#)

4.75.14 TThread.SpinWait

Synopsis: Prevent thread execution in a spin-wait loop

Declaration: `class procedure SpinWait(aIterations: LongWord); Static`

Visibility: public

Description: *SpinWait* blocks the execution of the thread in a spin-wait loop: it simply executes some simple instructions.

This can be used to create short time delays without an immediate thread switch (e.g. `SysUtils.Sleep` (231) can cause a thread switch). The input parameter (`alterations`) specifies the number of spin loops.

See also: [SysUtils.Sleep \(231\)](#), [TThread.Sleep \(453\)](#)

4.75.15 TThread.Sleep

Synopsis: Prevent thread execution

Declaration: `class procedure Sleep(aMilliseconds: Cardinal); Static`

Visibility: public

Description: Sleep blocks the execution of the thread for `aMilliseconds`. This function simply calls `sysutils.sleep` (231)

In difference with `TThread.SpinWait` (453), a thread switch may occur during the sleep.

See also: [SysUtils.Sleep \(231\)](#), [TThread.SpinWait \(453\)](#)

4.75.16 TThread.Yield

Synopsis: Yield execution to other threads

Declaration: `class procedure Yield; Static`

Visibility: `public`

Description: `TThread.Yield` yields the processor to other threads. It can be called from methods outside the thread class itself.

4.75.17 TThread.GetSystemTimes

Synopsis: Return CPU stats

Declaration: `class procedure GetSystemTimes(out aSystemTimes: TSystemTimes); Static`

Visibility: `public`

Description: `GetSystemTimes` is provided for Delphi compatibility only, it currently returns empty values only.

See also: `TSystemTimes` ([231](#))

4.75.18 TThread.GetTickCount

Synopsis: Return tick count (32-bit)

Declaration: `class function GetTickCount : LongWord; Static`

Visibility: `public`

Description: `GetTickCount` is deprecated and should not be used. Use `TThread.GetTickCount64` ([454](#)) instead.

See also: `TThread.GetTickCount64` ([454](#))

4.75.19 TThread.GetTickCount64

Synopsis: Return tick count (64-bit)

Declaration: `class function GetTickCount64 : QWord; Static`

Visibility: `public`

Description: `GetTickCount64` simply calls `SysUtils.GetTickCount64` ([231](#)) and is implemented for Delphi compatibility only.

See also: `SysUtils.GetTickCount64` ([231](#))

4.75.20 TThread.ExecuteInThread

Synopsis: Execute a method or static procedure in a thread

Declaration:

```

class function ExecuteInThread(AMethod: TThreadExecuteHandler;
                              AOnTerminate: TNotifyEvent) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusHandler;
                              AOnStatus: TThreadStatusNotifyEvent;
                              AOnTerminate: TNotifyEvent) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteCallBack;
                              AData: Pointer;
                              AOnTerminate: TNotifyCallBack) : TThread
    ; Overload; Static
class function ExecuteInThread(AMethod: TThreadExecuteStatusCallBack;
                              AOnStatus: TThreadStatusNotifyCallBack;
                              AData: Pointer;
                              AOnTerminate: TNotifyCallBack) : TThread
    ; Overload; Static

```

Visibility: public

Description: `TThread.ExecuteInThread` is a class method which allows to quickly execute a method or procedure in a thread. The method or procedure to be executed is passed in `Method`, this can be a method or a plain (static) procedure.

The caller can be notified of thread termination: In the optional argument `AOnTerminate` a callback (procedure or method, depending on the signature) can be specified that will be called when the thread terminated. This callback is executed in the main thread.

The signature of `AMethod` determines whether status reporting is enabled or not. If the method of type `TThreadExecuteStatusHandler` (247) or `TThreadExecuteStatusCallBack` (246), then an extra `AOnStatus` callback must be specified. This callback will be called in the main thread whenever the thread wishes to be report its status. The status callback should not do extensive work, because while the status callback is called, thread execution is suspended.

When using a plain procedure, extra data can be passed on to the procedure in `AData`. The `AData` pointer will be passed to the thread method, and also to the thread status callback and thread termination callback.

See also: `TThreadExecuteHandler` (246), `TThreadExecuteStatusHandler` (247), `TThreadExecuteStatusCallBack` (246), `TThreadExecuteCallBack` (246)

Listing: `./classesex/tthrc.pp`

```

program tthrc;

uses cthreads, sysutils, classes;

Var
    D : Integer;

Procedure DoneThread(Sender : TObject; AData : Pointer);

begin
    WriteLn('Thread ', TThread(Sender).ThreadID, ' done. D is currently: ', PInteger(AData)^);
end;

Procedure DoThread(AData : Pointer);

Var
    I : integer;

```



```

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Writeln('Thread ',TThread.CurrentThread.ThreadID,' ping ',I);
      Inc(PInteger(AData)^,i);
    end;
  end;

Var
  T1,T2 : TThread;

begin
  T1:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@D,@DoneThread);
  Writeln('Main thread done');
  T1.WaitFor;
  T2.WaitFor;
end.

```

Listing: ./classesex/tthre.pp

```

program tthre;

```

```

{$mode objfpc}
{$H+}

```

```

uses cthreads, sysutils, classes;

```

Type

```

TTestThread = Class(TObject)
  D : Integer;
  Procedure DoneThread(Sender : TObject);
  Procedure DoThread;
  Procedure Run;
end;

```

```

Procedure TTestThread.DoneThread(Sender : TObject);

```

begin

```

  Writeln('Thread ',TThread(Sender).ThreadID,' done. D is currently: ', D);
end;

```

```

Procedure TTestThread.DoThread;

```

Var

```

  I : integer;

```

begin

```

  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Writeln('Thread ',TThread.CurrentThread.ThreadID,' ping ',I);
      Inc(D,i);
    end;
  end;

```

end;

Procedure TTestThread.Run;

Var

T1,T2 : TThread;

begin

T1:=TThread.ExecuteInThread(@DoThread,@DoneThread);

T2:=TThread.ExecuteInThread(@DoThread,@DoneThread);

WriteIn('Main thread done');

T1.WaitFor;

T2.WaitFor;

end;

begin

With TTestThread.Create **do**

try

Run;

finally

Free;

end;

end.

Listing: ./classesex/tthrcs.pp

program tthrcs;

{ \$h+ }

uses cthreads, sysutils, classes;

Var

D : Integer;

DoneThreads : INteger;

Procedure DoneThread(Sender : TObject; Data : Pointer);

begin

Inc(DoneThreads);

WriteIn('Thread ',TThread(Sender).ThreadID, ' done. D is currently: ', PInteger(Data)^);

end;

Procedure ReportThreadStatus(Sender : TThread; AData : Pointer;**Const** status : **String**);

begin

WriteIn('Thread ',Sender.ThreadID, ' Status report : ',Status);

end;

Procedure DoThread(AData : Pointer; Report : TThreadReportStatus);

Var

I : integer;

begin

for I:=1 **to** 10 **do**

begin

Sleep(10***Random**(30));

Report('Ping '+**IntToStr**(i));

```

        Inc(PInteger(AData)^, i);
    end;
end;

Var
    T1, T2 : TThread;

begin
    DoneThreads:=0;
    T1:=TThread.ExecuteInThread(@DoThread, @ReportThreadStatus, @D, @DoneThread);
    T2:=TThread.ExecuteInThread(@DoThread, @ReportThreadStatus, @D, @DoneThread);
    WriteLn('Main thread loop');
    While DoneThreads<2 do
        begin
            Sleep(10);
            CheckSynchronize;
        end;
        T1.WaitFor;
        T2.WaitFor;
    end.

```

Listing: ./classesex/tthres.pp

```

program tthrc;

```

```

{$mode objfpc}
{$H+}

```

```

uses cthreads, sysutils, classes;

```

Type

```

TTestThread = Class(TObject)
    D : Integer;
    DoneThreads : integer;
    Procedure DoneThread(Sender : TObject);
    Procedure ReportThreadStatus(Sender : TThread; Const status : String);
    Procedure DoThread(Report: TThreadReportStatus);
    Procedure Run;
end;

```

```

Procedure TTestThread.DoneThread(Sender : TObject);

```

begin

```

    Inc(DoneThreads);
    WriteLn('Thread ', TThread(Sender).ThreadID, ' done. D is currently: ', D);
end;

```

```

Procedure TTestThread.ReportThreadStatus(Sender : TThread; Const status : String);

```

begin

```

    WriteLn('Thread ', Sender.ThreadID, ' Status report : ', Status);
end;

```

```

Procedure TTestThread.DoThread(Report : TThreadReportStatus);

```

Var

```

    I : integer;

```

```

begin
  for I:=1 to 10 do
    begin
      Sleep(10*Random(30));
      Report('Ping '+IntToStr(i));
      Inc(D,i);
    end;
end;

Procedure TTestThread.Run;

Var
  T1,T2 : TThread;

begin
  DoneThreads:=0;
  T1:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  T2:=TThread.ExecuteInThread(@DoThread,@ReportThreadStatus,@DoneThread);
  WriteLn('Main thread loop');
  While DoneThreads<2 do
    begin
      Sleep(10);
      CheckSynchronize;
    end;
    T1.WaitFor;
    T2.WaitFor;
end;

begin
  With TTestThread.Create do
    try
      Run;
    finally
      Free;
    end;
end.

```

4.75.21 TThread.AfterConstruction

Synopsis: Code to be executed after construction but before execute.

Declaration: `procedure AfterConstruction; Override`

Visibility: public

Description: `AfterConstruction` is overridden in `TThread`, it starts the thread if it was created in a suspended state. When overriding this method, the inherited method must be called.

4.75.22 TThread.Start

Synopsis: Starts a thread that was created in a suspended state.

Declaration: `procedure Start`

Visibility: public

Description: The effect of this method is currently the same as calling `TThread.Resume` after creating a thread in a suspended state. This method was added for Delphi-compatibility, where it was introduced after `TThread.Suspend` and `TThread.Resume` were deprecated.

See also: `TThread.Create` ([451](#))

4.75.23 TThread.Resume

Synopsis: Resumes the thread's execution. Deprecated, see `TThread.Start`

Declaration: `procedure Resume`

Visibility: `public`

Description: Resumes the thread's execution. Deprecated, see `TThread.Start`

See also: `TThread.Start` ([459](#)), `TThread.Suspend` ([460](#))

4.75.24 TThread.Suspend

Synopsis: Suspends the thread's execution.

Declaration: `procedure Suspend`

Visibility: `public`

Description: On non-Windows platforms, a thread can only suspend itself. Other threads can wake up a suspended thread by calling `TThread.Start`.

See also: `TThread.Resume` ([460](#)), `TThread.Start` ([459](#))

4.75.25 TThread.Terminate

Synopsis: Signals the thread it should terminate.

Declaration: `procedure Terminate`

Visibility: `public`

Description: Signals the thread it should terminate.

4.75.26 TThread.WaitFor

Synopsis: Waits for the thread to terminate and returns the exit status.

Declaration: `function WaitFor : Integer`

Visibility: `public`

Description: Waits for the thread to terminate and returns the exit status.

4.75.27 TThread.CurrentThread

Synopsis: Return current thread instance

Declaration: `Property CurrentThread : TThread`

Visibility: public

Access: Read

Description: `TThread.CurrentThread` can be used to get the current thread instance. This is useful in code that is not inside a `TThread` implementation, but which needs access to the current thread.

For threads that were created outside of FPC code (DLLs or a calling program) this will return a dummy `TThread` instance.

See also: `TThread.ExternalThread` ([462](#))

4.75.28 TThread.ProcessorCount

Synopsis: Return the processor count for this system

Declaration: `Property ProcessorCount : LongWord`

Visibility: public

Access: Read

Description: `ProcessorCount` returns the processor count for this system.

Whether this is the number of cores or the number of CPUs present in the hardware, is deliberately unspecified. The number of cores can also vary during the lifetime of the program, and the FPC implementation does not guarantee that this will always match, the value is set at program start.

As such, the number specified should only be used as an indication of how many threads can be executed at once by the system.

See also: `TThread.IsSingleProcessor` ([461](#))

4.75.29 TThread.IsSingleProcessor

Synopsis: Is the current system single processor or not

Declaration: `Property IsSingleProcessor : Boolean`

Visibility: public

Access: Read

Description: `Thread.IsSingleProcessor` returns `True` if `TThread.ProcessorCount` ([461](#)) is less than or equal to 1, `False` otherwise.

See also: `TThread.ProcessorCount` ([461](#))

4.75.30 TThread.FreeOnTerminate

Synopsis: Indicates whether the thread should free itself when it stops executing.

Declaration: `Property FreeOnTerminate : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread should free itself when it stops executing.

4.75.31 TThread.Handle

Synopsis: Returns the thread handle.

Declaration: `Property Handle : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread handle.

4.75.32 TThread.ExternalThread

Synopsis: Is the thread instance an external thread ?

Declaration: `Property ExternalThread : Boolean`

Visibility: `public`

Access: `Read`

Description: `ExternalThread` returns `True` if the thread is an externally created thread. If the thread was created by the FPC program, this returns `False`. This is useful for examining instances returned by `TThread.CurrentThread` ([461](#)).

See also: `TThread.CurrentThread` ([461](#))

4.75.33 TThread.Priority

Synopsis: Returns the thread priority.

Declaration: `Property Priority : TThreadPriority`

Visibility: `public`

Access: `Read,Write`

Description: Returns the thread priority.

4.75.34 TThread.Suspended

Synopsis: Indicates whether the thread is suspended.

Declaration: `Property Suspended : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: Indicates whether the thread is suspended.

4.75.35 TThread.Finished

Synopsis: Has the thread finished executing

Declaration: `Property Finished : Boolean`

Visibility: `public`

Access: `Read`

Description: `Finished` is `True` when `TThread.Execue` (449) has finished executing, but the thread is still cleaning up (calling `OnTerminate`, etc).

See also: `TThread.Execue` (449), `TThread.OnTerminate` (463)

4.75.36 TThread.ThreadID

Synopsis: Returns the thread ID.

Declaration: `Property ThreadID : TThreadID`

Visibility: `public`

Access: `Read`

Description: Returns the thread ID.

4.75.37 TThread.OnTerminate

Synopsis: Event called when the thread terminates.

Declaration: `Property OnTerminate : TNotifyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `TThread.OnTerminate` is called when the thread terminates. The event is always called in the context of the main thread, i.e. using `TThread.Synchronize` (451)

See also: `TThread.Synchronize` (451), `TThread.FreeOnTerminate` (462)

4.75.38 TThread.FatalException

Synopsis: Exception that occurred during thread execution

Declaration: `Property FatalException : TObject`

Visibility: `public`

Access: `Read`

Description: `FatalException` contains the exception that occurred during the thread's execution.

4.76 TThreadList

4.76.1 Description

TThreadList is a thread-safe TList (370) implementation. Unlike TList, it can be accessed read-write by multiple threads: the list implementation will take care of locking the list when adding or removing items from the list.

See also: TList (370)

4.76.2 Method overview

Page	Method	Description
465	Add	Adds an element to the list.
465	Clear	Removes all emements from the list.
464	Create	Creates a new thread-safe list.
464	Destroy	Destroys the list instance.
465	LockList	Locks the list for exclusive access.
465	Remove	Removes an item from the list.
466	UnlockList	Unlocks the list after it was locked.

4.76.3 Property overview

Page	Properties	Access	Description
466	Duplicates	rw	Describes what to do with duplicates

4.76.4 TThreadList.Create

Synopsis: Creates a new thread-safe list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new `TThreadList` instance. It initializes a critical section and an internal list object.

See also: `TThreadList.Destroy` ([464](#))

4.76.5 TThreadList.Destroy

Synopsis: Destroys the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` finalizes the critical section, clears the internal list object and calls the inherited destructor.

See also: `TThreadList.Create` ([464](#))

4.76.6 TThreadList.Add

Synopsis: Adds an element to the list.

Declaration: `procedure Add(Item: Pointer)`

Visibility: `public`

Description: `Add` attempts to lock the list and adds the pointer `Item` to the list. After the pointer was added, the list is unlocked again.

See also: `LockList` (465), `Clear` (465), `Remove` (465), `UnlockList` (466)

4.76.7 TThreadList.Clear

Synopsis: Removes all emements from the list.

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` attempts to lock the list and then clears the list; all items are removed from the list. After the list is cleared, it is again unlocked.

See also: `LockList` (465), `Add` (465), `Remove` (465), `UnlockList` (466)

4.76.8 TThreadList.LockList

Synopsis: Locks the list for exclusive access.

Declaration: `function LockList : TList`

Visibility: `public`

Description: `LockList` locks the list for exclusive access. Locklist uses an internal critical section, so all rules for multiple locking of critical sections apply to locklist/unlocklist as well.

See also: `Clear` (465), `Add` (465), `Remove` (465), `UnlockList` (466)

4.76.9 TThreadList.Remove

Synopsis: Removes an item from the list.

Declaration: `procedure Remove(Item: Pointer)`

Visibility: `public`

Description: `Remove` attempts to lock the list and then removes `Item` from the list. After the item is removed, the list is again unlocked.

See also: `LockList` (465), `Add` (465), `Clear` (465), `UnlockList` (466)

4.76.10 TThreadList.UnlockList

Synopsis: Unlocks the list after it was locked.

Declaration: `procedure UnlockList`

Visibility: `public`

Description: `UnLockList` unlocks the list when it was locked for exclusive access. `UnLocklist` and `LockList` use an internal critical section, so all rules for multiple locking/unlocking of critical sections apply.

See also: `Clear` (465), `Add` (465), `Remove` (465), `lockList` (465)

4.76.11 TThreadList.Duplicates

Synopsis: Describes what to do with duplicates

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: `Read,Write`

Description: `Duplicates` describes what the threadlist should do when a duplicate pointer is added to the list. It is identical in behaviour to the `Duplicates` (427) property of `TStringList` (424).

See also: `TDuplicates` (238)

4.77 TWriter

4.77.1 Description

The `TWriter` class is a writer class that implements generic component streaming capabilities, independent of the format of the data in the stream. It uses a driver class `TAbstractObjectWriter` (289) to do the actual reading of data. The interface of the `TWriter` class should be identical to the interface in Delphi.

Note that the `TWriter` design is such that it will write a single component to a stream. It will write all children of this component, but it is not designed to write multiple components in succession to one stream.

It should never be necessary to create an instance of this class directly. Instead, the `TStream.WriteComponent` (414) call should be used.

See also: `TFile` (348), `TWriter` (466), `TAbstractObjectReader` (281)

4.77.2 Method overview

Page	Method	Description
467	Create	Creates a new Writer with a stream and bufsize.
468	DefineBinaryProperty	Callback used when defining and streaming custom properties.
468	DefineProperty	Callback used when defining and streaming custom properties.
468	Destroy	Destroys the writer instance.
468	Write	Write raw data to stream
468	WriteBoolean	Write boolean value to the stream.
469	WriteChar	Write a character to the stream.
469	WriteCollection	Write a collection to the stream.
469	WriteComponent	Stream a component to the stream.
470	WriteCurrency	Write a currency value to the stream
470	WriteDate	Write a date to the stream.
469	WriteDescendent	Write descendent to stream
470	WriteFloat	Write a float to the stream.
470	WriteIdent	Write an identifier to the stream.
471	WriteInteger	Write an integer to the stream.
471	WriteListBegin	Write a start-of-list marker to the stream.
471	WriteListEnd	Write an end-of-list marker to the stream.
472	WriteRootComponent	Write a root component to the stream.
471	WriteSet	Write a set value to the stream
471	WriteSignature	Write a signature to the stream
470	WriteSingle	Write a single-type real to the stream.
472	WriteString	Write a string to the stream.
472	WriteUnicodeString	Write a unicode string to the stream.
472	WriteVariant	Write a variant to the stream
469	WriteWideChar	Write widechar to stream
472	WriteWideString	Write a widestring value to the stream

4.77.3 Property overview

Page	Properties	Access	Description
474	Driver	r	Driver used when writing to the stream.
473	OnFindAncestor	rw	Event occurring when an ancestor component must be found.
473	OnWriteMethodProperty	rw	Handler from writing method properties.
473	OnWriteStringProperty	rw	Event handler for translating strings written to stream.
474	PropertyPath	r	Path to the property that is currently being written
473	RootAncestor	rw	Ancestor of root component.

4.77.4 TWriter.Create

Synopsis: Creates a new Writer with a stream and bufsize.

Declaration: constructor Create(ADriver: TAbstractObjectWriter)
 constructor Create(Stream: TStream; BufSize: Integer)

Visibility: public

Description: Creates a new Writer with a stream and bufsize.

4.77.5 TWriter.Destroy

Synopsis: Destroys the writer instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: Destroys the writer instance.

4.77.6 TWriter.DefineProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineProperty(const Name: string; ReadData: TReaderProc;
AWriteData: TWriterProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.77.7 TWriter.DefineBinaryProperty

Synopsis: Callback used when defining and streaming custom properties.

Declaration: `procedure DefineBinaryProperty(const Name: string;
ReadData: TStreamProc;
AWriteData: TStreamProc; HasData: Boolean)
; Override`

Visibility: `public`

Description: Callback used when defining and streaming custom properties.

4.77.8 TWriter.Write

Synopsis: Write raw data to stream

Declaration: `procedure Write(const Buffer; Count: LongInt); Virtual`

Visibility: `public`

Description: `Write` is introduced for Delphi compatibility to write raw data to the component stream. This should not be used in new production code as it will totally mess up the streaming.

See also: `TBinaryObjectWriter.Write` ([310](#)), `TAbstractObjectWriter.Write` ([291](#))

4.77.9 TWriter.WriteBoolean

Synopsis: Write boolean value to the stream.

Declaration: `procedure WriteBoolean(Value: Boolean)`

Visibility: `public`

Description: Write boolean value to the stream.

4.77.10 TWriter.WriteCollection

Synopsis: Write a collection to the stream.

Declaration: `procedure WriteCollection(Value: TCollection)`

Visibility: `public`

Description: Write a collection to the stream.

4.77.11 TWriter.WriteComponent

Synopsis: Stream a component to the stream.

Declaration: `procedure WriteComponent(Component: TComponent)`

Visibility: `public`

Description: Stream a component to the stream.

4.77.12 TWriter.WriteChar

Synopsis: Write a character to the stream.

Declaration: `procedure WriteChar(Value: Char)`

Visibility: `public`

Description: Write a character to the stream.

4.77.13 TWriter.WriteWideChar

Synopsis: Write widechar to stream

Declaration: `procedure WriteWideChar(Value: WideChar)`

Visibility: `public`

Description: `WriteWideChar` writes a widechar to the stream. This actually writes a widestring of length 1.

See also: `TReader.ReadWideChar` ([399](#)), `TWriter.WriteWideString` ([472](#))

4.77.14 TWriter.WriteDescendent

Synopsis: Write descendent to stream

Declaration: `procedure WriteDescendent(ARoot: TComponent; AAncestor: TComponent)`

Visibility: `public`

Description: `WriteDescendent` writes `ARoot` as a descendent of `AAncestor`. This is used to create diff streams: only the properties where `ARoot` differs from `AAncestor` are written to the stream.

See also: `TStream.WriteDescendent` ([414](#))

4.77.15 TWriter.WriteFloat

Synopsis: Write a float to the stream.

Declaration: `procedure WriteFloat(const Value: Extended)`

Visibility: `public`

Description: Write a float to the stream.

4.77.16 TWriter.WriteSingle

Synopsis: Write a single-type real to the stream.

Declaration: `procedure WriteSingle(const Value: Single)`

Visibility: `public`

Description: Write a single-type real to the stream.

4.77.17 TWriter.WriteDate

Synopsis: Write a date to the stream.

Declaration: `procedure WriteDate(const Value: TDateTime)`

Visibility: `public`

Description: Write a date to the stream.

4.77.18 TWriter.WriteCurrency

Synopsis: Write a currency value to the stream

Declaration: `procedure WriteCurrency(const Value: Currency)`

Visibility: `public`

Description: `WriteCurrency` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadCurrency` ([400](#))

4.77.19 TWriter.WriteIdent

Synopsis: Write an identifier to the stream.

Declaration: `procedure WriteIdent(const Ident: string)`

Visibility: `public`

Description: Write an identifier to the stream.

4.77.20 TWriter.WriteInteger

Synopsis: Write an integer to the stream.

Declaration: `procedure WriteInteger(Value: LongInt); Overload`
`procedure WriteInteger(Value: Int64); Overload`

Visibility: public

Description: Write an integer to the stream.

4.77.21 TWriter.WriteSet

Synopsis: Write a set value to the stream

Declaration: `procedure WriteSet(Value: LongInt; SetType: Pointer)`

Visibility: public

Description: `WriteSet` writes a set `Value` consisting of elements with type `EnumType`. The set must be encoded as an integer where each element is encoded in a bit of the integer. Thus, at most an enumerated type with 32 elements can be written with this method.

Errors: No checking is performed on the validity of `EnumType`. It is assumed to be a valid `PTypeInfo` pointer.

See also: `TReader.ReadSet` ([401](#))

4.77.22 TWriter.WriteListBegin

Synopsis: Write a start-of-list marker to the stream.

Declaration: `procedure WriteListBegin`

Visibility: public

Description: Write a start-of-list marker to the stream.

4.77.23 TWriter.WriteListEnd

Synopsis: Write an end-of-list marker to the stream.

Declaration: `procedure WriteListEnd`

Visibility: public

Description: Write an end-of-list marker to the stream.

4.77.24 TWriter.WriteSignature

Synopsis: Write a signature to the stream

Declaration: `procedure WriteSignature`

Visibility: public

Description: `WriteSignature` writes the streaming signature (if any) to a stream. It is called once, at the start of writing the root component to a stream.

See also: `TAbstractObjectWriter.WriteSignature` ([290](#)), `TBinaryObjectWriter.WriteSignature` ([308](#))

4.77.25 TWriter.WriteRootComponent

Synopsis: Write a root component to the stream.

Declaration: `procedure WriteRootComponent (ARoot: TComponent)`

Visibility: `public`

Description: Write a root component to the stream.

4.77.26 TWriter.WriteString

Synopsis: Write a string to the stream.

Declaration: `procedure WriteString(const Value: string)`

Visibility: `public`

Description: Write a string to the stream.

4.77.27 TWriter.WriteString

Synopsis: Write a widestring value to the stream

Declaration: `procedure WriteWideString(const Value: WideString)`

Visibility: `public`

Description: `WriteWidestring` writes a currency typed value to the stream. This method does nothing except call the driver method of the driver being used.

See also: `TReader.ReadWideString` ([403](#))

4.77.28 TWriter.WriteString

Synopsis: Write a unicode string to the stream.

Declaration: `procedure WriteUnicodeString(const Value: UnicodeString)`

Visibility: `public`

Description: `WriteUnicodeString` writes `Value`, a `UnicodeString` string to the stream. It simply passes the string on to the `WriteUnicodeString` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteString` ([312](#)), `TReader.ReadUnicodeString` ([403](#))

4.77.29 TWriter.WriteVariant

Synopsis: Write a variant to the stream

Declaration: `procedure WriteVariant(const VarValue: Variant)`

Visibility: `public`

Description: `WriteVariant` writes `Value`, a simple variant, o the stream. It simply passes the string on to the `WriteVariant` method of the writer driver class.

See also: `TBinaryObjectWriter.WriteVariant` ([312](#)), `TReader.ReadVariant` ([402](#))

4.77.30 TWriter.RootAncestor

Synopsis: Ancestor of root component.

Declaration: `Property RootAncestor : TComponent`

Visibility: `public`

Access: `Read,Write`

Description: Ancestor of root component.

4.77.31 TWriter.OnFindAncestor

Synopsis: Event occurring when an ancestor component must be found.

Declaration: `Property OnFindAncestor : TFindAncestorEvent`

Visibility: `public`

Access: `Read,Write`

Description: Event occurring when an ancestor component must be found.

4.77.32 TWriter.OnWriteMethodProperty

Synopsis: Handler from writing method properties.

Declaration: `Property OnWriteMethodProperty : TWriteMethodPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteMethodProperty` can be set by an IDE or some streaming mechanism which handles dummy values for method properties; It can be used to write a real value to the stream which will be interpreted correctly when the stream is read. See `TWriteMethodPropertyEvent` (249) for a description of the arguments.

See also: `TWriteMethodPropertyEvent` (249), `TReader.OnSetMethodProperty` (405)

4.77.33 TWriter.OnWriteStringProperty

Synopsis: Event handler for translating strings written to stream.

Declaration: `Property OnWriteStringProperty : TReadWriteStringPropertyEvent`

Visibility: `public`

Access: `Read,Write`

Description: `OnWriteStringProperty` is called whenever a string property is written to the stream. It can be used e.g. by a translation mechanism to translate the strings on the fly, when a form is written. See `TReadWriteStringPropertyEvent` (243) for a description of the various parameters.

See also: `TReader.OnPropertyNotFound` (404), `TReader.OnSetMethodProperty` (405), `TReadWriteStringPropertyEvent` (243)

4.77.34 TWriter.Driver

Synopsis: Driver used when writing to the stream.

Declaration: `Property Driver : TAbstractObjectWriter`

Visibility: public

Access: Read

Description: Driver used when writing to the stream.

4.77.35 TWriter.PropertyPath

Synopsis: Path to the property that is currently being written

Declaration: `Property PropertyPath : string`

Visibility: public

Access: Read

Description: `PropertyPath` is set to the property name of the class currently being written to stream. This is only done when `TPersistent` ([390](#)) descendant class properties are written.

Chapter 5

Reference for unit 'clocale'

5.1 Used units

Table 5.1: Used units by unit 'clocale'

Name	Page
System	1194

5.2 Overview

The `clocale` offers no API by itself: it just initializes the internationalization settings of the `sysutils` ([1442](#)) unit with the values provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `clocale` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit, links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS - therefore it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}clocale{$endif},
  classes, sysutils;
```

Chapter 6

Reference for unit 'cmem'

6.1 Used units

Table 6.1: Used units by unit 'cmem'

Name	Page
System	1194

6.2 Overview

The `cmem` memory manager sets the system units memory manager to a C-based memory manager: all memory management calls are shunted through to the C memory manager, using `Malloc` ([477](#)), `Free` ([477](#)) and `ReAlloc` ([477](#)). For this reason, the `cmem` unit should be the first unit of the uses clause of the program.

The unit also offers the C memory calls directly as external declarations from the C library, but it is recommended to use the normal FPC routines for this.

Obviously, including this unit links your program to the C library.

6.3 Constants, types and variables

6.3.1 Constants

`LibName = 'c'`

`LibName` is the name of the library that is actually used. On most systems, this is simply "libc.so".

6.4 Procedures and functions

6.4.1 CAlloc

Synopsis: Allocate memory based on item size and count

Declaration: `function CAlloc(unitSize: PtrUInt; UnitCount: PtrUInt) : pointer`

Visibility: default

Description: `Calloc` allocates memory to hold `UnitCount` units of size `UnitSize` each. The memory is one block of memory. It returns a pointer to the newly allocated memory block.

See also: `Malloc` ([477](#)), `Free` ([477](#)), `Realloc` ([477](#))

6.4.2 Free

Synopsis: Free a previously allocated block

Declaration: `procedure Free(P: pointer)`

Visibility: default

Description: `Free` returns the memory block pointed to by `P` to the system. After `Free` was called, the pointer `P` is no longer valid.

See also: `Malloc` ([477](#)), `ReAlloc` ([477](#))

6.4.3 Malloc

Synopsis: Malloc external declaration.

Declaration: `function Malloc(Size: PtrUInt) : Pointer`

Visibility: default

Description: `Malloc` is the external declaration of the C librarys `malloc` call. It accepts a size parameter, and returns a pointer to a memory block of the requested size or `Nil` if no more memory could be allocated.

See also: `Free` ([477](#)), `ReAlloc` ([477](#))

6.4.4 ReAlloc

Synopsis: Reallocates a memory block

Declaration: `function ReAlloc(P: Pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAlloc` re-allocates a block of memory pointed to by `p`. The new block will have size `Size`, and as much data as was available or as much data as fits is copied from the old to the new location.

See also: `Malloc` ([477](#)), `Free` ([477](#))

Chapter 7

Reference for unit 'collation_de'

7.1 Used units

Table 7.1: Used units by unit 'collation_de'

Name	Page
System	1194

7.2 Overview

The `collation_de` unit registers the German Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 8

Reference for unit 'collation_es'

8.1 Used units

Table 8.1: Used units by unit 'collation_es'

Name	Page
System	1194

8.2 Overview

The `collation_es` unit registers the Spanish Unicode collation (de). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 9

Reference for unit 'collation_fr_ca'

9.1 Used units

Table 9.1: Used units by unit 'collation_fr_ca'

Name	Page
System	1194

9.2 Overview

The `collation_fr_ca` unit registers the French Unicode collation (fr). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 10

Reference for unit 'collation_ja'

10.1 Used units

Table 10.1: Used units by unit 'collation_ja'

Name	Page
System	1194

10.2 Overview

The `collation_ja` unit registers the Japanese Unicode collation (ja). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 11

Reference for unit 'collation_ko'

11.1 Used units

Table 11.1: Used units by unit 'collation_ko'

Name	Page
System	1194

11.2 Overview

The `collation_ko` unit registers the Korean Unicode collation (ko). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 12

Reference for unit 'collation_ru'

12.1 Used units

Table 12.1: Used units by unit 'collation_ru'

Name	Page
System	1194

12.2 Overview

The `collation_ru` unit registers the Russian Unicode collation (ru). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 13

Reference for unit 'collation_sv'

13.1 Used units

Table 13.1: Used units by unit 'collation_sv'

Name	Page
System	1194

13.2 Overview

The `collation_sv` unit registers the Swedish Unicode collation (sv). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 14

Reference for unit 'collation_zh'

14.1 Used units

Table 14.1: Used units by unit 'collation_zh'

Name	Page
System	1194

14.2 Overview

The `collation_zh` unit registers the Chinese Unicode collation (zh). This collation bases itself on the DUCET collation, so that collation will be included as well.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 15

Reference for unit 'cp1250'

15.1 Used units

Table 15.1: Used units by unit 'cp1250'

Name	Page
System	1194

15.2 Overview

The `cp1250` unit registers single-byte codepage 1250. This is necessary to convert single-byte strings using codepage 1250 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 16

Reference for unit 'cp1251'

16.1 Used units

Table 16.1: Used units by unit 'cp1251'

Name	Page
System	1194

16.2 Overview

The `cp1251` unit registers single-byte codepage 1251. This is necessary to convert single-byte strings using codepage 1251 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 17

Reference for unit 'cp1252'

17.1 Used units

Table 17.1: Used units by unit 'cp1252'

Name	Page
System	1194

17.2 Overview

The `cp1252` unit registers single-byte codepage 1252. This is necessary to convert single-byte strings using codepage 1252 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 18

Reference for unit 'cp1253'

18.1 Used units

Table 18.1: Used units by unit 'cp1253'

Name	Page
System	1194

18.2 Overview

The `cp1253` unit registers single-byte codepage 1253. This is necessary to convert single-byte strings using codepage 1253 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 19

Reference for unit 'cp1254'

19.1 Used units

Table 19.1: Used units by unit 'cp1254'

Name	Page
System	1194

19.2 Overview

The `cp1254` unit registers single-byte codepage 1254. This is necessary to convert single-byte strings using codepage 1254 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 20

Reference for unit 'cp1255'

20.1 Used units

Table 20.1: Used units by unit 'cp1255'

Name	Page
System	1194

20.2 Overview

The `cp1255` unit registers single-byte codepage 1255. This is necessary to convert single-byte strings using codepage 1255 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 21

Reference for unit 'cp1256'

21.1 Used units

Table 21.1: Used units by unit 'cp1256'

Name	Page
System	1194

21.2 Overview

The `cp1256` unit registers single-byte codepage 1256. This is necessary to convert single-byte strings using codepage 1256 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 22

Reference for unit 'cp1257'

22.1 Used units

Table 22.1: Used units by unit 'cp1257'

Name	Page
System	1194

22.2 Overview

The `cp1257` unit registers single-byte codepage 1257. This is necessary to convert single-byte strings using codepage 1257 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 23

Reference for unit 'cp1258'

23.1 Used units

Table 23.1: Used units by unit 'cp1258'

Name	Page
System	1194

23.2 Overview

The `cp1258` unit registers single-byte codepage 1258. This is necessary to convert single-byte strings using codepage 1258 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 24

Reference for unit 'cp437'

24.1 Used units

Table 24.1: Used units by unit 'cp437'

Name	Page
System	1194

24.2 Overview

The `cp437` unit registers single-byte codepage 437. This is necessary to convert single-byte strings using codepage 437 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 25

Reference for unit 'cp646'

25.1 Used units

Table 25.1: Used units by unit 'cp646'

Name	Page
System	1194

25.2 Overview

The `cp646` unit registers single-byte codepage 646. This is necessary to convert single-byte strings using codepage 646 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 26

Reference for unit 'cp850'

26.1 Used units

Table 26.1: Used units by unit 'cp850'

Name	Page
System	1194

26.2 Overview

The `cp850` unit registers single-byte codepage 850. This is necessary to convert single-byte strings using codepage 850 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 27

Reference for unit 'cp852'

27.1 Used units

Table 27.1: Used units by unit 'cp852'

Name	Page
System	1194

27.2 Overview

The `cp852` unit registers single-byte codepage 852. This is necessary to convert single-byte strings using codepage 852 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 28

Reference for unit 'cp856'

28.1 Used units

Table 28.1: Used units by unit 'cp856'

Name	Page
System	1194

28.2 Overview

The `cp856` unit registers single-byte codepage 856. This is necessary to convert single-byte strings using codepage 856 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 29

Reference for unit 'cp866'

29.1 Used units

Table 29.1: Used units by unit 'cp866'

Name	Page
System	1194

29.2 Overview

The `cp866` unit registers single-byte codepage 866. This is necessary to convert single-byte strings using codepage 866 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 30

Reference for unit 'cp874'

30.1 Used units

Table 30.1: Used units by unit 'cp874'

Name	Page
System	1194

30.2 Overview

The `cp874` unit registers single-byte codepage 874. This is necessary to convert single-byte strings using codepage 874 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 31

Reference for unit 'cp8859_1'

31.1 Used units

Table 31.1: Used units by unit 'cp8859_1'

Name	Page
System	1194

31.2 Overview

The `cp8859_1` unit registers single-byte codepage 8859-1. This is necessary to convert single-byte strings using codepage 8859-1 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 32

Reference for unit 'cp8859_2'

32.1 Used units

Table 32.1: Used units by unit 'cp8859_2'

Name	Page
System	1194

32.2 Overview

The `cp8859_2` unit registers single-byte codepage 8859-2. This is necessary to convert single-byte strings using codepage 8859-2 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 33

Reference for unit 'cp8859_5'

33.1 Used units

Table 33.1: Used units by unit 'cp8859_5'

Name	Page
System	1194

33.2 Overview

The `cp8859_5` unit registers single-byte codepage 8859-5. This is necessary to convert single-byte strings using codepage 8859-5 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 34

Reference for unit 'cp895'

34.1 Used units

Table 34.1: Used units by unit 'cp895'

Name	Page
System	1194

34.2 Overview

The `cp895` unit registers single-byte codepage 895. This is necessary to convert single-byte strings using codepage 895 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 35

Reference for unit 'cp932'

35.1 Used units

Table 35.1: Used units by unit 'cp932'

Name	Page
System	1194

35.2 Overview

The `cp932` unit registers single-byte codepage 932. This is necessary to convert single-byte strings using codepage 932 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the uses clause of the program is sufficient.

Chapter 36

Reference for unit 'cp936'

36.1 Used units

Table 36.1: Used units by unit 'cp936'

Name	Page
System	1194

36.2 Overview

The `cp936` unit registers single-byte codepage 936. This is necessary to convert single-byte strings using codepage 936 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 37

Reference for unit 'cp949'

37.1 Used units

Table 37.1: Used units by unit 'cp949'

Name	Page
System	1194

37.2 Overview

The `cp949` unit registers single-byte codepage 949. This is necessary to convert single-byte strings using codepage 949 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 38

Reference for unit 'cp950'

38.1 Used units

Table 38.1: Used units by unit 'cp950'

Name	Page
System	1194

38.2 Overview

The `cp950` unit registers single-byte codepage 950. This is necessary to convert single-byte strings using codepage 950 to unicode strings.

This unit does not contain any routines. It simply registers the code page data in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 39

Reference for unit 'cpall'

39.1 Used units

Table 39.1: Used units by unit 'cpall'

Name	Page
cp1250	486
cp1251	487
cp1252	488
cp1253	489
cp1254	490
cp1255	491
cp1256	492
cp1257	493
cp1258	494
cp437	495
cp646	496
cp850	497
cp852	498
cp856	499
cp866	500
cp874	501
cp8859_1	502
cp8859_2	503
cp8859_5	504
System	1194

39.2 Overview

The `cpall` unit registers all known single-byte codepages: 1251 ([510](#)), 866 ([510](#)), ISO 8856-5 ([510](#)) (cyrillic), 8859-1 ([510](#)), 8859-2 ([510](#)), 1253 ([510](#)) (greek), 850 ([510](#)), 437 ([510](#)), 1252 ([510](#)), 646 ([510](#)), 874 ([510](#)), 856 ([510](#)), 1250 ([510](#)), 1254 ([510](#)), 1255 ([510](#)), 1256 ([510](#)), 1257 ([510](#)), 1258 ([510](#)), 852 ([510](#)).

This unit does not contain any routines. It simply uses the other units so all corresponding code pages are registered.

Chapter 40

Reference for unit 'Crt'

40.1 Used units

Table 40.1: Used units by unit 'Crt'

Name	Page
System	1194

40.2 Overview

This chapter describes the CRT unit for Free Pascal, under all of Dos, Linux and Windows. The unit was first written for Dos by Florian Klaempfl. The unit was ported to Linux by Mark May and enhanced by Michael Van Canneyt and Peter Vreman. It works on the Linux console, and in xterm and rxvt windows under X-Windows. The functionality for both is the same, except that under Linux the use of an early implementation (versions 0.9.1 and earlier of the compiler) the CRT unit automatically cleared the screen at program startup.

There are some caveats when using the CRT unit:

- Programs using the CRT unit will *not* be usable when input/output is being redirected on the command-line.
- For similar reasons they are not usable as CGI-scripts for use with a webserver.
- The use of the CRT unit and the graph unit may not always be supported.
- The CRT unit is not thread safe.
- On Linux or other Unix OSes, executing other programs that expect special terminal behaviour (using one of the special functions in the Linux unit) will not work. The terminal is set in RAW mode, which will destroy most terminal emulation settings.
- The CRT unit stems from the TP/Dos area. It is designed to work with single-byte character sets, where 1 char = 1 byte. That means that widestrings or UTF-8 encoded (ansi)strings will not work correctly.

40.3 Constants, types and variables

40.3.1 Constants

`Black = 0`

Black color attribute

`Blink = 128`

Blink attribute

`Blue = 1`

Blue color attribute

`Brown = 6`

Brown color attribute

`BW40 = 0`

40 columns black and white screen mode.

`BW80 = 2`

80 columns black and white screen mode.

`C40 = CO40`

40 columns color screen mode.

`C80 = CO80`

80 columns color screen mode.

`CO40 = 1`

40 columns color screen mode.

`CO80 = 3`

80 columns color screen mode.

`ConsoleMaxX = 1024`

`ConsoleMaxY = 1024`

`Cyan = 3`

Cyan color attribute

DarkGray = 8

Dark gray color attribute

Flushing = False

Font8x8 = 256

Internal ROM font mode

Green = 2

Green color attribute

LightBlue = 9

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

Magenta = 5

Magenta color attribute

Mono = 7

Monochrome screen mode (hercules screens)

Red = 4

Red color attribute

```
ScreenHeight : LongInt = 25
```

Current screen height.

```
ScreenWidth : LongInt = 80
```

Current screen width

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

40.3.2 Types

```
tcrtcoord = 1..255
```

`tcrtcoord` is a subrange type for denoting CRT coordinates. It supports coordinates ranging from 1 to 255. Using this type together with range-checking turned on can be used to debug CRT code.

40.3.3 Variables

```
CheckBreak : Boolean
```

Check for CTRL-Break keystroke. Not used.

```
CheckEOF : Boolean
```

Check for EOF on standard input. Not used.

```
CheckSnow : Boolean
```

Check snow on CGA screens. Not used.

```
ConsoleBuf : PConsoleBuf
```

```
DirectVideo : Boolean
```

The `DirectVideo` variable controls the writing to the screen. If it is `True`, the cursor is set via direct port access. If `False`, then the BIOS is used. This is defined under dos only.

```
LastMode : Word = 3
```

The `Lastmode` variable tells you which mode was last selected for the screen. It is defined on DOS only.

`TextAttr : Byte = $07`

The `TextAttr` variable controls the attributes with which characters are written to screen.

`WindMax : Word = $184f`

The upper byte of `WindMax` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMaxX` and `WindMaxY` instead.

`WindMaxX : DWord`

X coordinate of lower right corner of the defined window

`WindMaxY : DWord`

Y coordinate of lower right corner of the defined window

`WindMin : Word = $0`

The upper byte of `WindMin` contains the Y coordinate while the lower byte contains the X coordinate. The use of this variable is deprecated, use `WindMinX` and `WindMinY` instead.

`WindMinX : DWord`

X coordinate of upper left corner of the defined window

`WindMinY : DWord`

Y coordinate of upper left corner of the defined window

40.4 Procedures and functions

40.4.1 AssignCrt

Synopsis: Assign file to CRT.

Declaration: `procedure AssignCrt (var F: Text)`

Visibility: default

Description: `AssignCrt` Assigns a file `F` to the console. Everything written to the file `F` goes to the console instead. If the console contains a window, everything is written to the window instead.

Errors: None.

See also: `Window` ([526](#))

Listing: `./crtex/ex1.pp`

```

Program Example1;
uses Crt;

{ Program to demonstrate the AssignCrt function. }

var
  F : Text;
begin
  AssignCrt(F);
  Rewrite(F); { Don't forget to open for output! }
  WriteLn(F, 'This is written to the Assigned File');
  Close(F);
end.

```

40.4.2 ClrEol

Synopsis: Clear from cursor position till end of line.

Declaration: `procedure ClrEol`

Visibility: default

Description: `ClrEol` clears the current line, starting from the cursor position, to the end of the window. The cursor doesn't move

Errors: None.

See also: `DelLine` ([518](#)), `InsLine` ([520](#)), `ClrScr` ([517](#))

Listing: `./crtex/ex9.pp`

```

Program Example9;
uses Crt;

{ Program to demonstrate the ClrEol function. }
var
  I,J : integer;

begin
  For I:=1 to 15 do
    For J:=1 to 80 do
      begin
        gotoxy(j,i);
        Write(j mod 10);
      end;
  Window(5,5,75,12);
  Write('This line will be cleared from',
        ' here till the right of the window');
  GotoXY(27,WhereY);
  ReadKey;
  ClrEol;
  WriteLn;
end.

```

40.4.3 ClrScr

Synopsis: Clear current window.

Declaration: `procedure ClrScr`

Visibility: default

Description: `ClrScr` clears the current window (using the current colors), and sets the cursor in the top left corner of the current window.

Errors: None.

See also: Window ([526](#))

Listing: `./crtex/ex8.pp`

```
Program Example8;  
uses Crt;  
  
  { Program to demonstrate the ClrScr function. }  
  
begin  
  WriteLn('Press any key to clear the screen');  
  ReadKey;  
  ClrScr;  
  WriteLn('Have fun with the cleared screen');  
end.
```

40.4.4 cursorbig

Synopsis: Show big cursor

Declaration: `procedure cursorbig`

Visibility: default

Description: `CursorBig` makes the cursor a big rectangle. Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([518](#)), `CursorOff` ([517](#))

40.4.5 cursoroff

Synopsis: Hide cursor

Declaration: `procedure cursoroff`

Visibility: default

Description: `CursorOff` switches the cursor off (i.e. the cursor is no longer visible). Not implemented on unixes.

Errors: None.

See also: `CursorOn` ([518](#)), `CursorBig` ([517](#))

40.4.6 cursoron

Synopsis: Display cursor

Declaration: `procedure cursoron`

Visibility: default

Description: `CursorOn` switches the cursor on. Not implemented on unixes.

Errors: None.

See also: `CursorBig` ([517](#)), `CursorOff` ([517](#))

40.4.7 Delay

Synopsis: Delay program execution.

Declaration: `procedure Delay (MS: Word)`

Visibility: default

Description: `Delay` waits a specified number of milliseconds. The number of specified seconds is an approximation, and may be off a lot, if system load is high.

Errors: None

See also: `Sound` ([523](#)), `NoSound` ([522](#))

Listing: `./crtex/ex15.pp`

```

Program Example15;
uses Crt;

{ Program to demonstrate the Delay function. }
var
  i : longint;
begin
  WriteLn('Counting Down');
  for i:=10 downto 1 do
    begin
      WriteLn(i);
      Delay(1000); { Wait one second }
    end;
  WriteLn('BOOM!!!');
end.
```

40.4.8 DelLine

Synopsis: Delete line at cursor position.

Declaration: `procedure DelLine`

Visibility: default

Description: `DelLine` removes the current line. Lines following the current line are scrolled 1 line up, and an empty line is inserted at the bottom of the current window. The cursor doesn't move.

Errors: None.

See also: [ClrEol \(516\)](#), [InsLine \(520\)](#), [ClrScr \(517\)](#)

Listing: ./crtex/ex11.pp

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 2');
  WriteLn('Line 2');
  WriteLn('Line 3');
  WriteLn;
  WriteLn('Oops, Line 2 is listed twice,',
          ' let''s delete the line at the cursor position');
  GotoXY(1,3);
  ReadKey;
  DelLine;
  GotoXY(1,10);
end.

```

40.4.9 GotoXY

Synopsis: Set cursor position on screen.

Declaration: `procedure GotoXY(X: tcoord; Y: tcoord)`

Visibility: default

Description: `GotoXY` positions the cursor at (X, Y), X in horizontal, Y in vertical direction relative to the origin of the current window. The origin is located at (1, 1), the upper-left corner of the window.

Errors: None.

See also: [WhereX \(525\)](#), [WhereY \(525\)](#), [Window \(526\)](#)

Listing: ./crtex/ex6.pp

```

Program Example6;
uses Crt;

{ Program to demonstrate the GotoXY function. }

begin
  ClrScr;
  GotoXY(10,10);
  Write('10,10');
  GotoXY(70,20);
  Write('70,20');
  GotoXY(1,22);
end.

```

40.4.10 HighVideo

Synopsis: Switch to highlighted text mode

Declaration: `procedure HighVideo`

Visibility: default

Description: `HighVideo` switches the output to highlighted text. (It sets the high intensity bit of the video attribute)

Errors: None.

See also: `TextColor` (524), `TextBackground` (523), `LowVideo` (521), `NormVideo` (522)

Listing: `./crtex/ex14.pp`

```

Program Example14;
uses Crt;

{ Program to demonstrate the LowVideo, HighVideo, NormVideo functions. }

begin
  LowVideo;
  WriteLn('This is written with LowVideo');
  HighVideo;
  WriteLn('This is written with HighVideo');
  NormVideo;
  WriteLn('This is written with NormVideo');
end.

```

40.4.11 InsLine

Synopsis: Insert an empty line at cursor position

Declaration: `procedure InsLine`

Visibility: default

Description: `InsLine` inserts an empty line at the current cursor position. Lines following the current line are scrolled 1 line down, causing the last line to disappear from the window. The cursor doesn't move.

Errors: None.

See also: `ClrEol` (516), `DelLine` (518), `ClrScr` (517)

Listing: `./crtex/ex10.pp`

```

Program Example10;
uses Crt;

{ Program to demonstrate the InsLine function. }

begin
  ClrScr;
  WriteLn;
  WriteLn('Line 1');
  WriteLn('Line 3');
  WriteLn;

```

```

WriteLn('Oops, forgot Line 2, let''s insert at the cursor postion');
GotoXY(1,3);
ReadKey;
InsLine;
Write('Line 2');
GotoXY(1,10);
end.

```

40.4.12 KeyPressed

Synopsis: Check if there is a keypress in the keybuffer

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` scans the keyboard buffer and sees if a key has been pressed. If this is the case, `True` is returned. If not, `False` is returned. The `Shift`, `Alt`, `Ctrl` keys are not reported. The key is not removed from the buffer, and can hence still be read after the `KeyPressed` function has been called.

Errors: None.

See also: `ReadKey` ([522](#))

Listing: `./crtex/ex2.pp`

```

Program Example2;
uses Crt;

{ Program to demonstrate the KeyPressed function. }

begin
  WriteLn('Waiting until a key is pressed');
  repeat
    until KeyPressed;
  { The key is not Read,
    so it should also be outputted at the commandline}
end.

```

40.4.13 LowVideo

Synopsis: Switch to low intensity colors.

Declaration: `procedure LowVideo`

Visibility: default

Description: `LowVideo` switches the output to non-highlighted text. (It clears the high intensity bit of the video attribute)

For an example, see `HighVideo` ([520](#))

Errors: None.

See also: `TextColor` ([524](#)), `TextBackground` ([523](#)), `HighVideo` ([520](#)), `NormVideo` ([522](#))

40.4.14 NormVideo

Synopsis: Return to normal (startup) modus

Declaration: `procedure NormVideo`

Visibility: default

Description: `NormVideo` switches the output to the defaults, read at startup. (The defaults are read from the cursor position at startup)

For an example, see `HighVideo` ([520](#))

Errors: None.

See also: `TextColor` ([524](#)), `TextBackground` ([523](#)), `LowVideo` ([521](#)), `HighVideo` ([520](#))

40.4.15 NoSound

Synopsis: Stop system speaker

Declaration: `procedure NoSound`

Visibility: default

Description: `NoSound` stops the speaker sound. This call is not supported on all operating systems.

Errors: None.

See also: `Sound` ([523](#))

Listing: `./crtex/ex16.pp`

```

Program Example16;
uses Crt;

{ Program to demonstrate the Sound and NoSound function. }

var
  i : longint;
begin
  WriteLn('You will hear some tones from your speaker');
  i:=0;
  while (i<15000) do
    begin
      inc(i,500);
      Sound(i);
      Delay(100);
    end;
  WriteLn('Quiet now!');
  NoSound; {Stop noise}
end.
```

40.4.16 ReadKey

Synopsis: Read key from keybuffer

Declaration: `function ReadKey : Char`

Visibility: default

Description: `ReadKey` reads 1 key from the keyboard buffer, and returns this. If an extended or function key has been pressed, then the zero ASCII code is returned. You can then read the scan code of the key with a second `ReadKey` call.

Key mappings under Linux can cause the wrong key to be reported by `ReadKey`, so caution is needed when using `ReadKey`.

Errors: None.

See also: `KeyPressed` ([521](#))

Listing: `./crtex/ex3.pp`

```
Program Example3;
uses Crt;

{ Program to demonstrate the ReadKey function. }

var
  ch : char;
begin
  writeln( 'Press Left/Right , Esc=Quit ' );
  repeat
    ch:=ReadKey;
    case ch of
      #0 : begin
        ch:=ReadKey; {Read ScanCode}
        case ch of
          #75 : WriteLn( ' Left ' );
          #77 : WriteLn( ' Right ' );
        end;
      end;
      #27 : WriteLn( 'ESC' );
    end;
  until ch=#27 {Esc}
end.
```

40.4.17 Sound

Synopsis: Sound system speaker

Declaration: `procedure Sound(Hz: Word)`

Visibility: default

Description: `Sound` sounds the speaker at a frequency of `hz`. Under Windows, a system sound is played and the frequency parameter is ignored. On other operating systems, this routine may not be implemented.

Errors: None.

See also: `NoSound` ([522](#))

40.4.18 TextBackground

Synopsis: Set text background

Declaration: `procedure TextBackground(Color: Byte)`

Visibility: default

Description: `TextBackground` sets the background color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextColor` ([524](#)), `HighVideo` ([520](#)), `LowVideo` ([521](#)), `NormVideo` ([522](#))

Listing: `./crtex/ex13.pp`

```
Program Example13;
uses Crt;

{ Program to demonstrate the TextBackground function. }

begin
  TextColor(White);
  WriteLn('This is written in with the default background color');
  TextBackground(Green);
  WriteLn('This is written in with a Green background');
  TextBackground(Brown);
  WriteLn('This is written in with a Brown background');
  TextBackground(Black);
  WriteLn('Back with a black background');
end.
```

40.4.19 TextColor

Synopsis: Set text color

Declaration: `procedure TextColor(Color: Byte)`

Visibility: default

Description: `TextColor` sets the foreground color to CL. CL can be one of the predefined color constants.

Errors: None.

See also: `TextBackground` ([523](#)), `HighVideo` ([520](#)), `LowVideo` ([521](#)), `NormVideo` ([522](#))

Listing: `./crtex/ex12.pp`

```
Program Example12;
uses Crt;

{ Program to demonstrate the TextColor function. }

begin
  WriteLn('This is written in the default color');
  TextColor(Red);
  WriteLn('This is written in Red');
  TextColor(White);
  WriteLn('This is written in White');
  TextColor(LightBlue);
  WriteLn('This is written in Light Blue');
end.
```

40.4.20 TextMode

Synopsis: Set screen mode.

Declaration: `procedure TextMode (Mode: Word)`

Visibility: default

Description: `TextMode` sets the textmode of the screen (i.e. the number of lines and columns of the screen). The lower byte is use to set the VGA text mode.

This procedure is only implemented on dos.

Errors: None.

See also: `Window` ([526](#))

40.4.21 WhereX

Synopsis: Return X (horizontal) cursor position

Declaration: `function WhereX : tcrtcoord`

Visibility: default

Description: `WhereX` returns the current X-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` ([519](#)), `WhereY` ([525](#)), `Window` ([526](#))

Listing: `./crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn ( 'Cursor postion: X= ',WhereX, ' Y= ',WhereY );
end.
```

40.4.22 WhereY

Synopsis: Return Y (vertical) cursor position

Declaration: `function WhereY : tcrtcoord`

Visibility: default

Description: `WhereY` returns the current Y-coordinate of the cursor, relative to the current window. The origin is (1, 1), in the upper-left corner of the window.

Errors: None.

See also: `GotoXY` ([519](#)), `WhereX` ([525](#)), `Window` ([526](#))

Listing: `./crtex/ex7.pp`

```

Program Example7;
uses Crt;

{ Program to demonstrate the WhereX and WhereY functions. }

begin
  WriteLn('Cursor position: X= ',WhereX, ' Y= ',WhereY);
end.

```

40.4.23 Window

Synopsis: Create new window on screen.

Declaration: `procedure Window(X1: Byte; Y1: Byte; X2: Byte; Y2: Byte)`

Visibility: default

Description: `Window` creates a window on the screen, to which output will be sent. (X1, Y1) are the coordinates of the upper left corner of the window, (X2, Y2) are the coordinates of the bottom right corner of the window. These coordinates are relative to the entire screen, with the top left corner equal to (1, 1). Further coordinate operations, except for the next `Window` call, are relative to the window's top left corner.

Errors: None.

See also: `GotoXY` ([519](#)), `WhereX` ([525](#)), `WhereY` ([525](#)), `ClrScr` ([517](#))

Listing: `./crtex/ex5.pp`

```

Program Example5;
uses Crt;

{ Program to demonstrate the Window function. }

begin
  ClrScr;
  WriteLn('Creating a window from 30,10 to 50,20');
  Window(30,10,50,20);
  WriteLn('We are now writing in this small window we just created, we '+
    'can''t get outside it when writing long lines like this one');
  Write('Press any key to clear the window');
  ReadKey;
  ClrScr;
  Write('The window is cleared, press any key to restore to fullscreen');
  ReadKey;
  { Full Screen is 80x25 }
  Window(1,1,80,25);
  Clrscr;
  WriteLn('Back in Full Screen');
end.

```

Chapter 41

Reference for unit 'cthreads'

41.1 Used units

Table 41.1: Used units by unit 'cthreads'

Name	Page
System	1194

41.2 Overview

The `CThreads` unit initializes the system unit's thread management routines with an implementation based on the POSIX thread managing routines in the C library. This assures that C libraries that are thread-aware still work if they are linked to by a FPC program.

It doesn't offer any API by itself: the initialization section of the unit just initializes the `ThreadManager` record in the `System` ([1194](#)) unit. This is done using the `SetCThreadManager` ([528](#)) call

The `cthreads` unit simply needs to be included in the `uses` clause of the program, preferably the very first unit, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-posix system: Windows, OS/2 or DOS, therefor it should always be between an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cthreads{$endif},
  classes, sysutils;
```

The Lazarus IDE inserts this conditional automatically for each new started program.

41.3 Procedures and functions

41.3.1 SetCThreadManager

Synopsis: Sets the thread manager to the C thread manager

Declaration: `procedure SetCThreadManager`

Visibility: `default`

Description: `SetCThreadManager` actually sets the thread manager to the C thread manager. It can be called to re-set the thread manager if the thread manager was set to some other thread manager during the life-time of the program.

Chapter 42

Reference for unit 'ctypes'

42.1 Used units

Table 42.1: Used units by unit 'ctypes'

Name	Page
System	1194
unixtype	1879

42.2 Overview

The `ctypes` unit contains the definitions of commonly found C types. It can be used when interfaces to C libraries need to be defined. The types here are correct on all platforms, 32 or 64 bit.

The main advantage of using this file is to make sure that all C header import units use the same definitions for basic C types.

The `h2pas` program can include the `ctypes` unit automatically in the units it generates. The `-C` command-line switch can be used for this.

42.3 Constants, types and variables

42.3.1 Types

```
cbool = UnixType.cbool
```

C boolean (longbool)

```
cchar = UnixType.cchar
```

C character type (No signedness specification, 8 bit integer)

```
cdouble = UnixType.cdouble
```

Double precision floating point type (double)

`cfloat = UnixType.cfloat`

Single precision floating point type (single)

`cint = UnixType.cint`

C integer (commonly 32 bit)

`cint16 = UnixType.cint16`

16-bit signed integer.

`cint32 = UnixType.cint32`

32-bit signed integer (commonly: int)

`cint64 = UnixType.cint64`

64-bit integer

`cint8 = UnixType.cint8`

8-bit signed integer

`clong = UnixType.clong`

long integer (32/64 bit, depending on CPU register size)

`clongdouble = Double`

Long precision floating point type (extended/double, depending on CPU)

`clonglong = UnixType.clonglong`

Long (64-bit) integer

`coff_t = UnixType.TOff`

Generic type to indicate offset

`cschar = UnixType.cschar`

C signed character type (8 bit signed integer)

`cshort = UnixType.cshort`

Short integer (16 bit)

`csigned = UnixType.csigned`

Signed integer (commonly 32 bit)

`csint = UnixType.csint`

Signed integer (commonly 32 bit)

`csize_t = UnixType.size_t`

Generic type to contain a size of all kinds of structures

`cslong = UnixType.cslong`

Signed long integer (32/64 bit, depending on CPU register size)

`cslonglong = UnixType.cslonglong`

Signed long (64-bit) integer

`csshort = UnixType.csshort`

Short signed integer (16 bit)

`cuchar = UnixType.cuchar`

C unsigned character type (8 bit unsigned integer).

`cuint = UnixType.cuint`

Unsigned integer (commonly 32 bit)

`cuint16 = UnixType.cuint16`

16-bit unsigned integer.

`cuint32 = UnixType.cuint32`

32-bit unsigned integer

`cuint64 = UnixType.cuint64`

Unsigned 64-bit integer

`cuint8 = UnixType.cuint8`

8-bit unsigned integer

`culong = UnixType.culong`

Unsigned long integer (32/64 bit, depending on CPU register size)

`culonglong = UnixType.culonglong`

Unsigned long (64-bit) integer

`cunsigned = UnixType.cunsigned`

Unsigned integer (commonly 32 bit)

`cushort = UnixType.cushort`

Short unsigned integer (16 bit)

`pcbool = UnixType.pcbbool`

Pointer to `cbool` (529) type.

`pcchar = UnixType.pcchar`

Pointer to `cchar` (529) type.

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (529) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (530) type.

`pcint = UnixType.pcint`

Pointer to `cint` (530) type.

`pcint16 = UnixType.pcint16`

Pointer to `cint16` (530) type.

`pcint32 = UnixType.pcint32`

Pointer to `cint32` (530) type.

`pcint64 = UnixType.pcint64`

Pointer to `cint64` (530) type.

`pcint8 = UnixType.pcint8`

Pointer to `cint8` (530) type.

`pclong = UnixType.pclong`

Pointer to `clong` (530) type.

`pclongdouble = ^clongdouble`

Pointer to `clongdouble` (530) type.

`pclonglong = UnixType.pclonglong`

Pointer to `clonglong` (530) type.

`pcschar = UnixType.pcschar`

Pointer to `cschar` (530) type.

`pcshort = UnixType.pcsshort`

Pointer to `cshort` (530) type.

`pcsigned = UnixType.pcsigned`

Pointer to `csigned` (530) type.

`pcsint = UnixType.pcsint`

Pointer to `csint` (531) type.

`pcsize_t = UnixType.psize_t`

Pointer to generic size type

`pcslong = UnixType.pcslong`

Pointer to `clong` (531) type.

`pcslonglong = UnixType.pcslonglong`

Pointer to `cslonglong` (531) type.

`pcsshort = UnixType.pcsshort`

Pointer to `csshort` (531) type.

`pcuchar = UnixType.pcuchar`

Pointer to `cuchar` (531) type.

`pcuint = UnixType.pcuint`

Pointer to `cuint` (531) type.

`pcuint16 = UnixType.pcuint16`

Pointer to `cuint16` (531) type.

`pcuint32 = UnixType.pcuint32`

Pointer to `cuint32` (531) type.

`pcuint64 = UnixType.pcuint64`

Pointer to `cuint64` (531) type.

`pcuint8 = UnixType.pcuint8`

Pointer to `cuint8` (531) type.

`pculong = UnixType.pculong`

Pointer to `culong` (531) type.

`pculonglong = UnixType.pculonglong`

Pointer to `culonglong` (531) type.

`pcunsigned = UnixType.punsigned`

Pointer to `cunsigned` (532) type.

`pcushort = UnixType.pcushort`

Pointer to `cushort` (532) type.

Chapter 43

Reference for unit 'cwstring'

43.1 Used units

Table 43.1: Used units by unit 'cwstring'

Name	Page
System	1194

43.2 Overview

The `cwstring` unit offers no API by itself: it just initializes the widestring manager record of the `system` ([1194](#)) unit with an implementation that uses collation and conversion routines which are provided by the C library found on most Unix or Linux systems that are POSIX compliant.

The `cwstring` should simply be included in the `uses` clause of the program, preferably as one of the first units, and the initialization section of the unit will do all the work.

Note that including this unit links your program to the C library of the system.

It makes no sense to use this unit on a non-POSIX system like Windows, OS/2 or DOS. Therefore it should always be enclosed with an `ifdef` statement:

```
program myprogram;

uses
  {$ifdef unix}cwstring, {$endif}
  classes, sysutils;
```

43.3 Procedures and functions

43.3.1 SetCWidestringManager

Synopsis: Set the Widestring manager of the system unit to the C version

Declaration: `procedure SetCWidestringManager`

Visibility: `default`

Description: `SetCWidestringManager` actually sets the widestring manager record of the system unit. It is called automatically by the initialization section of the unit.

Chapter 44

Reference for unit 'dateutils'

44.1 Used units

Table 44.1: Used units by unit 'dateutils'

Name	Page
math	900
System	1194
sysutils	1442

44.2 Overview

`DateUtils` contains a large number of date/time manipulation routines, all based on the `TDateTime` type. There are routines for date/time math, for comparing dates and times, for composing dates and decomposing dates in their constituent parts.

44.3 Constants, types and variables

44.3.1 Constants

`ApproxDaysPerMonth : Double = 30.4375`

Average number of days in a month, measured over a year. Used in `MonthsBetween` ([584](#)).

`ApproxDaysPerYear : Double = 365.25`

Average number of days in a year, measured over 4 years. Used in `YearsBetween` ([626](#)).

`DayFriday = 5`

ISO day number for Friday

`DayMonday = 1`

ISO day number for Monday

DaySaturday = 6

ISO day number for Saturday

DaysPerWeek = 7

Number of days in a week.

DaysPerYear : Array[Boolean] of Word = (365, 366)

Array with number of days in a year. The boolean index indicates whether it is a leap year or not.

DaySunday = 7

ISO day number for Sunday

DayThursday = 4

ISO day number for Thursday

DayTuesday = 2

ISO day number for Tuesday

DayWednesday = 3

ISO day number for Wednesday

MonthsPerYear = 12

Number of months in a year

OneHour = (1) / HoursPerDay

One hour as a fraction of a day (suitable for TDateTime)

OneMillisecond = (1) / MSecsPerDay

One millisecond as a fraction of a day (suitable for TDateTime)

OneMinute = (1) / MinsPerDay

One minute as a fraction of a day (suitable for TDateTime)

OneSecond = (1) / SecsPerDay

One second as a fraction of a day (suitable for TDateTime)

RecodeLeaveFieldAsIs = (Word)

Bitmask deciding what to do with each TDateTime field in recode routines

WeeksPerFortnight = 2

Number of weeks in fortnight

YearsPerCentury = 100

Number of years in a century

YearsPerDecade = 10

Number of years in a decade

YearsPerMillennium = 1000

Number of years in a millenium

44.4 Procedures and functions

44.4.1 CompareDate

Synopsis: Compare 2 dates, disregarding the time of day

Declaration: `function CompareDate(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareDate` compares the date parts of two timestamps A and B and returns the following results:

< 0 if the day part of A is earlier than the day part of B.

0 if A and B are the on same day (times may differ) .

> 0 if the day part of A is later than the day part of B.

See also: `CompareTime` (541), `CompareDateTime` (540), `SameDate` (594), `SameTime` (596), `SameDateTime` (595)

Listing: ./datutex/ex99.pp

Program Example99;

{ This program demonstrates the CompareDate function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy';

Procedure Test(D1,D2 : TDateTime);

Var

Cmp : Integer;

```

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDate(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.2 CompareDateTime

Synopsis: Compare 2 dates, taking into account the time of day

Declaration: `function CompareDateTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: CompareDateTime compares two timestamps A and B and returns the following results:

- < 0 if A is earlier in date/time than B.
- 0 if A and B are the same date/time .
- > 0 if A is later in date/time than B.

See also: CompareTime (541), CompareDate (539), SameDate (594), SameTime (596), SameDateTime (595)

Listing: ./datutex/ex98.pp

Program Example98;

{ This program demonstrates the CompareDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

```

Procedure Test(D1,D2 : TDateTime);

Var
  Cmp : Integer;

begin
  Write(FormatDateTime(Fmt,D1), ' is ');
  Cmp:=CompareDateTime(D1,D2);
  If Cmp<0 then
    write('earlier than ')
  else if Cmp>0 then
    Write('later than ')
  else
    Write('equal to ');
  WriteIn(FormatDateTime(Fmt,D2));
end;

Var
  D,N : TDateTime;

Begin
  D:=Today;
  N:=Now;
  Test(D,D);
  Test(N,N);
  Test(D+1,D);
  Test(D-1,D);
  Test(D+OneSecond,D);
  Test(D-OneSecond,D);
  Test(N+OneSecond,N);
  Test(N-OneSecond,N);
End.

```

44.4.3 CompareTime

Synopsis: Compares two times of the day, disregarding the date part.

Declaration: `function CompareTime(const A: TDateTime; const B: TDateTime)
: TValueRelationship`

Visibility: default

Description: `CompareTime` compares the time parts of two timestamps A and B and returns the following results:

< 0 if the time part of A is earlier than the time part of B.

0 if A and B have the same time part (dates may differ) .

> 0 if the time part of A is later than the time part of B.

See also: `CompareDateTime` (540), `CompareDate` (539), `SameDate` (594), `SameTime` (596), `SameDateTime` (595)

Listing: `./datutex/ex100.pp`

```

Program Example100;

{ This program demonstrates the CompareTime function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

Var
    Cmp : Integer;

begin
    Write(FormatDateTime(Fmt,D1), ' has ');
    Cmp:=CompareDateTime(D1,D2);
    If Cmp<0 then
        write('earlier time than ')
    else if Cmp>0 then
        Write('later time than ')
    else
        Write('equal time with ');
    WriteIn(FormatDateTime(Fmt,D2));
end;

Var
    D,N : TDateTime;

Begin
    D:=Today;
    N:=Now;
    Test(D,D);
    Test(N,N);
    Test(N+1,N);
    Test(N-1,N);
    Test(N+OneSecond,N);
    Test(N-OneSecond,N);
End.

```

44.4.4 DateOf

Synopsis: Extract the date part from a DateTime indication.

Declaration: `function DateOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: DateOf extracts the date part from AValue and returns the result.

Since the TDateTime is actually a double with the date part encoded in the integer part, this operation corresponds to a call to Trunc.

See also: TimeOf ([605](#)), YearOf ([625](#)), MonthOf ([583](#)), DayOf ([544](#)), HourOf ([559](#)), MinuteOf ([579](#)), SecondOf ([597](#)), MilliSecondOf ([575](#))

Listing: ./datutex/ex1.pp

Program Example1;

{ This program demonstrates the DateOf function }

Uses SysUtils, DateUtils;

Begin

 WriteLn('Date is: ', DateTimeToStr(DateOf(Now)));

End.

44.4.5 DateTimeToDosDateTime

Synopsis: Convert TDateTime format to DOS date/time format

Declaration: function DateTimeToDosDateTime(const AValue: TDateTime) : LongInt

Visibility: default

Description: DateTimeToDosDatetime takes Value, a TDateTime formatted timestamp, and recodes it to a MS-DOS encoded date/time value. This is a longint with the date/time encoded in the bits as:

0-4Seconds divided by 2

5-10Minutes

11-15Hours

16-20Day

21-24Month

25-31Years since 1980

See also: DosDateTimeToDateTime ([552](#))

44.4.6 DateTimeToJulianDate

Synopsis: Converts a TDateTime value to a Julian date representation

Declaration: function DateTimeToJulianDate(const AValue: TDateTime) : Double

Visibility: default

Description: DateTimeToJulianDate converts the AValue date/time indication to a julian (as opposed to Gregorian) date.

See also: JulianDateToDateTime ([574](#)), TryJulianDateToDateTime ([610](#)), DateTimeToModifiedJulianDate ([544](#)), TryModifiedJulianDateToDateTime ([611](#))

44.4.7 DateTimeToMac

Synopsis: Convert a TDateTime timestamp to a Mac timestamp

Declaration: function DateTimeToMac(const AValue: TDateTime) : Int64

Visibility: default

Description: DateTimeToMac converts the TDateTime value AValue to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: UnixTimeStampToMac ([612](#)), MacToDateTime ([575](#)), MacTimeStampToUnix ([575](#))

44.4.8 DateTimeToModifiedJulianDate

Synopsis: Convert a `TDateTime` value to a modified Julian date representation

Declaration: `function DateTimeToModifiedJulianDate(const AValue: TDateTime) : Double`

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: `DateTimeToJulianDate` (543), `JulianDateToDateTime` (574), `TryJulianDateToDateTime` (610), `TryModifiedJulianDateToDateTime` (611)

44.4.9 DateTimeToUnix

Synopsis: Convert a `TDateTime` value to Unix epoch time

Declaration: `function DateTimeToUnix(const AValue: TDateTime) : Int64`

Visibility: default

Description: `DateTimeToUnix` converts a `TDateTime` value to a epoch time (i.e. the number of seconds elapsed since 1/1/1970).

See also: `UnixToDateTime` (612)

44.4.10 DayOf

Synopsis: Extract the day (of month) part from a `DateTime` value

Declaration: `function DayOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOf` returns the day of the month part of the `AValue` date/time indication. It is a number between 1 and 31.

For an example, see `YearOf` (625)

See also: `YearOf` (625), `WeekOf` (613), `MonthOf` (583), `HourOf` (559), `MinuteOf` (579), `SecondOf` (597), `MilliSecondOf` (575)

44.4.11 DayOfTheMonth

Synopsis: Extract the day (of month) part of a `DateTime` value

Declaration: `function DayOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheMonth` returns the number of days that have passed since the start of the month till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the month will return 1.

For an example, see the `WeekOfTheMonth` (613) function.

See also: `DayOfTheYear` (545), `WeekOfTheMonth` (613), `HourOfTheMonth` (560), `MinuteOfTheMonth` (581), `SecondOfTheMonth` (598), `MilliSecondOfTheMonth` (576)

44.4.12 DayOfTheWeek

Synopsis: Extracts the day of the week from a `DateTime` value

Declaration: `function DayOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheWeek` returns the number of days that have passed since the start of the week till the moment indicated by `AValue`. This is a one-based number, i.e. the first day of the week will return 1.

See also: `DayOfTheYear` (545), `DayOfTheMonth` (544), `HourOfTheWeek` (560), `MinuteOfTheWeek` (581), `SecondOfTheWeek` (598), `MilliSecondOfTheWeek` (577)

Listing: `./datutex/ex42.pp`

Program Example42;

{ This program demonstrates the WeekOfTheMonth function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Day of the Week : ', DayOfTheWeek(N));

WriteLn('Hour of the Week : ', HourOfTheWeek(N));

WriteLn('Minute of the Week : ', MinuteOfTheWeek(N));

WriteLn('Second of the Week : ', SecondOfTheWeek(N));

WriteLn('MilliSecond of the Week : ',
MilliSecondOfTheWeek(N));

End.

44.4.13 DayOfTheYear

Synopsis: Extracts the day of the year from a `TDateTime` value

Declaration: `function DayOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `DayOfTheYear` returns the number of days that have passed since the start of the year till the moment indicated by `AValue`. This is a one-based number, i.e. January 1 will return 1.

For an example, see the `WeekOfTheYear` (614) function.

See also: `WeekOfTheYear` (614), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.14 DaysBetween

Synopsis: Number of whole days between two `DateTime` values.

Declaration: `function DaysBetween(const ANow: TDateTime; const AThen: TDateTime)
: Integer`

Visibility: default

Description: `DaysBetween` returns the number of whole days between `ANow` and `AThen`. This means the fractional part of a day (hours, minutes, etc.) is dropped.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `HoursBetween` (561), `MinutesBetween` (581), `SecondsBetween` (599), `MillisecondsBetween` (578)

Listing: `./datutex/ex58.pp`

Program `Example58`;

{ This program demonstrates the DaysBetween function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime)`;

begin

`Write('Number of days between ');`

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`WriteLn(' : ', DaysBetween(ANow, AThen));`

end;

Var

`D1, D2 : TDateTime`;

Begin

`D1 := Now;`

`D2 := Today - 23/24;`

`Test(D1, D2);`

`D2 := Today - 1;`

`Test(D1, D2);`

`D2 := Today - 25/24;`

`Test(D1, D2);`

`D2 := Today - 26/24;`

`Test(D1, D2);`

`D2 := Today - 5.4;`

`Test(D1, D2);`

`D2 := Today - 2.5;`

`Test(D1, D2);`

End.

44.4.15 DaysInAMonth

Synopsis: Number of days in a month of a certain year.

Declaration: `function DaysInAMonth(const AYear: Word; const AMonth: Word) : Word`

Visibility: default

Description: `DaysInMonth` returns the number of days in the month `AMonth` in the year `AYear`. The return value takes leap years into account.

See also: `WeeksInAYear` (615), `WeeksInYear` (616), `DaysInYear` (548), `DaysInAYear` (547), `DaysInMonth` (547)

Listing: `./datutex/ex17.pp`

```

Program Example17;

{ This program demonstrates the DaysInAMonth function }

Uses SysUtils, DateUtils;

Var
    Y,M : Word;

Begin
    For Y:=1992 to 2010 do
        For M:=1 to 12 do
            WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInAMonth(Y,M), ' days. ');
End.

```

44.4.16 DaysInAYear

Synopsis: Number of days in a particular year.

Declaration: `function DaysInAYear(const AYear: Word) : Word`

Visibility: default

Description: `DaysInAYear` returns the number of weeks in the year `AYear`. The return value is either 365 or 366.

See also: `WeeksInAYear` ([615](#)), `WeeksInYear` ([616](#)), `DaysInYear` ([548](#)), `DaysInMonth` ([547](#)), `DaysInAMonth` ([546](#))

Listing: `./datutex/ex15.pp`

```

Program Example15;

{ This program demonstrates the DaysInAYear function }

Uses SysUtils, DateUtils;

Var
    Y : Word;

Begin
    For Y:=1992 to 2010 do
        WriteLn(Y, ' has ', DaysInAYear(Y), ' days. ');
End.

```

44.4.17 DaysInMonth

Synopsis: Return the number of days in the month in which a date occurs.

Declaration: `function DaysInMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `DaysInMonth` returns the number of days in the month in which `AValue` falls. The return value takes leap years into account.

See also: [WeeksInAYear \(615\)](#), [WeeksInYear \(616\)](#), [DaysInYear \(548\)](#), [DaysInAYear \(547\)](#), [DaysInAMonth \(546\)](#)

Listing: ./datutex/ex16.pp

Program Example16;

{ This program demonstrates the DaysInMonth function }

Uses SysUtils, DateUtils;

Var

Y,M : Word;

Begin

For Y:=1992 to 2010 do

For M:=1 to 12 do

WriteLn(LongMonthNames[m], ' ', Y, ' has ', DaysInMonth(EncodeDate(Y,M,1)), ' days.');

End.

44.4.18 DaysInYear

Synopsis: Return the number of days in the year in which a date occurs.

Declaration: function DaysInYear(const AValue: TDateTime) : Word

Visibility: default

Description: daysInYear returns the number of days in the year part of AValue. The return value is either 365 or 366.

See also: [WeeksInAYear \(615\)](#), [WeeksInYear \(616\)](#), [DaysInAYear \(547\)](#), [DaysInMonth \(547\)](#), [DaysInAMonth \(546\)](#)

Listing: ./datutex/ex14.pp

Program Example14;

{ This program demonstrates the DaysInYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', DaysInYear(EncodeDate(Y,1,1)), ' days.');

End.

44.4.19 DaySpan

Synopsis: Calculate the approximate number of days between two DateTime values.

Declaration: function DaySpan(const ANow: TDateTime; const AThen: TDateTime) : Double

Visibility: default

Description: `DaySpan` returns the number of Days between `ANow` and `AThen`, including any fractional parts of a Day.

See also: `YearSpan` (627), `MonthSpan` (585), `WeekSpan` (616), `HourSpan` (562), `MinuteSpan` (582), `SecondSpan` (600), `MilliSecondSpan` (579), `DaysBetween` (545)

Listing: `./datutex/ex66.pp`

Program `Example66`;

{ This program demonstrates the DaySpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin

`Write('Number of days between ');`

`Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));`

`WriteLn(' : ', DaySpan(ANow, AThen));`

end;

Var

`D1, D2 : TDateTime;`

Begin

`D1:=Now;`

`D2:=Today-23/24;`

`Test(D1, D2);`

`D2:=Today-1;`

`Test(D1, D2);`

`D2:=Today-25/24;`

`Test(D1, D2);`

`D2:=Today-26/24;`

`Test(D1, D2);`

`D2:=Today-5.4;`

`Test(D1, D2);`

`D2:=Today-2.5;`

`Test(D1, D2);`

End.

44.4.20 DecodeDateDay

Synopsis: Decode a `DateTime` value in year and year of day.

Declaration: `procedure DecodeDateDay(const AValue: TDateTime; out AYear: Word;
out ADayOfYear: Word)`

Visibility: default

Description: `DecodeDateDay` decomposes the date indication in `AValue` and returns the various components in `AYear`, `ADayOfYear`.

See also: `EncodeDateTime` (553), `EncodeDateMonthWeek` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `DecodeDateTime` (550), `DecodeDateWeek` (551), `DecodeDateMonthWeek` (550)

Listing: ./datutex/ex83.pp

Program Example83;

{ This program demonstrates the DecodeDateDay function }

Uses SysUtils, DateUtils;

Var

Y, DoY : Word;
TS : TDateTime;

Begin

DecodeDateDay(**Now**, Y, DoY);
TS := EncodeDateDay(Y, DoY);
WriteIn('Today is : ', **DateToStr**(TS));

End.

44.4.21 DecodeDateMonthWeek

Synopsis: Decode a DateTime value in a month, week of month and day of week

Declaration: `procedure DecodeDateMonthWeek(const AValue: TDateTime; out AYear: Word;
out AMonth: Word; out AWeekOfMonth: Word;
out ADayOfWeek: Word)`

Visibility: default

Description: DecodeDateMonthWeek decomposes the date indication in AValue and returns the various components in AYear, AMonth, AWeekOfMonth and ADayOfWeek.

See also: EncodeDateTime (553), EncodeDateMonthWeek (553), EncodeDateWeek (554), EncodeDateDay (553), DecodeDateTime (550), DecodeDateWeek (551), DecodeDateDay (549)

Listing: ./datutex/ex85.pp

Program Example85;

{ This program demonstrates the DecodeDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y, M, WoM, DoW : Word;
TS : TDateTime;

Begin

DecodeDateMonthWeek(**Now**, Y, M, WoM, DoW);
TS := EncodeDateMonthWeek(Y, M, WoM, DoW);
WriteIn('Today is : ', **DateToStr**(TS));

End.

44.4.22 DecodeDateTime

Synopsis: Decode a datetime value in a date and time value

Declaration: `procedure DecodeDateTime(const AValue: TDateTime; out AYear: Word;
out AMonth: Word; out ADay: Word;
out AHour: Word; out AMinute: Word;
out ASecond: Word; out AMilliSecond: Word)`

Visibility: default

Description: `DecodeDateTime` decomposes the date/time indication in `AValue` and returns the various components in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond`, `AMilliSecond`

See also: `EncodeDateTime` (553), `EncodeDateMonthWeek` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `DecodeDateWeek` (551), `DecodeDateDay` (549), `DecodeDateMonthWeek` (550)

Listing: `./datutex/ex79.pp`

Program `Example79`;

{ This program demonstrates the DecodeDateTime function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, Mo, D, H, Mi, S, MS : Word;`
`TS : TDateTime;`

Begin

`DecodeDateTime(Now, Y, Mo, D, H, Mi, S, MS);`
`TS := EncodeDateTime(Y, Mo, D, H, Mi, S, MS);`
`WriteLn('Now is : ', DateTimeToStr(TS));`

End.

44.4.23 DecodeDateWeek

Synopsis: Decode a `DateTime` value in a week of year and day of week.

Declaration: `procedure DecodeDateWeek(const AValue: TDateTime; out AYear: Word;
out AWeekOfYear: Word; out ADayOfWeek: Word)`

Visibility: default

Description: `DecodeDateWeek` decomposes the date indication in `AValue` and returns the various components in `AYear`, `AWeekOfYear`, `ADayOfWeek`.

See also: `EncodeDateTime` (553), `EncodeDateMonthWeek` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `DecodeDateTime` (550), `DecodeDateDay` (549), `DecodeDateMonthWeek` (550)

Listing: `./datutex/ex81.pp`

Program `Example81`;

{ This program demonstrates the DecodeDateWeek function }

Uses `SysUtils`, `DateUtils`;

Var

`Y, W, Dow : Word;`
`TS : TDateTime;`

Begin

```
DecodeDateWeek(Now,Y,W,Dow);
TS:=EncodeDateWeek(Y,W,Dow);
WriteIn('Today is : ',DateToStr(TS));
End.
```

44.4.24 DecodeDayOfWeekInMonth

Synopsis: Decode a DateTime value in year, month, day of week parts

Declaration: `procedure DecodeDayOfWeekInMonth(const AValue: TDateTime;`
`out AYear: Word; out AMonth: Word;`
`out ANthDayOfWeek: Word;`
`out ADayOfWeek: Word)`

Visibility: default

Description: DecodeDayOfWeekInMonth decodes the date AValue in a AYear, AMonth, ADayOfWeek and ANthDayOfWeek. (This is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.)

See also: NthDayOfWeek ([586](#)), EncodeDateMonthWeek ([553](#)), #rtl.sysutils.DayOfWeek ([1503](#)), EncodeDayOfWeekInMonth ([554](#)), TryEncodeDayOfWeekInMonth ([609](#))

Listing: ./datutex/ex105.pp

Program Example105;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses SysUtils, DateUtils;

Var

```
Y,M,NDoW,DoW : Word;
D : TDateTime;
```

Begin

```
DecodeDayOfWeekInMonth(Date,Y,M,NDoW,DoW);
D:=EncodeDayOfWeekInMonth(Y,M,NDoW,DoW);
Write(DateToStr(D),' is the ',NDoW,'-th ');
WriteIn(formatDateTime('dddd',D),' of the month. ');
End.
```

44.4.25 DosDateTimeToDateTime

Synopsis: Convert DOS date/time format to TDateTime format

Declaration: `function DosDateTimeToDateTime(AValue: LongInt) : TDateTime`

Visibility: default

Description: DosDateTimeToDateTime takes a DOS encoded date/time AValue and recodes it as a TDateTime value.

The bit encoding of the DOS date/time is explained in the DateTimeToDosDateTime ([543](#)) function.

See also: DateTimeToDosDateTime ([543](#))

44.4.26 EncodeDateDay

Synopsis: Encodes a year and day of year to a `DateTime` value

Declaration: `function EncodeDateDay(const AYear: Word; const ADayOfYear: Word)
: TDateTime`

Visibility: default

Description: `EncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value.

For an example, see `DecodeDateDay` (549).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `EncodeDateMonthWeek` (553), `DecodeDateDay` (549), `EncodeDateTime` (553), `EncodeDateWeek` (554), `TryEncodeDateTime` (608), `TryEncodeDateMonthWeek` (607), `TryEncodeDateWeek` (609)

44.4.27 EncodeDateMonthWeek

Synopsis: Encodes a year, month, week of month and day of week to a `DateTime` value

Declaration: `function EncodeDateMonthWeek(const AYear: Word; const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word) : TDateTime`

Visibility: default

Description: `EncodeDateTime` encodes the values `AYearAMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value.

For an example, see `DecodeDateMonthWeek` (550).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `DecodeDateMonthWeek` (550), `EncodeDateTime` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `TryEncodeDateTime` (608), `TryEncodeDateWeek` (609), `TryEncodeDateMonthWeek` (607), `TryEncodeDateDay` (607), `NthDayOfWeek` (586)

44.4.28 EncodeDateTime

Synopsis: Encodes a `DateTime` value from all its parts

Declaration: `function EncodeDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: `EncodeDateTime` encodes the values `AYearAMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond` to a date/time value and returns this value.

For an example, see `DecodeDateTime` (550).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `DecodeDateTime` (550), `EncodeDateMonthWeek` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `TryEncodeDateTime` (608), `TryEncodeDateWeek` (609), `TryEncodeDateDay` (607), `TryEncodeDateMonthWeek` (607)

44.4.29 EncodeDateWeek

Synopsis: Encode a `TDateTime` value from a year, week and day of week triplet

Declaration:

```
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                        const ADayOfWeek: Word) : TDateTime
function EncodeDateWeek(const AYear: Word; const AWeekOfYear: Word)
                        : TDateTime
```

Visibility: default

Description: `EncodeDateWeek` encodes the values `AYear`, `AWeekOfYear` and `ADayOfWeek` to a date value and returns this value.

For an example, see `DecodeDateWeek` (551).

Errors: If any of the arguments is not valid, then an `EConvertError` exception is raised.

See also: `EncodeDateMonthWeek` (553), `DecodeDateWeek` (551), `EncodeDateTime` (553), `EncodeDateDay` (553), `TryEncodeDateTime` (608), `TryEncodeDateWeek` (609), `TryEncodeDateMonthWeek` (607)

44.4.30 EncodeDayOfWeekInMonth

Synopsis: Encodes a year, month, week, day of week specification to a `TDateTime` value

Declaration:

```
function EncodeDayOfWeekInMonth(const AYear: Word; const AMonth: Word;
                                const ANthDayOfWeek: Word;
                                const ADayOfWeek: Word) : TDateTime
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

For an example, see `DecodeDayOfWeekInMonth` (552).

Errors: If any of the values is not in range, then an `EConvertError` exception will be raised.

See also: `NthDayOfWeek` (586), `EncodeDateMonthWeek` (553), `#rtl.sysutils.DayOfWeek` (1503), `DecodeDayOfWeekInMonth` (552), `TryEncodeDayOfWeekInMonth` (609)

44.4.31 EncodeTimeInterval

Synopsis: Encode an interval as a `TDateTime` value.

Declaration:

```
function EncodeTimeInterval(Hour: Word; Minute: Word; Second: Word;
                            MilliSecond: Word) : TDateTime
```

Visibility: default

Description: `EncodeTimeInterval` encodes a time interval expressed in Hour, Min, Sec, MSec as a `TDateTime` value and returns the value in Time.

Errors: If Min, Sec, MSec do not contain a valid time indication, then an `EConvertError` exception is raised.

See also: `TryEncodeTimeInterval` (610)

44.4.32 EndOfDay

Synopsis: Calculates a `DateTime` value representing the end of a specified day

Declaration: `function EndOfDay(const AYear: Word; const AMonth: Word;
const ADay: Word) : TDateTime; Overload
function EndOfDay(const AYear: Word; const ADayOfYear: Word)
: TDateTime; Overload`

Visibility: default

Description: `EndOfDay` returns a `TDateTime` value with the date/time indication of the last moment (23:59:59.999) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` (603), `StartOfDay` (601), `StartOfTheWeek` (604), `StartOfAWeek` (602), `StartOfAMonth` (602), `StartOfTheMonth` (604), `EndOfTheWeek` (558), `EndOfAWeek` (556), `EndOfTheYear` (559), `EndOfAYear` (557), `EndOfTheMonth` (558), `EndOfAMonth` (555), `EndOfTheDay` (557)

Listing: `./datutex/ex39.pp`

Program Example39;

{ This program demonstrates the EndOfDay function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';

Var

 Y,M,D : Word;

Begin

 Y:=YearOf(Today);

 M:=MonthOf(Today);

 D:=DayOf(Today);

 WriteLn(FormatDateTime(Fmt, EndOfDay(Y,M,D)));

 DecodeDateDay(Today, Y,D);

 WriteLn(FormatDateTime(Fmt, EndOfDay(Y,D)));

End.

44.4.33 EndOfAMonth

Synopsis: Calculate a datetime value representing the last day of the indicated month

Declaration: `function EndOfAMonth(const AYear: Word; const AMonth: Word) : TDateTime`

Visibility: default

Description: `EndOfAMonth` returns a `TDateTime` value with the date of the last day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (604), `StartOfAMonth` (602), `EndOfTheMonth` (558), `EndOfTheYear` (559), `EndOfAYear` (557), `StartOfAWeek` (602), `StartOfTheWeek` (604)

Listing: `./datutex/ex31.pp`

```

Program Example31;

{ This program demonstrates the EndOfAMonth function }

Uses SysUtils, DateUtils;

Const
    Fmt = '"Last day of this month : "dd mmm yyyy';
Var
    Y,M : Word;

Begin
    Y:=YearOf(Today);
    M:=MonthOf(Today);
    WriteLn (FormatDateTime (Fmt, EndOfAMonth(Y,M)));
End.

```

44.4.34 EndOfAWeek

Synopsis: Return the last moment of day of the week, given a year and a week in the year.

Declaration:

```

function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word;
                    const ADayOfWeek: Word) : TDateTime
function EndOfAWeek(const AYear: Word; const AWeekOfYear: Word)
                    : TDateTime

```

Visibility: default

Description: EndOfAWeek returns a TDateTime value with the date of the last moment (23:59:59:999) on the indicated day of the week indicated by the AYear, AWeek, ADayOfWeek values.

The default value for ADayOfWeek is 7.

See also: StartOfTheWeek (604), EndOfTheWeek (558), EndOfAWeek (556), StartOfAMonth (602), EndOfTheYear (559), EndOfAYear (557), EndOfTheMonth (558), EndOfAMonth (555)

Listing: ./datutex/ex35.pp

```

Program Example35;

{ This program demonstrates the EndOfAWeek function }

Uses SysUtils, DateUtils;

Const
    Fmt = '"Last day of this week : "dd mmm yyyy hh:nn:ss';
    Fmt2 = '"Last-1 day of this week : "dd mmm yyyy hh:nn:ss';
Var
    Y,W : Word;

Begin
    Y:=YearOf(Today);
    W:=WeekOf(Today);
    WriteLn (FormatDateTime (Fmt, EndOfAWeek(Y,W)));
    WriteLn (FormatDateTime (Fmt2, EndOfAWeek(Y,W,6)));
End.

```

44.4.35 EndOfYear

Synopsis: Calculate a `DateTime` value representing the last day of a year

Declaration: `function EndOfYear(const AYear: Word) : TDateTime`

Visibility: default

Description: `StartOfYear` returns a `TDateTime` value with the date of the last day of the year `AYear` (December 31).

See also: `StartOfYear` (605), `EndOfYear` (559), `EndOfYear` (557), `EndOfMonth` (558), `EndOfMonth` (555), `StartOfWeek` (602), `StartOfWeek` (604)

Listing: `./datutex/ex27.pp`

Program Example27;

{ This program demonstrates the EndOfYear function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'Last day of this year : "dd mmm yyyy';

Begin

 WriteLn (FormatDateTime (Fmt, EndOfYear (YearOf (Today))));

End.

44.4.36 EndOfDay

Synopsis: Calculate a `datetime` value that represents the end of a given day.

Declaration: `function EndOfDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfDay` extracts the date part of `AValue` and returns a `TDateTime` value with the date/-time indication of the last moment (23:59:59.999) of this day.

See also: `StartOfDay` (603), `StartOfDay` (601), `StartOfWeek` (604), `StartOfWeek` (602), `StartOfMonth` (602), `StartOfMonth` (604), `EndOfWeek` (558), `EndOfWeek` (556), `EndOfYear` (559), `EndOfYear` (557), `EndOfMonth` (558), `EndOfMonth` (555), `EndOfDay` (555)

Listing: `./datutex/ex37.pp`

Program Example37;

{ This program demonstrates the EndOfDay function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'End of the day : "dd mmm yyyy hh:nn:ss';

Begin

 WriteLn (FormatDateTime (Fmt, EndOfDay (Today)));

End.

44.4.37 EndOfTheMonth

Synopsis: Calculate a `DateTime` value representing the last day of the month, given a day in that month.

Declaration: `function EndOfTheMonth(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheMonth` extracts the year and month parts of `AValue` and returns a `TDateTime` value with the date of the first day of that year and month as the `EndOfAMonth` (555) function.

See also: `StartOfAMonth` (602), `StartOfTheMonth` (604), `EndOfAMonth` (555), `EndOfTheYear` (559), `EndOfAYear` (557), `StartOfAWeek` (602), `StartOfTheWeek` (604)

Listing: `./datutex/ex29.pp`

Program Example29;

{ This program demonstrates the EndOfTheMonth function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "last day of this month : "dd mmm yyyy ';

Begin

WriteIn (FormatDateTime (Fmt, EndOfTheMonth (Today)));

End.

44.4.38 EndOfTheWeek

Synopsis: Calculate a `DateTime` value which represents the end of a week, given a date in that week.

Declaration: `function EndOfTheWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the last day of that week as the `EndOfAWeek` (556) function.

See also: `StartOfAWeek` (602), `StartOfTheWeek` (604), `EndOfAWeek` (556), `StartOfAMonth` (602), `EndOfTheYear` (559), `EndOfAYear` (557), `EndOfTheMonth` (558), `EndOfAMonth` (555)

Listing: `./datutex/ex33.pp`

Program Example33;

{ This program demonstrates the EndOfTheWeek function }

Uses SysUtils, DateUtils;

Const

Fmt = ' "last day of this week : "dd mmm yyyy ';

Begin

WriteIn (FormatDateTime (Fmt, EndOfTheWeek (Today)));

End.

44.4.39 EndOfTheYear

Synopsis: Calculate a `DateTime` value representing the last day of a year, given a date in that year.

Declaration: `function EndOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `EndOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the last day of that year (December 31), as the `EndOfAYear` (557) function.

See also: `StartOfAYear` (603), `StartOfTheYear` (605), `EndOfTheMonth` (558), `EndOfAMonth` (555), `StartOfAWeek` (602), `StartOfTheWeek` (604), `EndOfAYear` (557)

Listing: `./datutex/ex25.pp`

Program `Example25;`

`{ This program demonstrates the EndOfTheYear function }`

Uses `SysUtils, DateUtils;`

Const

`Fmt = ' "Last day of this year : "dd mmmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, EndOfTheYear (Today)));`

End.

44.4.40 HourOf

Synopsis: Extract the hour part from a `DateTime` value.

Declaration: `function HourOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOf` returns the hour of the day part of the `AValue` date/time indication. It is a number between 0 and 23.

For an example, see `YearOf` (625)

See also: `YearOf` (625), `WeekOf` (613), `MonthOf` (583), `DayOf` (544), `MinuteOf` (579), `SecondOf` (597), `MilliSecondOf` (575)

44.4.41 HourOfTheDay

Synopsis: Calculate the hour of a given `DateTime` value

Declaration: `function HourOfTheDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheDay` returns the number of hours that have passed since the start of the day till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:59:59 will return 0.

See also: `HourOfTheYear` (561), `HourOfTheMonth` (560), `HourOfTheWeek` (560), `MinuteOfTheDay` (580), `SecondOfTheDay` (597), `MilliSecondOfTheDay` (575)

Listing: ./datutex/ex43.pp

Program Example43;

{ This program demonstrates the HourOfDay function }

Uses SysUtils , DateUtils ;

Var

N : TDateTime ;

Begin

N:=Now;

WriteLn('Hour of the Day : ', HourOfDay(N));

WriteLn('Minute of the Day : ', MinuteOfDay(N));

WriteLn('Second of the Day : ', SecondOfDay(N));

WriteLn('MilliSecond of the Day : ',
MilliSecondOfDay(N));

End.

44.4.42 HourOfTheMonth

Synopsis: Calculate the number of hours passed since the start of the month.

Declaration: function HourOfTheMonth(const AValue: TDateTime) : Word

Visibility: default

Description: HourOfTheMonth returns the number of hours that have passed since the start of the month till the moment indicated by AValue. This is a zero-based number, i.e. 00:59:59 on the first day of the month will return 0.

For an example, see the WeekOfTheMonth (613) function.

See also: WeekOfTheMonth (613), DayOfTheMonth (544), MinuteOfTheMonth (581), SecondOfTheMonth (598), MilliSecondOfTheMonth (576)

44.4.43 HourOfTheWeek

Synopsis: Calculate the number of hours elapsed since the start of the week.

Declaration: function HourOfTheWeek(const AValue: TDateTime) : Word

Visibility: default

Description: HourOfTheWeek returns the number of hours that have passed since the start of the Week till the moment indicated by AValue. This is a zero-based number, i.e. 00:59:59 on the first day of the week will return 0.

For an example, see the DayOfTheWeek (545) function.

See also: HourOfTheYear (561), HourOfTheMonth (560), HourOfDay (559), DayOfTheWeek (545), MinuteOfTheWeek (581), SecondOfTheWeek (598), MilliSecondOfTheWeek (577)

44.4.44 HourOfTheYear

Synopsis: Calculate the number of hours passed since the start of the year.

Declaration: `function HourOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `HourOfTheYear` returns the number of hours that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:59:59 will return 0.

For an example, see the `WeekOfTheYear` (614) function.

See also: `WeekOfTheYear` (614), `DayOfTheYear` (545), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.45 HoursBetween

Synopsis: Calculate the number of whole hours between two `DateTime` values.

Declaration: `function HoursBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `HoursBetween` returns the number of whole hours between `ANow` and `AThen`. This means the fractional part of an hour (minutes,seconds etc.) is dropped.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `DaysBetween` (545), `MinutesBetween` (581), `SecondsBetween` (599), `MillisecondsBetween` (578)

Listing: `./datutex/ex59.pp`

Program Example59;

{ This program demonstrates the HoursBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

 Write('Number of hours between ');
 Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
 WriteLn(' : ', HoursBetween(ANow, AThen));
end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;
 D2:=D1-(59*OneMinute);
 Test(D1,D2);
 D2:=D1-(61*OneMinute);
 Test(D1,D2);
 D2:=D1-(122*OneMinute);
 Test(D1,D2);
 D2:=D1-(306*OneMinute);

44.4.47 IncDay

Synopsis: Increase a DateTime value with a number of days.

Declaration: `function IncDay(const AValue: TDateTime; const ANumberOfDays: Integer)
: TDateTime
function IncDay(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncDay` adds `ANumberOfDays` days to `AValue` and returns the resulting date/time. `ANumberOfDays` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncHour` (563), `IncMinute` (564), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex74.pp`

Program `Example74`;

{ This program demonstrates the IncDay function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('One Day from today is ', DateToStr(IncDay(Today, 1)));`

`WriteLn('One Day ago from today is ', DateToStr(IncDay(Today, -1)));`

End.

44.4.48 IncHour

Synopsis: Increase a DateTime value with a number of hours.

Declaration: `function IncHour(const AValue: TDateTime; const ANumberOfHours: Int64)
: TDateTime
function IncHour(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncHour` adds `ANumberOfHours` hours to `AValue` and returns the resulting date/time. `ANumberOfHours` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncDay` (563), `IncMinute` (564), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex75.pp`

Program `Example75`

;

{ This program demonstrates the IncHour function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('One Hour from now is ', DateTimeToStr(IncHour(Now, 1)));`

`WriteLn('One Hour ago from now is ', DateTimeToStr(IncHour(Now, -1)));`

End.

44.4.49 IncMilliSecond

Synopsis: Increase a DateTime value with a number of milliseconds.

Declaration: `function IncMilliSecond(const AValue: TDateTime;
const ANumberOfMilliseconds: Int64) : TDateTime
function IncMilliSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMilliSecond` adds `ANumberOfMilliseconds` milliseconds to `AValue` and returns the resulting date/time. `ANumberOfMilliseconds` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncDay` (563), `IncHour` (563), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex78.pp`

Program `Example78;`

`{ This program demonstrates the IncMilliSecond function }`

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One MilliSecond from now is ', TimeToStr(IncMilliSecond(Now, 1)));
WriteLn('One MilliSecond ago from now is ', TimeToStr(IncMilliSecond(Now, -1)));
End.`

44.4.50 IncMinute

Synopsis: Increase a DateTime value with a number of minutes.

Declaration: `function IncMinute(const AValue: TDateTime;
const ANumberOfMinutes: Int64) : TDateTime
function IncMinute(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncMinute` adds `ANumberOfMinutes` minutes to `AValue` and returns the resulting date/time. `ANumberOfMinutes` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncDay` (563), `IncHour` (563), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex76.pp`

Program `Example76;`

`{ This program demonstrates the IncMinute function }`

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Minute from now is ', TimeToStr(IncMinute(Time, 1)));
WriteLn('One Minute ago from now is ', TimeToStr(IncMinute(Time, -1)));
End.`

44.4.51 IncSecond

Synopsis: Increase a DateTime value with a number of seconds.

Declaration: `function IncSecond(const AValue: TDateTime;
const ANumberOfSeconds: Int64) : TDateTime
function IncSecond(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncSecond` adds `ANumberOfSeconds` seconds to `AValue` and returns the resulting date/time. `ANumberOfSeconds` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncDay` (563), `IncHour` (563), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex77.pp`

Program `Example77;`

{ This program demonstrates the IncSecond function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Second from now is ', TimeToStr(IncSecond(Time, 1)));`

`WriteLn('One Second ago from now is ', TimeToStr(IncSecond(Time, -1)));`

End.

44.4.52 IncWeek

Synopsis: Increase a DateTime value with a number of weeks.

Declaration: `function IncWeek(const AValue: TDateTime; const ANumberOfWeeks: Integer)
: TDateTime
function IncWeek(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncWeek` adds `ANumberOfWeeks` weeks to `AValue` and returns the resulting date/time. `ANumberOfWeeks` can be positive or negative.

See also: `IncYear` (566), `#rtl.sysutils.IncMonth` (1556), `IncDay` (563), `IncHour` (563), `IncMinute` (564), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex73.pp`

Program `Example73;`

{ This program demonstrates the IncWeek function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('One Week from today is ', DateToStr(IncWeek(Today, 1)));`

`WriteLn('One Week ago from today is ', DateToStr(IncWeek(Today, -1)));`

End.

44.4.53 IncYear

Synopsis: Increase a `DateTime` value with a number of years.

Declaration: `function IncYear(const AValue: TDateTime; const ANumberOfYears: Integer) : TDateTime`
`function IncYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `IncYear` adds `ANumberOfYears` years to `AValue` and returns the resulting date/time. `ANumberOfYears` can be positive or negative.

See also: `#rtl.sysutils.IncMonth` (1556), `IncWeek` (565), `IncDay` (563), `IncHour` (563), `IncMinute` (564), `IncSecond` (565), `IncMilliSecond` (564)

Listing: `./datutex/ex71.pp`

Program `Example71`;

{ This program demonstrates the IncYear function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('One year from today is ', DateToStr(IncYear(Today, 1)));`

`WriteLn('One year ago from today is ', DateToStr(IncYear(Today, -1)));`

End.

44.4.54 InvalidDateDayError

Synopsis: Raise an `EConvertError` exception when a day is not a valid day of a year.

Declaration: `procedure InvalidDateDayError(const AYear: Word; const ADayOfYear: Word)`

Visibility: default

Description: `InvalidDateDayError` raises an `EConvertError` (1616) exception and formats the error message with an appropriate description made up from the parts `AYear` and `ADayOfYear`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (567), `InvalidDateTimeError` (567), `InvalidDateMonthWeekError` (566), `InvalidDayOfWeekInMonthError` (568)

44.4.55 InvalidDateMonthWeekError

Synopsis: Raise an `EConvertError` exception when a `Year, Month, WeekOfMonth, DayOfWeek` is invalid.

Declaration: `procedure InvalidDateMonthWeekError(const AYear: Word;`
`const AMonth: Word;`
`const AWeekOfMonth: Word;`
`const ADayOfWeek: Word)`

Visibility: default

Description: `InvalidDateMonthWeekError` raises an `EConvertError` (1616) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (567), `InvalidDateTimeError` (567), `InvalidDateDayError` (566), `InvalidDay-Of-WeekInMonthError` (568)

44.4.56 InvalidDateTimeError

Synopsis: Raise an `EConvertError` about an invalid date-time specification.

Declaration:

```
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
                               const ADay: Word; const AHour: Word;
                               const AMinute: Word; const ASecond: Word;
                               const AMilliSecond: Word;
                               const ABaseDate: TDateTime)
procedure InvalidDateTimeError(const AYear: Word; const AMonth: Word;
                               const ADay: Word; const AHour: Word;
                               const AMinute: Word; const ASecond: Word;
                               const AMilliSecond: Word)
```

Visibility: default

Description: `InvalidDateTimeError` raises an `EConvertError` (1616) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (567), `InvalidDateDayError` (566), `InvalidDateMonthWeekError` (566), `InvalidDayOf-WeekInMonthError` (568)

44.4.57 InvalidDateWeekError

Synopsis: Raise an `EConvertError` with an invalid Year, WeekOfyear and DayOfWeek specification

Declaration:

```
procedure InvalidDateWeekError(const AYear: Word;
                               const AWeekOfYear: Word;
                               const ADayOfWeek: Word)
```

Visibility: default

Description: `InvalidDateWeekError` raises an `EConvertError` (1616) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AWeek`, `ADayOfWeek`

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateTimeError` (567), `InvalidDateDayError` (566), `InvalidDateMonthWeekError` (566), `InvalidDayOf-WeekInMonthError` (568)

44.4.58 InvalidDayOfWeekInMonthError

Synopsis: Raise an `EConvertError` exception when a `Year,Month,NthDayOfWeek,DayOfWeek` is invalid.

Declaration: `procedure InvalidDayOfWeekInMonthError(const AYear: Word;
const AMonth: Word;
const ANthDayOfWeek: Word;
const ADayOfWeek: Word)`

Visibility: default

Description: `InvalidDayOfWeekInMonthError` raises an `EConvertError` (1616) exception and formats the error message with an appropriate description made up from the parts `AYear`, `AMonth`, `ANthDayOfWeek` and `ADayOfWeek`.

Normally this function should not be needed, the conversion routines call it when they have received invalid arguments.

See also: `InvalidDateWeekError` (567), `InvalidDateTimeError` (567), `InvalidDateDayError` (566), `InvalidDate-MonthWeekError` (566)

44.4.59 IsInLeapYear

Synopsis: Determine whether a date is in a leap year.

Declaration: `function IsInLeapYear(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsInLeapYear` returns `True` if the year part of `AValue` is leap year, or `False` if not.

See also: `YearOf` (625), `IsPM` (568), `IsToday` (570), `IsSameDay` (569)

Listing: `./datutex/ex3.pp`

Program Example3;

{ This program demonstrates the IsInLeapYear function }

Uses SysUtils, DateUtils;

Begin

`WriteIn('Current year is leap year: ',IsInLeapYear(Date));`

End.

44.4.60 IsPM

Synopsis: Determine whether a time is PM or AM.

Declaration: `function IsPM(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsPM` returns `True` if the time part of `AValue` is later then 12:00 (PM, or afternoon).

See also: `YearOf` (625), `IsInLeapYear` (568), `IsToday` (570), `IsSameDay` (569)

Listing: `./datutex/ex4.pp`

```

Program Example4;

{ This program demonstrates the IsPM function }

Uses SysUtils, DateUtils;

Begin
    WriteLn('Current time is PM : ', IsPM(Now));
End.

```

44.4.61 IsSameDay

Synopsis: Check if two date/time indications are the same day.

Declaration: `function IsSameDay(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameDay` checks whether `AValue` and `ABasis` have the same date part, and returns `True` if they do, `False` if not.

See also: [Today \(606\)](#), [Yesterday \(627\)](#), [Tomorrow \(606\)](#), [IsToday \(570\)](#)

Listing: `./datutex/ex21.pp`

```

Program Example21;

{ This program demonstrates the IsSameDay function }

Uses SysUtils, DateUtils;

Var
    I : Integer;
    D : TDateTime;

Begin
    For I:=1 to 3 do
        begin
            D:=Today+Random(3)-1;
            Write(FormatDateTime('dd mmm yyyy "is today : "', D));
            WriteLn(IsSameDay(D, Today));
        end;
End.

```

44.4.62 IsSameMonth

Synopsis: Check if 2 dates are in the same month.

Declaration: `function IsSameMonth(const AValue: TDateTime; const ABasis: TDateTime) : Boolean`

Visibility: default

Description: `IsSameMonth` will return `True` if the two dates `AValue` and `ABasis` occur in the same year and month. (i.e. if their month and year parts match). Otherwise, `False` is returned.

See also: [IsSameDay \(569\)](#), [IsToday \(570\)](#), [SameDate \(594\)](#)

44.4.63 IsToday

Synopsis: Check whether a given date is today.

Declaration: `function IsToday(const AValue: TDateTime) : Boolean`

Visibility: default

Description: `IsToday` returns `True` if `AValue` is today's date, and `False` otherwise.

See also: [Today \(606\)](#), [Yesterday \(627\)](#), [Tomorrow \(606\)](#), [IsSameDay \(569\)](#)

Listing: `./datutex/ex20.pp`

Program `Example20;`

{ This program demonstrates the IsToday function }

Uses `SysUtils, DateUtils;`

Begin

`WriteLn('Today : ', IsToday(Today));`

`WriteLn('Tomorrow : ', IsToday(Tomorrow));`

`WriteLn('Yesterday : ', IsToday(Yesterday));`

End.

44.4.64 IsValidDate

Synopsis: Check whether a set of values is a valid date indication.

Declaration: `function IsValidDate(const AYear: Word; const AMonth: Word;
const ADay: Word) : Boolean`

Visibility: default

Description: `IsValidDate` returns `True` when the values `AYear`, `AMonth`, `ADay` form a valid date indication. If one of the values is not valid (e.g. the day is invalid or does not exist in that particular month), `False` is returned.

`AYear` must be in the range 1..9999 to be valid.

See also: [IsValidTime \(574\)](#), [IsValidDateTime \(572\)](#), [IsValidDateDay \(571\)](#), [IsValidDateWeek \(573\)](#), [IsValidDateMonthWeek \(571\)](#)

Listing: `./datutex/ex5.pp`

Program `Example5;`

{ This program demonstrates the IsValidDate function }

Uses `SysUtils, DateUtils;`

Var

`Y, M, D : Word;`

Begin

`For Y:=2000 to 2004 do`

`For M:=1 to 12 do`

`For D:=1 to 31 do`

```

    If Not IsValidDate(Y,M,D) then
        WriteLn(D, ' is not a valid day in ',Y,'/',M);
End.

```

44.4.65 IsValidDateDay

Synopsis: Check whether a given year/day of year combination is a valid date.

Declaration: `function IsValidDateDay(const AYear: Word; const ADayOfYear: Word) : Boolean`

Visibility: default

Description: `IsValidDateDay` returns `True` if `AYear` and `ADayOfYear` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `ADayOfYear` value is checked to see whether it falls within the valid range of dates for `AYear`.

See also: `IsValidDate` ([570](#)), `IsValidTime` ([574](#)), `IsValidDateTime` ([572](#)), `IsValidDateWeek` ([573](#)), `IsValidDateMonthWeek` ([571](#))

Listing: `./datutex/ex9.pp`

Program `Example9`;

{ This program demonstrates the IsValidDateDay function }

Uses `SysUtils`, `DateUtils`;

Var
Y : Word;

```

Begin
    For Y:=1996 to 2004 do
        if IsValidDateDay(Y,366) then
            WriteLn(Y, ' is a leap year');
End.

```

44.4.66 IsValidDateMonthWeek

Synopsis: Check whether a given year/month/week/day of the week combination is a valid day

Declaration: `function IsValidDateMonthWeek(const AYear: Word; const AMonth: Word; const AWeekOfMonth: Word; const ADayOfWeek: Word) : Boolean`

Visibility: default

Description: `IsValidDateMonthWeek` returns `True` if `AYear`, `AMonth`, `AWeekOfMonth` and `ADayOfWeek` form a valid date indication, or `False` otherwise.

`AYear` must be in the range 1..9999 to be valid.

The `AWeekOfMonth`, `ADayOfWeek` values are checked to see whether the combination falls within the valid range of weeks for the `AYear`, `AMonth` combination.

See also: [IsValidDate \(570\)](#), [IsValidTime \(574\)](#), [IsValidDateTime \(572\)](#), [IsValidDateDay \(571\)](#), [IsValidDateWeek \(573\)](#)

Listing: ./datutex/ex11.pp

Program Example11 ;

{ This program demonstrates the IsValidDateMonthWeek function }

Uses SysUtils , DateUtils ;

Var

Y,W,D : Word;
B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

B:=True;

For W:=4 to 6 do

For D:=1 to 7 do

If B then

begin

B:=IsValidDateMonthWeek(Y,12,W,D);

If Not B then

if (D=1) then

WriteLn('December ',Y,' has exactly ',W,' weeks.')

else

WriteLn('December ',Y,' has ',W,' weeks and ',D-1,' days.');

end;

end;

End.

44.4.67 IsValidDateTime

Synopsis: Check whether a set of values is a valid date and time indication.

Declaration: function IsValidDateTime(const AYear: Word; const AMonth: Word;
const ADay: Word; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : Boolean

Visibility: default

Description: IsValidTime returns True when the values AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond form a valid date and time indication. If one of the values is not valid (e.g. the seconds are larger than 60), False is returned.

AYear must be in the range 1..9999 to be valid.

See also: [IsValidDate \(570\)](#), [IsValidTime \(574\)](#), [IsValidDateDay \(571\)](#), [IsValidDateWeek \(573\)](#), [IsValidDateMonthWeek \(571\)](#)

Listing: ./datutex/ex7.pp

Program Example7 ;

{ This program demonstrates the IsValidDateTime function }

Uses SysUtils, DateUtils;

Var

Y, Mo, D : Word;
H, M, S, MS : Word;
I : Integer;

Begin

For I:=1 to 10 do

begin

Y:=2000+Random(5);

Mo:=Random(15);

D:=Random(40);

H:=Random(32);

M:=Random(90);

S:=Random(90);

MS:=Random(1500);

If Not IsValidDateTime(Y, Mo, D, H, M, S, MS) then

WriteLn(Y, '-', Mo, '-', D, ' ', H, ': ', M, ': ', S, '.', MS, ' is not a valid date/time.');

end;

End.

44.4.68 IsValidDateWeek

Synopsis: Check whether a given year/week/day of the week combination is a valid day.

Declaration: function IsValidDateWeek(const AYear: Word; const AWeekOfYear: Word;
const ADayOfWeek: Word) : Boolean

Visibility: default

Description: IsValidDateWeek returns True if AYear, AWeekOfYear and ADayOfWeek form a valid date indication, or False otherwise.

AYear must be in the range 1..9999 to be valid.

The ADayOfWeek, ADayOfWeek values are checked to see whether the combination falls within the valid range of weeks for AYear.

See also: IsValidDate (570), IsValidTime (574), IsValidDateTime (572), IsValidDateDay (571), IsValidDateMonthWeek (571)

Listing: ./datutex/ex10.pp

Program Example10;

{ This program demonstrates the IsValidDateWeek function }

Uses SysUtils, DateUtils;

Var

Y, W, D : Word;
B : Boolean;

Begin

For Y:=2000 to 2004 do

begin

```

B:=True;
For W:=51 to 54 do
  For D:=1 to 7 do
    If B then
      begin
        B:=IsValidDateWeek(Y,W,D);
        If Not B then
          if (D=1) then
            Writeln(Y, ' has exactly ',W, ' weeks. ');
          else
            Writeln(Y, ' has ',W, ' weeks and ',D-1, ' days. ');
          end;
        end;
      end;
    end;
  end;
End.

```

44.4.69 IsValidTime

Synopsis: Check whether a set of values is a valid time indication.

Declaration: `function IsValidTime(const AHour: Word; const AMinute: Word;
const ASecond: Word; const AMilliSecond: Word)
: Boolean`

Visibility: default

Description: Check whether a set of values is a valid time indication.

44.4.70 JulianDateToDateTime

Synopsis: Convert a Julian date representation to a TDateTime value.

Declaration: `function JulianDateToDateTime(const AValue: Double) : TDateTime`

Visibility: default

Description: `JulianDateToDateTime` converts the Julian `AValue` date/time indication to a regular `TDateTime` date/time indication.

See also: `DateTimeToJulianDate` ([543](#)), `TryJulianDateToDateTime` ([610](#)), `DateTimeToModifiedJulianDate` ([544](#)), `TryModifiedJulianDateToDateTime` ([611](#))

44.4.71 LocalTimeToUniversal

Synopsis: Convert local time to UTC time

Declaration: `function LocalTimeToUniversal(LT: TDateTime) : TDateTime`
`function LocalTimeToUniversal(LT: TDateTime; TZOffset: Integer)
: TDateTime`

Visibility: default

Description: `UniversalTimeToLocal` converts a local time indication to a universal time indication: it undoes the `TZOffset` timezone offset from the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` ([537](#)) is used.

Note that for times in the past or in the future, or for time zones with DST, omitting the `TZoffset` may lead to wrong results, as the current timezone offset is used. Calculation of the correct timezone offset for a given date is very complicated, and outside the scope of this call.

See also: [GetLocalTimeOffset \(537\)](#), [UniversalTimeToLocal \(612\)](#)

44.4.72 MacTimeStampToUnix

Synopsis: Convert a Mac timestamp to a Unix timestamp

Declaration: `function MacTimeStampToUnix(const AValue: Int64) : Int64`

Visibility: default

Description: `MacTimeStampToUnix` converts the Mac timestamp indication in `AValue` to a unix timestamp indication (epoch time)

Errors: None.

See also: [UnixTimeStampToMac \(612\)](#), [DateTimeToMac \(543\)](#), [MacToDateTime \(575\)](#)

44.4.73 MacToDateTime

Synopsis: Convert a Mac timestamp to a `TDateTime` timestamp

Declaration: `function MacToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `MacToDateTime` converts the Mac timestamp indication in `AValue` to a valid `TDateTime` indication.

Errors: None.

See also: [UnixTimeStampToMac \(612\)](#), [DateTimeToMac \(543\)](#), [MacTimeStampToUnix \(575\)](#)

44.4.74 MilliSecondOf

Synopsis: Extract the millisecond part from a `DateTime` value.

Declaration: `function MilliSecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 999.

For an example, see [YearOf \(625\)](#)

See also: [YearOf \(625\)](#), [WeekOf \(613\)](#), [MonthOf \(583\)](#), [DayOf \(544\)](#), [HourOf \(559\)](#), [MinuteOf \(579\)](#), [MilliSecondOf \(575\)](#)

44.4.75 MilliSecondOfDay

Synopsis: Calculate the number of milliseconds elapsed since the start of the day

Declaration: `function MilliSecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfDay` returns the number of milliseconds that have passed since the start of the Day (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 will return 0.

For an example, see the `HourOfDay` (559) function.

See also: `MilliSecondOfYear` (577), `MilliSecondOfMonth` (576), `MilliSecondOfWeek` (577), `MilliSecondOfHour` (576), `MilliSecondOfMinute` (576), `MilliSecondOfSecond` (577), `HourOfDay` (559), `MinuteOfDay` (580), `SecondOfDay` (597)

44.4.76 MilliSecondOfTheHour

Synopsis: Calculate the number of milliseconds elapsed since the start of the hour

Declaration: `function MilliSecondOfTheHour(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheHour` returns the number of milliseconds that have passed since the start of the Hour (HH:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.000 will return 0.

For an example, see the `MinuteOfTheHour` (580) function.

See also: `MilliSecondOfYear` (577), `MilliSecondOfMonth` (576), `MilliSecondOfWeek` (577), `MilliSecondOfDay` (575), `MilliSecondOfMinute` (576), `MilliSecondOfSecond` (577), `MinuteOfTheHour` (580), `SecondOfTheHour` (597)

44.4.77 MilliSecondOfTheMinute

Synopsis: Calculate the number of milliseconds elapsed since the start of the minute

Declaration: `function MilliSecondOfTheMinute(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMinute` returns the number of milliseconds that have passed since the start of the Minute (HH:MM:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.000 will return 0.

For an example, see the `SecondOfTheMinute` (598) function.

See also: `MilliSecondOfYear` (577), `MilliSecondOfMonth` (576), `MilliSecondOfWeek` (577), `MilliSecondOfDay` (575), `MilliSecondOfHour` (576), `MilliSecondOfMinute` (576), `MilliSecondOfSecond` (577), `SecondOfTheMinute` (598)

44.4.78 MilliSecondOfTheMonth

Synopsis: Calculate number of milliseconds elapsed since the start of the month.

Declaration: `function MilliSecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheMonth` returns the number of milliseconds that have passed since the start of the month (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the month will return 0.

For an example, see the `WeekOfTheMonth` (613) function.

See also: `WeekOfTheMonth` (613), `DayOfTheMonth` (544), `HourOfTheMonth` (560), `MinuteOfTheMonth` (581), `SecondOfTheMonth` (598), `MilliSecondOfTheMonth` (576)

44.4.79 MilliSecondOfTheSecond

Synopsis: Calculate the number of milliseconds elapsed since the start of the second

Declaration: `function MilliSecondOfTheSecond(const AValue: TDateTime) : Word`

Visibility: default

Description: `MilliSecondOfTheSecond` returns the number of milliseconds that have passed since the start of the second (HH:MM:SS.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:SS.000 will return 0.

See also: `MilliSecondOfTheYear` (577), `MilliSecondOfTheMonth` (576), `MilliSecondOfTheWeek` (577), `MilliSecondOfTheDay` (575), `MilliSecondOfTheHour` (576), `MilliSecondOfTheMinute` (576), `SecondOfTheMinute` (598)

Listing: `./datutex/ex46.pp`

Program Example46;

{ This program demonstrates the MilliSecondOfTheSecond function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('MilliSecond of the Second : ',
MilliSecondOfTheSecond(N));

End.

44.4.80 MilliSecondOfTheWeek

Synopsis: Calculate the number of milliseconds elapsed since the start of the week

Declaration: `function MilliSecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MilliSecondOfTheWeek` returns the number of milliseconds that have passed since the start of the Week (00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.000 on the first of the Week will return 0.

For an example, see the `DayOfTheWeek` (545) function.

See also: `MilliSecondOfTheYear` (577), `MilliSecondOfTheMonth` (576), `MilliSecondOfTheDay` (575), `MilliSecondOfTheHour` (576), `MilliSecondOfTheMinute` (576), `MilliSecondOfTheSecond` (577), `DayOfTheWeek` (545), `HourOfTheWeek` (560), `MinuteOfTheWeek` (581), `SecondOfTheWeek` (598)

44.4.81 MilliSecondOfTheYear

Synopsis: Calculate the number of milliseconds elapsed since the start of the year.

Declaration: `function MilliSecondOfTheYear(const AValue: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondOfTheYear` returns the number of milliseconds that have passed since the start of the year (January 1, 00:00:00.000) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.000 will return 0.

For an example, see the `WeekOfTheYear` (614) function.

See also: `WeekOfTheYear` (614), `DayOfTheYear` (545), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.82 MilliSecondsBetween

Synopsis: Calculate the number of whole milliseconds between two `DateTime` values.

Declaration: `function MilliSecondsBetween(const ANow: TDateTime;
const AThen: TDateTime) : Int64`

Visibility: default

Description: `MilliSecondsBetween` returns the number of whole milliseconds between `ANow` and `AThen`. This means a fractional part of a millisecond is dropped.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `DaysBetween` (545), `HoursBetween` (561), `MinutesBetween` (581), `SecondsBetween` (599)

Listing: `./datutex/ex62.pp`

Program Example62;

{ This program demonstrates the MilliSecondsBetween function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin
 Write('Number of milliseconds between ');
 Write(**TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));
 WriteLn(' : ', MilliSecondsBetween(ANow, AThen));
end;

Var
 D1, D2 : TDateTime;

Begin
 D1:=**Now**;
 D2:=D1-(0.9*OneMilliSecond);
 Test(D1, D2);
 D2:=D1-(1.0*OneMilliSecond);
 Test(D1, D2);
 D2:=D1-(1.1*OneMilliSecond);
 Test(D1, D2);
 D2:=D1-(2.5*OneMilliSecond);
 Test(D1, D2);
End.

44.4.83 MilliSecondSpan

Synopsis: Calculate the approximate number of milliseconds between two `DateTime` values.

Declaration: `function MilliSecondSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `MilliSecondSpan` returns the number of milliseconds between `ANow` and `AThen`. Since millisecond is the smallest fraction of a `TDateTime` indication, the returned number will always be an integer value.

See also: `YearSpan` (627), `MonthSpan` (585), `WeekSpan` (616), `DaySpan` (548), `HourSpan` (562), `MinuteSpan` (582), `SecondSpan` (600), `MillisecondsBetween` (578)

Listing: `./datutex/ex70.pp`

Program `Example70`;

{ This program demonstrates the MilliSecondSpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime)`;

begin

`Write('Number of milliseconds between ');`
 `Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));`
 `WriteLn(' : ', MilliSecondSpan(ANow, AThen));`
end;

Var

`D1, D2 : TDateTime;`

Begin

`D1:=Now;`
 `D2:=D1-(0.9*OneMilliSecond);`
 `Test(D1,D2);`
 `D2:=D1-(1.0*OneMilliSecond);`
 `Test(D1,D2);`
 `D2:=D1-(1.1*OneMilliSecond);`
 `Test(D1,D2);`
 `D2:=D1-(2.5*OneMilliSecond);`
 `Test(D1,D2);`

End.

44.4.84 MinuteOf

Synopsis: Extract the minute part from a `DateTime` value.

Declaration: `function MinuteOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOf` returns the minute of the hour part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see `YearOf` (625)

See also: YearOf ([625](#)), WeekOf ([613](#)), MonthOf ([583](#)), DayOf ([544](#)), HourOf ([559](#)), SecondOf ([597](#)), MilliSecondOf ([575](#))

44.4.85 MinuteOfDay

Synopsis: Calculate the number of minutes elapsed since the start of the day

Declaration: `function MinuteOfDay(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfDay` returns the number of minutes that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 will return 0.

For an example, see the `HourOfDay` ([559](#)) function.

See also: MinuteOfTheYear ([581](#)), MinuteOfTheMonth ([581](#)), MinuteOfTheWeek ([581](#)), MinuteOfTheHour ([580](#)), HourOfTheDay ([559](#)), SecondOfTheDay ([597](#)), MilliSecondOfTheDay ([575](#))

44.4.86 MinuteOfTheHour

Synopsis: Calculate the number of minutes elapsed since the start of the hour

Declaration: `function MinuteOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheHour` returns the number of minutes that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:59 will return 0.

See also: MinuteOfTheYear ([581](#)), MinuteOfTheMonth ([581](#)), MinuteOfTheWeek ([581](#)), MinuteOfTheDay ([580](#)), SecondOfTheHour ([597](#)), MilliSecondOfTheHour ([576](#))

Listing: `./datutex/ex44.pp`

Program Example44;

{ This program demonstrates the MinuteOfTheHour function }

Uses SysUtils, DateUtils;

Var

 N : TDateTime;

Begin

 N:=Now;

WriteLn('Minute of the Hour : ',MinuteOfTheHour(N));

WriteLn('Second of the Hour : ',SecondOfTheHour(N));

WriteLn('MilliSecond of the Hour : ',
 MilliSecondOfTheHour(N));

End.

44.4.87 MinuteOfTheMonth

Synopsis: Calculate number of minutes elapsed since the start of the month.

Declaration: `function MinuteOfTheMonth(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheMonth` returns the number of minutes that have passed since the start of the Month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (613) function.

See also: `WeekOfTheMonth` (613), `DayOfTheMonth` (544), `HourOfTheMonth` (560), `MinuteOfTheMonth` (581), `SecondOfTheMonth` (598), `MilliSecondOfTheMonth` (576)

44.4.88 MinuteOfTheWeek

Synopsis: Calculate the number of minutes elapsed since the start of the week

Declaration: `function MinuteOfTheWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `MinuteOfTheWeek` returns the number of minutes that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:59 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (545) function.

See also: `MinuteOfTheYear` (581), `MinuteOfTheMonth` (581), `MinuteOfTheDay` (580), `MinuteOfTheHour` (580), `DayOfTheWeek` (545), `HourOfTheWeek` (560), `SecondOfTheWeek` (598), `MilliSecondOfTheWeek` (577)

44.4.89 MinuteOfTheYear

Synopsis: Calculate the number of minutes elapsed since the start of the year

Declaration: `function MinuteOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `MinuteOfTheYear` returns the number of minutes that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:59 will return 0.

For an example, see the `WeekOfTheYear` (614) function.

See also: `WeekOfTheYear` (614), `DayOfTheYear` (545), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.90 MinutesBetween

Synopsis: Calculate the number of whole minutes between two `DateTime` values.

Declaration: `function MinutesBetween(const ANow: TDateTime; const AThen: TDateTime)
: Int64`

Visibility: default

Description: `MinutesBetween` returns the number of whole minutes between `ANow` and `AThen`. This means the fractional part of a minute (seconds, milliseconds etc.) is dropped.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `DaysBetween` (545), `HoursBetween` (561), `SecondsBetween` (599), `MillisecondsBetween` (578)

Listing: `./datutex/ex60.pp`

Program `Example60`;

{ This program demonstrates the MinutesBetween function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime)`;

```
begin
  Write('Number of minutes between ');
  Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
  WriteLn(' : ', MinutesBetween(ANow, AThen));
end;
```

Var
`D1, D2 : TDateTime`;

```
Begin
  D1:=Now;
  D2:=D1-(59*OneSecond);
  Test(D1,D2);
  D2:=D1-(61*OneSecond);
  Test(D1,D2);
  D2:=D1-(122*OneSecond);
  Test(D1,D2);
  D2:=D1-(306*OneSecond);
  Test(D1,D2);
  D2:=D1-(5.4*OneMinute);
  Test(D1,D2);
  D2:=D1-(2.5*OneMinute);
  Test(D1,D2);
End.
```

44.4.91 MinuteSpan

Synopsis: Calculate the approximate number of minutes between two `DateTime` values.

Declaration: `function MinuteSpan(const ANow: TDateTime; const AThen: TDateTime)`
`: Double`

Visibility: `default`

Description: `MinuteSpan` returns the number of minutes between `ANow` and `AThen`, including any fractional parts of a minute.

See also: `YearSpan` (627), `MonthSpan` (585), `WeekSpan` (616), `DaySpan` (548), `HourSpan` (562), `SecondSpan` (600), `MilliSecondSpan` (579), `MinutesBetween` (581)

Listing: `./datutex/ex68.pp`

Program Example68;

{ This program demonstrates the MinuteSpan function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

Write('Number of minutes between ');

Write(**TimeToStr**(AThen), ' and ', **TimeToStr**(ANow));

WriteLn(' : ', MinuteSpan(ANow, AThen));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := **Now**;

 D2 := D1 - (59 * OneSecond);

 Test(D1, D2);

 D2 := D1 - (61 * OneSecond);

 Test(D1, D2);

 D2 := D1 - (122 * OneSecond);

 Test(D1, D2);

 D2 := D1 - (306 * OneSecond);

 Test(D1, D2);

 D2 := D1 - (5.4 * OneMinute);

 Test(D1, D2);

 D2 := D1 - (2.5 * OneMinute);

 Test(D1, D2);

End.

44.4.92 ModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a TDateTime value.

Declaration: function ModifiedJulianDateToDateTime(const AValue: Double) : TDateTime

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: DateTimeToJulianDate ([543](#)), JulianDateToDateTime ([574](#)), TryJulianDateToDateTime ([610](#)), DateTimeToModifiedJulianDate ([544](#)), TryModifiedJulianDateToDateTime ([611](#))

44.4.93 MonthOf

Synopsis: Extract the month from a given date.

Declaration: function MonthOf(const AValue: TDateTime) : Word

Visibility: default

Description: `MonthOf` returns the month part of the `AValue` date/time indication. It is a number between 1 and 12.

For an example, see `YearOf` (625)

See also: `YearOf` (625), `DayOf` (544), `WeekOf` (613), `HourOf` (559), `MinuteOf` (579), `SecondOf` (597), `MilliSecondOf` (575)

44.4.94 MonthOfTheYear

Synopsis: Extract the month of a `DateTime` indication.

Declaration: `function MonthOfTheYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `MonthOfTheYear` extracts the month part of `Avalue` and returns it. It is an alias for `MonthOf` (583), and is provided for completeness only, corresponding to the other `PartOfTheYear` functions.

For an example, see the `WeekOfTheYear` (614) function.

See also: `MonthOf` (583), `WeekOfTheYear` (614), `DayOfTheYear` (545), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.95 MonthsBetween

Synopsis: Calculate the number of whole months between two `DateTime` values

Declaration: `function MonthsBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `MonthsBetween` returns the number of whole months between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years). This means the fractional part of a month is dropped.

See also: `YearsBetween` (626), `WeeksBetween` (614), `DaysBetween` (545), `HoursBetween` (561), `MinutesBetween` (581), `SecondsBetween` (599), `MillisecondsBetween` (578)

Listing: `./datutex/ex56.pp`

Program `Example56`;

{ This program demonstrates the MonthsBetween function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin

`Write('Number of months between ');`
 `Write(DateToStr(AThen), ' and ', DateToStr(ANow));`
 `WriteLn(' : ', MonthsBetween(ANow, AThen));`
end;

Var

`D1, D2 : TDateTime;`

Begin

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;
Test(D1,D2);
D2:=Today-366;
Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);

```

End.**44.4.96 MonthSpan**

Synopsis: Calculate the approximate number of months between two DateTime values.

Declaration: `function MonthSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: MonthSpan returns the number of month between ANow and AThen, including any fractional parts of a month. This number is an approximation, based on an average number of days of 30.4375 per month (average over 4 years).

See also: YearSpan ([627](#)), WeekSpan ([616](#)), DaySpan ([548](#)), HourSpan ([562](#)), MinuteSpan ([582](#)), SecondSpan ([600](#)), MilliSecondSpan ([579](#)), MonthsBetween ([584](#))

Listing: ./datutex/ex64.pp

Program Example64;

```
{ This program demonstrates the MonthSpan function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```

Write('Number of months between ');
Write(DateToStr(AThen), ' and ', DateToStr(ANow));
WriteLn(' : ', MonthSpan(ANow, AThen));
end;

```

Var

```
D1, D2 : TDateTime;
```

Begin

```

D1:=Today;
D2:=Today-364;
Test(D1,D2);
D2:=Today-365;

```

```

Test(D1,D2);
D2:=Today-366;
Test(D1,D2);
D2:=Today-390;
Test(D1,D2);
D2:=Today-368;
Test(D1,D2);
D2:=Today-1000;
Test(D1,D2);
End.

```

44.4.97 NthDayOfWeek

Synopsis: Calculate which occurrence of weekday in the month a given day represents

Declaration: `function NthDayOfWeek(const AValue: TDateTime) : Word`

Visibility: default

Description: `NthDayOfWeek` returns the occurrence of the weekday of `AValue` in the month. This is the N-th time that this weekday occurs in the month (e.g. the third saturday of the month).

See also: `EncodeDateMonthWeek` (553), `#rtl.sysutils.DayOfWeek` (1503), `DecodeDayOfWeekInMonth` (552), `EncodeDayOfWeekInMonth` (554), `TryEncodeDayOfWeekInMonth` (609)

Listing: `./datutex/ex104.pp`

Program Example104;

```
{ This program demonstrates the NthDayOfWeek function }
```

Uses SysUtils, DateUtils;

Begin

```

Write('Today is the ',NthDayOfWeek(Today),'-th ');
WriteIn(formatDateTime('dddd',Today),' of the month. ');
End.

```

44.4.98 PeriodBetween

Synopsis: Return the period (in years, months, days) between two dates

Declaration: `procedure PeriodBetween(const ANow: TDateTime; const AThen: TDateTime; out Years: Word; out months: Word; out days: Word)`

Visibility: default

Description: `PeriodBetween` returns the timespan between 2 dates (`ANow` and `AThen`), expressed as a number of years, months and days in the parameters `Years`, `months` and `days`. Only complete years, months and days are reported.

If `ANow` is before `AThen`, their values are reversed so the result is always positive.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `DaysBetween` (545)

44.4.99 PreviousDayOfWeek

Synopsis: Given a day of the week, return the previous day of the week.

Declaration: `function PreviousDayOfWeek (DayOfWeek: Word) : Word`

Visibility: default

Description: `PreviousDayOfWeek` returns the previous day of the week. If the current day is the first day of the week (1) then the last day will be returned (7).

Remark: Note that the days of the week are in ISO notation, i.e. 1-based.

See also: Yesterday ([627](#))

Listing: `./datutex/ex22.pp`

Program Example22;

{ This program demonstrates the PreviousDayOfWeek function }

Uses SysUtils, DateUtils;

Var

D : Word;

Begin

For D:=1 to 7 do

WriteLn('Previous day of ',D,' is : ',PreviousDayOfWeek(D));

End.

44.4.100 RecodeDate

Synopsis: Replace date part of a `TDateTime` value with another date.

Declaration: `function RecodeDate(const AValue: TDateTime; const AYear: Word;
const AMonth: Word; const ADay: Word) : TDateTime`

Visibility: default

Description: `RecodeDate` replaces the date part of the timestamp `AValue` with the date specified in `AYear`, `AMonth`, `ADay`. All other parts (the time part) of the date/time stamp are left untouched.

Errors: If one of the `AYear`, `AMonth`, `ADay` values is not within a valid range then an `EConvertError` exception is raised.

See also: `RecodeYear` ([593](#)), `RecodeMonth` ([591](#)), `RecodeDay` ([589](#)), `RecodeHour` ([589](#)), `RecodeMinute` ([591](#)), `RecodeSecond` ([592](#)), `RecodeDate` ([587](#)), `RecodeTime` ([593](#)), `RecodeDateTime` ([588](#))

Listing: `./datutex/ex94.pp`

Program Example94;

{ This program demonstrates the RecodeDate function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

```

Var
  S : AnsiString;

Begin
  S:=FormatDateTime(Fmt,RecodeDate(Now,2001,1,1));
  WriteLn('This moment on the first of the millenium : ',S);
End.

```

44.4.101 RecodeDateTime

Synopsis: Replace selected parts of a TDateTime value with other values

Declaration: function RecodeDateTime(const AValue: TDateTime; const AYear: Word;
const AMonth: Word; const ADay: Word;
const AHour: Word; const AMinute: Word;
const ASecond: Word; const AMilliSecond: Word)
: TDateTime

Visibility: default

Description: RecodeDateTime replaces selected parts of the timestamp AValue with the date/time values specified in AYear, AMonth, ADay, AHour, AMinute, ASecond and AMilliSecond. If any of these values equals the pre-defined constant RecodeLeaveFieldAsIs (539), then the corresponding part of the date/time stamp is left untouched.

Errors: If one of the values AYear, AMonth, ADay, AHour, AMinute, ASecondAMilliSecond is not within a valid range (RecodeLeaveFieldAsIs excepted) then an EConvertError exception is raised.

See also: RecodeYear (593), RecodeMonth (591), RecodeDay (589), RecodeHour (589), RecodeMinute (591), RecodeSecond (592), RecodeMilliSecond (590), RecodeDate (587), RecodeTime (593), TryRecodeDateTime (611)

Listing: ./datutex/ex96.pp

Program Example96;

{ This program demonstrates the RecodeDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

S : AnsiString;

D : TDateTime;

Begin

D:=**Now**;

D:=RecodeDateTime(D,2000,2,RecodeLeaveFieldAsIs,0,0,0,0);

S:=**FormatDateTime**(Fmt,D);

WriteLn('This moment in februari 2000 : ',S);

End.

44.4.102 RecodeDay

Synopsis: Replace day part of a `TDateTime` value with another day.

Declaration: `function RecodeDay(const AValue: TDateTime; const ADay: Word)
: TDateTime`

Visibility: default

Description: `RecodeDay` replaces the Day part of the timestamp `AValue` with `ADay`. All other parts of the date/time stamp are left untouched.

Errors: If the `ADay` value is not within a valid range (1 till the number of days in the month) then an `EConvertError` exception is raised.

See also: `RecodeYear` (593), `RecodeMonth` (591), `RecodeHour` (589), `RecodeMinute` (591), `RecodeSecond` (592), `RecodeMilliSecond` (590), `RecodeDate` (587), `RecodeTime` (593), `RecodeDateTime` (588)

Listing: `./datutex/ex89.pp`

Program Example89;

{ This program demonstrates the RecodeDay function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, **RecodeDay**(**Now**, 1));

WriteLn('This moment on the first of the month : ', S);

End.

44.4.103 RecodeHour

Synopsis: Replace hours part of a `TDateTime` value with another hour.

Declaration: `function RecodeHour(const AValue: TDateTime; const AHour: Word)
: TDateTime`

Visibility: default

Description: `RecodeHour` replaces the Hour part of the timestamp `AValue` with `AHour`. All other parts of the date/time stamp are left untouched.

Errors: If the `AHour` value is not within a valid range (0..23) then an `EConvertError` exception is raised.

See also: `RecodeYear` (593), `RecodeMonth` (591), `RecodeDay` (589), `RecodeMinute` (591), `RecodeSecond` (592), `RecodeMilliSecond` (590), `RecodeDate` (587), `RecodeTime` (593), `RecodeDateTime` (588)

Listing: `./datutex/ex90.pp`

Program Example90;

{ This program demonstrates the RecodeHour function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, RecodeHour(**Now**, 0));

WriteLn('Today, in the first hour : ', S);

End.

44.4.104 RecodeMilliSecond

Synopsis: Replace milliseconds part of a `TDateTime` value with another millisecond.

Declaration: `function RecodeMilliSecond(const AValue: TDateTime;
 const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: `RecodeMilliSecond` replaces the millisecond part of the timestamp `AValue` with `AMilliSecond`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMilliSecond` value is not within a valid range (0..999) then an `EConvertError` exception is raised.

See also: [RecodeYear \(593\)](#), [RecodeMonth \(591\)](#), [RecodeDay \(589\)](#), [RecodeHour \(589\)](#), [RecodeMinute \(591\)](#), [RecodeSecond \(592\)](#), [RecodeDate \(587\)](#), [RecodeTime \(593\)](#), [RecodeDateTime \(588\)](#)

Listing: ./datutex/ex93.pp

Program Example93;

{ This program demonstrates the RecodeMilliSecond function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, RecodeMilliSecond(**Now**, 0));

WriteLn('This moment, milliseconds stripped : ', S);

End.

44.4.105 RecodeMinute

Synopsis: Replace minutse part of a TDateTime value with another minute.

Declaration: `function RecodeMinute(const AValue: TDateTime; const AMinute: Word)
: TDateTime`

Visibility: default

Description: `RecodeMinute` replaces the Minute part of the timestamp `AValue` with `AMinute`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMinute` value is not within a valid range (0..59) then an `EConvertError` exception is raised.

See also: [RecodeYear \(593\)](#), [RecodeMonth \(591\)](#), [RecodeDay \(589\)](#), [RecodeHour \(589\)](#), [RecodeSecond \(592\)](#), [RecodeMilliSecond \(590\)](#), [RecodeDate \(587\)](#), [RecodeTime \(593\)](#), [RecodeDateTime \(588\)](#)

Listing: `./datutex/ex91.pp`

Program Example91 ;

{ This program demonstrates the RecodeMinute function }

Uses SysUtils , DateUtils ;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss' ;

Var

 S : AnsiString ;

Begin

 S:=**FormatDateTime**(Fmt,RecodeMinute(**Now**,0));

WriteIn('This moment in the first minute of the hour: ',S);

End.

44.4.106 RecodeMonth

Synopsis: Replace month part of a TDateTime value with another month.

Declaration: `function RecodeMonth(const AValue: TDateTime; const AMonth: Word)
: TDateTime`

Visibility: default

Description: `RecodeMonth` replaces the Month part of the timestamp `AValue` with `AMonth`. All other parts of the date/time stamp are left untouched.

Errors: If the `AMonth` value is not within a valid range (1..12) then an `EConvertError` exception is raised.

See also: [RecodeYear \(593\)](#), [RecodeDay \(589\)](#), [RecodeHour \(589\)](#), [RecodeMinute \(591\)](#), [RecodeSecond \(592\)](#), [RecodeMilliSecond \(590\)](#), [RecodeDate \(587\)](#), [RecodeTime \(593\)](#), [RecodeDateTime \(588\)](#)

Listing: `./datutex/ex88.pp`

44.4.108 RecodeTime

Synopsis: Replace time part of a `TDateTime` value with another time.

Declaration: `function RecodeTime(const AValue: TDateTime; const AHour: Word;
const AMinute: Word; const ASecond: Word;
const AMilliSecond: Word) : TDateTime`

Visibility: default

Description: `RecodeTime` replaces the time part of the timestamp `AValue` with the date specified in `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. All other parts (the date part) of the date/time stamp are left untouched.

Errors: If one of the values `AHour`, `AMinute`, `ASecond` or `AMilliSecond` is not within a valid range then an `EConvertError` exception is raised.

See also: `RecodeYear` (593), `RecodeMonth` (591), `RecodeDay` (589), `RecodeHour` (589), `RecodeMinute` (591), `RecodeSecond` (592), `RecodeMilliSecond` (590), `RecodeDate` (587), `RecodeDateTime` (588)

Listing: `./datutex/ex95.pp`

Program Example95;

{ This program demonstrates the RecodeTime function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmm yyyy hh:nn:ss';

Var

 S : AnsiString;

Begin

 S := **FormatDateTime**(Fmt, **RecodeTime**(**Now**, 8, 0, 0, 0));

WriteIn('Today, 8 AM : ', S);

End.

44.4.109 RecodeYear

Synopsis: Replace year part of a `TDateTime` value with another year.

Declaration: `function RecodeYear(const AValue: TDateTime; const AYear: Word)
: TDateTime`

Visibility: default

Description: `RecodeYear` replaces the year part of the timestamp `AValue` with `AYear`. All other parts of the date/time stamp are left untouched.

Errors: If the `AYear` value is not within a valid range (1..9999) then an `EConvertError` exception is raised.

See also: `RecodeMonth` (591), `RecodeDay` (589), `RecodeHour` (589), `RecodeMinute` (591), `RecodeSecond` (592), `RecodeMilliSecond` (590), `RecodeDate` (587), `RecodeTime` (593), `RecodeDateTime` (588)

Listing: `./datutex/ex87.pp`

```

Program Example87;

{ This program demonstrates the RecodeYear function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

Var
    S : AnsiString;

Begin
    S:=FormatDateTime(Fmt, RecodeYear(Now, 1999));
    WriteLn('This moment in 1999 : ', S);
End.

```

44.4.110 SameDate

Synopsis: Check whether two TDateTime values have the same date part.

Declaration: function SameDate(const A: TDateTime; const B: TDateTime) : Boolean

Visibility: default

Description: SameDate compares the date parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDate (539) returns zero.

See also: CompareDateTime (540), CompareDate (539), CompareTime (541), SameDateTime (595), SameTime (596)

Listing: ./datutex/ex102.pp

```

Program Example102;

{ This program demonstrates the SameDate function }

Uses SysUtils, DateUtils;

Const
    Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';

Procedure Test(D1, D2 : TDateTime);

begin
    Write(FormatDateTime(Fmt, D1), ' is the same date as ');
    WriteLn(FormatDateTime(Fmt, D2), ' : ', SameDate(D1, D2));
end;

Var
    D, N : TDateTime;

Begin
    D:=Today;
    N:=Now;

```

```

Test(D,D);
Test(N,N);
Test(N+1,N);
Test(N-1,N);
Test(N+OneSecond,N);
Test(N-OneSecond,N);
End.

```

44.4.111 SameDateTime

Synopsis: Check whether two TDateTime values have the same date and time parts.

Declaration: `function SameDateTime(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: SameDateTime compares the date/time parts of two timestamps A and B and returns True if they are equal, False if they are not.

The function simply checks whether CompareDateTime (540) returns zero.

See also: CompareDateTime (540), CompareDate (539), CompareTime (541), SameDate (594), SameTime (596)

Listing: ./datutex/ex101.pp

Program Example101;

{ This program demonstrates the SameDateTime function }

Uses SysUtils, DateUtils;

Const

Fmt = 'dddd dd mmm yyyy hh:nn:ss.zzz';

Procedure Test(D1,D2 : TDateTime);

begin

Write(FormatDateTime(Fmt,D1), ' is the same datetime as ');

WriteIn(FormatDateTime(Fmt,D2), ' : ', SameDateTime(D1,D2));

end;

Var

D,N : TDateTime;

Begin

D:=Today;

N:=Now;

Test(D,D);

Test(N,N);

Test(N+1,N);

Test(N-1,N);

Test(N+OneSecond,N);

Test(N-OneSecond,N);

End.

44.4.112 SameTime

Synopsis: Check whether two `TDateTime` values have the same time part.

Declaration: `function SameTime(const A: TDateTime; const B: TDateTime) : Boolean`

Visibility: default

Description: `SameTime` compares the time parts of two timestamps `A` and `B` and returns `True` if they are equal, `False` if they are not.

The function simply checks whether `CompareTime` (541) returns zero.

See also: `CompareDateTime` (540), `CompareDate` (539), `CompareTime` (541), `SameDateTime` (595), `SameDate` (594)

Listing: `./datutex/ex103.pp`

Program `Example102;`

{ This program demonstrates the SameTime function }

Uses `SysUtils, DateUtils;`

Const

`Fmt = 'dddd dd mmmm yyyy hh:nn:ss.zzz';`

Procedure `Test(D1,D2 : TDateTime);`

begin

`Write(FormatDateTime(Fmt,D1), ' is the same time as ');`

`WriteLn(FormatDateTime(Fmt,D2), ' : ', SameTime(D1,D2));`

end;

Var

`D,N : TDateTime;`

Begin

`D:=Today;`

`N:=Now;`

`Test(D,D);`

`Test(N,N);`

`Test(N+1,N);`

`Test(N-1,N);`

`Test(N+OneSecond,N);`

`Test(N-OneSecond,N);`

End.

44.4.113 ScanDateTime

Synopsis: Scans a string for a `DateTime` pattern and returns the date/time

Declaration: `function ScanDateTime(const Pattern: string; const s: string;
const fmt: TFormatSettings; startpos: Integer)
: TDateTime; Overload`
`function ScanDateTime(const Pattern: string; const s: string;
startpos: Integer) : TDateTime; Overload`

Visibility: default

Description: `ScanDateTime` scans string `S` for the date/time pattern `Pattern`, starting at position `StartPos` (default 1). Optionally, the format settings `fmt` can be specified.

In effect, this function does the opposite of what `FormatDateTime` (1545) does. The `Pattern` variable must contain a valid date/time pattern: note that not all possible `formatdatetime` patterns can be recognized, e.g., `hn` cannot be detected properly.

Errors: In case of an error, a `EConvertError` (1616) exception is raised.

See also: `FormatDateTime` (1545)

44.4.114 SecondOf

Synopsis: Extract the second part from a `DateTime` value.

Declaration: `function SecondOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOf` returns the second of the minute part of the `AValue` date/time indication. It is a number between 0 and 59.

For an example, see `YearOf` (625)

See also: `YearOf` (625), `WeekOf` (613), `MonthOf` (583), `DayOf` (544), `HourOf` (559), `MinuteOf` (579), `MilliSecondOf` (575)

44.4.115 SecondOfDay

Synopsis: Calculate the number of seconds elapsed since the start of the day

Declaration: `function SecondOfDay(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfDay` returns the number of seconds that have passed since the start of the Day (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 return 0.

For an example, see the `HourOfDay` (559) function.

See also: `SecondOfYear` (599), `SecondOfMonth` (598), `SecondOfWeek` (598), `SecondOfTheHour` (597), `SecondOfTheMinute` (598), `HourOfDay` (559), `MinuteOfDay` (580), `MilliSecondOfTheDay` (575)

44.4.116 SecondOfTheHour

Synopsis: Calculate the number of seconds elapsed since the start of the hour

Declaration: `function SecondOfTheHour(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheHour` returns the number of seconds that have passed since the start of the Hour (HH:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:00:00.999 return 0.

For an example, see the `MinuteOfTheHour` (580) function.

See also: `SecondOfYear` (599), `SecondOfMonth` (598), `SecondOfWeek` (598), `SecondOfDay` (597), `SecondOfTheMinute` (598), `MinuteOfTheHour` (580), `MilliSecondOfTheHour` (576)

44.4.117 SecondOfTheMinute

Synopsis: Calculate the number of seconds elapsed since the start of the minute

Declaration: `function SecondOfTheMinute(const AValue: TDateTime) : Word`

Visibility: default

Description: `SecondOfTheMinute` returns the number of seconds that have passed since the start of the minute (HH:MM:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. HH:MM:00.999 return 0.

See also: `SecondOfTheYear` (599), `SecondOfTheMonth` (598), `SecondOfTheWeek` (598), `SecondOfTheDay` (597), `SecondOfTheHour` (597), `MilliSecondOfTheMinute` (576)

Listing: `./datutex/ex45.pp`

Program Example45;

{ This program demonstrates the SecondOfTheMinute function }

Uses SysUtils, DateUtils;

Var

N : TDateTime;

Begin

N:=Now;

WriteLn('Second of the Minute : ',SecondOfTheMinute(N));

WriteLn('MilliSecond of the Minute : ',
MilliSecondOfTheMinute(N));

End.

44.4.118 SecondOfTheMonth

Synopsis: Calculate number of seconds elapsed since the start of the month.

Declaration: `function SecondOfTheMonth(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheMonth` returns the number of seconds that have passed since the start of the month (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the month will return 0.

For an example, see the `WeekOfTheMonth` (613) function.

See also: `WeekOfTheMonth` (613), `DayOfTheMonth` (544), `HourOfTheMonth` (560), `MinuteOfTheMonth` (581), `MilliSecondOfTheMonth` (576)

44.4.119 SecondOfTheWeek

Synopsis: Calculate the number of seconds elapsed since the start of the week

Declaration: `function SecondOfTheWeek(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheWeek` returns the number of seconds that have passed since the start of the week (00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. 00:00:00.999 on the first day of the week will return 0.

For an example, see the `DayOfTheWeek` (545) function.

See also: `SecondOfTheYear` (599), `SecondOfTheMonth` (598), `SecondOfTheDay` (597), `SecondOfTheHour` (597), `SecondOfTheMinute` (598), `DayOfTheWeek` (545), `HourOfTheWeek` (560), `MinuteOfTheWeek` (581), `MilliSecondOfTheWeek` (577)

44.4.120 `SecondOfTheYear`

Synopsis: Calculate the number of seconds elapsed since the start of the year.

Declaration: `function SecondOfTheYear(const AValue: TDateTime) : LongWord`

Visibility: default

Description: `SecondOfTheYear` returns the number of seconds that have passed since the start of the year (January 1, 00:00:00) till the moment indicated by `AValue`. This is a zero-based number, i.e. January 1 00:00:00.999 will return 0.

For an example, see the `WeekOfTheYear` (614) function.

See also: `WeekOfTheYear` (614), `DayOfTheYear` (545), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

44.4.121 `SecondsBetween`

Synopsis: Calculate the number of whole seconds between two `DateTime` values.

Declaration: `function SecondsBetween(const ANow: TDateTime; const AThen: TDateTime) : Int64`

Visibility: default

Description: `SecondsBetween` returns the number of whole seconds between `ANow` and `AThen`. This means the fractional part of a second (milliseconds etc.) is dropped.

See also: `YearsBetween` (626), `MonthsBetween` (584), `WeeksBetween` (614), `DaysBetween` (545), `HoursBetween` (561), `MinutesBetween` (581), `MilliSecondsBetween` (578)

Listing: `./datutex/ex61.pp`

Program `Example61` ;

{ This program demonstrates the SecondsBetween function }

Uses `SysUtils` , `DateUtils` ;

Procedure `Test` (`ANow`, `AThen` : `TDateTime`) ;

begin

Write ('Number of seconds between ');
 Write (`TimeToStr` (`AThen`) , ' and ' , `TimeToStr` (`ANow`));
 WriteLn (' : ' , `SecondsBetween` (`ANow`, `AThen`));
end ;

Var


```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(999*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5.4*OneSecond);
Test(D1,D2);
D2:=D1-(2.5*OneSecond);
Test(D1,D2);
```

End.**44.4.122 SecondSpan**

Synopsis: Calculate the approximate number of seconds between two DateTime values.

Declaration: `function SecondSpan(const ANow: TDateTime; const AThen: TDateTime) : Double`

Visibility: default

Description: `SecondSpan` returns the number of seconds between `ANow` and `AThen`, including any fractional parts of a second.

See also: `YearSpan` ([627](#)), `MonthSpan` ([585](#)), `WeekSpan` ([616](#)), `DaySpan` ([548](#)), `HourSpan` ([562](#)), `MinuteSpan` ([582](#)), `MilliSecondSpan` ([579](#)), `SecondsBetween` ([599](#))

Listing: `./datutex/ex69.pp`

Program Example69;

```
{ This program demonstrates the SecondSpan function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime);

begin

```
Write('Number of seconds between ');
Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
WriteLn(' : ', SecondSpan(ANow, AThen));
end;
```

Var

```
D1,D2 : TDateTime;
```

Begin

```
D1:=Now;
D2:=D1-(999*OneMilliSecond);
Test(D1,D2);
D2:=D1-(1001*OneMilliSecond);
```

```

Test(D1,D2);
D2:=D1-(2001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5001*OneMilliSecond);
Test(D1,D2);
D2:=D1-(5.4*OneSecond);
Test(D1,D2);
D2:=D1-(2.5*OneSecond);
Test(D1,D2);
End.

```

44.4.123 StartOfDay

Synopsis: Return the start of a day as a `DateTime` value, given a day indication

Declaration:

```

function StartOfDay(const AYear: Word; const AMonth: Word;
                    const ADay: Word) : TDateTime; Overload
function StartOfDay(const AYear: Word; const ADayOfYear: Word)
                    : TDateTime; Overload

```

Visibility: default

Description: `StartOfDay` returns a `TDateTime` value with the date/time indication of the start (0:0:0.000) of the day given by `AYear`, `AMonth`, `ADay`.

The day may also be indicated with a `AYear`, `ADayOfYear` pair.

See also: `StartOfDay` ([603](#)), `StartOfTheWeek` ([604](#)), `StartOfAWeek` ([602](#)), `StartOfAMonth` ([602](#)), `StartOfTheMonth` ([604](#)), `EndOfTheWeek` ([558](#)), `EndOfAWeek` ([556](#)), `EndOfTheYear` ([559](#)), `EndOfAYear` ([557](#)), `EndOfTheMonth` ([558](#)), `EndOfAMonth` ([555](#)), `EndOfTheDay` ([557](#)), `EndOfDay` ([555](#))

Listing: `./datutex/ex38.pp`

Program Example38;

```
{ This program demonstrates the StartOfDay function }
```

Uses SysUtils, DateUtils;

Const

```
Fmt = ' "Start of the day : "dd mmm yyyy hh:nn:ss ';
```

Var

```
Y,M,D : Word;
```

Begin

```
Y:=YearOf(Today);
```

```
M:=MonthOf(Today);
```

```
D:=DayOf(Today);
```

```
WriteLn(FormatDateTime(Fmt, StartOfDay(Y,M,D)));
```

```
DecodeDateDay(Today,Y,D);
```

```
WriteLn(FormatDateTime(Fmt, StartOfDay(Y,D)));
```

End.

44.4.124 StartOfAMonth

Synopsis: Return first date of month, given a year/month pair.

Declaration: `function StartOfAMonth(const AYear: Word; const AMonth: Word)
: TDateTime`

Visibility: default

Description: `StartOfAMonth` returns a `TDateTime` value with the date of the first day of the month indicated by the `AYear`, `AMonth` pair.

See also: `StartOfTheMonth` (604), `EndOfTheMonth` (558), `EndOfAMonth` (555), `EndOfTheYear` (559), `EndOfAYear` (557), `StartOfAWeek` (602), `StartOfTheWeek` (604)

Listing: ./datutex/ex30.pp

Program Example30;

{ This program demonstrates the StartOfAMonth function }

Uses SysUtils, DateUtils;

Const

 Fmt = ' "First day of this month : "dd mmm yyyy ';

Var

 Y,M : Word;

Begin

 Y:=YearOf(Today);

 M:=MonthOf(Today);

 WriteLn(FormatDateTime(Fmt, StartOfAMonth(Y,M)));

End.

44.4.125 StartOfAWeek

Synopsis: Return a day of the week, given a year, week and day in the week.

Declaration: `function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word;
 const ADayOfWeek: Word) : TDateTime`
`function StartOfAWeek(const AYear: Word; const AWeekOfYear: Word)
 : TDateTime`

Visibility: default

Description: `StartOfAWeek` returns a `TDateTime` value with the date of the indicated day of the week indicated by the `AYear`, `AWeek`, `ADayOfWeek` values.

The default value for `ADayOfWeek` is 1.

See also: `StartOfTheWeek` (604), `EndOfTheWeek` (558), `EndOfAWeek` (556), `StartOfAMonth` (602), `EndOfTheYear` (559), `EndOfAYear` (557), `EndOfTheMonth` (558), `EndOfAMonth` (555)

Listing: ./datutex/ex34.pp

Program Example34;

{ This program demonstrates the StartOfAWeek function }

Uses SysUtils , DateUtils ;

Const

```
Fmt = '"First day of this week : "dd mmm yyyy hh:nn:ss';
Fmt2 = '"Second day of this week : "dd mmm yyyy hh:nn:ss';
```

Var

```
Y,W : Word;
```

Begin

```
Y:=YearOf(Today);
W:=WeekOf(Today);
WriteLn(FormatDateTime(Fmt, StartOfAWeek(Y,W)));
WriteLn(FormatDateTime(Fmt2, StartOfAWeek(Y,W,2)));
```

End.

44.4.126 StartOfAYear

Synopsis: Return the first day of a given year.

Declaration: function StartOfAYear(const AYear: Word) : TDateTime

Visibility: default

Description: StartOfAYear returns a TDateTime value with the date of the first day of the year AYear (January 1).

See also: StartOfTheYear ([605](#)), EndOfTheYear ([559](#)), EndOfAYear ([557](#)), EndOfTheMonth ([558](#)), EndOfA-Month ([555](#)), StartOfAWeek ([602](#)), StartOfTheWeek ([604](#))

Listing: ./datutex/ex26.pp

Program Example26;

```
{ This program demonstrates the StartOfAYear function }
```

Uses SysUtils , DateUtils ;

Const

```
Fmt = '"First day of this year : "dd mmm yyyy';
```

Begin

```
WriteLn(FormatDateTime(Fmt, StartOfAYear(YearOf(Today))));
```

End.

44.4.127 StartOfTheDay

Synopsis: Calculate the start of the day as a DateTime value, given a moment in the day.

Declaration: function StartOfTheDay(const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheDay extracts the date part of AValue and returns a TDateTime value with the date/time indication of the start (0:0:0.000) of this day.

See also: [StartOfADay \(601\)](#), [StartOfTheWeek \(604\)](#), [StartOfAWeek \(602\)](#), [StartOfAMonth \(602\)](#), [StartOfTheMonth \(604\)](#), [EndOfTheWeek \(558\)](#), [EndOfAWeek \(556\)](#), [EndOfTheYear \(559\)](#), [EndOfAYear \(557\)](#), [EndOfTheMonth \(558\)](#), [EndOfAMonth \(555\)](#), [EndOftheDay \(557\)](#), [EndOfADay \(555\)](#)

Listing: ./datutex/ex36.pp

Program Example36;

{ This program demonstrates the StartOfTheDay function }

Uses SysUtils, DateUtils;

Const

Fmt = 'Start of the day : "dd mmm yyyy hh:nn:ss';

Begin

WriteIn (FormatDateTime (Fmt, StartOfTheDay (Today)));

End.

44.4.128 StartOfTheMonth

Synopsis: Calculate the first day of the month, given a date in that month.

Declaration: function StartOfTheMonth(const AValue: TDateTime) : TDateTime

Visibility: default

Description: StartOfTheMonth extracts the year and month parts of AValue and returns a TDateTime value with the date of the first day of that year and month as the StartOfAMonth ([602](#)) function.

See also: [StartOfAMonth \(602\)](#), [EndOfTheYear \(559\)](#), [EndOfAYear \(557\)](#), [EndOfTheMonth \(558\)](#), [EndOfAMonth \(555\)](#), [StartOfAWeek \(602\)](#), [StartOfTheWeek \(604\)](#)

Listing: ./datutex/ex28.pp

Program Example28;

{ This program demonstrates the StartOfTheMonth function }

Uses SysUtils, DateUtils;

Const

Fmt = 'First day of this month : "dd mmm yyyy';

Begin

WriteIn (FormatDateTime (Fmt, StartOfTheMonth (Today)));

End.

44.4.129 StartOfTheWeek

Synopsis: Return the first day of the week, given a date.

Declaration: function StartOfTheWeek(const AValue: TDateTime) : TDateTime

Visibility: default

Description: `StartOfTheWeek` extracts the year and week parts of `AValue` and returns a `TDateTime` value with the date of the first day of that week as the `StartOfAWeek` (602) function.

See also: `StartOfAWeek` (602), `EndOfTheWeek` (558), `EndOfAWeek` (556), `StartOfAMonth` (602), `EndOfTheYear` (559), `EndOfAYear` (557), `EndOfTheMonth` (558), `EndOfAMonth` (555)

Listing: `./datutex/ex32.pp`

Program `Example32`;

{ This program demonstrates the StartOfTheWeek function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this week : "dd mmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheWeek (Today)));`

End.

44.4.130 StartOfTheYear

Synopsis: Return the first day of the year, given a date in this year.

Declaration: `function StartOfTheYear(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `StartOfTheYear` extracts the year part of `AValue` and returns a `TDateTime` value with the date of the first day of that year (January 1), as the `StartOfAYear` (603) function.

See also: `StartOfAYear` (603), `EndOfTheYear` (559), `EndOfAYear` (557)

Listing: `./datutex/ex24.pp`

Program `Example24`;

{ This program demonstrates the StartOfTheYear function }

Uses `SysUtils`, `DateUtils`;

Const

`Fmt = ' "First day of this year : "dd mmm yyyy ';`

Begin

`WriteLn (FormatDateTime (Fmt, StartOfTheYear (Today)));`

End.

44.4.131 TimeOf

Synopsis: Extract the time part from a `DateTime` indication.

Declaration: `function TimeOf(const AValue: TDateTime) : TDateTime`

Visibility: default

Description: `TimeOf` extracts the time part from `AValue` and returns the result.

Since the `TDateTime` is actually a double with the time part encoded in the fractional part, this operation corresponds to a call to `Frac`.

See also: `DateOf` ([542](#)), `YearOf` ([625](#)), `MonthOf` ([583](#)), `DayOf` ([544](#)), `HourOf` ([559](#)), `MinuteOf` ([579](#)), `SecondOf` ([597](#)), `MilliSecondOf` ([575](#))

Listing: `./datutex/ex2.pp`

Program `Example2`;

{ This program demonstrates the TimeOf function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn('Time is : ', TimeToStr(TimeOf(Now)));`
End.

44.4.132 Today

Synopsis: Return the current date

Declaration: `function Today : TDateTime`

Visibility: `default`

Description: `Today` is an alias for the `Date` ([1499](#)) function in the `sysutils` ([1442](#)) unit.

For an example, see `Yesterday` ([627](#))

See also: `Date` ([1499](#)), `Yesterday` ([627](#)), `Tomorrow` ([606](#))

44.4.133 Tomorrow

Synopsis: Return the next day

Declaration: `function Tomorrow : TDateTime`

Visibility: `default`

Description: `Tomorrow` returns tomorrow's date. `Tomorrow` is determined from the system clock, i.e. it is `Today` ([606](#)) +1.

See also: `Today` ([606](#)), `Yesterday` ([627](#))

Listing: `./datutex/ex19.pp`

Program `Example19`;

{ This program demonstrates the Tomorrow function }

Uses `SysUtils`, `DateUtils`;

Begin

`WriteLn(FormatDateTime('"Today is" dd mmm yyyy', Today));`
`WriteLn(FormatDateTime('"Tomorrow will be" dd mmm yyyy', Tomorrow));`
End.

44.4.134 TryEncodeDateDay

Synopsis: Encode a year and day of year to a TDateTime value

Declaration: `function TryEncodeDateDay(const AYear: Word; const ADayOfYear: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateDay` encodes the values `AYear` and `ADayOfYear` to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned. `False` is returned if any of the arguments is not valid.

See also: `EncodeDateDay` (553), `EncodeDateTime` (553), `EncodeDateMonthWeek` (553), `EncodeDateWeek` (554), `TryEncodeDateTime` (608), `TryEncodeDateMonthWeek` (607), `TryEncodeDateWeek` (609)

Listing: `./datutex/ex84.pp`

Program Example84;

{ This program demonstrates the TryEncodeDateDay function }

Uses SysUtils, DateUtils;

Var

Y, DoY : Word;
TS : TDateTime;

Begin

DecodeDateDay(Now, Y, DoY);
If TryEncodeDateDay(Y, DoY, TS) then
WriteLn('Today is : ', DateToStr(TS))
else
WriteLn('Wrong year/day of year indication');

End.

44.4.135 TryEncodeDateMonthWeek

Synopsis: Encode a year, month, week of month and day of week to a TDateTime value

Declaration: `function TryEncodeDateMonthWeek(const AYear: Word; const AMonth: Word;
const AWeekOfMonth: Word;
const ADayOfWeek: Word;
out AValue: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDateMonthWeek` encodes the values `AYear`, `AMonth`, `WeekOfMonth`, `ADayOfWeek`, to a date value and returns this value in `AValue`.

If the encoding was successful, `True` is returned, `False` if any of the arguments is not valid.

See also: `DecodeDateMonthWeek` (550), `EncodeDateTime` (553), `EncodeDateWeek` (554), `EncodeDateDay` (553), `EncodeDateMonthWeek` (553), `TryEncodeDateTime` (608), `TryEncodeDateWeek` (609), `TryEncodeDateDay` (607), `NthDayOfWeek` (586)

Listing: `./datutex/ex86.pp`

Program Example86;

{ This program demonstrates the TryEncodeDateMonthWeek function }

Uses SysUtils, DateUtils;

Var

Y,M,WoM,Dow : Word;
TS : TDateTime;

Begin

DecodeDateMonthWeek(**Now**,Y,M,WoM,Dow);
If TryEncodeDateMonthWeek(Y,M,WoM,Dow,TS) **then**
 WriteLn('Today is : ',**DateToStr**(TS))
else
 WriteLn('Invalid year/month/week/dow indication ');

End.

44.4.136 TryEncodeDateTime

Synopsis: Encode a Year, Month, Day, Hour, minute, seconds, milliseconds tuple to a TDateTime value

Declaration: function TryEncodeDateTime(const AYear: Word; const AMonth: Word;
 const ADay: Word; const AHour: Word;
 const AMinute: Word; const ASecond: Word;
 const AMilliSecond: Word;
 out AValue: TDateTime) : Boolean

Visibility: default

Description: EncodeDateTime encodes the values AYearAMonth, ADay,AHour, AMinute,ASecond and AMilliSecond to a date/time value and returns this value in AValue.

If the date was encoded successfully, True is returned, False is returned if one of the arguments is not valid.

See also: EncodeDateTime (553), EncodeDateMonthWeek (553), EncodeDateWeek (554), EncodeDateDay (553), TryEncodeDateDay (607), TryEncodeDateWeek (609), TryEncodeDateMonthWeek (607)

Listing: ./datutex/ex80.pp

Program Example79;

{ This program demonstrates the TryEncodeDateTime function }

Uses SysUtils, DateUtils;

Var

Y,Mo,D,H,Mi,S,MS : Word;
TS : TDateTime;

Begin

DecodeDateTime(**Now**,Y,Mo,D,H,Mi,S,MS);
If TryEncodeDateTime(Y,Mo,D,H,Mi,S,MS,TS) **then**
 WriteLn('Now is : ',**DateTimeToStr**(TS))
else
 WriteLn('Wrong date/time indication ');

End.

44.4.137 TryEncodeDateWeek

Synopsis: Encode a year, week and day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                           out AValue: TDateTime; const ADayOfWeek: Word)
                           : Boolean
function TryEncodeDateWeek(const AYear: Word; const AWeekOfYear: Word;
                           out AValue: TDateTime) : Boolean
```

Visibility: default

Description: TryEncodeDateWeek encodes the values AYear, AWeekOfYear and ADayOfWeek to a date value and returns this value in AValue.

If the encoding was successful, True is returned. False is returned if any of the arguments is not valid.

See also: EncodeDateMonthWeek (553), EncodeDateWeek (554), EncodeDateTime (553), EncodeDateDay (553), TryEncodeDateTime (608), TryEncodeDateMonthWeek (607), TryEncodeDateDay (607)

Listing: ./datutex/ex82.pp

Program Example82;

{ This program demonstrates the TryEncodeDateWeek function }

Uses SysUtils, DateUtils;

Var

Y,W,Dow : Word;
TS : TDateTime;

Begin

DecodeDateWeek(**Now**,Y,W,Dow);
If TryEncodeDateWeek(Y,W,TS,Dow) **then**
 WriteLn('Today is : ',DateToStr(TS))
else
 WriteLn('Invalid date/week indication');

End.

44.4.138 TryEncodeDayOfWeekInMonth

Synopsis: Encode a year, month, week, day of week triplet to a TDateTime value

Declaration:

```
function TryEncodeDayOfWeekInMonth(const AYear: Word;
                                   const AMonth: Word;
                                   const ANthDayOfWeek: Word;
                                   const ADayOfWeek: Word;
                                   out AValue: TDateTime) : Boolean
```

Visibility: default

Description: `EncodeDayOfWeekInMonth` encodes `AYear`, `AMonth`, `ADayOfWeek` and `ANthDayOfWeek` to a valid date stamp and returns the result in `AValue`.

`ANthDayOfWeek` is the N-th time that this weekday occurs in the month, e.g. the third saturday of the month.

The function returns `True` if the encoding was succesful, `False` if any of the values is not in range.

See also: `NthDayOfWeek` (586), `EncodeDateMonthWeek` (553), `#rtl.sysutils.DayOfWeek` (1503), `DecodeDayOfWeekInMonth` (552), `EncodeDayOfWeekInMonth` (554)

Listing: `./datutex/ex106.pp`

Program `Example105`;

{ This program demonstrates the DecodeDayOfWeekInMonth function }

Uses `SysUtils`, `DateUtils`;

Var

`Y,M,NDoW,DoW` : `Word`;

`D` : `TDateTime`;

Begin

`DecodeDayOfWeekInMonth (Date , Y,M,NDoW,DoW)` ;

If `TryEncodeDayOfWeekInMonth (Y,M,NDoW,DoW,D)` **then**

begin

Write (`DateToStr(D)`, ' is the ', `NDoW`, '-th ');

WriteLn (`formatdateTime('dddd',D)`, ' of the month. ');

end

else

WriteLn ('Invalid year/month/NthDayOfWeek combination');

End.

44.4.139 TryEncodeTimeInterval

Synopsis: Try to encode an interval as a `TDateTime` value.

Declaration: `function TryEncodeTimeInterval (Hour: Word; Min: Word; Sec: Word; MSec: Word; out Time: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeTimeInterval` encodes a time interval expressed in `Hour`, `Min`, `Sec`, `MSec` as a `TDateTime` value and returns the value in `Time`. It returns `True` if `Min`, `Sec`, `MSec` contain valid time values (i.e. less than 60, 60 resp. `MSec`). The number of hours may be larger than 24.

See also: `EncodeTimeInterval` (554)

44.4.140 TryJulianDateToDateTime

Synopsis: Convert a Julian date representation to a `TDateTime` value.

Declaration: `function TryJulianDateToDateTime (const AValue: Double; out ADateTime: TDateTime) : Boolean`

Visibility: default

Description: Try to convert a Julian date to a regular `TDateTime` date/time representation.

See also: [DateTimeToJulianDate \(543\)](#), [JulianDateToDateTime \(574\)](#), [DateTimeToModifiedJulianDate \(544\)](#), [TryModifiedJulianDateToDateTime \(611\)](#)

44.4.141 TryModifiedJulianDateToDateTime

Synopsis: Convert a modified Julian date representation to a `TDateTime` value.

Declaration:

```
function TryModifiedJulianDateToDateTime(const AValue: Double;
                                         out ADateTime: TDateTime)
                                         : Boolean
```

Visibility: default

Description: Not yet implemented.

Errors: Currently, trying to use this function will raise an exception.

See also: [DateTimeToJulianDate \(543\)](#), [JulianDateToDateTime \(574\)](#), [TryJulianDateToDateTime \(610\)](#), [DateTimeToModifiedJulianDate \(544\)](#), [ModifiedJulianDateToDateTime \(583\)](#)

44.4.142 TryRecodeDateTime

Synopsis: Replace selected parts of a `TDateTime` value with other values

Declaration:

```
function TryRecodeDateTime(const AValue: TDateTime; const AYear: Word;
                           const AMonth: Word; const ADay: Word;
                           const AHour: Word; const AMinute: Word;
                           const ASecond: Word;
                           const AMilliSecond: Word;
                           out AResult: TDateTime) : Boolean
```

Visibility: default

Description: `TryRecodeDateTime` replaces selected parts of the timestamp `AValue` with the date/time values specified in `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` and `AMilliSecond`. If any of these values equals the pre-defined constant `RecodeLeaveFieldAsIs (539)`, then the corresponding part of the date/time stamp is left untouched.

The resulting date/time is returned in `AValue`.

The function returns `True` if the encoding was succesful. It returns `False` if one of the values `AYear`, `AMonth`, `ADay`, `AHour`, `AMinute`, `ASecond` or `AMilliSecond` is not within a valid range.

See also: [RecodeYear \(593\)](#), [RecodeMonth \(591\)](#), [RecodeDay \(589\)](#), [RecodeHour \(589\)](#), [RecodeMinute \(591\)](#), [RecodeSecond \(592\)](#), [RecodeMilliSecond \(590\)](#), [RecodeDate \(587\)](#), [RecodeTime \(593\)](#), [RecodeDateTime \(588\)](#)

Listing: `./datutex/ex97.pp`

Program Example97;

{ This program demonstrates the TryRecodeDateTime function }

Uses SysUtils, DateUtils;

Const

 Fmt = 'dddd dd mmmm yyyy hh:nn:ss';

```

Var
  S : AnsiString;
  D : TDateTime ;

Begin
  If TryRecodeDateTime(Now,2000,2,RecodeLeaveFieldAsIs,0,0,0,0,D) then
    begin
      S:=FormatDateTime(Fmt,D);
      WriteLn('This moment in februari 2000 : ',S);
    end
  else
    WriteLn('This moment did/does not exist in februari 2000');
  End.

```

44.4.143 UniversalTimeToLocal

Synopsis: Convert UTC time to local time

Declaration: `function UniversalTimeToLocal(UT: TDateTime) : TDateTime`
`function UniversalTimeToLocal(UT: TDateTime; TZOffset: Integer)`
`: TDateTime`

Visibility: default

Description: `UniversalTimeToLocal` converts a universal time indication to a local time: it applies the `TZOffset` timezone offset to the UT Universal time (UTC). If no `TZOffset` is specified, the local time offset as returned by `GetLocalTimeOffset` (537) is used.

Note that for times in the past or in the future, or for timezones with DST, omitting the `TZOffset` may lead to wrong results, as the current timezone offset is used. Calculation of the correct timezone offset for a given date is very complicated, and outside the scope of this call.

See also: `GetLocalTimeOffset` (537), `LocalTimeToUniversal` (574)

44.4.144 UnixTimeStampToMac

Synopsis: Convert Unix Timestamp to a Mac Timestamp

Declaration: `function UnixTimeStampToMac(const AValue: Int64) : Int64`

Visibility: default

Description: `UnixTimeStampToMac` converts the unix epoch time in `AValue` to a valid Mac timestamp indication and returns the result.

Errors: None.

See also: `DateTimeToMac` (543), `MacToDateTime` (575), `MacTimeStampToUnix` (575)

44.4.145 UnixToDateTime

Synopsis: Convert Unix epoch time to a TDateTime value

Declaration: `function UnixToDateTime(const AValue: Int64) : TDateTime`

Visibility: default

Description: `UnixToDateTime` converts epoch time (seconds elapsed since 1/1/1970) to a `TDateTime` value.

See also: `DateTimeToUnix` ([544](#))

44.4.146 WeekOf

Synopsis: Extract week (of the year) from a given date.

Declaration: `function WeekOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeekOf` returns the week-of-the-year part of the `AValue` date/time indication. It is a number between 1 and 53.

For an example, see `YearOf` ([625](#))

See also: `YearOf` ([625](#)), `DayOf` ([544](#)), `MonthOf` ([583](#)), `HourOf` ([559](#)), `MinuteOf` ([579](#)), `SecondOf` ([597](#)), `MilliSecondOf` ([575](#))

44.4.147 WeekOfTheMonth

Synopsis: Extract the week of the month (and optionally month and year) from a `DateTime` value

Declaration: `function WeekOfTheMonth(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheMonth(const AValue: TDateTime; out AYear: Word;`
`out AMonth: Word) : Word; Overload`

Visibility: default

Description: `WeekOfTheMonth` extracts the week of the month from `AValue` and returns it, and optionally returns the year and month as well (in `AYear`, `AMonth` respectively).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year and month may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: `WeekOfTheYear` ([614](#)), `DayOfTheMonth` ([544](#)), `HourOfTheMonth` ([560](#)), `MinuteOfTheMonth` ([581](#)), `SecondOfTheMonth` ([598](#)), `MilliSecondOfTheMonth` ([576](#))

Listing: `./datutex/ex41.pp`

Program `Example41`;

{ This program demonstrates the WeekOfTheMonth function }

Uses `SysUtils`, `DateUtils`;

Var

`N : TDateTime;`

Begin

```

N:=Now;
WriteLn('Week of the Month      : ',WeekOfTheMonth(N));
WriteLn('Day of the Month       : ',DayOfTheMonth(N));
WriteLn('Hour of the Month        : ',HourOfTheMonth(N));
WriteLn('Minute of the Month      : ',MinuteOfTheMonth(N));
WriteLn('Second of the Month     : ',SecondOfTheMonth(N));
WriteLn('MilliSecond of the Month : ',

```

```
MilliSecondOfTheMonth(N));
```

```
End.
```

44.4.148 WeekOfTheYear

Synopsis: Extract the week of the year (and optionally year) of a DateTime indication.

Declaration: `function WeekOfTheYear(const AValue: TDateTime) : Word; Overload`
`function WeekOfTheYear(const AValue: TDateTime; out AYear: Word) : Word`
`; Overload`

Visibility: default

Description: `WeekOfTheYear` extracts the week of the year from `AValue` and returns it, and optionally returns the year as well. It returns the same value as `WeekOf` (613).

Remark: Note that weeks are numbered from 1 using the ISO 8601 standard, and the day of the week as well. This means that the year may not be the same as the year part of the date, since the week may start in the previous year as the first week of the year is the week with at least 4 days in it.

See also: `WeekOf` (613), `MonthOfTheYear` (584), `DayOfTheYear` (545), `HourOfTheYear` (561), `MinuteOfTheYear` (581), `SecondOfTheYear` (599), `MilliSecondOfTheYear` (577)

Listing: `./datutex/ex40.pp`

Program `Example40;`

```
{ This program demonstrates the WeekOfTheYear function }
```

```
Uses SysUtils, DateUtils;
```

```
Var
```

```
  N : TDateTime;
```

```
Begin
```

```
  N:=Now;
```

```
  WriteLn('Month of the year      : ', MonthOfTheYear(N));
```

```
  WriteLn('Week of the year       : ', WeekOfTheYear(N));
```

```
  WriteLn('Day of the year        : ', DayOfTheYear(N));
```

```
  WriteLn('Hour of the year       : ', HourOfTheYear(N));
```

```
  WriteLn('Minute of the year    : ', MinuteOfTheYear(N));
```

```
  WriteLn('Second of the year    : ', SecondOfTheYear(N));
```

```
  WriteLn('MilliSecond of the year : ',  
          MilliSecondOfTheYear(N));
```

```
End.
```

44.4.149 WeeksBetween

Synopsis: Calculate the number of whole weeks between two DateTime values

Declaration: `function WeeksBetween(const ANow: TDateTime; const AThen: TDateTime)`
`: Integer`

Visibility: default

Description: `WeeksBetween` returns the number of whole weeks between `ANow` and `AThen`. This means the fractional part of a Week is dropped.

See also: [YearsBetween \(626\)](#), [MonthsBetween \(584\)](#), [DaysBetween \(545\)](#), [HoursBetween \(561\)](#), [MinutesBetween \(581\)](#), [SecondsBetween \(599\)](#), [MillisecondsBetween \(578\)](#)

Listing: ./datutex/ex57.pp

Program Example57 ;

{ This program demonstrates the WeeksBetween function }

Uses SysUtils , DateUtils ;

Procedure Test (ANow, AThen : TDateTime) ;

begin

Write ('Number of weeks between ') ;

Write (**DateToStr** (AThen) , ' and ' , **DateToStr** (ANow)) ;

WriteLn (' : ' , WeeksBetween (ANow, AThen)) ;

end ;

Var

 D1, D2 : TDateTime ;

Begin

 D1 := Today ;

 D2 := Today - 7 ;

 Test (D1, D2) ;

 D2 := Today - 8 ;

 Test (D1, D2) ;

 D2 := Today - 14 ;

 Test (D1, D2) ;

 D2 := Today - 35 ;

 Test (D1, D2) ;

 D2 := Today - 36 ;

 Test (D1, D2) ;

 D2 := Today - 17 ;

 Test (D1, D2) ;

End.

44.4.150 WeeksInAYear

Synopsis: Return the number of weeks in a given year

Declaration: `function WeeksInAYear(const AYear: Word) : Word`

Visibility: default

Description: `WeeksInAYear` returns the number of weeks in the year `AYear`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: [WeeksInYear \(616\)](#), [DaysInYear \(548\)](#), [DaysInAYear \(547\)](#), [DaysInMonth \(547\)](#), [DaysInAMonth \(546\)](#)

Listing: ./datutex/ex13.pp

Program Example13;

{ This program demonstrates the WeeksInAYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', WeeksInAYear(Y), ' weeks. ');

End.

44.4.151 WeeksInYear

Synopsis: return the number of weeks in the year, given a date

Declaration: `function WeeksInYear(const AValue: TDateTime) : Word`

Visibility: default

Description: `WeeksInYear` returns the number of weeks in the year part of `AValue`. The return value is either 52 or 53.

Remark: The first week of the year is determined according to the ISO 8601 standard: It is the first week that has at least 4 days in it, i.e. it includes a thursday.

See also: `WeeksInAYear` ([615](#)), `DaysInYear` ([548](#)), `DaysInAYear` ([547](#)), `DaysInMonth` ([547](#)), `DaysInAMonth` ([546](#))

Listing: ./datutex/ex12.pp

Program Example12;

{ This program demonstrates the WeeksInYear function }

Uses SysUtils, DateUtils;

Var

Y : Word;

Begin

For Y:=1992 to 2010 do

WriteLn(Y, ' has ', WeeksInYear(EncodeDate(Y,2,1)), ' weeks. ');

End.

44.4.152 WeekSpan

Synopsis: Calculate the approximate number of weeks between two DateTime values.

Declaration: `function WeekSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: `WeekSpan` returns the number of weeks between `ANow` and `AThen`, including any fractional parts of a week.

See also: `YearSpan` (627), `MonthSpan` (585), `DaySpan` (548), `HourSpan` (562), `MinuteSpan` (582), `SecondSpan` (600), `MilliSecondSpan` (579), `WeeksBetween` (614)

Listing: `./datutex/ex65.pp`

Program `Example57`;

{ This program demonstrates the WeekSpan function }

Uses `SysUtils`, `DateUtils`;

Procedure `Test(ANow, AThen : TDateTime);`

begin

`Write('Number of weeks between ');`

`Write(DateToStr(AThen), ' and ', DateToStr(ANow));`

`WriteLn(' : ', WeekSpan(ANow, AThen));`

end;

Var

`D1, D2 : TDateTime;`

Begin

`D1 := Today;`

`D2 := Today - 7;`

`Test(D1, D2);`

`D2 := Today - 8;`

`Test(D1, D2);`

`D2 := Today - 14;`

`Test(D1, D2);`

`D2 := Today - 35;`

`Test(D1, D2);`

`D2 := Today - 36;`

`Test(D1, D2);`

`D2 := Today - 17;`

`Test(D1, D2);`

End.

44.4.153 WithinPastDays

Synopsis: Check whether two datetimes are only a number of days apart

Declaration: `function WithinPastDays(const ANow: TDateTime; const AThen: TDateTime;
 const ADays: Integer) : Boolean`

Visibility: `default`

Description: `WithinPastDays` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `ADays` days apart, or `False` if they are further apart.

Remark: Since this function uses the `DaysBetween` (545) function to calculate the difference in days, this means that fractional days do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half days apart, the result will also be `True`

See also: `WithinPastYears` (624), `WithinPastMonths` (621), `WithinPastWeeks` (623), `WithinPastHours` (618), `WithinPastMinutes` (620), `WithinPastSeconds` (622), `WithinPastMilliseconds` (619)

Listing: ./datutex/ex50.pp

Program Example50;

{ This program demonstrates the WithinPastDays function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; ADays : Integer);

begin

Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));

Write(' are within ', ADays, ' days: ');

WriteLn(WithinPastDays(ANow, AThen, ADays));

end;

Var

 D1, D2 : TDateTime;

Begin

 D1 := Now;

 D2 := Today - 23/24;

 Test(D1, D2, 1);

 D2 := Today - 1;

 Test(D1, D2, 1);

 D2 := Today - 25/24;

 Test(D1, D2, 1);

 D2 := Today - 26/24;

 Test(D1, D2, 5);

 D2 := Today - 5.4;

 Test(D1, D2, 5);

 D2 := Today - 2.5;

 Test(D1, D2, 1);

 Test(D1, D2, 2);

 Test(D1, D2, 3);

End.

44.4.154 WithinPastHours

Synopsis: Check whether two datetimes are only a number of hours apart

Declaration: function WithinPastHours(const ANow: TDateTime; const AThen: TDateTime;
const AHours: Int64) : Boolean

Visibility: default

Description: WithinPastHours compares the timestamps ANow and AThen and returns True if the difference between them is at most AHours hours apart, or False if they are further apart.

Remark: Since this function uses the HoursBetween (561) function to calculate the difference in Hours, this means that fractional hours do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half hours apart, the result will also be True

See also: WithinPastYears (624), WithinPastMonths (621), WithinPastWeeks (623), WithinPastDays (617), WithinPastMinutes (620), WithinPastSeconds (622), WithinPastMilliseconds (619)

Listing: ./datutex/ex51.pp

```

Program Example51;

{ This program demonstrates the WithinPastHours function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AHours : Integer);

begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', AHours, ' hours: ');
  WriteLn(WithinPastHours(ANow, AThen, AHours));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Now;
  D2 := D1 - (59 * OneMinute);
  Test(D1, D2, 1);
  D2 := D1 - (61 * OneMinute);
  Test(D1, D2, 1);
  D2 := D1 - (122 * OneMinute);
  Test(D1, D2, 1);
  D2 := D1 - (306 * OneMinute);
  Test(D1, D2, 5);
  D2 := D1 - (5.4 * OneHour);
  Test(D1, D2, 5);
  D2 := D1 - (2.5 * OneHour);
  Test(D1, D2, 1);
  Test(D1, D2, 2);
  Test(D1, D2, 3);
End.

```

44.4.155 WithinPastMilliseconds

Synopsis: Check whether two datetimes are only a number of milliseconds apart

Declaration: `function WithinPastMilliseconds(const ANow: TDateTime;
const AThen: TDateTime;
const AMilliSeconds: Int64) : Boolean`

Visibility: default

Description: `WithinPastMilliseconds` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AMilliSeconds` milliseconds apart, or `False` if they are further apart.

Remark: Since this function uses the `MillisecondsBetween` (578) function to calculate the difference in milliseconds, this means that fractional milliseconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half milliseconds apart, the result will also be `True`

See also: `WithinPastYears` (624), `WithinPastMonths` (621), `WithinPastWeeks` (623), `WithinPastDays` (617), `WithinPastHours` (618), `WithinPastMinutes` (620), `WithinPastSeconds` (622)

Listing: `./datutex/ex54.pp`

Program Example54;

{ This program demonstrates the WithinPastMilliseconds function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMilliseconds : Integer);

begin

Write(TimeToStr(AThen), ' and ', TimeToStr(ANow));
 Write(' are within ', AMilliseconds, ' milliseconds: ');
 WriteLn(WithinPastMilliseconds(ANow, AThen, AMilliseconds));
end;

Var

 D1, D2 : TDateTime;

Begin

 D1:=Now;
 D2:=D1-(0.9*OneMillisecond);
 Test(D1, D2, 1);
 D2:=D1-(1.0*OneMillisecond);
 Test(D1, D2, 1);
 D2:=D1-(1.1*OneMillisecond);
 Test(D1, D2, 1);
 D2:=D1-(2.5*OneMillisecond);
 Test(D1, D2, 1);
 Test(D1, D2, 2);
 Test(D1, D2, 3);

End.

44.4.156 WithinPastMinutes

Synopsis: Check whether two datetimes are only a number of minutes apart

Declaration: function WithinPastMinutes(const ANow: TDateTime;
 const AThen: TDateTime; const AMinutes: Int64)
 : Boolean

Visibility: default

Description: WithinPastMinutes compares the timestamps ANow and AThen and returns True if the difference between them is at most AMinutes minutes apart, or False if they are further apart.

Remark: Since this function uses the MinutesBetween (581) function to calculate the difference in Minutes, this means that fractional minutes do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half minutes apart, the result will also be True

See also: WithinPastYears (624), WithinPastMonths (621), WithinPastWeeks (623), WithinPastDays (617), WithinPastHours (618), WithinPastSeconds (622), WithinPastMilliseconds (619)

Listing: ./datutex/ex52.pp

Program Example52;

{ This program demonstrates the WithinPastMinutes function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMinutes : Integer);

```
begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', AMinutes, ' Minutes: ');
  WriteLn(WithinPastMinutes(ANow, AThen, AMinutes));
end;
```

Var

D1, D2 : TDateTime;

Begin

```
D1:=Now;
D2:=D1-(59*OneSecond);
Test(D1,D2,1);
D2:=D1-(61*OneSecond);
Test(D1,D2,1);
D2:=D1-(122*OneSecond);
Test(D1,D2,1);
D2:=D1-(306*OneSecond);
Test(D1,D2,5);
D2:=D1-(5.4*OneMinute);
Test(D1,D2,5);
D2:=D1-(2.5*OneMinute);
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);
```

End.

44.4.157 WithinPastMonths

Synopsis: Check whether two datetimes are only a number of months apart

Declaration: function WithinPastMonths(const ANow: TDateTime;
const AThen: TDateTime; const AMonths: Integer)
: Boolean

Visibility: default

Description: WithinPastMonths compares the timestamps ANow and AThen and returns True if the difference between them is at most AMonths months apart, or False if they are further apart.

Remark: Since this function uses the MonthsBetween (584) function to calculate the difference in Months, this means that fractional months do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half months apart, the result will also be True

See also: WithinPastYears (624), WithinPastWeeks (623), WithinPastDays (617), WithinPastHours (618), WithinPastMinutes (620), WithinPastSeconds (622), WithinPastMilliseconds (619)

Listing: ./datutex/ex48.pp

Program Example48;

```
{ This program demonstrates the WithinPastMonths function }
```

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AMonths : Integer);

```
begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Write(' are within ', AMonths, ' months: ');
  WriteLn(WithinPastMonths(ANow, AThen, AMonths));
end;
```

```
Var
  D1, D2 : TDateTime;
```

```
Begin
  D1 := Today;
  D2 := Today - 364;
  Test(D1, D2, 12);
  D2 := Today - 365;
  Test(D1, D2, 12);
  D2 := Today - 366;
  Test(D1, D2, 12);
  D2 := Today - 390;
  Test(D1, D2, 12);
  D2 := Today - 368;
  Test(D1, D2, 11);
  D2 := Today - 1000;
  Test(D1, D2, 31);
  Test(D1, D2, 32);
  Test(D1, D2, 33);
```

```
End.
```

44.4.158 WithinPastSeconds

Synopsis: Check whether two datetimes are only a number of seconds apart

Declaration: function WithinPastSeconds(const ANow: TDateTime;
 const AThen: TDateTime; const ASeconds: Int64)
 : Boolean

Visibility: default

Description: WithinPastSeconds compares the timestamps ANow and AThen and returns True if the difference between them is at most ASeconds seconds apart, or False if they are further apart.

Remark: Since this function uses the SecondsBetween (599) function to calculate the difference in seconds, this means that fractional seconds do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half seconds apart, the result will also be True

See also: WithinPastYears (624), WithinPastMonths (621), WithinPastWeeks (623), WithinPastDays (617), WithinPastHours (618), WithinPastMinutes (620), WithinPastMilliseconds (619)

Listing: ./datutex/ex53.pp

Program Example53;

```
{ This program demonstrates the WithinPastSeconds function }
```

```
Uses SysUtils, DateUtils;
```

```

Procedure Test(ANow, AThen : TDateTime; ASeconds : Integer);

begin
  Write(DateTimeToStr(AThen), ' and ', DateTimeToStr(ANow));
  Write(' are within ', ASeconds, ' seconds: ');
  Writeln(WithinPastSeconds(ANow, AThen, ASeconds));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Now;
  D2 := D1 - (999 * OneMilliSecond);
  Test(D1, D2, 1);
  D2 := D1 - (1001 * OneMilliSecond);
  Test(D1, D2, 1);
  D2 := D1 - (2001 * OneMilliSecond);
  Test(D1, D2, 1);
  D2 := D1 - (5001 * OneMilliSecond);
  Test(D1, D2, 5);
  D2 := D1 - (5.4 * OneSecond);
  Test(D1, D2, 5);
  D2 := D1 - (2.5 * OneSecond);
  Test(D1, D2, 1);
  Test(D1, D2, 2);
  Test(D1, D2, 3);
End.

```

44.4.159 WithinPastWeeks

Synopsis: Check whether two datetimes are only a number of weeks apart

Declaration: `function WithinPastWeeks(const ANow: TDateTime; const AThen: TDateTime; const AWeeks: Integer) : Boolean`

Visibility: default

Description: `WithinPastWeeks` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AWeeks` weeks apart, or `False` if they are further apart.

Remark: Since this function uses the `WeeksBetween` (614) function to calculate the difference in Weeks, this means that fractional Weeks do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half weeks apart, the result will also be `True`

See also: `WithinPastYears` (624), `WithinPastMonths` (621), `WithinPastDays` (617), `WithinPastHours` (618), `WithinPastMinutes` (620), `WithinPastSeconds` (622), `WithinPastMilliseconds` (619)

Listing: `./datutex/ex49.pp`

Program Example49;

{ This program demonstrates the WithinPastWeeks function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AWeeks : Integer);


```

begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));
  Write(' are within ', AWeeks, ' weeks: ');
  WriteLn(WithinPastWeeks(ANow, AThen, AWeeks));
end;

Var
  D1, D2 : TDateTime;

Begin
  D1 := Today;
  D2 := Today - 7;
  Test(D1, D2, 1);
  D2 := Today - 8;
  Test(D1, D2, 1);
  D2 := Today - 14;
  Test(D1, D2, 1);
  D2 := Today - 35;
  Test(D1, D2, 5);
  D2 := Today - 36;
  Test(D1, D2, 5);
  D2 := Today - 17;
  Test(D1, D2, 1);
  Test(D1, D2, 2);
  Test(D1, D2, 3);
End.

```

44.4.160 WithinPastYears

Synopsis: Check whether two datetimes are only a number of years apart

Declaration: `function WithinPastYears(const ANow: TDateTime; const AThen: TDateTime; const AYears: Integer) : Boolean`

Visibility: default

Description: `WithinPastYears` compares the timestamps `ANow` and `AThen` and returns `True` if the difference between them is at most `AYears` years apart, or `False` if they are further apart.

Remark: Since this function uses the `YearsBetween` (626) function to calculate the difference in years, this means that fractional years do not count, and the fractional part is simply dropped, so for two dates actually 2 and a half years apart, the result will also be `True`

See also: `WithinPastMonths` (621), `WithinPastWeeks` (623), `WithinPastDays` (617), `WithinPastHours` (618), `WithinPastMinutes` (620), `WithinPastSeconds` (622), `WithinPastMilliseconds` (619)

Listing: `./datutex/ex47.pp`

Program Example47;

{ This program demonstrates the WithinPastYears function }

Uses SysUtils, DateUtils;

Procedure Test(ANow, AThen : TDateTime; AYears : Integer);

```

begin
  Write(DateToStr(AThen), ' and ', DateToStr(ANow));

```

```

Write( ' are within ',AYears, ' years: ');
WriteLn ( WithinPastYears (ANow,AThen,AYears));
end;

```

Var

```
D1,D2 : TDateTime;
```

Begin

```

D1:=Today;
D2:=Today-364;
Test(D1,D2,1);
D2:=Today-365;
Test(D1,D2,1);
D2:=Today-366;
Test(D1,D2,1);
D2:=Today-390;
Test(D1,D2,1);
D2:=Today-368;
Test(D1,D2,1);
D2:=Today-1000;
Test(D1,D2,1);
Test(D1,D2,2);
Test(D1,D2,3);

```

End.

44.4.161 YearOf

Synopsis: Extract the year from a given date.

Declaration: `function YearOf(const AValue: TDateTime) : Word`

Visibility: default

Description: `YearOf` returns the year part of the `AValue` date/time indication. It is a number between 1 and 9999.

See also: `MonthOf` ([583](#)), `DayOf` ([544](#)), `WeekOf` ([613](#)), `HourOf` ([559](#)), `MinuteOf` ([579](#)), `SecondOf` ([597](#)), `MilliSecondOf` ([575](#))

Listing: `./datutex/ex23.pp`

Program Example23;

```
{ This program demonstrates the YearOf function }
```

Uses SysUtils, DateUtils;

Var

```
D : TDateTime;
```

Begin

```

D:=Now;
WriteLn( 'Year           : ',YearOf(D));
WriteLn( 'Month         : ',MonthOf(D));
WriteLn( 'Day           : ',DayOf(D));
WriteLn( 'Week          : ',WeekOf(D));
WriteLn( 'Hour          : ',HourOf(D));

```

```

WriteIn ( 'Minute      : ', MinuteOf(D));
WriteIn ( 'Second      : ', SecondOf(D));
WriteIn ( 'MilliSecond : ', MilliSecondOf(D));
End.

```

44.4.162 YearsBetween

Synopsis: Calculate the number of whole years between two DateTime values

Declaration: `function YearsBetween(const ANow: TDateTime; const AThen: TDateTime) : Integer`

Visibility: default

Description: `YearsBetween` returns the number of whole years between `ANow` and `AThen`. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years). This means the fractional part of a year is dropped.

See also: `MonthsBetween` ([584](#)), `WeeksBetween` ([614](#)), `DaysBetween` ([545](#)), `HoursBetween` ([561](#)), `MinutesBetween` ([581](#)), `SecondsBetween` ([599](#)), `MillisecondsBetween` ([578](#)), `YearSpan` ([627](#))

Listing: `./datutex/ex55.pp`

Program `Example55;`

{ This program demonstrates the YearsBetween function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime);`

```

begin
  Write ( 'Number of years between ');
  Write (DateToStr(AThen), ' and ', DateToStr(ANow));
  WriteIn ( ' : ', YearsBetween(ANow, AThen));
end;

```

Var
`D1, D2 : TDateTime;`

```

Begin
  D1:=Today;
  D2:=Today-364;
  Test(D1,D2);
  D2:=Today-365;
  Test(D1,D2);
  D2:=Today-366;
  Test(D1,D2);
  D2:=Today-390;
  Test(D1,D2);
  D2:=Today-368;
  Test(D1,D2);
  D2:=Today-1000;
  Test(D1,D2);
End.

```

44.4.163 YearSpan

Synopsis: Calculate the approximate number of years between two DateTime values.

Declaration: `function YearSpan(const ANow: TDateTime; const AThen: TDateTime)
: Double`

Visibility: default

Description: `YearSpan` returns the number of years between `ANow` and `AThen`, including any fractional parts of a year. This number is an approximation, based on an average number of days of 365.25 per year (average over 4 years).

See also: `MonthSpan` (585), `WeekSpan` (616), `DaySpan` (548), `HourSpan` (562), `MinuteSpan` (582), `SecondSpan` (600), `MilliSecondSpan` (579), `YearsBetween` (626)

Listing: `./datutex/ex63.pp`

Program `Example63;`

{ This program demonstrates the YearSpan function }

Uses `SysUtils, DateUtils;`

Procedure `Test(ANow, AThen : TDateTime);`

begin

`Write('Number of years between ');`

`Write(DateToStr(AThen), ' and ', DateToStr(ANow));`

`WriteLn(' : ', YearSpan(ANow, AThen));`

end;

Var

`D1, D2 : TDateTime;`

Begin

`D1 := Today;`

`D2 := Today - 364;`

`Test(D1, D2);`

`D2 := Today - 365;`

`Test(D1, D2);`

`D2 := Today - 366;`

`Test(D1, D2);`

`D2 := Today - 390;`

`Test(D1, D2);`

`D2 := Today - 368;`

`Test(D1, D2);`

`D2 := Today - 1000;`

`Test(D1, D2);`

End.

44.4.164 Yesterday

Synopsis: Return the previous day.

Declaration: `function Yesterday : TDateTime`

Visibility: default

Description: `Yesterday` returns yesterday's date. Yesterday is determined from the system clock, i.e. it is Today (606) -1.

See also: Today (606), Tomorrow (606)

Listing: `./datutex/ex18.pp`

Program Example18;

{ This program demonstrates the Yesterday function }

Uses SysUtils , DateUtils ;

Begin

`WriteLn(FormatDateTime('"Today is " dd mmm yyyy ',Today));`

`WriteLn(FormatDateTime('"Yesterday was " dd mmm yyyy ',Yesterday));`

End.

Chapter 45

Reference for unit 'Dos'

45.1 Used units

Table 45.1: Used units by unit 'Dos'

Name	Page
BaseUnix	124
System	1194

45.2 Overview

The DOS unit gives access to some operating system calls related to files, the file system, date and time. Except for the PalmOS target, this unit is available to all supported platforms.

The unit was first written for Dos by Florian Klaempfl. It was ported to Linux by Mark May and enhanced by Michael Van Canneyt. The Amiga version was ported by Nils Sjöholm.

Under non-DOS systems, some of the functionality is lost, as it is either impossible or meaningless to implement it. Other than that, the functionality is the same for all operating systems.

Because the DOS unit is a Turbo Pascal compatibility unit, it is no longer actively developed: the interface is frozen and it is maintained only for the purpose of porting Turbo Pascal programs. For new development, it is recommended to use the sysutils ([1442](#)) unit instead.

45.3 System information

Functions for retrieving and setting general system information such as date and time.

Table 45.2:

Name	Description
DosVersion (1)	Get OS version
GetCBreak (644)	Get setting of control-break handling flag
GetDate (644)	Get system date
GetIntVec (647)	Get interrupt vector status
GetTime (648)	Get system time
GetVerify (649)	Get verify flag
Intr (649)	Execute an interrupt
Keep (649)	Keep process in memory and exit
MSDos (650)	Execute MS-Dos function call
PackTime (650)	Pack time for file time
SetCBreak (651)	Set control-break handling flag
SetDate (651)	Set system date
SetIntVec (652)	Set interrupt vectors
SetTime (653)	Set system time
SetVerify (653)	Set verify flag
SwapVectors (653)	Swap interrupt vectors
UnPackTime (654)	Unpack file time

45.4 Process handling

Functions to handle process information and starting new processes.

Table 45.3:

Name	Description
DosExitCode (1)	Exit code of last executed program
EnvCount (639)	Return number of environment variables
EnvStr (640)	Return environment string pair
Exec (640)	Execute program
GetEnv (645)	Return specified environment string

45.5 Directory and disk handling

Routines to handle disk information.

Table 45.4:

Name	Description
AddDisk (636)	Add disk to list of disks (UNIX only)
DiskFree (637)	Return size of free disk space
DiskSize (637)	Return total disk size

45.6 File handling

Routines to handle files on disk.

Table 45.5:

Name	Description
FExpand (641)	Expand filename to full path
FindClose (641)	Close finfirst/findnext session
FindFirst (641)	Start find of file
FindNext (642)	Find next file
FSearch (642)	Search for file in a path
FSplit (643)	Split filename in parts
GetFAttr (645)	Return file attributes
GetFTime (646)	Return file time
GetLongName (647)	Convert short filename to long filename (DOS only)
GetShortName (648)	Convert long filename to short filename (DOS only)
SetFAttr (651)	Set file attributes
SetFTime (652)	Set file time

45.7 File open mode constants.

These constants are used in the `Mode` field of the `TextRec` record. Gives information on the file-mode of the text I/O. For their definitions consult the following table:

Table 45.6: Possible mode constants

Constant	Description	Value
<code>fmclosed</code>	File is closed	<code>\$D7B0</code>
<code>fminput</code>	File is read only	<code>\$D7B1</code>
<code>fmoutput</code>	File is write only	<code>\$D7B2</code>
<code>fminout</code>	File is read and write	<code>\$D7B3</code>

45.8 File attributes

The File Attribute constants are used in `FindFirst` (641), `FindNext` (642) to determine what type of special file to search for in addition to normal files. These flags are also used in the `SetFAttr` (651) and `GetFAttr` (645) routines to set and retrieve attributes of files. For their definitions consult `fileattributes` (631).

Table 45.7: Possible file attributes

Constant	Description	Value
readonly	Read-Only file attribute	\$01
hidden	Hidden file attribute	\$02
sysfile	System file attribute	\$04
volumeid	Volume ID file attribute	\$08
directory	Directory file attribute	\$10
archive	Archive file attribute	\$20
anyfile	Match any file attribute	\$3F

45.9 Constants, types and variables

45.9.1 Constants

`anyfile = $3F`

Match any file attribute

`archive = $20`

Archive file attribute

`directory = $10`

Directory file attribute

`fauxiliary = $0010`

CPU auxiliary flag. Not used.

`fcarry = $0001`

CPU carry flag. Not used.

`FileNameLen = 255`

Maximum length of a filename

`fmclosed = $D7B0`

File is closed

`fminout = $D7B3`

File is read and write

`fminput = $D7B1`

File is read only

```
fmoutput = $D7B2
```

File is write only

```
foverflow = $0800
```

CPU overflow flag. Not used.

```
fparity = $0004
```

CPU parity flag. Not used.

```
fsign = $0080
```

CPU sign flag. Not used.

```
fzero = $0040
```

CPU zero flag. Not used.

```
hidden = $02
```

Hidden file attribute

```
readonly = $01
```

Read-Only file attribute

```
sysfile = $04
```

System file attribute

```
volumeid = $08
```

Volumd ID file attribute

45.9.2 Types

```
ComStr = string
```

Command-line string type

```
DateTime = packed record
```

```
  Year : Word;
```

```
  Month : Word;
```

```
  Day : Word
```

```
  ;
```

```
  Hour : Word;
```

```
  Min : Word;
```

```
  Sec : Word;
```

```
end
```

The `DateTime` type is used in `PackTime` (650) and `UnPackTime` (654) for setting/reading file times with `GetFTime` (646) and `SetFTime` (652).

```
DirStr = string
```

Full directory string type.

```
ExtStr = string
```

Filename extension string type.

```
NameStr = string
```

Fill filename string type.

```
PathStr = string
```

Full File path string type.

```
Registers = packed record
case i : Integer of
0: (
    ax : Word;
    f1 : Word;
    bx : Word;
    f2 : Word;
    cx : Word;
    f3 : Word;
    dx : Word;
    f4 : Word;
    bp : Word;
    f5 : Word;
    si : Word;
    f51 : Word;
    di : Word;
    f6 : Word;
    ds : Word;
    f7 : Word;
    es : Word;
    f8 : Word;
    flags : Word;
    fs : Word;
    gs : Word
    ;
);
1: (
    al : Byte;
    ah : Byte;
    f9 : Byte;
    f10 : Byte;
    bl
    : Byte;
```

```

bh : Byte;
f11 : Byte;
f12 : Byte;
cl : Byte;
ch
: Byte;
f13 : Byte;
f14 : Byte;
dl : Byte;
dh : Byte;
);
2: (
  eax : LongInt;
  ebx : LongInt;
  ecx : LongInt;
  edx : LongInt
;
  ebp : LongInt;
  esi : LongInt;
  edi : LongInt;
);
end

```

This structure is only defined on a i386 compatible 32-bit platform, and is not used anywhere: it is defined for Turbo Pascal backwards compatibility only.

```

SearchRec = packed record
  SearchPos : TOff;
  SearchNum : LongInt
;
  DirPtr : Pointer;
  SearchType : Byte;
  SearchAttr : Byte;
  Mode : Word;
  Fill : Array[1..1] of Byte;
  Attr : Byte;
  Time
  : LongInt;
  Size : LongInt;
  Reserved : Word;
  Name : string;
  SearchSpec : string;
  NamePos : Word;
end

```

SearchRec is filled by the FindFirst (641) call and can be used in subsequent FindNext (642) calls to search for files. The structure of this record depends on the platform. Only the following fields are present on all platforms:

Attr File attributes.

Time File modification time.

Size File size

Name File name (name part only, no path)

Mode File access mode (Linux only)

45.9.3 Variables

`DosError` : Integer

The `DosError` variable is used by the procedures in the `Dos` unit to report errors. It can have the following values :

Table 45.8: Dos error codes

Value	Meaning
2	File not found.
3	Path not found.
5	Access denied.
6	Invalid handle.
8	Not enough memory.
10	Invalid environment.
11	Invalid format.
18	No more files.

Other values are possible, but are not documented.

45.10 Procedures and functions

45.10.1 AddDisk

Synopsis: Add disk definition to list if drives (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: default

Description: `AddDisk` adds a filename `S` to the internal list of disks. It is implemented for systems which do not use DOS type drive letters. This list is used to determine which disks to use in the `DiskFree` (637) and `DiskSize` (637) calls. The `DiskFree` (637) and `DiskSize` (637) functions need a file on the specified drive, since this is required for the `statfs` system call. The names are added sequentially. The `Dos` initialization code presets the first three disks to:

- `'.'` for the current drive,
- `/'fd0/'` for the first floppy-drive (Linux only).
- `/'fd1/'` for the second floppy-drive (Linux only).
- `/'` for the first hard disk.

The first call to `AddDisk` will therefore add a name for the second harddisk, The second call for the third drive, and so on until 23 drives have been added (corresponding to drives `'D:'` to `'Z:'`)

Errors: None

See also: `DiskFree` (637), `DiskSize` (637)

45.10.2 DiskFree

Synopsis: Get free size on Disk.

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the number of free bytes on a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the free space on the current drive.

Remark: For Unices: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the Dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).
- `'/fd1/.'` for the second floppy-drive (Linux only).
- `'/'` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (636) procedure. These settings can be coded in `dos.pp`, in the initialization part.

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskSize` (637), `AddDisk` (636)

Listing: `./dosex/ex6.pp`

```

Program Example6;
uses Dos;

{ Program to demonstrate the DiskSize and DiskFree function. }

begin
  WriteLn('This partition size has ',DiskSize(0),' bytes');
  WriteLn('Currently ',DiskFree(0),' bytes are free');
end.

```

45.10.3 DiskSize

Synopsis: Get total size of disk.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the total size (in bytes) of a disk. The parameter `Drive` indicates which disk should be checked. This parameter is 1 for floppy a:, 2 for floppy b:, etc. A value of 0 returns the size of the current drive.

Remark: For Unix only: The `diskfree` and `disksize` functions need a file on the specified drive, since this is required for the `statfs` system call. These filenames are set in the initialization of the Dos unit, and have been preset to :

- `'.'` for the current drive,
- `'/fd0/.'` for the first floppy-drive (Linux only).

- `' /fd1 / '` for the second floppy-drive (Linux only).
- `' / '` for the first hard disk.

There is room for 1-26 drives. You can add a drive with the `AddDisk` (636) procedure. These settings can be coded in `dos.pp`, in the initialization part.

For an example, see `DiskFree` (637).

Errors: -1 when a failure occurs, or an invalid drive number is given.

See also: `DiskFree` (637), `AddDisk` (636)

45.10.4 DosExitCode

Synopsis: Exit code of last executed program.

Declaration: `function DosExitCode : Word`

Visibility: default

Description: `DosExitCode` contains (in the low byte) the exit-code of a program executed with the `Exec` call.

Errors: None.

See also: `Exec` (640)

Listing: `./dosex/ex5.pp`

```
Program Example5;
uses Dos;

{ Program to demonstrate the Exec and DosExitCode function. }

begin
  {$IFDEF Unix}
    WriteLn( 'Executing /bin/ls -la ' );
    Exec( '/bin/ls ', '-la ' );
  {$ELSE}
    WriteLn( 'Executing Dir ' );
    Exec( GetEnv( 'COMSPEC' ), '/C dir ' );
  {$ENDIF}
  WriteLn( 'Program returned with ExitCode ', Lo(DosExitCode) );
end.
```

45.10.5 DosVersion

Synopsis: Current OS version

Declaration: `function DosVersion : Word`

Visibility: default

Description: `DosVersion` returns the operating system or kernel version. The low byte contains the major version number, while the high byte contains the minor version number.

Remark: On systems where versions consists of more then two numbers, only the first two numbers will be returned. For example Linux version 2.1.76 will give you `DosVersion` 2.1. Some operating systems, such as FreeBSD, do not have system calls to return the kernel version, in that case a value of 0 will be returned.

Errors: None.

Listing: ./dosex/ex1.pp

```

Program Example1;
uses Dos;

{ Program to demonstrate the DosVersion function. }

var
    OS      : string[32];
    Version : word;
begin
    {$IFDEF LINUX}
        OS:= 'Linux';
    {$ENDIF}
    {$ifdef FreeBSD}
        OS:= 'FreeBSD';
    {$endif}
    {$ifdef NetBSD}
        OS:= 'NetBSD';
    {$endif}
    {$ifdef Solaris}
        OS:= 'Solaris';
    {$endif}
    {$ifdef QNX}
        OS:= 'QNX';
    {$endif}

    {$IFDEF DOS}
        OS:= 'Dos';
    {$ENDIF}
    Version:=DosVersion;
    WriteLn('Current ',OS,' version is ',Lo(Version),'. ',Hi(Version));
end.

```

45.10.6 DTToUnixDate

Synopsis: Convert a DateTime to Unix timestamp

Declaration: `function DTToUnixDate(DT: DateTime) : LongInt`

Visibility: default

Description: `DTToUnixDate` converts the `DateTime` value in `DT` to a Unix timestamp. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `UnixDateToDT` ([654](#)), `PackTime` ([650](#)), `UnpackTime` ([654](#)), `GetTime` ([648](#)), `SetTime` ([653](#))

45.10.7 EnvCount

Synopsis: Return the number of environment variables

Declaration: `function EnvCount : LongInt`

Visibility: default

Description: `EnvCount` returns the number of environment variables.

Errors: None.

See also: `EnvStr` (640), `GetEnv` (645)

45.10.8 EnvStr

Synopsis: Return environment variable by index

Declaration: `function EnvStr(Index: LongInt) : string`

Visibility: default

Description: `EnvStr` returns the `Index`-th `Name=Value` pair from the list of environment variables. The index of the first pair is zero.

Errors: The length is limited to 255 characters.

See also: `EnvCount` (639), `GetEnv` (645)

Listing: `./dosex/ex13.pp`

Program `Example13;`

uses `Dos;`

{ Program to demonstrate the EnvCount and EnvStr function. }

var

i : `Longint`;

begin

`WriteLn('Current Environment is:');`

for `i:=1 to EnvCount` **do**

`WriteLn(EnvStr(i));`

end.

45.10.9 Exec

Synopsis: Execute another program, and wait for it to finish.

Declaration: `procedure Exec(const path: PathStr; const comline: ComStr)`

Visibility: default

Description: `Exec` executes the program in `Path`, with the options given by `ComLine`. The program name should *not* appear again in `ComLine`, it is specified in `Path`. `Comline` contains only the parameters that are passed to the program.

After the program has terminated, the procedure returns. The Exit value of the program can be consulted with the `DosExitCode` function.

For an example, see `DosExitCode` (1)

Errors: Errors are reported in `DosError`.

See also: `DosExitCode` (1)

45.10.10 FExpand

Synopsis: Expand a relative path to an absolute path

Declaration: `function FExpand(const path: PathStr) : PathStr`

Visibility: default

Description: `FExpand` takes its argument and expands it to a complete filename, i.e. a filename starting from the root directory of the current drive, prepended with the drive-letter or volume name (when supported).

Remark: On case sensitive file systems (such as Unix and Linux), the resulting name is left as it is, otherwise it is converted to uppercase.

Errors: `FSplit` (643)

Listing: `./dosex/ex11.pp`

```

Program Example11;
uses Dos;

{ Program to demonstrate the FExpand function. }

begin
  WriteLn('Expanded Name of this program is ',FExpand(ParamStr(0)));
end.

```

45.10.11 FindClose

Synopsis: Dispose resources allocated by a `FindFirst` (641)/`FindNext` (642) sequence.

Declaration: `procedure FindClose(var f: SearchRec)`

Visibility: default

Description: `FindClose` frees any resources associated with the search record `F`.

This call is needed to free any internal resources allocated by the `FindFirst` (641) or `FindNext` (642) calls.

The Unix implementation of the `Dos` unit therefore keeps a table of open directories, and when the table is full, closes one of the directories, and reopens another. This system is adequate but slow if you use a lot of `searchrecs`.

So, to speed up the `findfirst/findnext` system, the `FindClose` call was implemented. When you don't need a `searchrec` any more, you can tell this to the `Dos` unit by issuing a `FindClose` call. The directory which is kept open for this `searchrec` is then closed, and the table slot freed.

Remark: It is recommended to use the Linux call `Glob` when looking for files on Linux.

Errors: Errors are reported in `DosError`.

See also: `FindFirst` (641), `FindNext` (642)

45.10.12 FindFirst

Synopsis: Start search for one or more files.

Declaration: `procedure FindFirst(const path: PathStr; attr: Word; var f: SearchRec)`

Visibility: default

Description: `FindFirst` searches the file specified in `Path`. Normal files, as well as all special files which have the attributes specified in `Attr` will be returned.

It returns a `SearchRec` record for further searching in `F.Path` can contain the wildcard characters `?` (matches any single character) and `*` (matches 0 ore more arbitrary characters). In this case `FindFirst` will return the first file which matches the specified criteria. If `DosError` is different from zero, no file(s) matching the criteria was(were) found.

Remark: On the EMX target, you cannot issue two different `FindFirst` calls. That is, you must close any previous search operation with `FindClose` (641) before starting a new one. Failure to do so will end in a Run-Time Error 6 (Invalid file handle)

Errors: Errors are reported in `DosError`.

See also: `FindNext` (642), `FindClose` (641)

Listing: `./dosex/ex7.pp`

```

Program Example7;
uses Dos;

{ Program to demonstrate the FindFirst and FindNext function. }

var
  Dir : SearchRec;
begin
  FindFirst( '*.*', archive, Dir );
  WriteLn( 'FileName'+Space(32), 'FileSize':9);
  while (DosError=0) do
    begin
      WriteLn( Dir.Name+Space(40-Length( Dir.Name)), Dir.Size:9);
      FindNext( Dir );
    end;
  FindClose( Dir );
end.
```

45.10.13 FindNext

Synopsis: Find next matching file after `FindFirst` (641)

Declaration: `procedure FindNext (var f: SearchRec)`

Visibility: default

Description: `FindNext` takes as an argument a `SearchRec` from a previous `FindNext` call, or a `FindFirst` call, and tries to find another file which matches the criteria, specified in the `FindFirst` call. If `DosError` is different from zero, no more files matching the criteria were found.

For an example, see `FindFirst` (641).

Errors: `DosError` is used to report errors.

See also: `FindFirst` (641), `FindClose` (641)

45.10.14 FSearch

Synopsis: Search a file in searchpath

Declaration: `function FSearch(path: PathStr; dirlist: string) : PathStr`

Visibility: default

Description: `FSearch` searches the file `Path` in all directories listed in `DirList`. The full name of the found file is returned. `DirList` must be a list of directories, separated by semi-colons. When no file is found, an empty string is returned.

Remark: On Unix systems, `DirList` can also be separated by colons, as is customary on those environments.

Errors: None.

See also: `FExpand` ([641](#))

Listing: `./dosex/ex10.pp`

```

program Example10;

uses Dos;

{ Program to demonstrate the FSearch function. }

var s:pathstr;

begin
  s:=FSearch(ParamStr(1),GetEnv('PATH'));
  if s='' then
    WriteLn(ParamStr(1),' not Found in PATH')
  else
    WriteLn(ParamStr(1),' Found in PATH at ',s);
end.
```

45.10.15 FSplit

Synopsis: Split a full-path filename in parts.

Declaration: `procedure FSplit(path: PathStr; var dir: DirStr; var name: NameStr; var ext: ExtStr)`

Visibility: default

Description: `FSplit` splits a full file name into 3 parts : A `Path`, a `Name` and an extension (in `ext`.) The extension is taken to be all letters after the *last* dot (.). For Dos, however, an exception is made when `LFNSupport=False`, then the extension is defined as all characters after the *first* dot.

Errors: None.

See also: `FSearch` ([642](#))

Listing: `./dosex/ex12.pp`

```

program Example12;

uses Dos;

{ Program to demonstrate the FSplit function. }

var dir:dirstr;
    name:namestr;
    ext:extstr;
```

```

begin
  FSplit(ParamStr(1), dir, name, ext);
  WriteLn('Splitted ', ParamStr(1), ' in:');
  WriteLn('Path      : ', dir);
  WriteLn('Name       : ', name);
  WriteLn('Extension: ', ext);
end.

```

45.10.16 GetCBreak

Synopsis: Get control-Break flag

Declaration: `procedure GetCBreak(var breakvalue: Boolean)`

Visibility: default

Description: `GetCBreak` gets the status of CTRL-Break checking under Dos and Amiga. When `BreakValue` is `false`, then Dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to `True`, then a check is done at every system call.

Remark: Under non-Dos and non-Amiga operating systems, `BreakValue` always returns `True`.

Errors: None

See also: `SetCBreak` ([651](#))

45.10.17 GetDate

Synopsis: Get the current date

Declaration: `procedure GetDate(var year: Word; var month: Word; var mday: Word; var wday: Word)`

Visibility: default

Description: `GetDate` returns the system's date. `Year` is a number in the range 1980..2099. `mday` is the day of the month, `wday` is the day of the week, starting with Sunday as day 0.

Errors: None.

See also: `GetTime` ([648](#)), `SetDate` ([651](#))

Listing: `./dosex/ex2.pp`

```

Program Example2;
uses Dos;

{ Program to demonstrate the GetDate function. }

const
  DayStr: array[0..6] of string[3] = ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat');
  MonthStr: array[1..12] of string[3] = ('Jan', 'Feb', 'Mar', 'Apr', 'May', 'Jun',
                                         'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
var
  Year, Month, Day, WDay : word;
begin
  GetDate(Year, Month, Day, WDay);
  WriteLn('Current date');
  WriteLn(DayStr[WDay], ', ', Day, ', ', MonthStr[Month], ', ', Year, '.');
end.

```

45.10.18 GetEnv

Synopsis: Get environment variable by name.

Declaration: `function GetEnv(envvar: string) : string`

Visibility: default

Description: `GetEnv` returns the value of the environment variable `EnvVar`. When there is no environment variable `EnvVar` defined, an empty string is returned.

Remark: Under some operating systems (such as Unix), case is important when looking for `EnvVar`.

Errors: None.

See also: `EnvCount` ([639](#)), `EnvStr` ([640](#))

Listing: `./dosex/ex14.pp`

```

Program Example14;
uses Dos;

{ Program to demonstrate the GetEnv function. }

begin
  WriteLn('Current PATH is ',GetEnv('PATH'));
end

```

45.10.19 GetFAttr

Synopsis: Get file attributes

Declaration: `procedure GetFAttr(var f; var attr: Word)`

Visibility: default

Description: `GetFAttr` returns the file attributes of the file-variable `f`. `F` can be a untyped or typed file, or of type `Text`. `f` must have been assigned, but not opened. The attributes can be examined with the following constants :

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Under Linux, supported attributes are:

- `Directory`
- `ReadOnly` if the current process doesn't have access to the file.
- `Hidden` for files whose name starts with a dot (`'.'`).

Errors: Errors are reported in `DosError`

See also: `SetFAttr` ([651](#))

Listing: ./dosex/ex8.pp

```

Program Example8;
uses Dos;

{ Program to demonstrate the GetFAttr function. }

var
  Attr : Word;
  f    : File;
begin
  Assign(f, ParamStr(1));
  GetFAttr(f, Attr);
  WriteLn('File ', ParamStr(1), ' has attribute ', Attr);
  if (Attr and archive) <> 0 then WriteLn('– Archive');
  if (Attr and directory) <> 0 then WriteLn('– Directory');
  if (Attr and readonly) <> 0 then WriteLn('– Read-Only');
  if (Attr and sysfile) <> 0 then WriteLn('– System');
  if (Attr and hidden) <> 0 then WriteLn('– Hidden');
end.

```

45.10.20 GetFTime

Synopsis: Get file last modification time.

Declaration: `procedure GetFTime(var f; var time: LongInt)`

Visibility: default

Description: `GetFTime` returns the modification time of a file. This time is encoded and must be decoded with `UnPackTime`. `F` must be a file type, which has been assigned, and opened.

Errors: Errors are reported in `DosError`

See also: `SetFTime` ([652](#)), `PackTime` ([650](#)), `UnPackTime` ([654](#))

Listing: ./dosex/ex9.pp

```

Program Example9;
uses Dos;

{ Program to demonstrate the GetFTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w, s);
  if w < 10 then
    L0 := '0' + s
  else
    L0 := s;
end;

var
  f    : File;
  Time : Longint;
  DT   : DateTime;

```

```

begin
  if Paramcount>0 then
    Assign(f, ParamStr(1))
  else
    Assign(f, 'ex9.pp' );
  Reset(f);
  GetFTime(f, Time);
  Close(f);
  UnPackTime(Time, DT);
  Write ('File ', ParamStr(1), ' is last modified on ');
  WriteLn (L0(DT.Month), '-', L0(DT.Day), '-', DT.Year,
           ' at ', L0(DT.Hour), ': ', L0(DT.Min));
end.

```

45.10.21 GetIntVec

Synopsis: Get interrupt vector

Declaration: `procedure GetIntVec(intno: Byte; var vector: pointer)`

Visibility: default

Description: `GetIntVec` returns the address of interrupt vector `IntNo`.

Remark: This call does nothing, it is present for compatibility only. Modern systems do not allow low level access to the hardware.

Errors: None.

See also: `SetIntVec` ([652](#))

45.10.22 GetLongName

Synopsis: Get the long filename of a DOS 8.3 filename.

Declaration: `function GetLongName(var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetLongName` changes the filename `p` to a long filename if the API call to do this is successful. The resulting string is the long file name corresponding to the short filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetShortName` ([648](#))

45.10.23 GetMsCount

Synopsis: Number of milliseconds since a starting point.

Declaration: `function GetMsCount : Int64`

Visibility: default

Description: `GetMSCount` returns a number of milliseconds elapsed since a certain moment in time. This moment in time is implementation dependent. This function is used for timing purposes: Subtracting the results of 2 subsequent calls to this function returns the number of milliseconds elapsed between the two calls.

This call is not very reliable, it is recommended to use some system specific calls for timings.

See also: `GetTime` ([648](#))

45.10.24 GetShortName

Synopsis: Get the short (8.3) filename of a long filename.

Declaration: `function GetShortName(var p: string) : Boolean`

Visibility: default

Description: This function is only implemented in the GO32V2 and Win32 versions of Free Pascal.

`GetShortName` changes the filename `p` to a short filename if the API call to do this is successful. The resulting string is the short file name corresponding to the long filename `p`.

The function returns `True` if the API call was successful, `False` otherwise.

This function should only be necessary when using the DOS extender under Windows 95 and higher.

Errors: If the API call was not successful, `False` is returned.

See also: `GetLongName` ([647](#))

45.10.25 GetTime

Synopsis: Return the current time

Declaration: `procedure GetTime(var hour: Word; var minute: Word; var second: Word;
var sec100: Word)`

Visibility: default

Description: `GetTime` returns the system's time. `Hour` is on a 24-hour time scale. `sec100` is in hundredth of a second.

Remark: Certain operating systems (such as Amiga), always set the `sec100` field to zero.

Errors: None.

See also: `GetDate` ([644](#)), `SetTime` ([653](#))

Listing: `./dosex/ex3.pp`

```

Program Example3;
uses Dos;

{ Program to demonstrate the GetTime function. }

Function L0(w: word): string;
var
  s : string;
begin
  Str(w,s);
  if w<10 then

```

```

    L0:= '0'+s
  else
    L0:=s;
end;

var
  Hour,Min,Sec,HSec : word;
begin
  GetTime(Hour,Min,Sec,HSec);
  WriteLn('Current time ');
  WriteLn(L0(Hour),':',L0(Min),':',L0(Sec));
end.

```

45.10.26 GetVerify

Synopsis: Get verify flag

Declaration: `procedure GetVerify(var verify: Boolean)`

Visibility: default

Description: `GetVerify` returns the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-Dos systems (excluding EMX applications running under vanilla DOS), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([653](#))

45.10.27 Intr

Synopsis: Execute interrupt

Declaration: `procedure Intr(intno: Byte; var regs: Registers)`

Visibility: default

Description: `Intr` executes a software interrupt number `IntNo` (must be between 0 and 255), with processor registers set to `Regs`. After the interrupt call returned, the processor registers are saved in `Regs`.

Remark: Under non-Dos operating systems, this call does nothing.

Errors: None.

See also: `MSDos` ([650](#))

45.10.28 Keep

Synopsis: Terminate and stay resident.

Declaration: `procedure Keep(exitcode: Word)`

Visibility: default

Description: `Keep` terminates the program, but stays in memory. This is used for TSR (Terminate Stay Resident) programs which catch some interrupt. `ExitCode` is the same parameter as the `Halt` function takes.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

45.10.29 MSDos

Synopsis: Execute MS-DOS system call

Declaration: `procedure MSDos (var regs: Registers)`

Visibility: default

Description: `MSDos` executes an operating system call. This is the same as doing a `Intr` call with the interrupt number for an os call.

Remark: Under non-Dos operating systems, this call does nothing. On DOS systems, this calls interrupt \$21.

Errors: None.

See also: `Intr` ([649](#))

45.10.30 PackTime

Synopsis: Pack `DateTime` value to a packed-time format.

Declaration: `procedure PackTime (var t: DateTime; var p: LongInt)`

Visibility: default

Description: `UnPackTime` converts the date and time specified in `T` to a packed-time format which can be fed to `SetFTime`.

Errors: None.

See also: `SetFTime` ([652](#)), `FindFirst` ([641](#)), `FindNext` ([642](#)), `UnPackTime` ([654](#))

Listing: `./dosex/ex4.pp`

```

Program Example4;
uses Dos;

{ Program to demonstrate the PackTime and UnPackTime functions. }

var
  DT   : DateTime;
  Time : longint;
begin
  with DT do
    begin
      Year:=2008;
      Month:=11;
      Day:=11;
      Hour:=11;
      Min:=11;
      Sec:=11;
    end;
  PackTime(DT, Time);

```

```

WriteLn( 'Packed Time : ',Time);
UnPackTime(Time,DT);
WriteLn( 'Unpacked Again: ');
with DT do
  begin
    WriteLn( 'Year   ',Year);
    WriteLn( 'Month  ',Month);
    WriteLn( 'Day    ',Day);
    WriteLn( 'Hour   ',Hour);
    WriteLn( 'Min    ',Min);
    WriteLn( 'Sec    ',Sec);
  end;
end.

```

45.10.31 SetCBreak

Synopsis: Set Control-Break flag status

Declaration: `procedure SetCBreak(breakvalue: Boolean)`

Visibility: default

Description: `SetCBreak` sets the status of CTRL-Break checking. When `BreakValue` is false, then Dos only checks for the CTRL-Break key-press when I/O is performed. When it is set to True, then a check is done at every system call.

Remark: Under non-Dos and non-Amiga operating systems, this call does nothing.

Errors: None.

See also: `GetCBreak` ([644](#))

45.10.32 SetDate

Synopsis: Set system date

Declaration: `procedure SetDate(year: Word; month: Word; day: Word)`

Visibility: default

Description: `SetDate` sets the system's internal date. Year is a number between 1980 and 2099.

Remark: On a Unix machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetDate` ([644](#)), `SetTime` ([653](#))

45.10.33 SetFAttr

Synopsis: Set file attributes

Declaration: `procedure SetFAttr(var f; attr: Word)`

Visibility: default

Description: `SetFAttr` sets the file attributes of the file-variable `F`. `F` can be a untyped or typed file, or of type `Text`. `F` must have been assigned, but not opened. The attributes can be a sum of the following constants:

- `ReadOnly`
- `Hidden`
- `SysFile`
- `VolumeId`
- `Directory`
- `Archive`

Remark: Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`.

See also: `GetFAttr` (645)

45.10.34 SetFTime

Synopsis: Set file modification time.

Declaration: `procedure SetFTime(var f; time: LongInt)`

Visibility: default

Description: `SetFTime` sets the modification time of a file, this time is encoded and must be encoded with `PackTime`. `F` must be a file type, which has been assigned, and opened.

Remark: Under Unix like systems (such as Linux and BeOS) the call exists, but is not implemented, i.e. it does nothing.

Errors: Errors are reported in `DosError`

See also: `GetFTime` (646), `PackTime` (650), `UnPackTime` (654)

45.10.35 SetIntVec

Synopsis: Set interrupt vector

Declaration: `procedure SetIntVec(intno: Byte; vector: pointer)`

Visibility: default

Description: `SetIntVec` sets interrupt vector `IntNo` to `Vector`. `Vector` should point to an interrupt procedure.

Remark: This call does nothing, it is present for compatibility only.

Errors: None.

See also: `GetIntVec` (647)

45.10.36 SetTime

Synopsis: Set system time

Declaration: `procedure SetTime(hour: Word; minute: Word; second: Word; sec100: Word)`

Visibility: default

Description: `SetTime` sets the system's internal clock. The `Hour` parameter is on a 24-hour time scale.

Remark: On a Linux machine, there must be root privileges, otherwise this routine will do nothing. On other Unix systems, this call currently does nothing.

Errors: None.

See also: `GetTime` ([648](#)), `SetDate` ([651](#))

45.10.37 SetVerify

Synopsis: Set verify flag

Declaration: `procedure SetVerify(verify: Boolean)`

Visibility: default

Description: `SetVerify` sets the status of the verify flag under Dos. When `Verify` is `True`, then Dos checks data which are written to disk, by reading them after writing. If `Verify` is `False`, then data written to disk are not verified.

Remark: Under non-Dos operating systems (excluding EMX applications running under vanilla Dos), `Verify` is always `True`.

Errors: None.

See also: `SetVerify` ([653](#))

45.10.38 SwapVectors

Synopsis: Swap interrupt vectors

Declaration: `procedure SwapVectors`

Visibility: default

Description: `SwapVectors` swaps the contents of the internal table of interrupt vectors with the current contents of the interrupt vectors. This is called typically in before and after an `Exec` call.

Remark: Under certain operating systems, this routine may be implemented as an empty stub.

Errors: None.

See also: `Exec` ([640](#)), `SetIntVec` ([652](#))

45.10.39 UnixDateToDt

Synopsis: Convert a Unix timestamp to a DateTime record

Declaration: `procedure UnixDateToDt (SecsPast: LongInt; var Dt: DateTime)`

Visibility: default

Description: `DTToUnixDate` converts the Unix timestamp value in `SecsPast` to a `DateTime` representation in `DT`. It is an internal function, implemented on Unix platforms, and should not be used.

Errors: None.

See also: `DTToUnixDate` (639), `PackTime` (650), `UnpackTime` (654), `GetTime` (648), `SetTime` (653)

45.10.40 UnpackTime

Synopsis: Unpack packed file time to a DateTime value

Declaration: `procedure UnpackTime (p: LongInt; var t: DateTime)`

Visibility: default

Description: `UnPackTime` converts the file-modification time in `p` to a `DateTime` record. The file-modification time can be returned by `GetFTime`, `FindFirst` or `FindNext` calls.

For an example, see `PackTime` (650).

Errors: None.

See also: `GetFTime` (646), `FindFirst` (641), `FindNext` (642), `PackTime` (650)

45.10.41 weekday

Synopsis: Return the day of the week

Declaration: `function weekday (y: LongInt; m: LongInt; d: LongInt) : LongInt`

Visibility: default

Description: `WeekDay` returns the day of the week on which the day `Y/M/D` falls. Sunday is represented by 0, Saturday is 6.

Errors: On error, -1 is returned.

See also: `PackTime` (650), `UnpackTime` (654), `GetTime` (648), `SetTime` (653)

Chapter 46

Reference for unit 'dxeload'

46.1 Used units

Table 46.1: Used units by unit 'dxeload'

Name	Page
System	1194

46.2 Overview

The `dxeload` unit was implemented by Pierre Mueller for dos, it allows to load a DXE file (an object file with 1 entry point) into memory and return a pointer to the entry point.

It exists only for dos.

46.3 Procedures and functions

46.3.1 `dxeload`

Synopsis: Load DXE file in memory

Declaration: `function dxeload(filename: string) : pointer`

Visibility: default

Description: `dxeload` loads the contents of the file `filename` into memory. It performs the necessary relocations in the object code, and returns then a pointer to the entry point of the code.

For an example, see the `emu387` ([660](#)) unit in the RTL.

Errors: If an error occurs during the load or relocations, `Nil` is returned.

Chapter 47

Reference for unit 'dynlibs'

47.1 Used units

Table 47.1: Used units by unit 'dynlibs'

Name	Page
System	1194

47.2 Overview

The Dynlibs unit provides support for dynamically loading shared libraries. It is available only on those platforms that support shared libraries. The functionality available here may only be a part of the functionality available on each separate platform, in the interest of portability.

On unix platforms, using this unit will cause the program to be linked to the C library, as most shared libraries are implemented in C and the dynamical linker too.

47.3 Constants, types and variables

47.3.1 Constants

`NilHandle = (0)`

Correctly typed Nil handle - returned on error by `LoadLibrary` ([658](#))

`SharedSuffix = 'so'`

`SharedSuffix` contains the extension of a shared library (dynamically loadable library) on the current platform. It does not contain the . (dot) character. This can be used to determine the name of a shared library in a platform independent way.

47.3.2 Types

`HModule = TLibHandle`

Alias for `TLibHandle` (657) type.

```
TLibHandle = PtrInt
```

`TLibHandle` should be considered an opaque type. It is defined differently on various platforms. The definition shown here depends on the platform for which the documentation was generated.

```
TOrdinalEntry = SizeUInt
```

`TOrdinalEntry` is mainly used on Windows and OS/2 operating systems to retrieve the address of a procedure using the index (ordinal) of the procedure. On these operating systems, entry points can be loaded using name or ordinal value.

47.4 Procedures and functions

47.4.1 FreeLibrary

Synopsis: For compatibility with Delphi/Windows: Unload a library

Declaration: `function FreeLibrary(Lib: TLibHandle) : Boolean`

Visibility: default

Description: `FreeLibrary` provides the same functionality as `UnloadLibrary` (659), and is provided for compatibility with Delphi.

See also: `UnloadLibrary` (659)

47.4.2 GetLoadErrorStr

Synopsis: Return a textual description of the last load error

Declaration: `function GetLoadErrorStr : string`

Visibility: default

Description: `GetLoadErrorStr` returns a textual description of the last library loading or unloading error. No other system calls may be made between the load call and the call of `GetLoadErrorStr`

See also: `LoadLibrary` (658)

47.4.3 GetProcAddress

Synopsis: For compatibility with Delphi/Windows: Get the address of a procedure

Declaration: `function GetProcAddress(Lib: TLibHandle; const ProcName: AnsiString)
: Pointer`

Visibility: default

Description: `GetProcAddress` provides the same functionality as `GetProcedureAddress` (658), and is provided for compatibility with Delphi.

See also: `GetProcedureAddress` (658)

47.4.4 GetProcedureAddress

Synopsis: Get the address of a procedure or symbol in a dynamic library.

Declaration:

```
function GetProcedureAddress(Lib: TLibHandle;
                           const ProcName: AnsiString) : Pointer
function GetProcedureAddress(Lib: TLibHandle; Ordinal: TOrdinalEntry)
                           : Pointer
```

Visibility: default

Description: `GetProcedureAddress` returns a pointer to the location in memory of the symbol `ProcName` or ordinal value `Ordinal` in the dynamically loaded library specified by its handle `lib`. If the symbol cannot be found or the handle is invalid, `Nil` is returned.

On Windows, only an exported procedure or function can be searched this way. On Unix platforms the location of any exported symbol can be retrieved this way.

Only windows and OS/2 support getting the address of a function using an ordinal value.

Errors: If the symbol cannot be found, `Nil` is returned.

See also: `LoadLibrary` (658), `UnLoadLibrary` (659)

47.4.5 LoadLibrary

Synopsis: Load a dynamic library and return a handle to it.

Declaration:

```
function LoadLibrary(const Name: RawByteString) : TLibHandle
function LoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `LoadLibrary` loads a dynamic library in file `Name` and returns a handle to it. If the library cannot be loaded, `NilHandle` (656) is returned.

No assumptions should be made about the location of the loaded library if a relative pathname is specified. The behaviour is dependent on the platform. Therefore it is best to specify an absolute pathname if possible.

Errors: On error, `NilHandle` (656) is returned.

See also: `UnLoadLibrary` (659), `GetProcedureAddress` (658)

47.4.6 SafeLoadLibrary

Synopsis: Saves the control word and loads a library

Declaration:

```
function SafeLoadLibrary(const Name: RawByteString) : TLibHandle
function SafeLoadLibrary(const Name: UnicodeString) : TLibHandle
```

Visibility: default

Description: `SafeLoadLibrary` saves the FPU control word, and calls `LoadLibrary` (658) with library name `Name`. After that function has returned, the FPU control word is saved again. (only on Intel i386 CPUs).

See also: `LoadLibrary` (658)

47.4.7 UnloadLibrary

Synopsis: Unload a previously loaded library

Declaration: `function UnloadLibrary(Lib: TLibHandle) : Boolean`

Visibility: `default`

Description: `UnloadLibrary` unloads a previously loaded library (specified by the handle `lib`). The call returns `True` if succesful, `False` otherwisa.

Errors: On error, `False` is returned.

See also: `LoadLibrary` ([658](#)), `GetProcAddress` ([658](#))

Chapter 48

Reference for unit 'emu387'

48.1 Used units

Table 48.1: Used units by unit 'emu387'

Name	Page
System	1194

48.2 Overview

The `emu387` unit was written by Pierre Mueller for dos. It sets up the coprocessor emulation for FPC under dos. It is not necessary to use this unit on other OS platforms because they either simply do not run on a machine without coprocessor, or they provide the coprocessor emulation themselves.

It shouldn't be necessary to use the function in this unit, it should be enough to place this unit in the `uses` clause of your program to enable the coprocessor emulation under dos. The unit initialization code will try and load the coprocessor emulation code and initialize it.

48.3 Procedures and functions

48.3.1 `npxsetup`

Synopsis: Set up coprocessor emulation.

Declaration: `procedure npxsetup(prog_name: string)`

Visibility: `default`

Description: `npxsetup` checks whether a coprocessor is found. If not, it loads the file `wmemu387.dxe` into memory and initializes the code in it.

If the environment variable `387` is set to `N`, then the emulation will be loaded, even if there is a coprocessor present. If the variable doesn't exist, or is set to any other value, the unit will try to detect the presence of a coprocessor unit.

The function searches the file `wmemu387.dxe` in the following way:

- 1.If the environment variable `EMU387` is set, then it is assumed to point at the `wmemu387.dxe` file.
- 2.if the environment variable `EMU387` does not exist, then the function will take the path part of `prog_name` and look in that directory for the file `wmemu387.dxe`.

It should never be necessary to call this function, because the initialization code of the unit contains a call to the function with as an argument `paramstr(0)`. This means that you should deliver the file `wmemu387.dxe` together with your program.

Errors: If there is an error, an error message is printed to standard error, and the program is halted, since any floating-point code is bound to fail anyhow.

Chapter 49

Reference for unit 'errors'

49.1 Used units

Table 49.1: Used units by unit 'errors'

Name	Page
System	1194
unixtype	1879

49.2 Overview

The errors unit contains routines to convert a unix system call error code to an error message: StrError ([664](#)). It is only available on unix platforms.

49.3 Constants, types and variables

49.3.1 Constants

```
sys_errlist : Array[0..sys_errn-1] of PChar = ('Success', 'Operation not permitted',  
  , 'No such file or directory', 'No such process', 'Interrupted system call'  
  , 'I/O error', 'No such device or address', 'Arg list too long', 'Exec format erro  
  , 'Bad file number', 'No child processes', 'Try again', 'Out of memory'  
  , 'Permission denied', 'Bad address', 'Block device required', 'Device or resource  
  , 'File exists', 'Cross-device link', 'No such device', 'Not a directory'  
  , 'Is a directory', 'Invalid argument', 'File table overflow', 'Too many open file  
  , 'Not a typewriter', 'Text (code segment) file busy', 'File too large'  
  , 'No space left on device', 'Illegal seek', 'Read-only file system'  
  , 'Too many links', 'Broken pipe', 'Math argument out of domain of func'  
  , 'Math result not representable', 'Resource deadlock would occur'  
  , 'File name too long', 'No record locks available', 'Function not implemented'  
  , 'Directory not empty', 'Too many symbolic links encountered', 'Operation would b  
  , 'No message of desired type', 'Identifier removed', 'Channel number out of range  
  , 'Level 2 not synchronized', 'Level 3 halted', 'Level 3 reset', 'Link number out o  
  , 'Protocol driver not attached', 'No CSI structure available', 'Level 2 halted'
```

```
, 'Invalid exchange', 'Invalid request descriptor', 'Exchange full'
, 'No anode', 'Invalid request code', 'Invalid slot', 'File locking deadlock error'
, 'Bad font file format', 'Device not a stream', 'No data available'
, 'Timer expired', 'Out of streams resources', 'Machine is not on the network'
, 'Package not installed', 'Object is remote', 'Link has been severed'
, 'Advertise error', 'Srmount error', 'Communication error on send'
, 'Protocol error', 'Multihop attempted', 'RFS specific error', 'Not a data message'
, 'Value too large for defined data type', 'Name not unique on network'
, 'File descriptor in bad state', 'Remote address changed', 'Can not access a needed file'
, 'Accessing a corrupted shared library', '.lib section in a.out corrupted'
, 'Attempting to link in too many shared libraries', 'Cannot exec a shared library'
, 'Illegal byte sequence', 'Interrupted system call should be restarted'
, 'Streams pipe error', 'Too many users', 'Socket operation on non-socket'
, 'Destination address required', 'Message too long', 'Protocol wrong type for socket'
, 'Protocol not available', 'Protocol not supported', 'Socket type not supported'
, 'Operation not supported on transport endpoint', 'Protocol family not supported'
, 'Address family not supported by protocol', 'Address already in use'
, 'Cannot assign requested address', 'Network is down', 'Network is unreachable'
, 'Network dropped connection because of reset', 'Software caused connection abort'
, 'Connection reset by peer', 'No buffer space available', 'Transport endpoint is already connected'
, 'Transport endpoint is not connected', 'Cannot send after transport endpoint shutdown'
, 'Too many references: cannot splice', 'Connection timed out', 'Connection refused'
, 'Host is down', 'No route to host', 'Operation already in progress'
, 'Operation now in progress', 'Stale NFS file handle', 'Structure needs cleaning'
, 'Not a XENIX named type file', 'No XENIX semaphores available',
'Is a named type file', 'Remote I/O error', 'Quota exceeded', 'No medium found'
, 'Wrong medium type')
```

`sys_errn` is an array with then error codes for the current operating system. It should not be used directly, instead use `StrError` (664).

```
sys_errn = 125
```

`sys_errn` is the number of error codes for the current operating system. It should not be used directly, instead use `StrError` (664).

49.4 Procedures and functions

49.4.1 PError

Synopsis: Print error on standard error routput

Declaration: `procedure PError(const s: string; Errno: cint)`

Visibility: default

Description: `PError` will print the error message `S` followed by the `errNo` and the result for `StrError(errNo)` for `ErrNo` on standard output.

Errors: None.

See also: `StrError` (664)

49.4.2 StrError

Synopsis: Convert an error code to a string

Declaration: `function StrError(err: cint) : string`

Visibility: default

Description: `StrError` will convert the error code `err` to a string.

Errors: If the error code is unknown or out of bounds, an 'Unknown error (err)' string will be returned.

See also: `PError` ([663](#))

Chapter 50

Reference for unit 'exeinfo'

50.1 Used units

Table 50.1: Used units by unit 'exeinfo'

Name	Page
System	1194

50.2 Overview

The `exeinfo` unit implements some cross-platform routines to examine the contents of an executable: information about sections, mapping addresses to loaded modules etc.

It is mainly used by the `lineinfo` ([869](#)) and `Infodwrf` ([898](#)) unit to examine the binary for debug info.

50.3 Constants, types and variables

50.3.1 Types

```
TExeFile = record
  f : File;
  size : Int64;
  isopen : Boolean;
  nsects : LongInt;
  sechdrofs : PtrUInt;
  secstrofs : PtrUInt
;
  processaddress : PtrUInt;
  FunctionRelative : Boolean;
  ImgOffset
  : PtrUInt;
  filename : string;
  buf : Array[0..4095] of Byte;
  bufsize : LongInt;
  bufcnt : LongInt;
```

end

`TExeFile` is a record used in the various calls of this unit. It contains a file descriptor, and various fields that describe the executable.

The structure of `TExeFile` is opaque, that is, one shouldn't rely on the exactness of this structure, it may change any time in the future.

50.4 Procedures and functions

50.4.1 CloseExeFile

Synopsis: Close a previously opened file.

Declaration: `function CloseExeFile(var e: TExeFile) : Boolean`

Visibility: default

Description: `CloseExeFile` closes an executable file image previously opened with `OpenExeFile` (667), and represented by `e`.

The function returns `True` if the file was closed succesfully, or `False` if something went wrong.

Errors: In case of an error, `False` is returned.

See also: `OpenExeFile` (667)

50.4.2 FindExeSection

Synopsis: Find a section in the binary image.

Declaration: `function FindExeSection(var e: TExeFile; const secname: string;
var secofs: LongInt; var seclen: LongInt)
: Boolean`

Visibility: default

Description: `FindExeSection` examines the binary that was opened with `OpenExeFile` (667) (represented by `e`) and searches for the section named `secname`. If found, the section offset is returned in `secofs` and the section length (in bytes) is returned in `seclen`.

The function returns `True` if the section was found, `False` if not.

See also: `OpenExeFile` (667)

50.4.3 GetModuleByAddr

Synopsis: Return the module name by address

Declaration: `procedure GetModuleByAddr(addr: pointer; var baseaddr: pointer;
var filename: string)`

Visibility: default

Description: `GetModuleByAddr` returns the name of the module that contains address `addr`. If succesful, it returns `True` and returns the filename in `FileName` and the base address at which it is loaded in `BaseAddr`.

50.4.4 OpenExeFile

Synopsis: Open an executable file

Declaration: `function OpenExeFile(var e: TExeFile; const fn: string) : Boolean`

Visibility: default

Description: `OpenExeFile` opens the executable file `fn` and initializes the structure `e` for subsequent calls to routines in the `exeinfo` unit.

The function returns `True` if the file was opened successfully, false otherwise.

See also: `FindExeSection` ([666](#)), `CloseExeFile` ([666](#)), `ReadDebugLink` ([667](#))

50.4.5 ReadDebugLink

Synopsis: Read the location of a debug info filename

Declaration: `function ReadDebugLink(var e: TExeFile; var dbgfn: string) : Boolean`

Visibility: default

Description: `ReadDebugLink` examines the `.gnu_debuglink` section to see if the debug information is stored in an external file. If so, then the name of the file with the debug information is returned in the `dbgfn` parameter.

The function returns `false` if there is no external debug information file, or if the file with debug information does not exist. It is searched next to the binary file or in the current directory.

See also: `OpenExeFile` ([667](#)), `CloseExeFile` ([666](#))

Chapter 51

Reference for unit 'fgl'

51.1 Used units

Table 51.1: Used units by unit 'fgl'

Name	Page
System	1194
sysutils	1442
Types	1722

51.2 Overview

The `fgl` unit contains some basic list-related generic classes.

51.3 Constants, types and variables

51.3.1 Constants

```
MaxGListSize = MaxInt div 1024
```

`MaxGListSize` is the maximum number of elements in the `TFPGList` ([673](#)) list.

```
MaxListSize = Maxint div 16
```

`MaxListSize` is the maximum number of elements a list can contain before the memory runs out.

51.3.2 Types

```
TFPSListCompareFunc = function(Key1: Pointer; Key2: Pointer) : Integer  
  of object
```

`TFPSListCompareFunc` is used in the `TFPSList.Sort` ([703](#)) method to compare 2 elements. The list passes 2 pointers to the actual items to the compare function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

51.4 EListError

51.4.1 Description

`EListError` is the exception used in the `TFPSList` (698) class to indicate errors such as a list index out of bounds, wrong capacity etc.

See also: `TFPSList.Capacity` (704), `TFPSList.Exchange` (701), `TFPSList.Items` (704)

51.5 TFPGInterfacedObjectList

51.5.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that requires reference counting (all objects that implement `IInterface` or `IUnknown`). It will specialize to a list with the same methods as `TFPSList` (698) or `classes.TFPList` (668) or `TFPObjectList`

Classes that implement `IInterface` or `IUnknown` require special care to maintain the reference count. The `TFPGInterfacedObjectList` list provides the necessary functionality to deal with this.

See also: `TFPSList` (698), `classes.TFPList` (668)

51.5.2 Method overview

Page	Method	Description
670	Add	Add new object of class <code>T</code> to the list.
671	Assign	Copy objects from Source list
670	Create	Instantiate a new interfaced object list.
670	Extract	Extract an item from the list
670	GetEnumerator	Return a list enumerator for <code>T</code>
671	IndexOf	Index of object
671	Insert	Insert a new object in the list
671	Remove	Remove an object from the list.
672	Sort	Sort the objects in the list

51.5.3 Property overview

Page	Properties	Access	Description
672	First	rw	First non-nil object
673	Items	rw	Indexed access to objects in the list.
672	Last	rw	Last non- <code>Nil</code> object
673	List	r	Internal list pointer

51.5.4 TFPGInterfacedObjectList.Create

Synopsis: Instantiate a new interfaced object list.

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size.

See also: `TFPSList.Destroy` ([699](#))

51.5.5 TFPGInterfacedObjectList.Add

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added. `Add` will increase the reference count of the object.

Errors: If the item could not be added, an `EListError` ([669](#)) exception is raised.

See also: `TFPGInterfacedObjectList.Extract` ([670](#)), `TFPGInterfacedObjectList.Items` ([673](#)), `TFPGInterfacedObjectList.IndexOf` ([671](#))

51.5.6 TFPGInterfacedObjectList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: `public`

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found. The extracted object will not be destroyed.

Errors: None.

See also: `TFPSList.Delete` ([700](#))

51.5.7 TFPGInterfacedObjectList.GetEnumerator

Synopsis: Return a list enumerator for `T`

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: `public`

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` ([677](#)).

See also: `TFPGListEnumerator` ([677](#))

51.5.8 TFPGInterfacedObjectList.IndexOf

Synopsis: Index of object

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the object does not appear in the list.

Errors: None.

See also: `TFPGInterfacedObjectList.Items` (673), `TFPGInterfacedObjectList.Insert` (671), `TFPGInterfacedObjectList.Add` (670)

51.5.9 TFPGInterfacedObjectList.Insert

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` (704).

Errors: If an invalid index is specified, an `EListError` (669) exception is raised.

See also: `TFPGInterfacedObjectList.Items` (673), `TFPGInterfacedObjectList.Add` (670)

51.5.10 TFPGInterfacedObjectList.Assign

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGInterfacedObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` (700), `TFPGObjectList.Add` (695)

51.5.11 TFPGInterfacedObjectList.Remove

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, -1 is returned. Only the first object is removed.

Removing an object from the list may cause the object to be freed.

Errors: None.

See also: `TFPGInterfacedObjectList.IndexOf` (671), `TFPSList.Delete` (700), `TFPGInterfacedObjectList.FreeObjects` (669)

51.5.12 TFPGInterfacedObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- If the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

See also: `TFPSList.Sorted` ([698](#))

51.5.13 TFPGInterfacedObjectList.First

Synopsis: First non-nil object

Declaration: `Property First : T`

Visibility: `public`

Access: `Read, Write`

Description: `First` returns the first non-nil object. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` ([705](#)), `TFPGInterfacedObjectList.Last` ([672](#)), `TFPSList.Pack` ([703](#))

51.5.14 TFPGInterfacedObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: `public`

Access: `Read, Write`

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil` is returned.

See also: `TFPGInterfacedObjectList.First` ([672](#)), `TFPSList.Last` ([705](#))

51.5.15 TFPGInterfacedObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (704).

The previous object at position `Index` may be freed when setting the property, depending on its reference count.

Errors: If an invalid index is used, an `EListError` (669) exception is raised.

See also: `TFPSList.Count` (704)

51.5.16 TFPGInterfacedObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGInterfacedObjectList.Items` (673)

51.6 TFPGList

51.6.1 Description

`TFPGList` can be used to specialize a list for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` (698) or `classes.TFPList` (668)

See also: `TFPSList` (698), `classes.TFPList` (668)

51.6.2 Method overview

Page	Method	Description
674	Add	Add new item of type <code>T</code> to the list.
675	Assign	Copy elements from Source list
674	Create	Instantiate a new list
674	Extract	Extract an item from the list
674	GetEnumerator	Return a list enumerator for <code>T</code> .
675	IndexOf	Index of item
675	Insert	Insert a new item in the list
675	Remove	Remove an item from the list.
676	Sort	Sort the list

51.6.3 Property overview

Page	Properties	Access	Description
676	First	rw	First non-empty item
676	Items	rw	Indexed access to items in the list
676	Last	rw	Last non-empty item
677	List	r	Internal list object

51.6.4 TFPGList.Create

Synopsis: Instantiate a new list

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new list. It will simply call the inherited constructor with the correct item size: `sizeof(T)`.

51.6.5 TFPGList.Add

Synopsis: Add new item of type `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: `public`

Description: `Add` adds a new item `Item` of generic type `T` to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` ([669](#)) exception is raised.

See also: `TFPGList.Extract` ([674](#)), `TFPGList.Items` ([676](#)), `TFPGList.IndexOf` ([675](#))

51.6.6 TFPGList.Extract

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: `public`

Description: `Extract` removes `Item` from the list and returns the removed item, or an expression equivalent to `T(0)` if it was not found.

Errors: None.

See also: `TFPSList.Delete` ([700](#))

51.6.7 TFPGList.GetEnumerator

Synopsis: Return a list enumerator for `T`.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: `public`

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` ([677](#)).

See also: `TFPGListEnumerator` ([677](#))

51.6.8 TFPGList.IndexOf

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGList.Items` (676), `TFPGList.Insert` (675), `TFPSList.Add` (700)

51.6.9 TFPGList.Insert

Synopsis: Insert a new item in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new item in the list at position `Index`. The index is zero based and must be less than `Count` (704).

Errors: If an invalid index is specified, an `EListError` (669) exception is raised.

See also: `TFPGList.Items` (676), `TFPGList.Insert` (675), `TFPSList.Add` (700)

51.6.10 TFPGList.Assign

Synopsis: Copy elements from Source list

Declaration: `procedure Assign(Source: TFPGList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

See also: `TFPSList.Clear` (700), `TFPGList.Add` (674)

51.6.11 TFPGList.Remove

Synopsis: Remove an item from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the item `Item` from the list, and returns the index of the removed item. If no item was removed, -1 is returned. Only the first item is removed.

Errors: None.

See also: `TFPGList.IndexOf` (675)

51.6.12 TFPGList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: public

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first item (`Item1`) is assumed to be 'less' than the second item (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first item (`Item1`) is assumed to be 'greater than' the second item (`Item2`) and will be moved after the second in the list.
- if the function result is zero, the items are assumed to be 'equal' and no moving will take place.

51.6.13 TFPGList.First

Synopsis: First non-empty item

Declaration: `Property First : T`

Visibility: public

Access: Read,Write

Description: `First` returns the first non-empty item, which means the first item not equal to `T(0)`. If no such element is present, `T(0)` is returned.

See also: `TFPSList.First` ([705](#)), `TFPGList.Last` ([676](#))

51.6.14 TFPGList.Last

Synopsis: Last non-empty item

Declaration: `Property Last : T`

Visibility: public

Access: Read,Write

Description: `Last` returns the last non-empty item, which means the last item not equal to `T(0)`. If no such element is present, `T(0)` is returned.

See also: `TFPGList.First` ([676](#)), `TFPSList.Last` ([705](#))

51.6.15 TFPGList.Items

Synopsis: Indexed access to items in the list

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: public

Access: Read,Write

Description: `Items` provides indexed access to the items in the list. The items can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (704).

Errors: If an invalid index is used, an `EListError` (669) exception is raised.

See also: `TFPSList.Count` (704)

51.6.16 TFPGList.List

Synopsis: Internal list object

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of items. It should not be used directly.

See also: `TFPGList.Items` (676)

51.7 TFPGListEnumerator

51.7.1 Description

`TFPGListEnumerator` is a generic list enumerator. It is used in the `TFPGList` (673) class to implement the enumerator for the list.

Normally there should be no need to instantiate or use this class directly.

See also: `TFPGList` (673)

51.7.2 Method overview

Page	Method	Description
677	<code>Create</code>	Create a new list enumerator
678	<code>MoveNext</code>	Move to next element in the list

51.7.3 Property overview

Page	Properties	Access	Description
678	<code>Current</code>	r	Current enumerated element

51.7.4 TFPGListEnumerator.Create

Synopsis: Create a new list enumerator

Declaration: `constructor Create (AList: TFPSList)`

Visibility: public

Description: `Create` is called by the list `AList` to initialize a new enumerator. There should be no need to call this directly.

See also: `TFPGList` (673)

51.7.5 TFPGListEnumerator.MoveNext

Synopsis: Move to next element in the list

Declaration: `function MoveNext : Boolean`

Visibility: public

Description: `MoveNext` moves to the next element in the list.

See also: `TFPGListEnumerator.Current` ([678](#))

51.7.6 TFPGListEnumerator.Current

Synopsis: Current enumerated element

Declaration: `Property Current : T`

Visibility: public

Access: Read

Description: `Current` returns the currently enumerated element. It is only valid after `TFPGListEnumerator.MoveNext` ([678](#)) was called and returned `True`.

See also: `TFPGListEnumerator.MoveNext` ([678](#))

51.8 TFPGMap

51.8.1 Description

`TFPGMap` is a generic map class. It can be used to specialize a map for any key type and data type that do not require manual reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` ([683](#)) must be used.

See also: `TFPGMapInterfacedObjectData` ([683](#))

51.8.2 Method overview

Page	Method	Description
679	<code>Add</code>	Add a key and value to the map
680	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
679	<code>Create</code>	Create a new instance of the map
679	<code>Find</code>	Find item based on key
680	<code>IndexOf</code>	Find index of a key in the list.
680	<code>IndexOfData</code>	Find index of data value in the list.
681	<code>InsertKey</code>	Insert a new key in the list
681	<code>InsertKeyData</code>	Insert a new key with associated data in the list
681	<code>Remove</code>	Remove a key from the list
680	<code>TryGetData</code>	Find data or return default

51.8.3 Property overview

Page	Properties	Access	Description
682	Data	rw	Indexed access to the data in the list
682	KeyData	rw	Access to data based on key
681	Keys	rw	Indexed access to the keys in the list.
682	OnCompare	rw	Alias for OnKeyCompare
683	OnDataCompare	rw	Compare function for data values.
683	OnKeyCompare	rw	Compare function for key values.

51.8.4 TFPGMap.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([706](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([706](#))

51.8.5 TFPGMap.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: `public`

Description: `Add` adds a new key `AKey` of generic type `TKey` with data value `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([669](#)) exception is raised. If `Duplicates` ([709](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([669](#)) exception is raised.

See also: `TFPGMap.Keys` ([681](#)), `TFPGMap.IndexOf` ([680](#)), `TFPGMap.KeyData` ([682](#)), `TFPGMap.Data` ([682](#)), `TFPSMap.Duplicates` ([709](#))

51.8.6 TFPGMap.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: `public`

Description: `Find` will search the key equal to `AKey` and return its index in `AIndex`. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

The behaviour of `Find` is undefined if the map is not sorted. For unsorted maps, use `IndexOf` ([680](#)) instead.

See also: `TFPGMap.IndexOf` ([680](#)), `TFPGMap.IndexOfData` ([680](#))

51.8.7 TFPGMap.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMap.Find` (679)

51.8.8 TFPGMap.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMap.TryGetData` (680), `TFPGMap.Add` (679), `TFPGMap.Find` (679)

51.8.9 TFPGMap.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMap.Find` (679), `TFPGMap.IndexOfData` (680)

51.8.10 TFPGMap.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMap.Find` (679), `TFPGMap.IndexOf` (680)

51.8.11 TFPGMap.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMap.InsertKeyData` (681), `TFPGMap.Add` (679), `TFPSMap.Delete` (706), `TFPSMap.Remove` (709)

51.8.12 TFPGMap.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMap.InsertKey` (681), `TFPGMap.Add` (679), `TFPSMap.Delete` (706), `TFPGMap.Remove` (681)

51.8.13 TFPGMap.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMap.InsertKey` (681), `TFPGMap.InsertKeyData` (681), `TFPGMap.Add` (679), `TFPSMap.Delete` (706)

51.8.14 TFPGMap.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (704), `TFPGMap.Data` (682), `TFPGMap.KeyData` (682)

51.8.15 TFPGMap.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMap.Keys` (681), `TFPGMap.KeyData` (682)

51.8.16 TFPGMap.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (669) will be raised.

Errors: If the key does not exist, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMap.Keys` (681), `TFPGMap.Data` (682)

51.8.17 TFPGMap.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnCompare` is a deprecated property, use `TFPGMap.OnKeyCompare` (683) instead.

See also: `TFPGMap.OnKeyCompare` (683)

51.8.18 TFPGMap.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnDataCompare` ([683](#))

51.8.19 TFPGMap.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMap.OnKeyCompare` ([683](#))

51.9 TFPGMapInterfacedObjectData

51.9.1 Description

`TFPGInterfacedObjectMap` is a generic map class. It can be used to specialize a map for any key type, with associated data type that requires manual reference counting: any type which implements `IInterface`. For non-reference counted objects, `TFPGMap` ([678](#)) should be used.

This map class is entirely equivalent to `TFPGMap` ([678](#)), but operates on data items that require additional reference counting code on the data.

See also: `TFPGMap` ([678](#))

51.9.2 Method overview

Page	Method	Description
684	Add	Add a key and value to the map
685	AddOrSetData	Add data with given or set value if the key already exists.
684	Create	Create a new instance of the map
685	Find	Find item based on key
685	IndexOf	Find index of a key in the list.
686	IndexOfData	Find index of data value in the list.
686	InsertKey	Insert a new key in the list
686	InsertKeyData	Insert a new key with associated data in the list
686	Remove	Remove a key from the list
685	TryGetData	Find data or return default

51.9.3 Property overview

Page	Properties	Access	Description
687	Data	rw	Indexed access to the data in the list
687	KeyData	rw	Access to data based on key
687	Keys	rw	Indexed access to the keys in the list.
688	OnCompare	rw	Alias for OnKeyCompare
688	OnDataCompare	rw	Compare function for data values.
688	OnKeyCompare	rw	Compare function for key values.

51.9.4 TFPGMapInterfacedObjectData.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` ([706](#)) parent with the sized of the key and data.

See also: `TFPSMap.Create` ([706](#))

51.9.5 TFPGMapInterfacedObjectData.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: `public`

Description: `Add` adds a new key `AKey` of generic type `TKey` with data value `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` ([669](#)) exception is raised. If `Duplicates` ([709](#)) is set to `dupError` and a duplicate key is added, an `EListError` ([669](#)) exception is raised.

See also: `TFPGMapInterfacedObjectData.Keys` ([687](#)), `TFPGMapInterfacedObjectData.IndexOf` ([685](#)), `TFPGMapInterfacedObjectData.KeyData` ([687](#)), `TFPGMapInterfacedObjectData.Data` ([687](#)), `TFPS.Duplicates` ([668](#))

51.9.6 TFPGMapInterfacedObjectData.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapInterfacedObjectData.IndexOf` ([685](#)), `TFPGMapInterfacedObjectData.IndexOfData` ([686](#))

51.9.7 TFPGMapInterfacedObjectData.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` ([685](#))

51.9.8 TFPGMapInterfacedObjectData.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapInterfacedObjectData.TryGetData` ([685](#)), `TFPGMapInterfacedObjectData.Add` ([684](#)), `TFPGMapInterfacedObjectData.Find` ([685](#))

51.9.9 TFPGMapInterfacedObjectData.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` ([685](#)), `TFPGMapInterfacedObjectData.IndexOfData` ([686](#))

51.9.10 TFPGMapInterfacedObjectData.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapInterfacedObjectData.Find` (685), `TFPGMapInterfacedObjectData.IndexOf` (685)

51.9.11 TFPGMapInterfacedObjectData.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKeyData` (686), `TFPGMapInterfacedObjectData.Add` (684), `TFPSMapInterfacedObjectData.Delete` (668), `TFPSMapInterfacedObjectData.Remove` (668)

51.9.12 TFPGMapInterfacedObjectData.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMapInterfacedObjectData.InsertKey` (686), `TFPGMapInterfacedObjectData.Add` (684), `TFPSMapInterfacedObjectData.Delete` (668), `TFPGMapInterfacedObjectData.Remove` (686)

51.9.13 TFPGMapInterfacedObjectData.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMap.InsertKey` (681), `TFPGMap.InsertKeyData` (681), `TFPGMap.Add` (679), `TFPGMapInterfacedObjectData.Delete` (683)

51.9.14 `TFPGMapInterfacedObjectData.Keys`

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (704), `TFPGMapInterfacedObjectData.Data` (687), `TFPGMapInterfacedObjectData.KeyData` (687)

51.9.15 `TFPGMapInterfacedObjectData.Data`

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMapInterfacedObjectData.Keys` (687), `TFPGMapInterfacedObjectData.KeyData` (687)

51.9.16 `TFPGMapInterfacedObjectData.KeyData`

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (669) will be raised.

Errors: If the key does not exist, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMapInterfacedObjectData.Keys` (687), `TFPGMapInterfacedObjectData.Data` (687)

51.9.17 TFPGMapInterfacedObjectData.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnCompare` is a deprecated property, use `TFPGMapInterfacedObjectData.OnKeyCompare` (688) instead.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` (688)

51.9.18 TFPGMapInterfacedObjectData.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnDataCompare` (688)

51.9.19 TFPGMapInterfacedObjectData.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- if the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapInterfacedObjectData.OnKeyCompare` (688)

51.10 TFPGMapObject

51.10.1 Description

`TFPGMapObject` is a generic map class. It can be used to specialize a map for object types, but not objects with automated reference counting: For reference counted interface objects, `TFPGMapInterfacedObjectData` (683) must be used.

See also: `TFPGMapInterfacedObjectData` (683)

51.10.2 Method overview

Page	Method	Description
689	<code>Add</code>	Add a key and value to the map
690	<code>AddOrSetData</code>	Add data with given or set value if the key already exists.
689	<code>Create</code>	Create a new instance of the map
690	<code>Find</code>	Find item based on key
691	<code>IndexOf</code>	Find index of a key in the list.
691	<code>IndexOfData</code>	Find index of data value in the list.
691	<code>InsertKey</code>	Insert a new key in the list
691	<code>InsertKeyData</code>	Insert a new key with associated data in the list
692	<code>Remove</code>	Remove a key from the list
690	<code>TryGetData</code>	Find data or return default

51.10.3 Property overview

Page	Properties	Access	Description
692	<code>Data</code>	rw	Indexed access to the data in the list
692	<code>KeyData</code>	rw	Access to data based on key
692	<code>Keys</code>	rw	Indexed access to the keys in the list.
693	<code>OnCompare</code>	rw	Alias for <code>OnKeyCompare</code>
693	<code>OnDataCompare</code>	rw	Compare function for data values.
693	<code>OnKeyCompare</code>	rw	Compare function for key values.

51.10.4 TFPGMapObject.Create

Synopsis: Create a new instance of the map

Declaration: `constructor Create(AFreeObjects: Boolean)`
`constructor Create`

Visibility: `public`

Description: `Create` instantiates a new map. It mainly initializes the `TFPSMap` (706) parent with the sized of the key and data.

See also: `TFPSMap.Create` (706)

51.10.5 TFPGMapObject.Add

Synopsis: Add a key and value to the map

Declaration: `function Add(const AKey: TKey; const AData: TData) : Integer`
`function Add(const AKey: TKey) : Integer`

Visibility: public

Description: Add adds a new key `AKey` of generic type `TKey` with data object `AData` to the list and returns the position at which the key was added.

Errors: If the item could not be added, an `EListError` (669) exception is raised. If `Duplicates` (709) is set to `dupError` and a duplicate key is added, an `EListError` (669) exception is raised.

See also: `TFPGMapObject.Keys` (692), `TFPGMapObject.IndexOf` (691), `TFPGMapObject.KeyData` (692), `TFPGMapObject.Data` (692), `TFPSMap.Duplicates` (709)

51.10.6 TFPGMapObject.Find

Synopsis: Find item based on key

Declaration: `function Find(const AKey: TKey; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` will search the first key smaller than or equal to `AKey` and return its index in `AIndex`. If the key was not found then -1 is returned. The return value of the function is `True` if an exact match for `AKey` is found, `False` otherwise.

See also: `TFPGMapObject.IndexOf` (691), `TFPGMapObject.IndexOfData` (691)

51.10.7 TFPGMapObject.TryGetData

Synopsis: Find data or return default

Declaration: `function TryGetData(const AKey: TKey; out AData: TData) : Boolean`

Visibility: public

Description: `TryGetData` will search the map for `AKey` and return `True` or `False` depending on whether the value with the given key was found. If the key was found, the associated value is returned in `AData`, if it is not found a default value (using `Default`) is returned.

Errors: None.

See also: `TFPGMapObject.Find` (690)

51.10.8 TFPGMapObject.AddOrSetData

Synopsis: Add data with given or set value if the key already exists.

Declaration: `procedure AddOrSetData(const AKey: TKey; const AData: TData)`

Visibility: public

Description: `AddOrSetData` will check if key `AKey` already exists. if yes, the value associated with it will be replaced with `AData`. If the key does not yet exist, it will be added with value `AData`.

Errors: None.

See also: `TFPGMapObject.TryGetData` (690), `TFPGMapObject.Add` (689), `TFPGMapObject.Find` (690)

51.10.9 TFPGMapObject.IndexOf

Synopsis: Find index of a key in the list.

Declaration: `function IndexOf(const AKey: TKey) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `AKey` in the list, or -1 if the key was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` (690), `TFPGMapObject.IndexOfData` (691)

51.10.10 TFPGMapObject.IndexOfData

Synopsis: Find index of data value in the list.

Declaration: `function IndexOfData(const AData: TData) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of object `AData` in the list, or -1 if the data was not found in the list.

Errors: None.

See also: `TFPGMapObject.Find` (690), `TFPGMapObject.IndexOf` (691)

51.10.11 TFPGMapObject.InsertKey

Synopsis: Insert a new key in the list

Declaration: `procedure InsertKey(Index: Integer; const AKey: TKey)`

Visibility: public

Description: `InsertKey` inserts key `AKey` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMapObject.InsertKeyData` (691), `TFPGMapObject.Add` (689), `TFPSMap.Delete` (706), `TFPSMap.Remove` (709)

51.10.12 TFPGMapObject.InsertKeyData

Synopsis: Insert a new key with associated data in the list

Declaration: `procedure InsertKeyData(Index: Integer; const AKey: TKey;
const AData: TData)`

Visibility: public

Description: `InsertKey` inserts key `AKey` with associated data `AData` at position `Index` in the list. It is not allowed to insert a key in a sorted list.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, or the list is sorted, an `EListError` (669) exception will be raised.

See also: `TFPGMapObject.InsertKey` (691), `TFPGMapObject.Add` (689), `TFPSMap.Delete` (706), `TFPGMapObject.Remove` (692)

51.10.13 TFPGMapObject.Remove

Synopsis: Remove a key from the list

Declaration: `function Remove(const AKey: TKey) : Integer`

Visibility: public

Description: `Remove` removes the key `AKey` from the list, together with its associated data. The function returns the index of `AKey` prior to removal from the list, or -1 if `AKey` was not present in the list.

Errors: None.

See also: `TFPGMapObject.InsertKey` (691), `TFPGMapObject.InsertKeyData` (691), `TFPGMapObject.Add` (689), `TFPSMap.Delete` (706)

51.10.14 TFPGMapObject.Keys

Synopsis: Indexed access to the keys in the list.

Declaration: `Property Keys[Index: Integer]: TKey`

Visibility: public

Access: Read,Write

Description: `Keys` provides indexed access to the key values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Key values can always be read, but can only be written if the list is unsorted.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised. The same exception is raised if a key is written and the list is sorted.

See also: `TFPSList.Count` (704), `TFPGMapObject.Data` (692), `TFPGMapObject.KeyData` (692)

51.10.15 TFPGMapObject.Data

Synopsis: Indexed access to the data in the list

Declaration: `Property Data[Index: Integer]: TData`

Visibility: public

Access: Read,Write

Description: `Data` provides indexed access to the data values in the list. Valid values for `Index` are in the range `[0..Count-1]`. Data can always be read or written.

Errors: If the index `AIndex` is out of range `[0..Count-1]`, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMapObject.Keys` (692), `TFPGMapObject.KeyData` (692)

51.10.16 TFPGMapObject.KeyData

Synopsis: Access to data based on key

Declaration: `Property KeyData[AKey: TKey]: TData; default`

Visibility: public

Access: Read,Write

Description: `KeyData` allows access to the data based on the key value `AKey`. The data can be read and written. When writing, writing using an existing key will overwrite the current data. If it does not exist yet, it will be created. When reading, if the key is not present, an `EListError` (669) will be raised.

Errors: If the key does not exist, an `EListError` (669) exception will be raised.

See also: `TFPSList.Count` (704), `TFPGMapObject.Keys` (692), `TFPGMapObject.Data` (692)

51.10.17 TFPGMapObject.OnCompare

Synopsis: Alias for `OnKeyCompare`

Declaration: `Property OnCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnCompare` is a deprecated property, use `TFPGMapObject.OnKeyCompare` (693) instead.

See also: `TFPGMapObject.OnKeyCompare` (693)

51.10.18 TFPGMapObject.OnKeyCompare

Synopsis: Compare function for key values.

Declaration: `Property OnKeyCompare : TKeyCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnKeyCompare` can be set to a function that compares key values. The default value for this event is a function that compares keys based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first key (`key1`) is assumed to be 'less' than the second key (`key2`) and will be moved before the second in the list.
- If the function result is positive, the first key (`key1`) pointer is assumed to be 'greater than' the second key (`key2`) and will be moved after the second in the list.
- if the function result is zero, the keys are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnDataCompare` (693)

51.10.19 TFPGMapObject.OnDataCompare

Synopsis: Compare function for data values.

Declaration: `Property OnDataCompare : TDataCompareFunc`

Visibility: `public`

Access: `Read,Write`

Description: `OnDataCompare` can be set to a function that compares data values. The default value for this event is a function that compares data based on a byte-by-byte comparison of the memory block. The function must have the following semantics:

- If the result of this function is negative, the first data item (`Data1`) is assumed to be 'less' than the second data item (`Data2`) and will be moved before the second in the list.
- If the function result is positive, the first data item (`Data1`) pointer is assumed to be 'greater than' the second data item (`Data2`) and will be moved after the second in the list.
- If the function result is zero, the data items are assumed to be 'equal' and no moving will take place.

See also: `TFPGMapObject.OnKeyCompare` (693)

51.11 TFPGObjectList

51.11.1 Description

`TFPGList` can be used to specialize a list for any class type `T` that does not require reference counting (such as interfaced objects). It will specialize to a list with the same methods as `TFPSList` (698) or `classes.TFPList` (668) or `TFPObjectList`

See also: `TFPSList` (698), `classes.TFPList` (668)

51.11.2 Method overview

Page	Method	Description
695	Add	Add new object of class <code>T</code> to the list.
696	Assign	Copy objects from Source list
694	Create	Instantiate a new object list.
695	Extract	Extract an item from the list
695	GetEnumerator	Return a list enumerator for <code>T</code> .
695	IndexOf	Index of item
696	Insert	Insert a new object in the list
696	Remove	Remove an object from the list.
697	Sort	Sort the objects in the list

51.11.3 Property overview

Page	Properties	Access	Description
697	First	rw	First non-nil item
698	FreeObjects	rw	Does the list own the objects or not?
697	Items	rw	Indexed access to objects in the list.
697	Last	rw	Last non- <code>Nil</code> object
698	List	r	Internal list pointer

51.11.4 TFPGObjectList.Create

Synopsis: Instantiate a new object list.

Declaration: `constructor Create (FreeObjects: Boolean)`

Visibility: `public`

Description: `Create` instantiates a new object list. It will simply call the inherited constructor with the correct item size and will initialize `TFPGObjectList.FreeObjects` (698) with `FreeObjects`.

If `FreeObjects` is true, then the list owns the objects. Freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

See also: `TFPGObjectList.FreeObjects` ([698](#))

51.11.5 `TFPGObjectList.Add`

Synopsis: Add new object of class `T` to the list.

Declaration: `function Add(const Item: T) : Integer`

Visibility: public

Description: `Add` adds a new item `Item` of class type `T` to the list and returns the position at which the item was added.

Errors: If the item could not be added, an `EListError` ([669](#)) exception is raised.

See also: `TFPGObjectList.Extract` ([695](#)), `TFPGObjectList.Items` ([697](#)), `TFPGObjectList.IndexOf` ([695](#))

51.11.6 `TFPGObjectList.Extract`

Synopsis: Extract an item from the list

Declaration: `function Extract(const Item: T) : T`

Visibility: public

Description: `Extract` removes `Item` from the list and returns the removed item, or `Nil` if it was not found.

The extracted object will not be destroyed even if the list owns the objects.

Errors: None.

See also: `TFPSList.Delete` ([700](#))

51.11.7 `TFPGObjectList.GetEnumerator`

Synopsis: Return a list enumerator for `T`.

Declaration: `function GetEnumerator : TFPGListEnumeratorSpec`

Visibility: public

Description: `GetEnumerator` returns an enumerator for the elements in the list. It is a specialized version of `TFPGListEnumerator` ([677](#)).

See also: `TFPGListEnumerator` ([677](#))

51.11.8 `TFPGObjectList.IndexOf`

Synopsis: Index of item

Declaration: `function IndexOf(const Item: T) : Integer`

Visibility: public

Description: `IndexOf` returns the index of `Item` in the list, or -1 if the item does not appear in the list.

Errors: None.

See also: `TFPGObjectList.Items` ([697](#)), `TFPGObjectList.Insert` ([696](#)), `TFPGObjectList.Add` ([695](#))

51.11.9 `TFPGObjectList.Insert`

Synopsis: Insert a new object in the list

Declaration: `procedure Insert(Index: Integer; const Item: T)`

Visibility: public

Description: `Insert` inserts a new object (`Item`) in the list at position `Index`. The index is zero based and must be less than `Count` ([704](#)).

Errors: If an invalid index is specified, an `EListError` ([669](#)) exception is raised.

See also: `TFPGList.Items` ([676](#)), `TFPGList.Insert` ([675](#)), `TFPSList.Add` ([700](#))

51.11.10 `TFPGObjectList.Assign`

Synopsis: Copy objects from Source list

Declaration: `procedure Assign(Source: TFPGObjectList)`

Visibility: public

Description: `Assign` clears the list and copies all items in `Source` to the list. The source list must be of the same type as the destination list.

Take care if both the list owns the objects (i.e. have `TFPGObjectList.FreeObjects` ([698](#)) set to `True`), this may result to access violations.

See also: `TFPSList.Clear` ([700](#)), `TFPGObjectList.Add` ([695](#))

51.11.11 `TFPGObjectList.Remove`

Synopsis: Remove an object from the list.

Declaration: `function Remove(const Item: T) : Integer`

Visibility: public

Description: `Remove` removes the object `Item` from the list, and returns the index of the removed item. If no item was removed, `-1` is returned. Only the first object is removed.

If the list owns the objects, (`TFPGObjectList.FreeObjects` ([698](#)) is set to `True`) then the object is freed.

Errors: None.

See also: `TFPGObjectList.IndexOf` ([695](#)), `TFPSList.Delete` ([700](#)), `TFPGObjectList.FreeObjects` ([698](#))

51.11.12 TFPGObjectList.Sort

Synopsis: Sort the objects in the list

Declaration: `procedure Sort (Compare: TCompareFunc)`

Visibility: `public`

Description: `Sort` sorts the elements in the list using the provided `Compare` function. The list passes 2 items to the compare function. The result of this function determines how the items will be sorted:

- If the result of this function is negative, the first object (`Item1`) is assumed to be 'less' than the second object (`Item2`) and will be moved before the second in the list.
- If the function result is positive, the first object (`Item1`) is assumed to be 'greater than' the second object (`Item2`) and will be moved after the second in the list.
- If the function result is zero, the objects are assumed to be 'equal' and no moving will take place.

Errors: None.

51.11.13 TFPGObjectList.First

Synopsis: First non-nil item

Declaration: `Property First : T`

Visibility: `public`

Access: Read, Write

Description: `First` returns the first non-nil item. If no such element is present, `Nil` is returned.

See also: `TFPSList.First` ([705](#)), `TFPGList.Last` ([676](#)), `TFPSList.Pack` ([703](#))

51.11.14 TFPGObjectList.Last

Synopsis: Last non-`Nil` object

Declaration: `Property Last : T`

Visibility: `public`

Access: Read, Write

Description: `Last` returns the last non-`Nil` object. If no such element is present, `Nil` is returned.

See also: `TFPGObjectList.First` ([697](#)), `TFPSList.Last` ([705](#))

51.11.15 TFPGObjectList.Items

Synopsis: Indexed access to objects in the list.

Declaration: `Property Items[Index: Integer]: T; default`

Visibility: `public`

Access: Read, Write

Description: `Items` provides indexed access to the objects in the list. The objects can be get or set.

The index `Index` is zero based, and has a maximum value of `Count-1` (704).

If the list owns the objects, (`TFPGObjectList.FreeObjects` (698) is set to `True`) then the previous object at position `Index` is freed when setting the property.

Errors: If an invalid index is used, an `EListError` (669) exception is raised.

See also: `TFPSList.Count` (704), `TFPGObjectList.FreeObjects` (698)

51.11.16 TFPGObjectList.List

Synopsis: Internal list pointer

Declaration: `Property List : PTypeList`

Visibility: public

Access: Read

Description: `List` is the internal list of objects. It should not be used directly.

See also: `TFPGObjectList.Items` (697)

51.11.17 TFPGObjectList.FreeObjects

Synopsis: Does the list own the objects or not?

Declaration: `Property FreeObjects : Boolean`

Visibility: public

Access: Read,Write

Description: `FreeObjects` indicates whether the list owns the objects or not. If set to `True`, freeing or clearing the list will remove all objects from memory by calling the destructor. Deleting or removing an item from the list will also dispose of the element.

The initial value for this property is set in the constructor and is `True` by default.

See also: `TFPGObjectList.FreeObjects` (698)

51.12 TFPSList

51.12.1 Description

`TFPSList` can be seen as the generalized equivalent of the classes unit `TFPList` (668) list. It is used as a base class for the `TFPGList` (673), `TFPGMap` (678), `TFPGObjectList` (694), `TFPGInterfaceObjectList` (669) and `TFPGMapInterfacedObjectData` (683) generic classes.

This list is not meant to be used directly, it is an auxiliary class for the actual generic list classes.

See also: `classes.TFPList` (668), `TFPGMap` (678), `TFPGObjectList` (694), `TFPGInterfacedObjectList` (669), `TFPGMapInterfacedObjectData` (683)

51.12.2 Method overview

Page	Method	Description
700	Add	Add a new item to the list
702	Assign	Copy one list to another
700	Clear	Clear the list
699	Create	Create a new instance of <code>TFPSList</code>
700	Delete	Delete an item from the list
699	Destroy	Destroy the list instance.
700	Error	Raise an <code>EListError</code> exception.
701	Exchange	Exchange two items in the list
701	Expand	Expand the capacity of the list
701	Extract	delete an element from the list
701	IndexOf	Search an item in the list
702	Insert	Insert a new item in the list.
702	Move	Moves an item from one position in the list to another.
703	Pack	Remove empty items from the list
703	Remove	Remove the item from the list
703	Sort	Sort the list

51.12.3 Property overview

Page	Properties	Access	Description
704	Capacity	rw	Current capacity of the list
704	Count	rw	Current element count
705	First	rw	Pointer to first non-empty item in the list
704	Items	rw	Items in the list
705	ItemSize	r	Size of the items in the list
705	Last	rw	Pointer to last non-empty item in the list
705	List	r	Internal list pointer

51.12.4 TFPSList.Create

Synopsis: Create a new instance of `TFPSList`

Declaration: `constructor Create(AItemSize: Integer)`

Visibility: `public`

Description: `Create` creates a new instance of `TFPSList`, and initializes the item size to `ItemSize`, which defaults to the size of a pointer.

See also: `TFPSList.ItemSize` ([705](#)), `TFPSList.Destroy` ([699](#))

51.12.5 TFPSList.Destroy

Synopsis: Destroy the list instance.

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` clears and cleans up the list instance. Depending on the descendant, this may also remove the items in the list from memory.

See also: `TFPSList.Clear` ([700](#))

51.12.6 TFPSList.Add

Synopsis: Add a new item to the list

Declaration: `function Add(Item: Pointer) : Integer`

Visibility: `public`

Description: `Add` adds the item pointed to by `Item` to the list. It is not the pointer `Item` itself which is added to the list, but rather the `TFPSList.ItemSize` (705) bytes of memory to which `Item` is pointing.

The function returns the index of the newly added item.

Errors: If the maximum list size is reached, an `EListError` (669) is raised.

See also: `TFPSList.Delete` (700), `TFPSList.Items` (704), `TFPSList.Clear` (700)

51.12.7 TFPSList.Clear

Synopsis: Clear the list

Declaration: `procedure Clear`

Visibility: `public`

Description: `Clear` removes all the items in the list. Depending on the descendent, the list items themselves may be cleared as well.

See also: `TFPSList.Delete` (700), `TFPSList.Items` (704), `TFPSList.Add` (700)

51.12.8 TFPSList.Delete

Synopsis: Delete an item from the list

Declaration: `procedure Delete(Index: Integer)`

Visibility: `public`

Description: `Delete` deletes the item at position `Index` from the list. Depending on the descendent, the list items itself may be cleared as well.

Errors: If `Index` is out of bounds, an `EListError` (669) exception is raised.

See also: `TFPSList.Clear` (700), `TFPSList.Items` (704), `TFPSList.Add` (700)

51.12.9 TFPSList.Error

Synopsis: Raise an `EListError` exception.

Declaration: `class procedure Error(const Msg: string; Data: PtrInt)`

Visibility: `public`

Description: `Error` is an auxiliary routine which raises an `EListError` (669) exception formatted from `Msg` and `Data`.

See also: `EListError` (669)

51.12.10 TFPSList.Exchange

Synopsis: Exchange two items in the list

Declaration: `procedure Exchange (Index1: Integer; Index2: Integer)`

Visibility: public

Description: `Exchange` will exchange 2 items at positions `Index1` and `Index2` in the list.

Errors: If `Index1` or `Index2` are out of bounds, an `EListError` (669) exception is raised.

51.12.11 TFPSList.Expand

Synopsis: Expand the capacity of the list

Declaration: `function Expand : TFPSList`

Visibility: public

Description: `Expand` will expand the capacity of the list, and returns itself.

Errors: If the size will become larger than `MaxListSize` (668) an `EListError` (669) exception will be raised.

See also: `MaxListSize` (668), `TFPSList.Capacity` (704)

51.12.12 TFPSList.Extract

Synopsis: delete an element from the list

Declaration: `procedure Extract (Item: Pointer; ResultPtr: Pointer)`

Visibility: public

Description: `Extract` removes the item pointed to by `Item` from the list. It returns a pointer to the actually removed item from the list. The item is searched using `TFPSList.IndexOf` (701). If the item is not found, `nil` is returned.

Some descendants own the items in the list. `Extract` will not dispose of the item, as `TFPSList.Delete` (700) does.

Errors: None.

See also: `TFPSList.Delete` (700), `TFPSList.Add` (700), `TFPSList.IndexOf` (701)

51.12.13 TFPSList.IndexOf

Synopsis: Search an item in the list

Declaration: `function IndexOf (Item: Pointer) : Integer`

Visibility: public

Description: `IndexOf` searches in the list for the item pointed to by `Item`, and returns the position (0-based index) of the item in the list, or -1 if it was not found. The items are compared using `system.CompareMem` (668), so an exact memory layout match.

See also: `TFPSList.Extract` (701)

51.12.14 TFPSList.Insert

Synopsis: Insert a new item in the list.

Declaration: `procedure Insert (Index: Integer; Item: Pointer)`
`function Insert (Index: Integer) : Pointer`

Visibility: public

Description: `Insert` comes in 2 overloaded version. The version without `Item` creates a slot for a new item at position `Index` in the list, and returns a pointer to the new slot. The slot will be of size `TFPSList.ItemSize` (705).

The version with `Item` argument will allocate a slot in the list at position `Index` and will copy the item pointed to by `Item` to the slot in the list.

In both cases, `Index` must be 0-based.

Errors: If `Index` is invalid, an `EListError` (669) exception will be raised.

See also: `TFPSList.Add` (700), `TFPSList.Delete` (700), `TFPSList.Extract` (701)

51.12.15 TFPSList.Move

Synopsis: Moves an item from one position in the list to another.

Declaration: `procedure Move (CurIndex: Integer; NewIndex: Integer)`

Visibility: public

Description: `Move` moves the item at position `CurIndex` to position `NewIndex`. This is done by storing the value at position `CurIndex`, deleting the pointer at position `CurIndex`, and reinserting the value at position `NewIndex`.

Errors: If `CurIndex` or `Newindex` are not inside the valid range of indices, an `EListError` (669) exception is raised.

See also: `Exchange` (701)

51.12.16 TFPSList.Assign

Synopsis: Copy one list to another

Declaration: `procedure Assign (Obj: TFPSList)`

Visibility: public

Description: `Assign` clears the list and will add all items from `Obj` to the list. The items are copied one by one.

Errors: If the `TFPSList.ItemSize` (705) differs for the two lists, an `EListError` (669) exception is raised.

See also: `TFPSList.Add` (700)

51.12.17 TFPSList.Remove

Synopsis: Remove the item from the list

Declaration: `function Remove(Item: Pointer) : Integer`

Visibility: `public`

Description: `Remove` searches `Item` in the list, and deletes it from the list. It returns the index of the item that was removed, or -1 if it was not found. Only the first match is removed.

If a descendent of `TFPSList` owns the object of the list, the item is removed from memory. If this is not desired, then `TFPSList.Extract (701)` must be used instead.

See also: `TFPSList.Extract (701)`, `TFPSList.IndexOf (701)`

51.12.18 TFPSList.Pack

Synopsis: Remove empty items from the list

Declaration: `procedure Pack`

Visibility: `public`

Description: `Pack` will remove all empty items from the list. An item is considered to be empty if the memory location where the item is stored contains only zero bytes.

See also: `TFPSList.Clear (700)`, `TFPSList.Sort (703)`

51.12.19 TFPSList.Sort

Synopsis: Sort the list

Declaration: `procedure Sort(Compare: TFPSListCompareFunc)`

Visibility: `public`

Description: `Sort`> sorts the items in the list. Two pointers are compared by passing them to the `Compare` function. The result of this function determines how the pointers will be sorted:

- If the result of this function is negative, the first item is assumed to be 'less' than the second and will be moved before the second item in the list.
- If the function result is positive, the first item is assumed to be 'greater than' the second and will be moved after the second item in the list.
- If the function result is zero, the pointers are assumed to be 'equal' and no moving will take place.

The sort is done using a quicksort algorithm.

See also: `TFPSListCompareFunc (668)`

51.12.20 TFPSList.Capacity

Synopsis: Current capacity of the list

Declaration: `Property Capacity : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Capacity` is the current capacity (maximum amount of elements) of the list. The list capacity will expand automatically if an item is added and the capacity is reached (i.e. `TFPSList.Count` (704) equals `capacity`). Expanding the list is an expensive operation involving reallocation of memory and moving of list data in memort, so capacity can be set to a large amount to avoid frequent reallocations.

See also: `TFPSList.Count` (704), `TFPSList.Expand` (701), `TFPSList.Items` (704)

51.12.21 TFPSList.Count

Synopsis: Current element count

Declaration: `Property Count : Integer`

Visibility: `public`

Access: `Read,Write`

Description: `Count` is the current amount of elements in the list. It is initially zero. A valid item index is always a value between zero and `Count-1`.

See also: `TFPSList.Items` (704), `TFPSList.Capacity` (704)

51.12.22 TFPSList.Items

Synopsis: Items in the list

Declaration: `Property Items[Index: Integer]: Pointer; default`

Visibility: `public`

Access: `Read,Write`

Description: `Items` provides indexed access to the items in the list, the returned pointers are not the actual list items, but pointers to the elements in the list. The items can be get or set.

When assigning to the `Items` property, the memory area pointed to by the assigned pointer is copied to the list. Exactly `TFPSList.ItemSize` (705) bytes are copied.

The index `Index` is zero based, and has a maximum value of `Count-1` (704).

Errors: If an invalid index is used, an `EListError` (669) exception is raised.

See also: `TFPSList.ItemSize` (705), `TFPSList.Count` (704)

51.12.23 TFPSList.ItemSize

Synopsis: Size of the items in the list

Declaration: `Property ItemSize : Integer`

Visibility: public

Access: Read

Description: `ItemSize` is the memory size of the items in the list. It is specified in the constructor and cannot be changed during the lifetime of the list.

See also: `TFPSList.Create` ([699](#))

51.12.24 TFPSList.List

Synopsis: Internal list pointer

Declaration: `Property List : PByte`

Visibility: public

Access: Read

Description: `List` is a pointer to the memory area used for the items in the list. It should not be manipulated.

51.12.25 TFPSList.First

Synopsis: Pointer to first non-empty item in the list

Declaration: `Property First : Pointer`

Visibility: public

Access: Read, Write

Description: `First` returns the value of the first non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` ([705](#)) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` ([705](#)), `TFPSList.Pack` ([703](#))

51.12.26 TFPSList.Last

Synopsis: Pointer to last non-empty item in the list

Declaration: `Property Last : Pointer`

Visibility: public

Access: Read, Write

Description: `Last` returns the value of the last non-empty item in the list. An item is considered empty if consists of `TFPSList.ItemSize` ([705](#)) zero bytes.

If there are no non-empty items in the list, then `Nil` is returned.

See also: `TFPSList.Last` ([705](#)), `TFPSList.Pack` ([703](#))

51.13 TFPSMap

51.13.1 Description

TFPSMap can be used to create a map for any type `T` that does not require reference counting (such as interfaced objects). It will specialize to a map which is a generalized list with an arbitrary type as the list index (called the key).

This class should normally not be used directly, instead use one of the generic map objects such as TFPGMap (678).

See also: TFPGMap (678)

51.13.2 Method overview

Page	Method	Description
707	Add	Add a key, value pair to the map.
706	Create	Create a new map with given key and data size.
707	Find	Find data using the associated key
707	IndexOf	Index of key pointed to by AKey
708	IndexOfData	Index of data item AData
708	Insert	Insert a new slot for key and associated data item in the list
708	InsertKey	Insert a key in the list
708	InsertKeyData	Insert a key and associated in the list
709	Remove	Remove a key/value pair from the map.
709	Sort	Sort the list according to key

51.13.3 Property overview

Page	Properties	Access	Description
710	Data	rw	Indexed access to the locations of all data items
710	DataSize	r	Size (in bytes) for the data associated with keys
709	Duplicates	rw	What to do with duplicate key values
711	KeyData	rw	Access to data locations using key
710	Keys	rw	Indexed access to the locations of all keys
710	KeySize	r	Size (in bytes) for the key
712	OnDataPtrCompare	rw	Callback to compare 2 data items
711	OnKeyPtrCompare	rw	Callback to compare 2 keys
711	OnPtrCompare	rw	Alias for OnKeyPtrCompare
711	Sorted	rw	Is the map permanently sorted on key ?

51.13.4 TFPSMap.Create

Synopsis: Create a new map with given key and data size.

Declaration: `constructor Create(AKeySize: Integer; ADataSize: Integer)`

Visibility: `public`

Description: `Create` instantiates a new TFPSMap instance and initializes TFPSMap.KeySize (710) and TFPSMap.DataSize (710) with `AKeySize` and `ADataSize`, respectively. It also initializes the TFPSMap.OnDataPtrCompare (712) and TFPSMap.OnKeyPtrCompare (711) properties to functions that compare memory blocks.

Errors: None.

See also: [TFPSMap.Destroy \(706\)](#), [TFPSMap.KeySize \(710\)](#), [TFPSMap.DataSize \(710\)](#), [TFPSMap.OnDataPtrCompare \(712\)](#), [TFPSMap.OnKeyPtrCompare \(711\)](#)

51.13.5 TFPSMap.Add

Synopsis: Add a key, value pair to the map.

Declaration: `function Add(AKey: Pointer; AData: Pointer) : Integer`
`function Add(AKey: Pointer) : Integer`

Visibility: public

Description: `Add` adds the memory pointed to by `AData` to the map using the memory pointed to by `AKey` as the key. If no data is specified, it allocates a slot for `AKey` and returns a pointer to that slot.

Errors: If the maximum amount of values is reached, `Add` will raise an `EListError (669)` exception.

See also: [TFPSMap.Insert \(708\)](#), [TFPSMap.IndexOf \(707\)](#)

51.13.6 TFPSMap.Find

Synopsis: Find data using the associated key

Declaration: `function Find(AKey: Pointer; out Index: Integer) : Boolean`

Visibility: public

Description: `Find` searches for the first key less than or equal to `AKey` and returns its index in the list in `Index`. It returns `True` if an exact match for the key was found. It returns `False` if the key was not found, and `Index` is then set to `-1`.

This function performs a binary search using the key comparing function specified in `OnKeyPtrCompare (711)`.

Errors: if `OnKeyPtrCompare` is not set, an access violation will occur.

See also: [TFPSMap.OnKeyPtrCompare \(711\)](#)

51.13.7 TFPSMap.IndexOf

Synopsis: Index of key pointed to by `AKey`

Declaration: `function IndexOf(AKey: Pointer) : Integer`

Visibility: public

Description: `IndexOf` returns the index of the element with a key pointed to by `AKey`. It returns `-1` if the key was not found.

If the list is sorted, then a binary search is performed, otherwise a linear search is used to find the key.

Errors: None.

See also: [TFPSMap.Find \(707\)](#), [TFPSMap.IndexOfData \(708\)](#), [TFPSMap.Keys \(710\)](#), [TFPSMap.Data \(710\)](#)

51.13.8 TFPSMap.IndexOfData

Synopsis: Index of data item AData

Declaration: `function IndexOfData (AData: Pointer) : Integer`

Visibility: public

Description: `IndexOfData` returns the index of the element with data pointed to by AData. It returns -1 if the data item was not found. The search is always performed using a linear search.

See also: `TFPSMap.Find` (707), `TFPSMap.IndexOf` (707), `TFPSMap.Keys` (710), `TFPSMap.Data` (710)

51.13.9 TFPSMap.Insert

Synopsis: Insert a new slot for key and associated data item in the list

Declaration: `function Insert (Index: Integer) : Pointer`
`procedure Insert (Index: Integer; out AKey: Pointer; out AData: Pointer)`

Visibility: public

Description: `Insert` will allocate a new slot in the list. It returns a pointer to the new slot. If AKey and AData are given, then they will point to the positions in the slot for the key and data items.

Errors: If the maximum amount of values is reached or an invalid index is specified, `Insert` will raise an `EListError` (669) exception.

See also: `TFPSMap.Add` (707), `TFPSMap.InsertKey` (708), `TFPSMap.InsertKeyData` (708)

51.13.10 TFPSMap.InsertKey

Synopsis: Insert a key in the list

Declaration: `procedure InsertKey (Index: Integer; AKey: Pointer)`

Visibility: public

Description: `InsertKey` will allocate a new slot in the list for a key value as pointed to by AKey, and copy the key pointed to by AKey to the slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKey` will raise an `EListError` (669) exception.

See also: `TFPSMap.Add` (707), `TFPSMap.Insert` (708), `TFPSMap.InsertKeyData` (708)

51.13.11 TFPSMap.InsertKeyData

Synopsis: Insert a key and associated in the list

Declaration: `procedure InsertKeyData (Index: Integer; AKey: Pointer; AData: Pointer)`

Visibility: public

Description: `InsertKeyData` will allocate a new slot in the list for a key value as pointed to by AKey, and copy the key pointed to by AKey as well as the data pointed to by AData to the newly allocated slot.

Errors: If the maximum amount of values is reached or an invalid index is specified, `InsertKeyData` will raise an `EListError` (669) exception.

See also: `TFPSMap.Add` (707), `TFPSMap.Insert` (708), `TFPSMap.InsertKey` (708)

51.13.12 TFPSMap.Remove

Synopsis: Remove a key/value pair from the map.

Declaration: `function Remove(AKey: Pointer) : Integer`

Visibility: `public`

Description: `Remove` removes the key/value pair pointing to by `AKey` from the map. It returns the index of `Akey` prior to removal from the list. If `AKey` was not found, -1 is returned.

Errors: None.

See also: `TFPSList.Delete` (700), `TFPSMap.IndexOf` (707)

51.13.13 TFPSMap.Sort

Synopsis: Sort the list according to key

Declaration: `procedure Sort`

Visibility: `public`

Description: `Sort` sorts the list according to the key value, using the compare function provided in `TFPSMap.OnKeyPtrCompare` (711)

Errors: None.

See also: `TFPSMap.OnKeyPtrCompare` (711), `TFPSMap.OnDataPtrCompare` (712)

51.13.14 TFPSMap.Duplicates

Synopsis: What to do with duplicate key values

Declaration: `Property Duplicates : TDuplicates`

Visibility: `public`

Access: Read,Write

Description: `Duplicates` can be set to determine what to do with duplicate key values in the map:

dupIgnoreIgnore the new item, do not add it to the list.

dupAcceptAccept duplicates, adding them to the list.

dupErrorRaise an error when an attempt is made to add a duplicate.

The value is ignored if `Sorted` (711) is `False`.

See also: `TFPSMap.Sorted` (711), `types.TDuplicates` (668)

51.13.15 TFPSMap.KeySize

Synopsis: Size (in bytes) for the key

Declaration: `Property KeySize : Integer`

Visibility: `public`

Access: `Read`

Description: `KeySize` is the size (in bytes) for the keys in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (706), `TFPSMap.DataSize` (710), `TFPSMap.Keys` (710), `TFPSMap.KeyData` (711)

51.13.16 TFPSMap.DataSize

Synopsis: Size (in bytes) for the data associated with keys

Declaration: `Property DataSize : Integer`

Visibility: `public`

Access: `Read`

Description: `DataSize` is the size (in bytes) for the data in the map. This size is initialized during list construction and defaults to the size of a pointer.

See also: `TFPSMap.Create` (706), `TFPSMap.KeySize` (710), `TFPSMap.Keys` (710), `TFPSMap.KeyData` (711), `TFPSMap.Data` (710)

51.13.17 TFPSMap.Keys

Synopsis: Indexed access to the locations of all keys

Declaration: `Property Keys[Index: Integer]: Pointer`

Visibility: `public`

Access: `Read,Write`

Description: `Keys` provides indexed access to all keys. It does not return the key, but returns a pointer to the key value. When setting the `Keys` property, a pointer to the key value must be set, and the key value is copied from the pointer.

See also: `TFPSMap.KeySize` (710), `TFPSMap.KeyData` (711), `TFPSMap.Data` (710)

51.13.18 TFPSMap.Data

Synopsis: Indexed access to the locations of all data items

Declaration: `Property Data[Index: Integer]: Pointer`

Visibility: `public`

Access: `Read,Write`

Description: `Data` provides indexed access to all data. It does not return the actual data, but returns a pointer to the data. When setting the `Data` property, a pointer to the data value must be set, and the data value is copied from the pointer.

See also: `TFPSMap.DataSize` (710), `TFPSMap.KeyData` (711), `TFPSMap.Keys` (710)

51.13.19 TFPSMap.KeyData

Synopsis: Access to data locations using key

Declaration: `Property KeyData[Key: Pointer]: Pointer; default`

Visibility: public

Access: Read,Write

Description: `KeyData` provides access to the data items, using their key value (as pointed to by `AKey`) as an index. When reading a non-existent key value, `Nil` is returned. If the key is found, a pointer to the associated data's location is returned. When writing, the key pointed to by `Key` is added if it was not present, and the data data is copied from the written pointer.

See also: `TFPSMap.DataSize` (710), `TFPSMap.KeyData` (711), `TFPSMap.Data` (710), `TFPSMap.Keys` (710), `TFPSMap.KeySize` (710)

51.13.20 TFPSMap.Sorted

Synopsis: Is the map permanently sorted on key ?

Declaration: `Property Sorted : Boolean`

Visibility: public

Access: Read,Write

Description: `Sorted` can be set to true to keep the map permanently sorted on key value. The sorting happens using `TFPSMap.OnKeyPtrCompare` (711).

See also: `TFPSMap.OnKeyPtrCompare` (711), `TFPSMap.Sort` (709), `TFPSMap.Duplicates` (709)

51.13.21 TFPSMap.OnPtrCompare

Synopsis: Alias for `OnKeyPtrCompare`

Declaration: `Property OnPtrCompare : TFPSListCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnPtrCompare` is a deprecated alias for `OnKeyPtrCompare` (711).

See also: `TFPSMap.OnKeyPtrCompare` (711), `TFPSMap.OnDataPtrCompare` (712)

51.13.22 TFPSMap.OnKeyPtrCompare

Synopsis: Callback to compare 2 keys

Declaration: `Property OnKeyPtrCompare : TFPSListCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyPtrCompare` is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to sort the list or find a key.

See also: `TFPSListCompareFunc` (668), `TFPSMap.OnDataPtrCompare` (712), `TFPSMap.Sort` (709), `TFPSMap.Find` (707), `TFPSMap.IndexOf` (707)

51.13.23 TFPSMap.OnDataPtrCompare

Synopsis: Callback to compare 2 data items

Declaration: `Property OnDataPtrCompare : TFPSListCompareFunc`

Visibility: public

Access: Read,Write

Description: `OnKeyPtrCompare` is used to compare the values of 2 keys. By default it simply compares the byte values of the key memory block. It can be set to any function that performs another comparison. (e.g. a function that treats the memory blocks as a string pointer and compare the actual strings).

This function is used to find a data item (`IndexOf` (708)).

See also: `TFPSListCompareFunc` (668), `TFPSMap.OnKeyPtrCompare` (711), `TFPSMap.IndexOfData` (708)

Chapter 52

Reference for unit 'fpwiderstring'

52.1 Used units

Table 52.1: Used units by unit 'fpwiderstring'

Name	Page
System	1194
unicodedata	1807

52.2 Overview

`fpwiderstring` implements unicode string support for the Free Pascal RTL using native Object Pascal routines. It is meant to be used on operating systems where the operating system does not natively support Unicode transformations and operations.

In general, it is sufficient to include the unit in the uses clause of a program. The initialization code of the unit will set the unicode string manager of the system unit to the object pascal implementation contained in this unit.

This unit needs unicode collation and character set tables in order to be able to do its work correctly. These must be registered using the routines of the `unicodedata` ([713](#)) unit: the FPC project distributes some unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([1816](#)) routine.

In order for sorting and comparing of strings to work, a collation must be used. The collation in general depends on the internationalization of the application. Since the system unit does not know about collations, the collation must be set in the `fpWideString` unit using the `SetActiveCollation` ([714](#)) function. The collation can be set on a per-thread basis.

New threads get `DefaultCollationName` ([714](#)) as the active collation name.

The `fpwiderstring` unit performs conversions between unicode and single-byte ansistring conversions (excluding UTF8). Support for various single-byte encodings are based on the `charset` ([713](#)) unit. This unit can be used to load single byte code pages. Various code page units such as `cp895`, `cp932`, `cp950` are provided by the "rtl-unicode" package.

The `fpwiderstring` requires at least the Default Unicode Collation Element Table to be registered (called `DUCET`). The `DUCET` encoding is provided by the `unicodeducet` unit. More information can be found in the `unicodedata` ([713](#)) unit.

52.3 Constants, types and variables

52.3.1 Variables

`DefaultCollationName` : `TCollationName` = ''

`DefaultCollationName` is the collation name for new threads. It is empty by default.

52.4 Procedures and functions

52.4.1 GetActiveCollation

Synopsis: Return the currently active collation for the current thread

Declaration: `function GetActiveCollation : PUCA_DataBook`

Visibility: default

Description: `GetActiveCollation` returns the currently active collation, for the current thread, as set using the `SetActiveCollation` (714) function.

New threads get `DefaultCollationName` (714) as the active collation name. The collation can be changed per thread using the `SetActiveCollation` (714) function.

Errors: None.

See also: `SetActiveCollation` (714), `DefaultCollationName` (714)

52.4.2 SetActiveCollation

Synopsis: Set the active collation for the current thread.

Declaration: `function SetActiveCollation(const AName: TCollationName) : Boolean`
`function SetActiveCollation(const ACollation: PUCA_DataBook) : Boolean`

Visibility: default

Description: `SetActiveCollation` sets the collation used in the current thread of the application. This can be done using the name of the collation (`AName`) as registered or in the `unicodedata` (713) unit or using the actual collation data (`ACollation`).

Errors: If the collation `AName` was not found, or `ACollation` is nil, then `False` is returned.

See also: `GetActiveCollation` (714), `DefaultCollationName` (714)

Chapter 53

Reference for unit 'getopts'

53.1 Used units

Table 53.1: Used units by unit 'getopts'

Name	Page
System	1194

53.2 Overview

This document describes the GETOPTS unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It now also works for all supported platforms.

The getopts unit provides a mechanism to handle command-line options in a structured way, much like the GNU getopts mechanism. It allows you to define the valid options for your program, and the unit will then parse the command-line options for you, and inform you of any errors.

53.3 Constants, types and variables

53.3.1 Constants

`EndOfOptions = #255`

Returned by `getopt` ([717](#)), `getlongopts` ([717](#)) to indicate that there are no more options.

`No_Argument = 0`

Specifies that a long option does not take an argument.

`Optional_Argument = 2`

Specifies that a long option optionally takes an argument.

`OptSpecifier : Set of Char = ['-',']`

Character indicating an option on the command-line.

`Required_Argument = 1`

Specifies that a long option needs an argument.

53.3.2 Types

`Orderings = (require_order, permute, return_in_order)`

Table 53.2: Enumeration values for type `Orderings`

Value	Explanation
<code>permute</code>	Change command-line options.
<code>require_order</code>	Don't touch the ordering of the command-line options
<code>return_in_order</code>	Return options in the correct order.

Command-line ordering options.

`POption = ^TOption`

Pointer to `TOption` (716) record.

```
TOption = record
  Name : string;
  Has_arg : Integer;
  Flag : PChar
;
  Value : Char;
end
```

The `TOption` type is used to communicate the long options to `GetLongOpts` (717). The `Name` field is the name of the option. `Has_arg` specifies if the option wants an argument, `Flag` is a pointer to a char, which is set to `Value`, if it is non-nil.

53.3.3 Variables

`OptArg : string`

Set to the argument of an option, if the option needs one.

`OptErr : Boolean`

Indicates whether `getopt()` prints error messages.

`OptInd : LongInt`

when all options have been processed, `optind` is the index of the first non-option parameter. This is a read-only variable. Note that it can become equal to `paramcount+1`.

`OptOpt : Char`

In case of an error, contains the character causing the error.

53.4 Procedures and functions

53.4.1 GetLongOpts

Synopsis: Return next long option.

Declaration: `function GetLongOpts (ShortOpts: string; LongOpts: POption;
var Longind: LongInt) : Char`

Visibility: default

Description: Returns the next option found on the command-line, taking into account long options as well. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

if any of the option definitions in `LongOpts` array has the `Flag` pointer set, then the return value is the null character (`#0` or `char(0)`) and the actual option letter is written in the location pointed to by `Flag`.

`ShortOptions` is a string containing all possible one-letter options. (see [Getopt \(717\)](#) for its description and use) `LongOpts` is a pointer to the first element of an array of `Option` records, the last of which needs a name of zero length.

The function tries to match the names even partially (i.e. `-app` will match e.g. the append option), but will report an error in case of ambiguity.

If the option needs an argument, set `Has_arg` to `Required_argument` (1), if the option optionally has an argument, set `Has_arg` to `Optional_argument` (2). If the option needs no argument, set `Has_arg` to zero.

Required arguments can be specified in two ways :

1. Pasted to the option : `-option=value`
2. As a separate argument : `-option value`

Optional arguments can only be specified through the first method.

Errors: see [Getopt \(717\)](#).

See also: [Getopt \(717\)](#)

53.4.2 GetOpt

Synopsis: Get next short option.

Declaration: `function GetOpt (ShortOpts: string) : Char`

Visibility: default

Description: Returns the next option found on the command-line. If no more options are found, returns `EndOfOptions`. If the option requires an argument, it is returned in the `OptArg` variable.

`ShortOptions` is a string containing all possible one-letter options. If a letter is followed by a colon (:), then that option needs an argument. If a letter is followed by 2 colons, the option has an optional argument. If the first character of `shortoptions` is a '+' then options following a non-option are regarded as non-options (standard Unix behavior). If it is a '-', then all non-options are treated as arguments of a option with character `#0`. This is useful for applications that require their options in the exact order as they appear on the command-line. If the first character of `shortoptions` is none of the above, options and non-options are permuted, so all non-options are behind all options. This allows options and non-options to be in random order on the command line.

Errors: Errors are reported through giving back a '?' character. OptOpt then gives the character which caused the error. If OptErr is True then getopt prints an error-message to stdout.

See also: GetLongOpts (717)

Listing: ./optex/optex.pp

```

program testopt;

{ Program to depmonstrate the getopt function. }

{
  Valid calls to this program are
  optex —verbose —add me —delete you
  optex —append —create child
  optex -ab -c me -d you
  and so on
}
uses getopt;

var c : char;
    optionindex : Longint;
    theopts : array[1..7] of TOption;

begin
  with theopts[1] do
    begin
      name:= 'add';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[2] do
    begin
      name:= 'append';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[3] do
    begin
      name:= 'delete';
      has_arg:=1;
      flag:= nil;
      value:=#0;
    end;
  with theopts[4] do
    begin
      name:= 'verbose';
      has_arg:=0;
      flag:= nil;
      value:=#0;
    end;
  with theopts[5] do
    begin
      name:= 'create';
      has_arg:=1;
      flag:= nil;
      value:= 'c'

```

```

end;
with theopts[6] do
begin
  name:= 'file';
  has_arg:=1;
  flag:=nil;
  value:=#0;
end;
with theopts[7] do
begin
  name:= '';
  has_arg:=0;
  flag:=nil;
end;
c:=#0;
repeat
  c:=getlongopts('abc:d:012',@theargs[1],optionindex);
  case c of
    '1','2','3','4','5','6','7','8','9' :
      begin
        writeln('Got optind : ',c)
      end;
    #0 : begin
      write('Long option : ',theargs[optionindex].name);
      if theargs[optionindex].has_arg>0 then
        writeln(' With value : ',optarg)
      else
        writeln
      end;
    'a' : writeln('Option a. ');
    'b' : writeln('Option b. ');
    'c' : writeln('Option c : ', optarg);
    'd' : writeln('Option d : ', optarg);
    '?' : writeln('Error with opt : ',optopt);
  end; { case }
until c=endofoptions;
if optind<=paramcount then
begin
  write('Non options : ');
  while optind<=paramcount do
  begin
    write(paramstr(optind), ' ');
    inc(optind)
  end;
  writeln
end
end.

```

Chapter 54

Reference for unit 'go32'

54.1 Used units

Table 54.1: Used units by unit 'go32'

Name	Page
System	1194

54.2 Overview

This document describes the GO32 unit for the Free Pascal compiler under dos. It was donated by Thomas Schatzl (tom_at_work@geocities.com), for which my thanks. This unit was first written for dos by Florian Klaempfl.

Only the GO32V2 DPMI mode is discussed by me here due to the fact that new applications shouldn't be created with the older GO32V1 model. The go32v2 version is much more advanced and better. Additionally a lot of functions only work in DPMI mode anyway. I hope the following explanations and introductions aren't too confusing at all. If you notice an error or bug send it to the FPC mailing list or directly to me. So let's get started and happy and error free coding I wish you.... Thomas Schatzl, 25. August 1998

54.3 Real mode callbacks

The callback mechanism can be thought of as the converse of calling a real mode procedure (i.e. interrupt), which allows your program to pass information to a real mode program, or obtain services from it in a manner that's transparent to the real mode program. In order to make a real mode callback available, you must first get the real mode callback address of your procedure and the selector and offset of a register data structure. This real mode callback address (this is a segment:offset address) can be passed to a real mode program via a software interrupt, a dos memory block or any other convenient mechanism. When the real mode program calls the callback (via a far call), the DPMI host saves the registers contents in the supplied register data structure, switches into protected mode, and enters the callback routine with the following settings:

- interrupts disabled

- `%CS : %EIP` = 48 bit pointer specified in the original call to `get_rm_callback` (747)
- `%DS : %ESI` = 48 bit pointer to real mode `SS : SP`
- `%ES : %EDI` = 48 bit pointer of real mode register data structure.
- `%SS : %ESP` = locked protected mode stack
- All other registers undefined

The callback procedure can then extract its parameters from the real mode register data structure and/or copy parameters from the real mode stack to the protected mode stack. Recall that the segment register fields of the real mode register data structure contain segment or paragraph addresses that are not valid in protected mode. Far pointers passed in the real mode register data structure must be translated to virtual addresses before they can be used with a protected mode program. The callback procedure exits by executing an `IRET` with the address of the real mode register data structure in `%ES : %EDI`, passing information back to the real mode caller by modifying the contents of the real mode register data structure and/or manipulating the contents of the real mode stack. The callback procedure is responsible for setting the proper address for resumption of real mode execution into the real mode register data structure; typically, this is accomplished by extracting the return address from the real mode stack and placing it into the `%CS : %EIP` fields of the real mode register data structure. After the `IRET`, the DPMI host switches the CPU back into real mode, loads ALL registers with the contents of the real mode register data structure, and finally returns control to the real mode program. All variables and code touched by the callback procedure **MUST** be locked to prevent page faults.

See also: `get_rm_callback` (747), `free_rm_callback` (742), `lock_code` (758), `lock_data` (758)

54.4 Executing software interrupts

Simply execute a `realintr()` call with the desired interrupt number and the supplied register data structure. But some of these interrupts require you to supply them a pointer to a buffer where they can store data to or obtain data from in memory. These interrupts are real mode functions and so they only can access the first Mb of linear address space, not FPC's data segment. For this reason FPC supplies a pre-initialized dos memory location within the GO32 unit. This buffer is internally used for dos functions too and so it's contents may change when calling other procedures. It's size can be obtained with `tb_size` (768) and it's linear address via `transfer_buffer` (769). Another way is to allocate a completely new dos memory area via the `global_dos_alloc` (754) function for your use and supply its real mode address.

See also: `tb_size` (768), `transfer_buffer` (769), `global_dos_alloc` (754), `global_dos_free` (756), `realintr` (760)

Listing: `./go32ex/softint.pp`

```
{ Executes a real mode software interrupt

Exactly the interrupt call to get the DOS version.

get DOS version Int 21h / function 30h
Input:
    AH = $30
    AL = $1
Return:
    AL = major version number
    AH = minor version number
}
```

```

uses
    go32;

var
    r : trealregs;

begin
    r.ah := $30;
    r.al := $01;
    realintr($21, r);
    WriteLn( 'DOS v', r.al, '.', r.ah, ' detected' );
end.

```

Listing: ./go32ex/rmpmint.pp

{ This example shows the difference between protected and real mode interrupts; it redirects the protected mode handler to an own handler which returns an impossible function result and calls it afterwards. Then the real mode handler is called directly, to show the difference between the two. }

Used Interrupt:
get DOS version Int 21h / function 30h
Input: AH = \$30
AL = \$1
Return: AL = major version number
AH = minor version number
}

```

uses
    crt ,
    go32;

var
    r : trealregs;
    { temporary variable used for the protected mode int call }
    axreg : Word;

    oldint21h : tseginfo;
    newint21h : tseginfo;

{ this is our int 21h protected mode interupt handler. It catches the function call to get the DOS version, all other int 21h calls are redirected to the old handler; it is written in assembly because the old handler can't be called with pascal }
procedure int21h_handler; assembler;
asm
    cmpw $0x3001, %ax
    jne .LCallOld
    movw $0x3112, %ax
    iret

.LCallOld:
    ljmp %cs:oldint21h
end;

{ a small helper procedure, which waits for a keypress }
procedure resume;

```

```

begin
    Writeln;
    Write('— press any key to resume —'); readkey;
    gotoxy(1, wherey); clreol;
end;

begin
    { see the text messages for further detail }
    clrscr;
    Writeln('Executing real mode interrupt');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    Writeln('Executing protected mode interrupt without our own',
            ' handler');
    Writeln;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    resume;
    Writeln('As you can see the DPML hosts default protected mode',
            ' handler');
    Writeln('simply redirects it to the real mode handler');
    resume;
    Writeln('Now exchanging the protected mode interrupt with our ',
            ' own handler');
    resume;

    newint21h.offset := @int21h_handler;
    newint21h.segment := get_cs;
    get_pm_interrupt($21, oldint21h);
    set_pm_interrupt($21, newint21h);

    Writeln('Executing real mode interrupt again');
    resume;
    r.ah := $30; r.al := $01; realintr($21, r);
    Writeln('DOS v', r.al, '.', r.ah, ' detected');
    Writeln;
    Writeln('See, it didn''t change in any way. ');
    resume;
    Writeln('Now calling protected mode interrupt');
    resume;
    asm
        movb $0x30, %ah
        movb $0x01, %al
        int $0x21
        movw %ax, axreg
    end;
    Writeln('DOS v', lo(axreg), '.', hi(axreg), ' detected');
    Writeln;
    Writeln('Now you can see that there''s a distinction between ',
            ' the two ways of calling interrupts... ');
    set_pm_interrupt($21, oldint21h);

```

end.

54.5 Software interrupts

Ordinarily, a handler installed with `set_pm_interrupt` (765) only services software interrupts that are executed in protected mode; real mode software interrupts can be redirected by `set_rm_interrupt` (767).

See also: `set_rm_interrupt` (767), `get_rm_interrupt` (751), `set_pm_interrupt` (765), `get_pm_interrupt` (746), `lock_data` (758), `lock_code` (758), `enable` (741), `disable` (739), `outportb` (759)

54.6 Hardware interrupts

Hardware interrupts are generated by hardware devices when something unusual happens; this could be a keypress or a mouse move or any other action. This is done to minimize CPU time, else the CPU would have to check all installed hardware for data in a big loop (this method is called 'polling') and this would take much time. A standard IBM-PC has two interrupt controllers, that are responsible for these hardware interrupts: both allow up to 8 different interrupt sources (IRQs, interrupt requests). The second controller is connected to the first through IRQ 2 for compatibility reasons, e.g. if controller 1 gets an IRQ 2, he hands the IRQ over to controller 2. Because of this up to 15 different hardware interrupt sources can be handled. IRQ 0 through IRQ 7 are mapped to interrupts 8h to Fh and the second controller (IRQ 8 to 15) is mapped to interrupt 70h to 77h. All of the code and data touched by these handlers MUST be locked (via the various locking functions) to avoid page faults at interrupt time. Because hardware interrupts are called (as in real mode) with interrupts disabled, the handler has to enable them before it returns to normal program execution. Additionally a hardware interrupt must send an EOI (end of interrupt) command to the responsible controller; this is accomplished by sending the value 20h to port 20h (for the first controller) or A0h (for the second controller). The following example shows how to redirect the keyboard interrupt.

Listing: ./go32ex/keyclick.pp

{ This example demonstrates how to chain to a hardware interrupt.

In more detail, it hooks the keyboard interrupt, calls a user procedure which in this case simply turns the PC speaker on and off. Then the old interrupt is called.

```
{ $ASMMODE ATT }
{ $MODE FPC }
```

uses

```
crt ,
go32;
```

const

```
{ keyboard is IRQ 1 -> interrupt 9 }
kbdint = $9;
```

var

```
{ holds old PM interrupt handler address }
oldint9_handler : tseginfo;
{ new PM interrupt handler }
```

```

newint9_handler : tseinfo;

{ pointer to interrupt handler }
clickproc : pointer;
{ the data segment selector }
backupDS : Word; external name '___v2prt0_ds_alias';

{ interrupt handler }
procedure int9_handler; assembler;
asm
    cli
    { save all registers, because we don't know which the compiler
      uses for the called procedure }
    pushl %ds
    pushl %es
    pushl %fs
    pushl %gs
    pushal
    { set up to call a FPC procedure }
    movw %cs:backupDS, %ax
    movw %ax, %ds
    movw %ax, %es
    movw dosmemselector, %ax
    movw %ax, %fs
    { call user procedure }
    call *clickproc
    { restore all registers }
    popal
    popl %gs
    popl %fs
    popl %es
    popl %ds
    { note: in go32v2 mode %cs=%ds=%es !!! }
    jmp %cs:oldint9_handler { call old handler }
    { we don't need to do anything more, because the old interrupt
      handler does this for us (send EOI command, iret, sti...) }
end;
{ dummy procedure to retrieve exact length of handler, for locking
  and unlocking functions }
procedure int9_dummy; begin end;

{ demo user procedure, simply clicks on every keypress }
procedure clicker;
begin
    sound(500); delay(10); nosound;
end;
{ dummy procedure to retrieve exact length of user procedure for
  locking and unlocking functions }
procedure clicker_dummy; begin end;

{ installs our new handler }
procedure install_click;
begin
    clickproc := @clicker;
    { lock used code and data }
    lock_data(clickproc, sizeof(clickproc));
    lock_data(dosmemselector, sizeof(dosmemselector));

```

```

    lock_code(@clicker ,
              longint(@clicker_dummy) - longint(@clicker));
    lock_code(@int9_handler ,
              longint(@int9_dummy)-longint(@int9_handler));
    { fill in new handler's 48 bit pointer }
    newint9_handler.offset := @int9_handler;
    newint9_handler.segment := get_cs;
    { get old PM interrupt handler }
    get_pm_interrupt(kbdint , oldint9_handler);
    { set the new interrupt handler }
    set_pm_interrupt(kbdint , newint9_handler);
end;

{ deinstalls our interrupt handler }
procedure remove_click;
begin
    { set old handler }
    set_pm_interrupt(kbdint , oldint9_handler);
    { unlock used code & data }
    unlock_data(dosmemselector , sizeof(dosmemselector));
    unlock_data(clickproc , sizeof(clickproc));

    unlock_code(@clicker ,
                longint(@clicker_dummy)-longint(@clicker));
    unlock_code(@int9_handler ,
                longint(@int9_dummy)-longint(@int9_handler));
end;

var
    ch : char;

begin
    install_click;
    Writeln('Enter any message. Press return when finished');
    while (ch <> #13) do begin
        ch := readkey; write(ch);
    end;
    remove_click;
end.

```

54.7 Disabling interrupts

The GO32 unit provides the two procedures `disable()` and `enable()` to disable and enable all interrupts.

54.8 Creating your own interrupt handlers

Interrupt redirection with FPC pascal is done via the `set_pm_interrupt()` for protected mode interrupts or via the `set_rm_interrupt()` for real mode interrupts.

54.9 Protected mode interrupts vs. Real mode interrupts

As mentioned before, there's a distinction between real mode interrupts and protected mode interrupts; the latter are protected mode programs, while the former must be real mode programs. To call a protected mode interrupt handler, an assembly 'int' call must be issued, while the other is called via the `realintr()` or `intr()` function. Consequently, a real mode interrupt then must either reside in dos memory (<1MB) or the application must allocate a real mode callback address via the `get_rm_callback()` function.

54.10 Handling interrupts with DPMI

The interrupt functions are real-mode procedures; they normally can't be called in protected mode without the risk of an protection fault. So the DPMI host creates an interrupt descriptor table for the application. Initially all software interrupts (except for int 31h, 2Fh and 21h function 4Ch) or external hardware interrupts are simply directed to a handler that reflects the interrupt in real-mode, i.e. the DPMI host's default handlers switch the CPU to real-mode, issue the interrupt and switch back to protected mode. The contents of general registers and flags are passed to the real mode handler and the modified registers and flags are returned to the protected mode handler. Segment registers and stack pointer are not passed between modes.

54.11 Interrupt redirection

Interrupts are program interruption requests, which in one or another way get to the processor; there's a distinction between software and hardware interrupts. The former are explicitly called by an 'int' instruction and are a bit comparable to normal functions. Hardware interrupts come from external devices like the keyboard or mouse. Functions that handle hardware interrupts are called handlers.

54.12 Processor access

These are some functions to access various segment registers (`%cs`, `%ds`, `%ss`) which makes your work a bit easier.

See also: `get_cs` ([742](#)), `get_ds` ([743](#)), `get_ss` ([753](#))

54.13 I/O port access

The I/O port access is done via the various `inportb` ([757](#)), `outportb` ([759](#)) functions which are available. Additionally Free Pascal supports the Turbo Pascal `PORT[]`-arrays but it is by no means recommended to use them, because they're only for compatibility purposes.

See also: `outportb` ([759](#)), `inportb` ([757](#))

54.14 dos memory access

Dos memory is accessed by the predefined `dosmemselector` selector; the GO32 unit additionally provides some functions to help you with standard tasks, like copying memory from heap to dos memory and the likes. Because of this it is strongly recommended to use them, but you are still free

to use the provided standard memory accessing functions which use 48 bit pointers. The third, but only thought for compatibility purposes, is using the `mem[]`-arrays. These arrays map the whole 1 Mb dos space. They shouldn't be used within new programs. To convert a segment:offset real mode address to a protected mode linear address you have to multiply the segment by 16 and add its offset. This linear address can be used in combination with the `DOSMEMSELECTOR` variable.

See also: [dosmemget \(729\)](#), [dosmempnt \(730\)](#), [dosmemmove \(730\)](#), [dosmemfillchar \(729\)](#), [dosmemfillword \(729\)](#), [seg_move \(764\)](#), [seg_fillchar \(762\)](#), [seg_fillword \(763\)](#)

54.15 FPC specialities

The `%ds` and `%es` selector MUST always contain the same value or some system routines may crash when called. The `%fs` selector is preloaded with the `DOSMEMSELECTOR` variable at startup, and it MUST be restored after use, because again FPC relies on this for some functions. Luckily we asm programmers can still use the `%gs` selector for our own purposes, but for how long ?

See also: [get_cs \(742\)](#), [get_ds \(743\)](#), [get_ss \(753\)](#), [allocate_ldt_descriptors \(735\)](#), [free_ldt_descriptor \(741\)](#), [segment_to_descriptor \(762\)](#), [get_next_selector_increment_value \(745\)](#), [get_segment_base_address \(753\)](#), [set_segment_base_address \(767\)](#), [set_segment_limit \(767\)](#), [create_code_segment_alias_descriptor \(739\)](#)

54.16 Selectors and descriptors

Descriptors are a bit like real mode segments; they describe (as the name implies) a memory area in protected mode. A descriptor contains information about segment length, its base address and the attributes of it (i.e. type, access rights, ...). These descriptors are stored internally in a so-called descriptor table, which is basically an array of such descriptors. Selectors are roughly an index into this table. Because these 'segments' can be up to 4 GB in size, 32 bits aren't sufficient anymore to describe a single memory location like in real mode. 48 bits are now needed to do this, a 32 bit address and a 16 bit sized selector. The GO32 unit provides the `tseginfo` record to store such a pointer. But due to the fact that most of the time data is stored and accessed in the `%ds` selector, FPC assumes that all pointers point to a memory location of this selector. So a single pointer is still only 32 bits in size. This value represents the offset from the data segment base address to this memory location.

54.17 What is DPMI

The dos Protected Mode Interface helps you with various aspects of protected mode programming. These are roughly divided into descriptor handling, access to dos memory, management of interrupts and exceptions, calls to real mode functions and other stuff. Additionally it automatically provides swapping to disk for memory intensive applications. A DPMI host (either a Windows dos box or `CWSDPMI.EXE`) provides these functions for your programs.

54.18 Constants, types and variables

54.18.1 Constants

```
auxcarryflag = $010
```

Check for auxiliary carry flag in `trealregs` (734)

```
carryflag = $001
```

Check for carry flag in `trealregs` (734)

```
directionflag = $400
```

Check for direction flag in `trealregs` (734)

```
dosmemfillchar : procedure(seg: Word; ofs: Word; count: LongInt; c
    : Char) = @dpmi_dosmemfillchar
```

Sets a region of dos memory to a specific byte value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of bytes to set.

c value to set memory to.

Notes: No range check is performed.

```
dosmemfillword : procedure(seg: Word; ofs: Word; count: LongInt; w
    : Word) = @dpmi_dosmemfillword
```

Sets a region of dos memory to a specific word value.

Parameters:

seg real mode segment.

ofs real mode offset.

count number of words to set.

w value to set memory to.

Notes: No range check is performed.

```
dosmemget : procedure(seg: Word; ofs: Word; var data; count: LongInt
    ) = @dpmi_dosmemget
```

Copies data from the dos memory onto the heap.

Parameters:

seg source real mode segment.

ofs source real mode offset.

data destination.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (754).

```
dosmemmove : procedure(sseg: Word; sofs: Word; dseg: Word; dofs: Word
;
count: LongInt) = @dpmi_dosmemmove
```

Copies count bytes of data between two dos real mode memory locations.

Parameters:

sseg source real mode segment.

sofs source real mode offset.

dseg destination real mode segment.

dofs destination real mode offset.

count number of bytes to copy.

Notes: No range check is performed in any way.

```
dosmemput : procedure(seg: Word; ofs: Word; var data; count: LongInt
) = @dpmi_dosmemput
```

Copies heap data to dos real mode memory.

Parameters:

seg destination real mode segment.

ofs destination real mode offset.

data source.

count number of bytes to copy.

Notes: No range checking is performed.

For an example, see `global_dos_alloc` (754).

```
interruptflag = $200
```

Check for interrupt flag in `trealregs` (734)

```
overflowflag = $800
```

Check for overflow flag in `trealregs` (734)

```
parityflag = $004
```

Check for parity flag in `trealregs` (734)

```
rm_dpml = 4
```

`get_run_mode` (752) return value: DPMI (e.g. dos box or 386Max)

```
rm_raw = 1
```

`get_run_mode` (752) return value: raw (without HIMEM)

```
rm_unknown = 0
```

`get_run_mode` (752) return value: Unknown runmode

```
rm_vcpi = 3
```

`get_run_mode` (752) return value: VCPI (with HIMEM and EMM386)

```
rm_xms = 2
```

`get_run_mode` (752) return value: XMS (with HIMEM, without EMM386)

```
signflag = $080
```

Check for sign flag in `trealregs` (734)

```
trapflag = $100
```

Check for trap flag in `trealregs` (734)

```
zeroflag = $040
```

Check for zero flag in `trealregs` (734)

54.18.2 Types

```
registers = trealregs
```

Alias for `trealregs` (734)

```
tdpmiversioninfo = record
  major : Byte;
  minor : Byte;
  flags
    : Word;
  cpu : Byte;
  master_pic : Byte;
  slave_pic : Byte;
end
```

`tdpmiversioninfo` describes the dpml version information, as returned by `get_dpml_version` (743). The CPU field can have the following values:

\$02H 80286**\$03H** 80386**\$04H** 80486**\$05H-** Newer than 80486

The flags field is a bitmask with the following bits:

0 0 for 16 bit DPML, 1 for 32-bit

1 0 for virtual 86 mode for reflected interrupts, 1 for return to real mode.

2 0 for no virtual memory support, 1 for virtual memory support.

```
tmeminfo = record
  available_memory : LongInt;
  available_pages
    : LongInt;
  available_lockable_pages : LongInt;
  linear_space
    : LongInt;
  unlocked_pages : LongInt;
  available_physical_pages
    : LongInt;
  total_physical_pages : LongInt;
  free_linear_space
    : LongInt;
  max_pages_in_paging_file : LongInt;
  reserved0 : LongInt
  ;
  reserved1 : LongInt;
  reserved2 : LongInt;
end
```

tmeminfo Holds information about the memory allocation, etc.

NOTE: The value of a field is -1 (0ffffffh) if the value is unknown, it's only guaranteed, that available_memory contains a valid value. The size of the pages can be determined by the get_page_size() function.

```
trealregs = record
case Integer of
1: (
  EDI : LongInt;
  ESI : LongInt
  ;
  EBP : LongInt;
  Res : LongInt;
  EBX : LongInt;
  EDX : LongInt
  ;
  ECX : LongInt;
  EAX : LongInt;
```

```
Flags : Word;
ES : Word;
DS : Word;
FS : Word;
GS : Word;
IP : Word;
CS : Word;
SP : Word;
SS : Word;
);
2: (
  DI : Word;
  DI2 : Word;
  SI
  : Word;
  SI2 : Word;
  BP : Word;
  BP2 : Word;
  R1 : Word;
  R2
  : Word;
  BX : Word;
  BX2 : Word;
  DX : Word;
  DX2 : Word;
  CX
  : Word;
  CX2 : Word;
  AX : Word;
  AX2 : Word;
);
3: (
  stuff
  : Array[1..4] of LongInt;
  BL : Byte;
  BH : Byte;
  BL2 : Byte
  ;
  BH2 : Byte;
  DL : Byte;
  DH : Byte;
  DL2 : Byte;
  DH2 : Byte
  ;
  CL : Byte;
  CH : Byte;
  CL2 : Byte;
  CH2 : Byte;
  AL : Byte
  ;
  AH : Byte;
  AL2 : Byte;
  AH2 : Byte;
);
```

```

4: (
  RealEDI : LongInt
  ;
  RealESI : LongInt;
  RealEBP : LongInt;
  RealRES : LongInt;
  RealEBX : LongInt;
  RealEDX : LongInt;
  RealECX : LongInt;
  RealEAX
  : LongInt;
  RealFlags : Word;
  RealES : Word;
  RealDS : Word;
  RealFS : Word;
  RealGS : Word;
  RealIP : Word;
  RealCS : Word
  ;
  RealSP : Word;
  RealSS : Word;
);
end

```

The `trealregs` type contains the data structure to pass register values to a interrupt handler or real mode callback.

```

tseginfo = record
  offset : pointer;
  segment : Word;
end

```

This record is used to store a full 48-bit pointer. This may be either a protected mode selector:offset address or in real mode a segment:offset address, depending on application.

See also: Selectors and descriptors, dos memory access, Interrupt redirection

54.18.3 Variables

```
dosmemselector : Word
```

Selector to the dos memory. The whole dos memory is automatically mapped to this single descriptor at startup. This selector is the recommended way to access dos memory.

```
int31error : Word
```

This variable holds the result of a DPMI interrupt call. Any nonzero value must be treated as a critical failure.

54.19 Procedures and functions

54.19.1 allocate_ldt_descriptors

Synopsis: Allocate a number of descriptors

Declaration: `function allocate_ldt_descriptors(count: Word) : Word`

Visibility: default

Description: Allocates a number of new descriptors.

Parameters:

count: \specifies the number of requested unique descriptors.

Return value: The base selector.

Remark: Notes: The descriptors allocated must be initialized by the application with other function calls. This function returns descriptors with a limit and size value set to zero. If more than one descriptor was requested, the function returns a base selector referencing the first of a contiguous array of descriptors. The selector values for subsequent descriptors in the array can be calculated by adding the value returned by the `get_next_selector_increment_value` (745) function.

Errors: Check the `int31error` (734) variable.

See also: `free_ldt_descriptor` (741), `get_next_selector_increment_value` (745), `segment_to_descriptor` (762), `create_code_segment_alias_descriptor` (739), `set_segment_limit` (767), `set_segment_base_address` (767)

Listing: `./go32ex/seldes.pp`

```
{
This example demonstrates the usage of descriptors and the effects of
changing its limit and base address.
```

```
In more detail, the program fills the region described by an
allocated descriptor in text screen memory with various characters.
Before doing this it saves the entire screen contents to the heap and
restores it afterwards.
```

```
Some additional background:
```

```
The text screen of a VGA card has it's address space at $B800:0;
screen memory is organized in a linear fashion, e.g. the second line
comes directly after the first, where each cell occupies 2 bytes of
memory (1 byte character data, 1 byte attributes). It is 32 kb in
size.
```

```
Hence the offset of a single memory cell from its origin is:
```

$$Y * columns * 2 + X * 2$$

```
where X and Y mark the point and columns is the number of character
cells per line
```

```
}
{$mode delphi}
```

```
uses
```

```
    crt ,
    go32;
```


const

```

    { screen x and y dimensions }
    maxx = 80;
    maxy = 25;
    { bytes used for every character cell }
    bytespercell = 2;
    { screen size in bytes }
    screensize = maxx * maxy * bytespercell;

    { the linear address of $B800:0 }
    linB8000 = $B800 * 16;

```

type

```
string80 = string[80];
```

var

```

    { holds the old screen contents }
    text_save : array[0..screensize-1] of byte;
    { old cursor x and y coordinates }
    text_oldx, text_oldy : Word;

    { selector to the text mode screen }
    text_sel : Word;

```

```

{ prints a status message on the first line of the screen and then
waits for a keypress }

```

```
procedure status(s : string80);
```

begin

```
    gotoxy(1, 1); clreol; write(s); readkey;
```

end;

```
{ writes some descriptor info on the last 2 lines }
```

```
procedure selinfo(sel : Word);
```

begin

```
    gotoxy(1, 24);
```

```
    clreol; writeln('Descriptor base address : $',
    hexstr(get_segment_base_address(sel), 8));
```

```
    clreol; write('Descriptor limit : ', get_segment_limit(sel));
```

end;

```

{ returns a 2 byte character cell, which includes character data
and its color attributes }

```

```
function makechar(ch : char; color : byte) : Word;
```

begin

```
    result := byte(ch) or (color shl 8);
```

end;**begin**

```

    { save original screen contents to variable, this time by using
    seg_move() and the dosmemselector variable }

```

```
    seg_move(dosmemselector, linB8000, get_ds, longint(@text_save),
    screensize);
```

```

    { additionally we have to save the old screen cursor
    coordinates }

```

```
    text_oldx := wherex; text_oldy := wherey;
```

```
    { clear the whole screen }
```

```
    seg_fillword(dosmemselector, linB8000, screensize div 2,
```

```

    makechar(' ', Black or (Black shl 4));
{ output message }
status('Creating selector ''text_sel'' to a part of ' +
    'text screen memory');
{ allocate descriptor }
text_sel := allocate_ldt_descriptors(1);
{ set its base address to the linear address of the text screen
+ the byte size of one line (=maxx * bytespercell * 1) }
set_segment_base_address(text_sel,
    linB8000 + bytespercell * maxx * 1);
{ the limit is set to the screensize reduced by one (a must be)
and the number of lines we don't want to have touched (first
line + lower 2 lines) }
set_segment_limit(text_sel, screensize - 1 - bytespercell *
    maxx * 3);
{ write descriptor info }
selinfo(text_sel);

status('and clearing entire memory selected by ''text_sel''' +
    ' descriptor');
{ fill the entire selected memory with single characters }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(' ', LightBlue shl 4));

status('Notice that only the memory described by the ' +
    'descriptor changed, nothing else');

status('Now reducing it''s limit and base and setting it''s ' +
    'described memory');
{ set the base address of the descriptor (increase it by the
byte size of one line) }
set_segment_base_address(text_sel,
    get_segment_base_address(text_sel) + bytespercell * maxx);
{ decrease the limit by byte size of 2 lines (1 line because
base address changed, one line on the lower end) }
set_segment_limit(text_sel,
    get_segment_limit(text_sel) - bytespercell * maxx * 2);
{ write descriptor info }
selinfo(text_sel);
status('Notice that the base addr increased by one line but ' +
    'the limit decreased by 2 lines');
status('This should give you the hint that the limit is ' +
    'relative to the base');
{ fill the descriptor area }
seg_fillword(text_sel, 0, (get_segment_limit(text_sel)+1) div 2,
    makechar(#176, LightMagenta or Brown shl 4));

status('Now let''s get crazy and copy 10 lines of data from ' +
    'the previously saved screen');
{ copy memory from the data segment to screen }
seg_move(get_ds, longint(@text_save), text_sel,
    maxx * bytespercell * 2, maxx * bytespercell * 10);

status('At last freeing the descriptor and restoring the old ' +
    'screen contents..');
status('I hope this little program may give you some hints ' +
    'on working with descriptors');
{ free the descriptor so that it can be used for things }

```

```

    free_ldt_descriptor(text_sel);
    { restore old state }
    seg_move(get_ds, longint(@text_save), dosmemselector,
            linB8000, screensize);
    gotoxy(text_oldx, text_oldy);
end.

```

54.19.2 allocate_memory_block

Synopsis: Allocate a block of linear memory

Declaration: `function allocate_memory_block(size: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of linear memory.

Parameters:

size:Size of requested linear memory block in bytes.

Returned values: blockhandle - the memory handle to this memory block. Linear address of the requested memory.

Remark: *warning* According to my DPMI docs this function is not implemented correctly. Normally you should also get a blockhandle to this block after successful operation. This handle can then be used to free the memory block afterwards or use this handle for other purposes. Since the function isn't implemented correctly, and doesn't return a blockhandle, the block can't be deallocated and is hence unusable ! This function doesn't allocate any descriptors for this block, it's the applications responsibility to allocate and initialize for accessing this memory.

Errors: Check the `int31error` (734) variable.

See also: `free_memory_block` (742)

54.19.3 copyfromdos

Synopsis: Copy data from DOS to heap

Declaration: `procedure copyfromdos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from the pre-allocated dos memory transfer buffer to the heap.

Parameters:

addrdata to copy to.

lennumber of bytes to copy to heap.

Notes: Can only be used in conjunction with the dos memory transfer buffer.

Errors: Check the `int31error` (734) variable.

See also: `tb_size` (768), `transfer_buffer` (769), `copytodos` (739)

54.19.4 copytodos

Synopsis: Copy data from heap to DOS memory

Declaration: `procedure copytodos(var addr; len: LongInt)`

Visibility: default

Description: Copies data from heap to the pre-allocated dos memory buffer.

Parameters:

addr data to copy from.

len number of bytes to copy to dos memory buffer.

Notes: This function fails if you try to copy more bytes than the transfer buffer is in size. It can only be used in conjunction with the transfer buffer.

Errors: Check the `int31error` (734) variable.

See also: `tb_size` (768), `transfer_buffer` (769), `copyfromdos` (738)

54.19.5 create_code_segment_alias_descriptor

Synopsis: Create new descriptor from existing descriptor

Declaration: `function create_code_segment_alias_descriptor(seg: Word) : Word`

Visibility: default

Description: Creates a new descriptor that has the same base and limit as the specified descriptor.

Parameters:

seg Descriptor.

Return values: The data selector (alias).

Notes: In effect, the function returns a copy of the descriptor. The descriptor alias returned by this function will not track changes to the original descriptor. In other words, if an alias is created with this function, and the base or limit of the original segment is then changed, the two descriptors will no longer map the same memory.

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `set_segment_limit` (767), `set_segment_base_address` (767)

54.19.6 disable

Synopsis: Disable hardware interrupts

Declaration: `procedure disable`

Visibility: default

Description: Disables all hardware interrupts by execution a CLI instruction.

Errors: None.

See also: `enable` (741)

54.19.7 dpmi_dosmemfillchar

Synopsis: Fill DOS memory with a character

Declaration: `procedure dpmi_dosmemfillchar(seg: Word; ofs: Word; count: LongInt;
c: Char)`

Visibility: default

Description: `dpmi_dosmemfillchar` fills the DOS memory region indicated by `seg,ofs` with `count` characters `c`.

See also: `dpmi_dosmempout` (741), `dpmi_dosmemget` (740), `dpmi_dosmemmove` (740), `dpmi_dosmemfillword` (740)

54.19.8 dpmi_dosmemfillword

Synopsis: Fill DOS memory with a word value

Declaration: `procedure dpmi_dosmemfillword(seg: Word; ofs: Word; count: LongInt;
w: Word)`

Visibility: default

Description: `dpmi_dosmemfillword` fills the DOS memory region indicated by `seg,ofs` with `count` words `W`.

See also: `dpmi_dosmempout` (741), `dpmi_dosmemget` (740), `dpmi_dosmemfillchar` (740), `dpmi_dosmemmove` (740)

54.19.9 dpmi_dosmemget

Synopsis: Move data from DOS memory to DPMI memory

Declaration: `procedure dpmi_dosmemget(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmempout` moves `count` bytes of data from the DOS memory location indicated by `seg` and `ofs` to DPMI memory indicated by `data`.

See also: `dpmi_dosmempout` (741), `dpmi_dosmemmove` (740), `dpmi_dosmemfillchar` (740), `dpmi_dosmemfillword` (740)

54.19.10 dpmi_dosmemmove

Synopsis: Move DOS memory

Declaration: `procedure dpmi_dosmemmove(sseg: Word; sofs: Word; dseg: Word;
dofs: Word; count: LongInt)`

Visibility: default

Description: `dpmi_dosmemmove` moves `count` bytes from DOS memory `sseg,sofs` to `dseg,dofs`.

See also: `dpmi_dosmempout` (741), `dpmi_dosmemget` (740), `dpmi_dosmemfillchar` (740), `dpmi_dosmemfillword` (740)

54.19.11 dpmi_dosmemput

Synopsis: Move data from DPMI memory to DOS memory.

Declaration: `procedure dpmi_dosmemput(seg: Word; ofs: Word; var data; count: LongInt)`

Visibility: default

Description: `dpmi_dosmemput` moves `count` bytes of data from `data` to the DOS memory location indicated by `seg` and `ofs`.

See also: `dpmi_dosmemget` (740), `dpmi_dosmemmove` (740), `dpmi_dosmemfillchar` (740), `dpmi_dosmemfillword` (740)

54.19.12 enable

Synopsis: Enable hardware interrupts

Declaration: `procedure enable`

Visibility: default

Description: Enables all hardware interrupts by executing a STI instruction.

Errors: None.

See also: `disable` (739)

54.19.13 free_ldt_descriptor

Synopsis: Free a descriptor

Declaration: `function free_ldt_descriptor(d: Word) : Boolean`

Visibility: default

Description: Frees a previously allocated descriptor.

Parameters:

des The descriptor to be freed.

Return value: `True` if successful, `False` otherwise. Notes: After this call this selector is invalid and must not be used for any memory operations anymore. Each descriptor allocated with `allocate_ldt_descriptors` (735) must be freed individually with this function, even if it was previously allocated as a part of a contiguous array of descriptors.

For an example, see `allocate_ldt_descriptors` (735).

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `get_next_selector_increment_value` (745)

54.19.14 free_linear_addr_mapping

Synopsis: ? No description available

Declaration: `function free_linear_addr_mapping(linear_addr: DWord) : Boolean`

Visibility: default

54.19.15 free_memory_block

Synopsis: Free allocated memory block

Declaration: `function free_memory_block(blockhandle: LongInt) : Boolean`

Visibility: default

Description: Frees a previously allocated memory block.

Parameters:

blockhandle the handle to the memory area to free.

Return value: `True` if successful, `false` otherwise. Notes: Frees memory that was previously allocated with `allocate_memory_block` (738) . This function doesn't free any descriptors mapped to this block, it's the application's responsibility.

Errors: Check `int31error` (734) variable.

See also: `allocate_memory_block` (738)

54.19.16 free_rm_callback

Synopsis: Release real mode callback.

Declaration: `function free_rm_callback(var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Releases a real mode callback address that was previously allocated with the `get_rm_callback` (747) function.

Parameters:

intaddr real mode address buffer returned by `get_rm_callback` (747) .

Return values: `True` if successful, `False` if not

For an example, see `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `set_rm_interrupt` (767), `get_rm_callback` (747)

54.19.17 get_cs

Synopsis: Get CS selector

Declaration: `function get_cs : Word`

Visibility: default

Description: Returns the cs selector.

Return value: The content of the cs segment register.

For an example, see `set_pm_interrupt` (765).

Errors: None.

See also: `get_ds` (743), `get_ss` (753)

54.19.18 get_descriptor_access_right

Synopsis: Get descriptor's access rights

Declaration: `function get_descriptor_access_right(d: Word) : LongInt`

Visibility: default

Description: Gets the access rights of a descriptor.

Parameters:

`d` selector to descriptor.

Return value: Access rights bit field.

Errors: Check the `int31error` (734) variable.

See also: `set_descriptor_access_right` (764)

54.19.19 get_dpmi_version

Synopsis: Return DPMI information

Declaration: `function get_dpmi_version(var version: tdpmiversioninfo) : Boolean`

Visibility: default

Description: `get_dpmi_version` returns version information (Int \$31 Function \$0400) in `Version` and returns `True` if the information was retrieved successfully, `false` if the call failed.

Errors: The call returns `false` if the information could not be retrieved.

See also: `tdpmiversioninfo` (731)

54.19.20 get_ds

Synopsis: Get DS Selector

Declaration: `function get_ds : Word`

Visibility: default

Description: Returns the ds selector.

Return values: The content of the ds segment register.

Errors: None.

See also: `get_cs` (742), `get_ss` (753)

54.19.21 get_exception_handler

Synopsis: Return current exception handler

Declaration: `function get_exception_handler(e: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: `get_exception_handler` returns the exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (764), `get_pm_exception_handler` (746)

54.19.22 get_linear_addr

Synopsis: Convert physical to linear address

Declaration: `function get_linear_addr(phys_addr: DWord; size: LongInt) : DWord`

Visibility: default

Description: Converts a physical address into a linear address.

Parameters:

phys_addr physical address of device.

size Size of region to map in bytes.

Return value: Linear address that can be used to access the physical memory. Notes: It's the applications responsibility to allocate and set up a descriptor for access to the memory. This function shouldn't be used to map real mode addresses.

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `set_segment_limit` (767), `set_segment_base_address` (767)

54.19.23 get_meminfo

Synopsis: Return information on the available memory

Declaration: `function get_meminfo(var meminfo: tmeminfo) : Boolean`

Visibility: default

Description: Returns information about the amount of available physical memory, linear address space, and disk space for page swapping.

Parameters:

meminfo buffer to fill memory information into.

Return values: Due to an implementation bug this function always returns `False`, but it always succeeds.

Remark: Notes: Only the first field of the returned structure is guaranteed to contain a valid value. Any fields that are not supported by the DPMI host will be set by the host to `-1` (`0FFFFFFFFH`) to indicate that the information is not available. The size of the pages used by the DPMI host can be obtained with the `get_page_size` (746) function.

Errors: Check the `int31error` (734) variable.

See also: `get_page_size` (746)

Listing: `./go32ex/meminfo.pp`

```
{ Shows how to obtain memory information via get_meminfo();

notice the checks if any of the returned information is invalid (-1)
}

uses
    go32;

var
```

```

    meminfo : tmeminfo;

begin
    get_meminfo(meminfo);
    if (int31error <> 0) then begin
        Writeln('Error getting DPML memory information... Halting');
        Writeln('DPML error number : ', int31error);
    end else begin
        with meminfo do begin
            Writeln('Largest available free block : ',
                available_memory div 1024, ' kbytes');
            if (available_pages <> -1) then
                Writeln('Maximum available unlocked pages : ',
                    available_pages);
            if (available_lockable_pages <> -1) then
                Writeln('Maximum lockable available pages : ',
                    available_lockable_pages);
            if (linear_space <> -1) then
                Writeln('Linear address space size : ',
                    linear_space*get_page_size div 1024, ' kbytes');
            if (unlocked_pages <> -1) then
                Writeln('Total number of unlocked pages : ',
                    unlocked_pages);
            if (available_physical_pages <> -1) then
                Writeln('Total number of free pages : ',
                    available_physical_pages);
            if (total_physical_pages <> -1) then
                Writeln('Total number of physical pages : ',
                    total_physical_pages);
            if (free_linear_space <> -1) then
                Writeln('Free linear address space : ',
                    free_linear_space*get_page_size div 1024,
                    ' kbytes');
            if (max_pages_in_paging_file <> -1) then
                Writeln('Maximum size of paging file : ',
                    max_pages_in_paging_file*get_page_size div 1024,
                    ' kbytes');
        end;
    end;
end.

```

54.19.24 get_next_selector_increment_value

Synopsis: Return selector increment value

Declaration: function get_next_selector_increment_value : Word

Visibility: default

Description: Returns the selector increment value when allocating multiple subsequent descriptors via allocate_ldt_descriptors (735).

Return value: Selector increment value.

Remark: Notes: Because allocate_ldt_descriptors (735) only returns the selector for the first descriptor and so the value returned by this function can be used to calculate the selectors for subsequent descriptors in the array.

Errors: Check the int31error (734) variable.

See also: [allocate_ldt_descriptors \(735\)](#), [free_ldt_descriptor \(741\)](#)

54.19.25 `get_page_attributes`

Synopsis: ? No description available

Declaration: `function get_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.26 `get_page_size`

Synopsis: Return the page size

Declaration: `function get_page_size : LongInt`

Visibility: default

Description: Returns the size of a single memory page.

Return value: Size of a single page in bytes.

Remark: The returned size is typically 4096 bytes.

For an example, see [get_meminfo \(744\)](#).

Errors: Check the [int31error \(734\)](#) variable.

See also: [get_meminfo \(744\)](#)

54.19.27 `get_pm_exception_handler`

Synopsis: Get protected mode exception handler

Declaration: `function get_pm_exception_handler(e: Byte; var intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `get_pm_exception_handler` returns the protected mode exception handler for exception `E` in `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: [get_exception_handler \(743\)](#), [set_pm_exception_handler \(765\)](#)

54.19.28 `get_pm_interrupt`

Synopsis: Return protected mode interrupt handler

Declaration: `function get_pm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the address of a current protected mode interrupt handler.

Parameters:

vector interrupt handler number you want the address to.

intaddr buffer to store address.

Return values: `True` if successful, `False` if not.

Remark: The returned address is a protected mode selector:offset address.

For an example, see `set_pm_interrupt` (765).

Errors: Check the `int31error` (734) variable.

See also: `set_pm_interrupt` (765), `set_rm_interrupt` (767), `get_rm_interrupt` (751)

54.19.29 `get_rm_callback`

Synopsis: Return real mode callback

Declaration: `function get_rm_callback(pm_func: pointer; const reg: trealregs;
var rmcb: tseginfo) : Boolean`

Visibility: default

Description: Returns a unique real mode `segment:offset` address, known as a "real mode callback," that will transfer control from real mode to a protected mode procedure.

Parameters:

pm_func pointer to the protected mode callback function.

regs supplied registers structure.

rmcb buffer to real mode address of callback function.

Return values: `True` if successful, otherwise `False`.

Remark: Callback addresses obtained with this function can be passed by a protected mode program for example to an interrupt handler, device driver, or TSR, so that the real mode program can call procedures within the protected mode program or notify the protected mode program of an event. The contents of the supplied `regs` structure is not valid after function call, but only at the time of the actual callback.

Errors: Check the `int31error` (734) variable.

See also: `free_rm_callback` (742)

Listing: `./go32ex/callback.pp`

*{ This program tries to give an example how to install a callback
procedure with the help of the GO32 unit.*

*It installs a callback which is supplied by any Microsoft compatible
mouse driver; at a specified mouse action this routine is called.
This callback must provide the services explained in the docs. The
main callback has to be in assembly, because it isn't possible to do
these services with pascal alone. But is written as general as
possible to provide maximum re-usability for other applications and
hence it simply calls a normal pascal user procedure in addition to
some initialization and callback service code, so you don't need to
hassle around with it too much.*

Notes to this user procedure :

**) it should not last too long to execute it*

**) ALL data and code touched in this proc MUST be locked BEFORE it is
called the first time*

Used software interrupt calls (rough descriptions , only what's used):

Int 33h 0000h – Microsoft Mouse driver : Reset mouse

Input : AX = 0000h

Return : AX = FFFFh if successful

BX = number of buttons (if FFFFh then mouse has 2 buttons)

Int 33h 0001h – Microsoft Mouse driver : Show mouse cursor

Input : AX = 0001h

Return : Mouse cursor shown on screen

Int 33h 0002h – Microsoft mouse driver : Hide mouse cursor

Input : AX = 0002h

Return : Hides mouse cursor again

Int 33h 000Ch – Microsoft mouse driver : Install user callback

Input : AX = 000Ch

CX = bit mask which tells the mouse driver at which actions the callback should be called, i.e. if button pressed, mouse moved etc.

(In this example it's set to 7Fh so that the callback is called on every action)

ES:EDX = pointer to callback procedure to call

Note : The registers structure supplied to the callback contains valid mouse data when the handler is called.

BX = button state information

CX = mouse X coordinates

DX = mouse Y coordinates

For more detailed information consult any mouse reference or interrupt list.

```

}
{$CALLING REGISTER}
{$ASMMODE ATT}
{$MODE FPC}

```

uses

```

crt ,
go32;

```

const

```

{ the mouse interrupt number }
mouseint = $33;

```

var

```

{ supplied register structure to the callback }
mouse_regs : trealregs; external name '___v2prt0_rmcb_regs';
{ real mode 48 bit pointer to the callback }
mouse_seginfo : tseginfo;

```

var

```

{ number of mouse buttons }
mouse_numbuttons : longint;

{ bit mask for the action which triggered the callback }
mouse_action : word;
{ current mouse x and y coordinates }
mouse_x, mouse_y : Word;

```

```

    { button state }
    mouse_b : Word;

    { is an additional user procedure installed }
    userproc_installed : Longbool;
    { length of additional user procedure }
    userproc_length : Longint;
    { pointer to user proc }
    userproc_proc : pointer;

{ callback control handler, calls a user procedure if installed }

{ callback control handler, calls a user procedure if installed }
procedure callback_handler; assembler;
asm
    pushw %ds
    pushl %eax
    movw %es, %ax
    movw %ax, %ds

    { give control to user procedure if installed }
    cmpl $0, USERPROC_INSTALLED
    je .LNoCallback
    pushal
    movw DOSmemSELECTOR, %ax
    movw %ax, %fs { set fs for FPC }
    call *USERPROC_PROC
    popal
.LNoCallback:

    popl %eax
    popw %ds

    pushl %eax
    movl (%esi), %eax
    movl %eax, %es: 42(%edi) { adjust stack }
    addw $4, %es:46(%edi)
    popl %eax
    iret
end;
{ This dummy is used to obtain the length of the callback control
function. It has to be right after the callback_handler() function.
}
procedure mouse_dummy; begin end;

{ This is the supplied user procedure. In this case we simply
transform the virtual 640x200 mouse coordinate system to a 80x25
text mode coordinate system }
procedure textuserproc;
begin
    { the mouse_regs record contains the real mode registers now }
    mouse_b := mouse_regs.bx;
    mouse_x := (mouse_regs.cx shr 3) + 1;
    mouse_y := (mouse_regs.dx shr 3) + 1;
end;

{ Description : Installs the mouse callback control handler and
handles all necessary mouse related initialization.
}

```

```

    Input : userproc – pointer to a user procedure, nil if none
           userproclen – length of user procedure
}
procedure install_mouse(userproc : pointer; userproclen : longint);
var r : trealregs;
begin
    { mouse driver reset }
    r.eax := $0; realintr(mouseint, r);
    if (r.eax <> $FFFF) then begin
        WriteLn('No Microsoft compatible mouse found');
        WriteLn('A Microsoft compatible mouse driver is necessary ',
            'to run this example');
        halt;
    end;
    { obtain number of mouse buttons }
    if (r.bx = $ffff) then mouse_numbuttons := 2
    else mouse_numbuttons := r.bx;
    WriteLn(mouse_numbuttons, ' button Microsoft compatible mouse ',
        ' found. ');
    { check for additional user procedure, and install it if
    available }
    if (userproc <> nil) then begin
        userproc_proc := userproc;
        userproc_installed := true;
        userproc_length := userproclen;
        { lock code for user procedure }
        lock_code(userproc_proc, userproc_length);
    end else begin
        { clear variables }
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { lock code & data which is touched in the callback handler }
    lock_data(mouse_x, sizeof(mouse_x));
    lock_data(mouse_y, sizeof(mouse_y));
    lock_data(mouse_b, sizeof(mouse_b));
    lock_data(mouse_action, sizeof(mouse_action));

    lock_data(userproc_installed, sizeof(userproc_installed));
    lock_data(userproc_proc, sizeof(userproc_proc));

    lock_data(mouse_regs, sizeof(mouse_regs));
    lock_data(mouse_seginf, sizeof(mouse_seginf));
    lock_code(@callback_handler,
        longint(@mouse_dummy) – longint(@callback_handler));
    { allocate callback (supply registers structure) }
    get_rm_callback(@callback_handler, mouse_regs, mouse_seginf);
    { install callback }
    r.eax := $0c; r.ecx := $7f;
    r.edx := longint(mouse_seginf.offset);
    r.es := mouse_seginf.segment;
    realintr(mouseint, r);
    { show mouse cursor }
    r.eax := $01;
    realintr(mouseint, r);
end;

```

```

procedure remove_mouse;
var
    r : trealregs;
begin
    { hide mouse cursor }
    r.eax := $02; realintr(mouseint, r);
    { remove callback handler }
    r.eax := $0c; r.ecx := 0; r.edx := 0; r.es := 0;
    realintr(mouseint, r);
    { free callback }
    free_rm_callback(mouse_seginfo);
    { check if additional userproc is installed, and clean up if needed }
    if (userproc_installed) then begin
        unlock_code(userproc_proc, userproc_length);
        userproc_proc := nil;
        userproc_length := 0;
        userproc_installed := false;
    end;
    { unlock used code & data }
    unlock_data(mouse_x, sizeof(mouse_x));
    unlock_data(mouse_y, sizeof(mouse_y));
    unlock_data(mouse_b, sizeof(mouse_b));
    unlock_data(mouse_action, sizeof(mouse_action));

    unlock_data(userproc_proc, sizeof(userproc_proc));
    unlock_data(userproc_installed, sizeof(userproc_installed));

    unlock_data(mouse_regs, sizeof(mouse_regs));
    unlock_data(mouse_seginfo, sizeof(mouse_seginfo));
    unlock_code(@callback_handler,
        longint(@mouse_dummy) - longint(@callback_handler));
    fillchar(mouse_seginfo, sizeof(mouse_seginfo), 0);
end;

begin
    install_mouse(@textuserproc, 400);
    Writeln('Press any key to exit...');
    while (not keypressed) do begin
        { write mouse state info }
        gotoxy(1, wherey);
        write('MouseX : ', mouse_x:2, ' MouseY : ', mouse_y:2,
            ' Buttons : ', mouse_b:2);
    end;
    remove_mouse;
end.

```

54.19.30 get_rm_interrupt

Synopsis: Get real mode interrupt vector

Declaration: `function get_rm_interrupt(vector: Byte; var intaddr: tseginfo) : Boolean`

Visibility: default

Description: Returns the contents of the current machine's real mode interrupt vector for the specified interrupt.

Parameters:

vector interrupt vector number.

intaddr buffer to store real mode segment : offset address.

Return values: `True` if successful, `False` otherwise.

Remark: The returned address is a real mode segment address, which isn't valid in protected mode.

Errors: Check the `int31error` (734) variable.

See also: `set_rm_interrupt` (767), `set_pm_interrupt` (765), `get_pm_interrupt` (746)

54.19.31 `get_run_mode`

Synopsis: Return current run mode

Declaration: `function get_run_mode : Word`

Visibility: `default`

Description: Returns the current mode your application runs with.

Return values: One of the constants used by this function.

Errors: None.

See also: `get_run_mode` (752)

Listing: `./go32ex/getrunmd.pp`

```
{ Simply write a message according to the current environment }

uses
    go32;

begin
    { depending on the detected environment we simply write
    another message Note: in go32v2 this will always be rm_dpml. }

    case (get_run_mode) of
        rm_unknown :
            WriteLn('Unknown environment found');
        rm_raw :
            WriteLn('You are currently running in raw mode ',
                '(without HIMEM)');
        rm_xms :
            WriteLn('You are currently using HIMEM.SYS only');
        rm_vcpi :
            WriteLn('VCPI server detected. You''re using HIMEM and ',
                'EMM386');
        rm_dpml :
            WriteLn('DPML detected. You''re using a DPML host like ',
                'a windows DOS box or CWSDPML');
    end;
end.
```

54.19.32 get_segment_base_address

Synopsis: Return base address from descriptor table

Declaration: `function get_segment_base_address(d: Word) : LongInt`

Visibility: default

Description: Returns the 32-bit linear base address from the descriptor table for the specified segment.

Parameters:

dselector of the descriptor you want the base address of.

Return values: Linear base address of specified descriptor.

For an example, see `allocate_ldt_descriptors` (735).

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `set_segment_base_address` (767), `allocate_ldt_descriptors` (735), `set_segment_limit` (767), `get_segment_limit` (753)

54.19.33 get_segment_limit

Synopsis: Return segment limit from descriptor

Declaration: `function get_segment_limit(d: Word) : DWord`

Visibility: default

Description: Returns a descriptors segment limit.

Parameters:

dselector.

Return value: Limit of the descriptor in bytes.

Errors: Returns zero if descriptor is invalid.

See also: `allocate_ldt_descriptors` (735), `set_segment_limit` (767), `set_segment_base_address` (767), `get_segment_base_address` (753)

54.19.34 get_ss

Synopsis: Return SS selector

Declaration: `function get_ss : Word`

Visibility: default

Description: Returns the ss selector.

Return values: The content of the ss segment register.

Errors: None.

See also: `get_ds` (743), `get_cs` (742)

54.19.35 global_dos_alloc

Synopsis: Allocate DOS real mode memory

Declaration: `function global_dos_alloc(bytes: LongInt) : LongInt`

Visibility: default

Description: Allocates a block of dos real mode memory.

Parameters:

bytesize of requested real mode memory.

Return values: The low word of the returned value contains the selector to the allocated dos memory block, the high word the corresponding real mode segment value. The offset value is always zero. This function allocates memory from dos memory pool, i.e. memory below the 1 MB boundary that is controlled by dos. Such memory blocks are typically used to exchange data with real mode programs, TSRs, or device drivers. The function returns both the real mode segment base address of the block and one descriptor that can be used by protected mode applications to access the block. This function should only be used for temporary buffers to get real mode information (e.g. interrupts that need a data structure in ES:(E)DI), because every single block needs a unique selector. The returned selector should only be freed by a `global_dos_free` (756) call.

Errors: Check the `int31error` (734) variable.

See also: `global_dos_free` (756)

Listing: `./go32ex/buffer.pp`

{ This program demonstrates the usage of DOS real mode memory by executing a software interrupt which needs a buffer to store data into. Because these interrupts are real mode funcs, the buffer must be located in real mode memory space (first MB of memory). Such memory can only be allocated by the global_dos_alloc() and global_dos_free() functions of the GO32 unit.

In more detail this program tries to detect a VESA 2.0 BIOS extension of your graphics card and outputs its version.

Here's the necessary interrupt call description:

*Int 10h 4f00h : VESA BIOS extension installation check
Input : AX = 4F00h
 ES:DI = pointer to 512 byte information buffer
Output : AX = 004Fh if successful
 ES:DI = pointer to filled buffer*

Buffer structure : (relevant to this example)

*must be 'VESA' in the first 4 chars of the buffer to be
 valid VBE version in the next word*

*Note : to request VBE 2.0 information, the first 4 bytes of the
 buffer must contain 'VBE2' prior to the interrupt call.*

*(this makes the problem a bit tougher; we first have to copy the
 buffer with the 'VBE2' id to dos memory...)*

}

uses

go32;

*{The following 2 functions are wrappers to the GO32
global_dos_alloc() and global_dos_free() functions to simplify their
usage }*

{ Function : dosalloc }

{ Input : size of a real mode location }

{ Output : selector and segment of a real mode location }

procedure dosalloc(**var** selector : word;
var segment : word; size : longint);

var

res : longint;

begin

{ try to allocate real mode memory }

res := global_dos_alloc(size);

*{ the lower 16 bits of the result contain the selector to the
allocated memory block }*

selector := word(res);

*{ the upper 16 bits contain the real mode segment address of
this block; the offset is always 0, so we don't need to return
this }*

segment := word(res shr 16);

end;

{ Function : dosfree }

{ Input : selector of a real mode block }

{ Output : none }

*{ Description : de-allocates a previously allocated real mode
memory }*

procedure dosfree(selector : word);

begin

{ call the GO32 function with the selector }

global_dos_free(selector);

end;

type

VBEInfoBuf = **packed record**

{ contains 'VESA' if successful }

Signature : **array**[0..3] **of** char;

Version : Word;

{ pad to 512 bytes length }

reserved : **array**[0..505] **of** byte;

end;

var

{ selector to our real mode buffer }

selector,

{ real mode segment address of buffer }

segment : Word;

{ register structure to issue a software interrupt }

r : treatregs;

infobuf : VBEInfoBuf;

begin

{ first we reset the registers and infobuf variable }

```

    fillchar(r, sizeof(r), 0);
    fillchar(infobuf, sizeof(VBEInfoBuf), 0);
    { allocate real mode memory }
    dosalloc(selector, segment, sizeof(VBEInfoBuf));
    { check if an error occurred during allocation }
    if (int31error <> 0) then begin
        Writeln('Error while allocating real mode memory, halting');
        halt;
    end;
    { request VBE 2.0 information, fill out information buffer }
    infobuf.Signature := 'VBE2';
    { copy buffer to the allocated real mode memory }
    dosmemput(segment, 0, infobuf, sizeof(infobuf));
    { issue the interrupt; remember : DI = 0 }
    r.ax := $4f00; r.es := segment;
    realintr($10, r);
    { copy buffer to our infobuf variable again }
    dosmemget(segment, 0, infobuf, sizeof(infobuf));
    { free allocated real mode memory, because we don't need it anymore }
    dosfree(selector);
    { check if interrupt call was successful }
    if (r.ax <> $4f) then begin
        { write message and exit, because the infobuf doesn't contain any useful data we could tell the user }
        Writeln('VBE BIOS extension not available, function call ', 'failed');
        halt;
    end;
    { check if buffer is valid }
    if (infobuf.signature[0] = 'V') and
        (infobuf.signature[1] = 'E') and
        (infobuf.signature[2] = 'S') and
        (infobuf.signature[3] = 'A') then begin
        Writeln('VBE version ', hi(infobuf.version), '.', lo(infobuf.version), ' detected');
    end;
end.

```

54.19.36 global_dos_free

Synopsis: Free DOS memory block

Declaration: function global_dos_free(selector: Word) : Boolean

Visibility: default

Description: Frees a previously allocated dos memory block.

Parameters:

selector selector to the dos memory block.

Return value: True if successful, False otherwise.

Remark: The descriptor allocated for the memory block is automatically freed and hence invalid for further use. This function should only be used for memory allocated by global_dos_alloc (754).

For an example, see global_dos_alloc (754).

Errors: Check the `int31error` (734) variable.

See also: `global_dos_alloc` (754)

54.19.37 `inportb`

Synopsis: Read byte from I/O port

Declaration: `function inportb(port: Word) : Byte`

Visibility: default

Description: Reads 1 byte from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (759), `inportw` (757), `inportl` (757)

54.19.38 `inportl`

Synopsis: Read longint from I/O port

Declaration: `function inportl(port: Word) : LongInt`

Visibility: default

Description: Reads 1 longint from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportb` (759), `inportb` (757), `inportw` (757)

54.19.39 `inportw`

Synopsis: Read word from I/O port

Declaration: `function inportw(port: Word) : Word`

Visibility: default

Description: Reads 1 word from the selected I/O port.

Parameters:

port the I/O port number which is read.

Return values: Current I/O port value.

Errors: None.

See also: `outportw` (760), `inportb` (757), `inportl` (757)

54.19.40 lock_code

Synopsis: Lock code memory range

Declaration: `function lock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which is in the code segment selector.

Parameters:

functionaddr address of the function to be locked.

size size in bytes to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `lock_linear_region` (758), `lock_data` (758), `unlock_linear_region` (770), `unlock_data` (769), `unlock_code` (769)

54.19.41 lock_data

Synopsis: Lock data memory range

Declaration: `function lock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Locks a memory range which resides in the data segment selector.

Parameters:

data address of data to be locked.

size length of data to be locked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `lock_linear_region` (758), `lock_code` (758), `unlock_linear_region` (770), `unlock_data` (769), `unlock_code` (769)

54.19.42 lock_linear_region

Synopsis: Lock linear memory region

Declaration: `function lock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Locks a memory region to prevent swapping of it.

Parameters:

linearaddr the linear address of the memory are to be locked.

size size in bytes to be locked.

Return value: True if successful, False otherwise.

Errors: Check the `int31error` (734) variable.

See also: `lock_data` (758), `lock_code` (758), `unlock_linear_region` (770), `unlock_data` (769), `unlock_code` (769)

54.19.43 map_device_in_memory_block

Synopsis: Map a device into program's memory space

Declaration: `function map_device_in_memory_block(handle: DWord; offset: DWord; pagecount: DWord; device: DWord) : Boolean`

Visibility: default

Description: `map_device_in_memory_block` allows to map a device in memory. This function is a direct call of the extender. For more information about it's arguments, see the extender documentation.

54.19.44 outportb

Synopsis: Write byte to I/O port

Declaration: `procedure outportb(port: Word; data: Byte)`

Visibility: default

Description: Sends 1 byte of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

Errors: None.

See also: `inportb` (757), `outportl` (760), `outportw` (760)

Listing: `./go32ex/outport.pp`

```
{ This example demonstrates the use of the outport functions.

It simply turns the PC's internal speaker on for 50 ms and off again
}
uses
    crt ,
    go32;

begin
    { turn on speaker }
    outportb($61, $ff);
    { wait a little bit }
    delay(50);
    { turn it off again }
    outportb($61, $0);

end.
```

54.19.45 outportl

Synopsis: Write longint to I/O port

Declaration: `procedure outportl(port: Word; data: LongInt)`

Visibility: default

Description: Sends 1 longint of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` (759).

Errors: None.

See also: `inportl` (757), `outportw` (760), `outportb` (759)

54.19.46 outportw

Synopsis: Write word to I/O port

Declaration: `procedure outportw(port: Word; data: Word)`

Visibility: default

Description: Sends 1 word of data to the specified I/O port.

Parameters:

port the I/O port number to send data to.

data value sent to I/O port.

Return values: None.

For an example, see `outportb` (759).

Errors: None.

See also: `inportw` (757), `outportl` (760), `outportb` (759)

54.19.47 realintr

Synopsis: Simulate interrupt

Declaration: `function realintr(intnr: Word; var regs: trealregs) : Boolean`

Visibility: default

Description: Simulates an interrupt in real mode.

Parameters:

intnr interrupt number to issue in real mode.

regs registers data structure.

Return values: The supplied registers data structure contains the values that were returned by the real mode interrupt. `True` if successful, `False` if not.

Remark: The function transfers control to the address specified by the real mode interrupt vector of `intr`. The real mode handler must return by executing an `IRET`.

Errors: Check the `int31error` (734) variable.

Listing: `./go32ex/flags.pp`

```
{ This example demonstrates the use of the flag constants in
conjunction with an interrupt call

In detail it checks if APM (advanced power management) is
available.

Int 15h 5300h – APM specification : Installation check
Input : AX = 5300h
        BX = device id of system BIOS (= 0000h)
Return : Carry clear if successful
        AH = major version (BCD)
        AL = minor version (BCD)
}
```

```
uses
    go32;

var
    r : trealregs;

begin
    { set register values and issue real mode interrupt call }
    r.ax := $5300;
    r.bx := 0;
    realintr($15, r);
    { check if carry clear and write a suited message }
    if ((r.flags and carryflag)=0) then begin
        Writeln('APM v', (r.ah and $f), '.',
                (r.al shr 4), (r.al and $f), ' detected');
    end else
        Writeln('APM not present');
end.
```

54.19.48 request_linear_region

Synopsis: Request linear address region.

Declaration: `function request_linear_region(linearaddr: LongInt; size: LongInt; var blockhandle: LongInt) : Boolean`

Visibility: default

Description: `request_linear_region` requests a linear range of addresses of size `Size`, starting at `linearaddr`. If successful, `True` is returned, and a handle to the address region is returned in `blockhandle`.

Errors: On error, `False` is returned.

54.19.49 segment_to_descriptor

Synopsis: Map segment address to descriptor

Declaration: `function segment_to_descriptor(seg: Word) : Word`

Visibility: default

Description: Maps a real mode segment (paragraph) address onto an descriptor that can be used by a protected mode program to access the same memory.

Parameters:

seg the real mode segment you want the descriptor to.

Return values: Descriptor to real mode segment address.

Remark: The returned descriptors limit will be set to 64 kB. Multiple calls to this function with the same segment address will return the same selector. Descriptors created by this function can never be modified or freed. Programs which need to examine various real mode addresses using the same selector should use the function `allocate_ldt_descriptors` (735) and change the base address as necessary.

For an example, see `seg_fillchar` (762).

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `free_ldt_descriptor` (741), `set_segment_base_address` (767)

54.19.50 seg_fillchar

Synopsis: Fill segment with byte value

Declaration: `procedure seg_fillchar(seg: Word; ofs: LongInt; count: LongInt; c: Char)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of bytes to set.

c byte data which is set.

Return values: None.

Notes: No range check is done in any way.

Errors: None.

See also: `seg_move` (764), `seg_fillword` (763), `dosmemfillchar` (729), `dosmemfillword` (729), `dosmemget` (729), `dosmemput` (730), `dosmemmove` (730)

Listing: `./go32ex/vgasel.pp`

{ This example demonstrates the use of the segment_to_descriptor() function .

It switches to VGA mode 13h (320x200x256 color), creates a selector to the memory (based at \$A000:0000), clears this memory with color 15 (white) and waits until the enter key is pressed }

uses go32;

var

 vgasel : Word;
 r : treatregs;

begin

{ set VGA mode 13h }
 r.eax := \$13; realintr(\$10, r);
 { allocate descriptor to VGA memory quickly; it could be done with allocate_ldt_descriptors() too, but we would have to initialize it by ourselves... unlike segment_to_descriptor() which automatically sets the limit and the base address correctly }
 vgasel := segment_to_descriptor(\$A000);
 { simply fill the screen memory with color 15 }
 seg_fillchar(vgasel, 0, 64000, #15);
 { wait for a return press }
 readln;
 { back to text mode }
 r.eax := \$3; realintr(\$10, r);
 { don't deallocate vgasel, that can't be done }

end.

54.19.51 seg_fillword

Synopsis: Fill segment with word value

Declaration: `procedure seg_fillword(seg: Word; ofs: LongInt; count: LongInt; w: Word)`

Visibility: default

Description: Sets a memory area to a specific value.

Parameters:

seg selector to memory area.

ofs offset to memory.

count number of words to set.

w word data which is set.

Return values: None.

Notes: No range check is done in any way.

For an example, see `allocate_ldt_descriptors` ([735](#)).

Errors: None.

See also: `seg_move` ([764](#)), `seg_fillchar` ([762](#)), `dosmemfillchar` ([729](#)), `dosmemfillword` ([729](#)), `dosmemget` ([729](#)), `dosmemput` ([730](#)), `dosmemmove` ([730](#))

54.19.52 seg_move

Synopsis: Move data between 2 locations

Declaration: `procedure seg_move(sseg: Word; source: LongInt; dseg: Word;
dest: LongInt; count: LongInt)`

Visibility: default

Description: Copies data between two memory locations.

Parameters:

ssegsource selector.

sourcesource offset.

dsegdestination selector.

destdestination offset.

countsize in bytes to copy.

Return values: None.

Remark: Overlapping is only checked if the source selector is equal to the destination selector. No range check is done.

For an example, see `allocate_ldt_descriptors` (735).

Errors: None.

See also: `seg_fillchar` (762), `seg_fillword` (763), `dosmemfillchar` (729), `dosmemfillword` (729), `dosmemget` (729), `dosmemput` (730), `dosmemmove` (730)

54.19.53 set_descriptor_access_right

Synopsis: Set access rights to memory descriptor

Declaration: `function set_descriptor_access_right(d: Word; w: Word) : Boolean`

Visibility: default

Description: `set_descriptor_access_right` sets the access rights for descriptor `d` to `w`

54.19.54 set_exception_handler

Synopsis: Set exception handler

Declaration: `function set_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_exception_handler` sets the exception handler for exception `E` to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `get_exception_handler` (743), `set_pm_exception_handler` (765)

54.19.55 set_page_attributes

Synopsis: ? No description available

Declaration: `function set_page_attributes(handle: DWord; offset: DWord;
pagecount: DWord; buf: pointer) : Boolean`

Visibility: default

54.19.56 set_pm_exception_handler

Synopsis: Set protected mode exception handler

Declaration: `function set_pm_exception_handler(e: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: `set_pm_exception_handler` sets the protected mode exception handler for exception E to `intaddr`. It returns `True` if the call was successful, `False` if not.

See also: `set_exception_handler` (764), `get_pm_exception_handler` (746)

54.19.57 set_pm_interrupt

Synopsis: Set protected mode interrupt handler

Declaration: `function set_pm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets the address of the protected mode handler for an interrupt.

Parameters:

vector number of protected mode interrupt to set.

intaddr selector:offset address to the interrupt vector.

Return values: `True` if successful, `False` otherwise.

Remark: The address supplied must be a valid `selector:offset` protected mode address.

Errors: Check the `int31error` (734) variable.

See also: `get_pm_interrupt` (746), `set_rm_interrupt` (767), `get_rm_interrupt` (751)

Listing: `./go32ex/intpm.pp`

{ This example shows how to redirect a software interrupt by changing the protected mode handler of the DPMI host.

In more detail it hooks interrupt 1Ch which is called every time the timer interrupt (int 08) is executed. This is the preferred way to hook the timer, because int 1Ch is a software interrupt which doesn't need so much initialization stuff compared to hooking a hardware interrupt.

}

uses

```

    crt ,
    go32;

const
    { interrupt number we want to hook }
    int1c = $1c;

var
    { 48 bit pointer to old interrupt handler }
    oldint1c : tseinfo;
    { 48 bit pointer to new interrupt handler }
    newint1c : tseinfo;

    { increased every time the interrupt is called }
    int1c_counter : Longint;

    { the current data selector }
    int1c_ds : Word; external name '___v2prt0_ds_alias';

    { the actual handler code }
procedure int1c_handler; assembler;
asm
    cli
    { save all registers }
    pushw %ds
    pushw %ax
    { prepare segment registers for FPC procedure }
    movw %cs:int1c_ds, %ax
    movw %ax, %ds
    { simply increase the counter by one }
    incl int1c_counter
    { restore registers }
    popw %ax
    popw %ds
    sti
    iret
end;

var i : Longint;

begin
    { insert right handler data into new handler variable }
    newint1c.offset := @int1c_handler;
    newint1c.segment := get_cs;
    { get the old handler }
    get_pm_interrupt(int1c, oldint1c);
    Writeln('— Press any key to exit —');
    { set new handler }
    set_pm_interrupt(int1c, newint1c);
    { write the number of interrupts occurred }
    while (not keypressed) do begin
        gotoxy(1, wherey);
        write('Number of interrupts occurred : ', int1c_counter);
    end;
    { restore old handler }
    set_pm_interrupt(int1c, oldint1c);
end.

```

54.19.58 set_rm_interrupt

Synopsis: Set real mode interrupt handler

Declaration: `function set_rm_interrupt(vector: Byte; const intaddr: tseginfo)
: Boolean`

Visibility: default

Description: Sets a real mode interrupt handler.

Parameters:

vector the interrupt vector number to set.

intaddr address of new interrupt vector.

Return values: True if successful, otherwise False.

Remark: The address supplied MUST be a real mode segment address, not a `selector:offset` address. So the interrupt handler must either reside in dos memory (below 1 Mb boundary) or the application must allocate a real mode callback address with `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `get_rm_interrupt` (751), `set_pm_interrupt` (765), `get_pm_interrupt` (746), `get_rm_callback` (747)

54.19.59 set_segment_base_address

Synopsis: Set descriptor's base address

Declaration: `function set_segment_base_address(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the 32-bit linear base address of a descriptor.

Parameters:

d selector.

s new base address of the descriptor.

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `get_segment_base_address` (753), `allocate_ldt_descriptors` (735), `set_segment_limit` (767), `get_segment_base_address` (753), `get_segment_limit` (753)

54.19.60 set_segment_limit

Synopsis: Set descriptor limit

Declaration: `function set_segment_limit(d: Word; s: DWord) : Boolean`

Visibility: default

Description: Sets the limit of a descriptor.

Parameters:

d selector.

s new limit of the descriptor.

Return values: Returns `True` if successful, else `False`.

Remark: The new limit specified must be the byte length of the segment - 1. Segment limits bigger than or equal to 1MB must be page aligned, they must have the lower 12 bits set.

For an example, see `allocate_ldt_descriptors` (735).

Errors: Check the `int31error` (734) variable.

See also: `allocate_ldt_descriptors` (735), `set_segment_base_address` (767), `get_segment_limit` (753), `set_segment_limit` (767)

54.19.61 `tb_offset`

Synopsis: Return DOS transfer buffer offset

Declaration: `function tb_offset : LongInt`

Visibility: default

Description: `tb_offset` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (769), `tb_segment` (768), `tb_size` (768)

54.19.62 `tb_segment`

Synopsis: Return DOS transfer buffer segment

Declaration: `function tb_segment : LongInt`

Visibility: default

Description: `tb_segment` returns the DOS transfer buffer segment.

See also: `transfer_buffer` (769), `tb_offset` (768), `tb_size` (768)

54.19.63 `tb_size`

Synopsis: Return DOS transfer memory buffer size

Declaration: `function tb_size : LongInt`

Visibility: default

Description: Returns the size of the pre-allocated dos memory buffer.

Return values: The size of the pre-allocated dos memory buffer. This block always seems to be 16k in size, but don't rely on this.

Errors: None.

See also: `transfer_buffer` (769), `copyfromdos` (738), `copytodos` (739)

54.19.64 transfer_buffer

Synopsis: Return offset of DOS transfer buffer

Declaration: `function transfer_buffer : LongInt`

Visibility: default

Description: `transfer_buffer` returns the offset of the transfer buffer.

Errors: None.

See also: `tb_size` (768)

54.19.65 unlock_code

Synopsis: Unlock code segment

Declaration: `function unlock_code(functionaddr: pointer; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the code segment selector.

Parameters:

functionaddr address of function to be unlocked.

size size bytes to be unlocked.

Return value: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `unlock_linear_region` (770), `unlock_data` (769), `lock_linear_region` (758), `lock_data` (758), `lock_code` (758)

54.19.66 unlock_data

Synopsis: Unlock data segment

Declaration: `function unlock_data(var data; size: LongInt) : Boolean`

Visibility: default

Description: Unlocks a memory range which resides in the data segment selector.

Parameters:

data address of memory to be unlocked.

size size bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

For an example, see `get_rm_callback` (747).

Errors: Check the `int31error` (734) variable.

See also: `unlock_linear_region` (770), `unlock_code` (769), `lock_linear_region` (758), `lock_data` (758), `lock_code` (758)

54.19.67 unlock_linear_region

Synopsis: Unlock linear memory region

Declaration: `function unlock_linear_region(linearaddr: LongInt; size: LongInt)
: Boolean`

Visibility: default

Description: Unlocks a previously locked linear region range to allow it to be swapped out again if needed.

Parameters:

linearaddrlinear address of the memory to be unlocked.

sizesize bytes to be unlocked.

Return values: `True` if successful, `False` otherwise.

Errors: Check the `int31error` (734) variable.

See also: `unlock_data` (769), `unlock_code` (769), `lock_linear_region` (758), `lock_data` (758), `lock_code` (758)

Chapter 55

Reference for unit 'gpm'

55.1 Used units

Table 55.1: Used units by unit 'gpm'

Name	Page
BaseUnix	124
System	1194

55.2 Overview

The GPM unit implements an interface to `libgpm`, the console program for mouse handling. This unit was created by Peter Vreman, and is only available on Linux.

When this unit is used, your program is linked to the C libraries, so you must take care of the C library version. Also, it will only work with version 1.17 or higher of the `libgpm` library.

55.3 Constants, types and variables

55.3.1 Constants

`GPM_BOT` = 2

Bottom of area.

`GPM_B_LEFT` = 4

Left mouse button identifier.

`GPM_B_MIDDLE` = 2

Middle mouse button identifier.

`GPM_B_RIGHT` = 1

Right mouse button identifier.

GPM_DOUBLE = 32

Mouse double click event.

GPM_DOWN = 4

Mouse button down event.

GPM_DRAG = 2

Mouse drag event.

GPM_ENTER = 512

Enter area event.

GPM_HARD = 256

?

GPM_LEAVE = 1024

Leave area event.

GPM_LEFT = 4

Left side of area.

GPM_MAGIC = \$47706D4C

Constant identifying GPM in Gpm_Open ([779](#)).

GPM_MFLAG = 128

Motion flag.

GPM_MOVE = 1

Mouse move event.

GPM_NODE_CTL = GPM_NODE_DEV

Control socket

GPM_NODE_DEV = '/dev/gpmctl'

Device socket filename

GPM_NODE_DIR = _PATH_VARRUN

Where to write socket.

`GPM_NODE_DIR_MODE = 0775`

Mode of socket.

`GPM_NODE_FIFO = '/dev/gpmdata'`

FIFO name

`GPM_NODE_PID = '/var/run/gpm.pid'`

Name of PID file.

`GPM_RGT = 8`

Right side of area.

`GPM_SINGLE = 16`

Mouse single click event.

`GPM_TOP = 1`

Top of area.

`GPM_TRIPLE = 64`

Mouse triple click event.

`GPM_UP = 8`

Mouse button up event.

`_PATH_DEV = '/dev/'`

Location of `/dev` directory.

`_PATH_VARRUN = '/var/run/'`

Location of run PID files directory.

55.3.2 Types

`Pgpmconnect = Pgpm_connect`

Pointer to `TGpmConnect` (774) record.

`Pgpmevent = Pgpm_event`

Pointer to TGpmEvent (774) record

```
Pgpmroi = Pgpm_roi
```

Pointer to TGpmRoi (774) record.

```
Pgpm_connect = ^TGpm_connect
```

Pointer to TGpm_Connect (775) record.

```
Pgpm_event = ^Tgpm_event
```

Pointer to TGpm_Event (775) record

```
Pgpm_roi = ^Tgpm_roi
```

Pointer to Tgpm_roi (775) record.

```
Tgpmconnect = Tgpm_connect
```

Alias for TGpm_Connect (775) record.

```
TGpmEtype = LongInt
```

Type for event type.

```
Tgpmevent = Tgpm_event
```

Alias for TGPM_EVent (775) record

```
TGpmHandler = function(var event: Tgpmevent; clientdata: pointer)
    : LongInt
```

Mouse event handler callback.

```
TGpmMargin = LongInt
```

Type to hold area margin.

```
Tgpmroi = Tgpm_roi
```

Alias for TGpm_roi (775)Record

```
Tgpm_connect = record
    eventMask : Word;
    defaultMask : Word;
    minMod : Word;
    maxMod : Word;
    pid : LongInt;
    vc : LongInt;
end
```

GPM server connection information.

```
Tgpm_event = record
  buttons : Byte;
  modifiers : Byte;
  vc : Word
;
  dx : Word;
  dy : Word;
  x : Word;
  y : Word;
  EventType :
  TGpmEtype;
  clicks : LongInt;
  margin : TGpmMargin;
  wdx : Word
;
  wdy : Word;
end
```

Tgpm_event describes the events that are reported by GPM.

```
Tgpm_roi = record
  xmin : Integer;
  xmax : Integer;
  ymin : Integer
;
  ymax : Integer;
  minmod : Word;
  maxmod : Word;
  eventmask
  : Word;
  owned : Word;
  handler : TGpmHandler;
  clientdata : pointer
;
  prev : Pgpm_roi;
  next : Pgpm_roi;
end
```

Record used to define regions of interest.

55.3.3 Variables

gpm_current_roi : Pgpm_roi

Internal gpm library variable. Do not use.

gpm_handler : TGpmHandler

Internal gpm library variable. Do not use.

gpm_roi : Pgpm_roi

Internal gpm library variable. Do not use.

`gpm_roi_data` : pointer

Internal gpm library variable. Do not use.

`gpm_roi_handler` : TGpmHandler

Internal gpm library variable. Do not use.

55.4 Procedures and functions

55.4.1 Gpm_AnyDouble

Synopsis: Check whether event has double click event.

Declaration: `function Gpm_AnyDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnyDouble` returns True if `EventType` contains the `GPM_DOUBLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (781), `Gpm_AnySingle` (776), `Gpm_StrictDouble` (781), `Gpm_StrictTriple` (781), `Gpm_AnyTriple` (776)

55.4.2 Gpm_AnySingle

Synopsis: Check whether event has a single click event.

Declaration: `function Gpm_AnySingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_SINGLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (781), `Gpm_AnyDouble` (776), `Gpm_StrictDouble` (781), `Gpm_StrictTriple` (781), `Gpm_AnyTriple` (776)

55.4.3 Gpm_AnyTriple

Synopsis: Check whether event has a triple click event.

Declaration: `function Gpm_AnyTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_AnySingle` returns True if `EventType` contains the `GPM_TRIPLE` flag, False otherwise.

Errors: None.

See also: `Gpm_StrictSingle` (781), `Gpm_AnyDouble` (776), `Gpm_StrictDouble` (781), `Gpm_StrictTriple` (781), `Gpm_AnySingle` (776)

55.4.4 gpm_close

Synopsis: Close connection to GPM server.

Declaration: `function gpm_close : LongInt`

Visibility: default

Description: `Gpm_Close` closes the current connection, and pops the connection stack; this means that the previous connection becomes active again.

The function returns -1 if the current connection is not the last one, and it returns 0 if the current connection is the last one.

for an example, see `Gpm_GetEvent` (777).

Errors: None.

See also: `Gpm_Open` (779)

55.4.5 gpm_fitvalues

Synopsis: Change coordinates to fit physical screen.

Declaration: `function gpm_fitvalues(var x: LongInt; var y: LongInt) : LongInt`

Visibility: default

Description: `Gpm_fitValues` changes `x` and `y` so they fit in the visible screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValuesM` (777)

55.4.6 gpm_fitvaluesM

Synopsis: Change coordinates to fit margin.

Declaration: `function gpm_fitvaluesM(var x: LongInt; var y: LongInt; margin: LongInt) : LongInt`

Visibility: default

Description: `Gpm_FitValuesM` changes `x` and `y` so they fit in the margin indicated by `margin`. If `margin` is -1, then the values are fitted to the screen. The actual mouse pointer is not affected by this function.

Errors: None.

See also: `Gpm_FitValues` (777)

55.4.7 gpm_getevent

Synopsis: Get event from event queue.

Declaration: `function gpm_getevent(var event: Tgpm_event) : LongInt`

Visibility: default

Description: `Gpm_GetEvent` Reads an event from the file descriptor `gpm_fd`. This file is only for internal use and should never be called by a client application.

It returns 1 on succes, and -1 on failue.

Errors: On error, -1 is returned.

See also: `Gpm_GetSnapshot` ([779](#))

Listing: `./gpmex/gpmex.pp`

```

program gpmex;

{
  Example program to demonstrate the use of the gpm unit.
}

uses gpm;

var
  connect : TGPMConnect;
  event : tgpmevent;

begin
  connect.EventMask:=GPM_MOVE or GPM_DRAG or GPM_DOWN or GPM_UP;
  connect.DefaultMask:=0;
  connect.MinMod:=0;
  connect.MaxMod:=0;
  if Gpm_Open(connect,0)=-1 then
    begin
      Writeln('No mouse handler present. ');
      Halt(1);
    end;
  Writeln('Click right button to end. ');
  Repeat
    gpm_getevent(Event);
    With Event do
      begin
        Write('Pos = (',X,',',',Y,') Buttons : ( ');
        if (buttons and Gpm_b_left)<>0 then
          write('left ');
        if (buttons and Gpm_b_right)<>0 then
          write('right ');
        if (buttons and Gpm_b_middle)<>0 then
          Write('middle ');
        Write(') Event : ');
        Case EventType and $F of
          GPM_MOVE: write('Move');
          GPM_DRAG: write('Drag');
          GPM_DOWN: write('Down');
          GPM_UP: write('Up');
        end;
        Writeln;
      end;
    Until (Event.Buttons and gpm_b_right)<>0;
    gpm_close;
  end.

```

55.4.8 gpm_getsnapshot

Synopsis: Return servers' current image of mouse state.

Declaration: `function gpm_getsnapshot (eptr: Pgpmevent) : LongInt`
`function gpm_getsnapshot (var eptr: Tgpmevent) : LongInt`

Visibility: default

Description: `Gpm_GetSnapshot` returns the picture that the server has of the current situation in `Event`. This call will not read the current situation from the mouse file descriptor, but returns a buffered version.

The function returns the number of mouse buttons, or -1 if this information is not available.

Errors: None.

See also: `Gpm_GetEvent` ([777](#))

55.4.9 gpm_lowerroi

Synopsis: Lower a region of interest in the stack.

Declaration: `function gpm_lowerroi (which: Pgpm_roi; after: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_LowerRoi` lowers the region of interest `which` after `after`. If `after` is `Nil`, the region of interest is moved to the bottom of the stack.

The return value is the new top of the region-of-interest stack.

Errors: None.

See also: `Gpm_RaiseRoi` ([780](#)), `Gpm_PopRoi` ([780](#)), `Gpm_PushRoi` ([780](#))

55.4.10 gpm_open

Synopsis: Open connection to GPM server.

Declaration: `function gpm_open (var conn: Tgpm_connect; flag: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Open` opens a new connection to the mouse server. The connection is described by the fields of the `conn` record of type `TGPMConnect` ([774](#)).

if `Flag` is 0, then the application only receives events that come from its own terminal device. If it is negative it will receive all events. If the value is positive then it is considered a console number to which to connect.

The return value is -1 on error, or the file descriptor used to communicate with the client. Under an X-Term the return value is -2.

for an example, see `Gpm_GetEvent` ([777](#)).

Errors: On Error, the return value is -1.

See also: `Gpm_Open` ([779](#))

55.4.11 gpm_poproi

Synopsis: Pop region of interest from the stack.

Declaration: `function gpm_poproi(which: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_PopRoi` pops the topmost region of interest from the stack. It returns the next element on the stack, or `Nil` if the current element was the last one.

Errors: None.

See also: `Gpm_RaiseRoi` (780), `Gpm_LowerRoi` (779), `Gpm_PushRoi` (780)

55.4.12 gpm_pushroi

Synopsis: Push region of interest on the stack.

Declaration: `function gpm_pushroi(x1: LongInt; y1: LongInt; x2: LongInt;
y2: LongInt; mask: LongInt; fun: TGpmHandler;
xtradata: pointer) : Pgpm_roi`

Visibility: default

Description: `Gpm_PushRoi` puts a new *region of interest* on the stack. The region of interest is defined by a rectangle described by the corners (X1, Y1) and (X2, Y2).

The mask describes which events the handler {fun} will handle; `ExtraData` will be put in the `xtradata` field of the {TGPM_Roi} record passed to the fun handler.

Errors: None.

See also: `Gpm_RaiseRoi` (780), `Gpm_PopRoi` (780), `Gpm_LowerRoi` (779)

55.4.13 gpm_raiseroi

Synopsis: Raise region of interest in the stack.

Declaration: `function gpm_raiseroi(which: Pgpm_roi; before: Pgpm_roi) : Pgpm_roi`

Visibility: default

Description: `Gpm_RaiseRoi` raises the *region of interest* which till it is on top of region before. If before is nil then the region is put on top of the stack. The returned value is the top of the stack.

Errors: None.

See also: `Gpm_PushRoi` (780), `Gpm_PopRoi` (780), `Gpm_LowerRoi` (779)

55.4.14 gpm_repeat

Synopsis: Check for presence of mouse event.

Declaration: `function gpm_repeat(millisecond: LongInt) : LongInt`

Visibility: default

Description: `Gpm_Repeat` returns 1 if no mouse event arrives in the next millisecond, it returns 0 otherwise.

Errors: None.

See also: [Gpm_GetEvent \(777\)](#)

55.4.15 Gpm_StrictDouble

Synopsis: Check whether event contains only a double-click event.

Declaration: `function Gpm_StrictDouble(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictDouble` returns `true` if `EventType` contains only a `doubleclick` event, `False` otherwise.

Errors: None.

See also: [Gpm_StrictSingle \(781\)](#), [Gpm_AnyTriple \(776\)](#), [Gpm_AnyDouble \(776\)](#), [Gpm_StrictTriple \(781\)](#), [Gpm_AnySingle \(776\)](#)

55.4.16 Gpm_StrictSingle

Synopsis: Check whether event contains only a single-click event.

Declaration: `function Gpm_StrictSingle(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictSingle` returns `True` if `EventType` contains only a `singleclick` event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(776\)](#), [Gpm_StrictDouble \(781\)](#), [Gpm_AnyDouble \(776\)](#), [Gpm_StrictTriple \(781\)](#), [Gpm_AnySingle \(776\)](#)

55.4.17 Gpm_StrictTriple

Synopsis: Check whether event contains only a triple-click event.

Declaration: `function Gpm_StrictTriple(EventType: LongInt) : Boolean`

Visibility: default

Description: `Gpm_StrictTriple` returns `true` if `EventType` contains only a `triple click` event, `False` otherwise.

Errors: None.

See also: [Gpm_AnyTriple \(776\)](#), [Gpm_StrictDouble \(781\)](#), [Gpm_AnyDouble \(776\)](#), [Gpm_StrictSingle \(781\)](#), [Gpm_AnySingle \(776\)](#)

Chapter 56

Reference for unit 'Graph'

56.1 Used units

Table 56.1: Used units by unit 'Graph'

Name	Page
System	1194

56.2 Overview

This document describes the `GRAPH` unit for Free Pascal, for all platforms. The unit was first written for dos by Florian Klaempfl, but was later completely rewritten by Carl-Eric Codere to be completely portable. The unit is provided for compatibility only: It is recommended to use more modern graphical systems. The graph unit will allow to recompile old programs. They will work to some extent, but if the application has heavy graphical needs, it's recommended to use another set of graphical routines, suited to the platform the program should work on.

56.3 Categorized functions: Text and font handling

Functions to set texts on the screen.

Table 56.2:

Name	Description
GetTextSettings (824)	Get current text settings
InstallUserFont (827)	Install a new font
OutText (828)	Write text at current cursor position
OutTextXY (815)	Write text at coordinates X,Y
RegisterBGIFont (829)	Register a new font
SetTextJustify (833)	Set text justification
SetTextStyle (833)	Set text style
SetUserCharSize (834)	Set text size
TextHeight (835)	Calculate height of text
TextWidth (835)	Calculate width of text

56.4 Categorized functions: Filled drawings

Functions for drawing filled regions.

Table 56.3:

Name	Description
Bar3D (817)	Draw a filled 3D-style bar
Bar (817)	Draw a filled rectangle
FloodFill (819)	Fill starting from coordinate
FillEllipse (818)	Draw a filled ellipse
FillPoly (819)	Draw a filled polygone
GetFillPattern (821)	Get current fill pattern
GetFillSettings (821)	Get current fill settings
SetFillPattern (831)	Set current fill pattern
SetFillStyle (831)	Set current fill settings

56.5 Categorized functions: Drawing primitives

Functions for simple drawing.

Table 56.4:

Name	Description
Arc (816)	Draw an arc
Circle (814)	Draw a complete circle
DrawPoly (818)	Draw a polygon with N points
Ellipse (818)	Draw an ellipse
GetArcCoords (819)	Get arc coordinates
GetLineSettings (822)	Get current line drawing settings
Line (815)	Draw line between 2 points
LineRel (827)	Draw line relative to current position
LineTo (827)	Draw line from current position to absolute position
MoveRel (828)	Move cursor relative to current position
MoveTo (828)	Move cursor to absolute position
PieSlice (828)	Draw a pie slice
PutPixel (815)	Draw 1 pixel
Rectangle (829)	Draw a non-filled rectangle
Sector (830)	Draw a sector
SetLineStyle (832)	Set current line drawing style

56.6 Categorized functions: Color management

All functions related to color management.

Table 56.5:

Name	Description
GetBkColor (814)	Get current background color
GetColor (820)	Get current foreground color
GetDefaultPalette (820)	Get default palette entries
GetMaxColor (822)	Get maximum valid color
GetPaletteSize (824)	Get size of palette for current mode
GetPixel (814)	Get color of selected pixel
GetPalette (823)	Get palette entry
SetAllPalette (816)	Set all colors in palette
SetBkColor (816)	Set background color
SetColor (830)	Set foreground color
SetPalette (832)	Set palette entry
SetRGBPalette (816)	Set palette entry with RGB values

56.7 Categorized functions: Screen management

General drawing screen management functions.

Table 56.6:

Name	Description
ClearViewPort (814)	Clear the current viewport
GetImage (814)	Copy image from screen to memory
GetMaxX (822)	Get maximum X coordinate
GetMaxY (823)	Get maximum Y coordinate
GetX (824)	Get current X position
GetY (825)	Get current Y position
ImageSize (815)	Get size of selected image
GetViewSettings (824)	Get current viewport settings
PutImage (815)	Copy image from memory to screen
SetActivePage (816)	Set active video page
SetAspectRatio (830)	Set aspect ratio for drawing routines
SetViewPort (834)	Set current viewport
SetVisualPage (816)	Set visual page
SetWriteMode (834)	Set write mode for screen operations

56.8 Categorized functions: Initialization

Initialization of the graphics screen.

Table 56.7:

Name	Description
ClearDevice (817)	Empty the graphics screen
CloseGraph (817)	Finish drawing session, return to text mode
DetectGraph (818)	Detect graphical modes
GetAspectRatio (820)	Get aspect ratio of screen
GetModeRange (823)	Get range of valid modes for current driver
GraphDefaults (1)	Set defaults
GetDriverName (821)	Return name of graphical driver
GetGraphMode (821)	Return current or last used graphics mode
GetMaxMode (822)	Get maximum mode for current driver
GetModeName (823)	Get name of current mode
GraphErrorMsg (1)	String representation of graphical error
GraphResult (1)	Result of last drawing operation
InitGraph (826)	Initialize graphics drivers
InstallUserDriver (826)	Install a new driver
RegisterBGIDriver (829)	Register a new driver
RestoreCRTMode (830)	Go back to text mode
SetGraphMode (832)	Set graphical mode

56.9 Target specific issues: Linux

There are several issues on Linux that need to be taken care of:

The Linux version of the Graph unit uses the libvga library. This library works on the console, not under X.

If you get an error similar to

```
/usr/bin/ld: cannot find -lvga
```

This can mean one of two things: either `libvga` and its development package is not installed properly, or the directory where it is installed is not in the linker path.

To remedy the former, you should install both the `libvga` package and `libvga-devel` package (or compile and install from scratch).

To remedy the latter, you should add the path to the compiler command-line using the `-F1` option.

Programs using `libvga` need root privileges to run. You can make them `setuid` root with the following command:

```
chown root.root myprogram
chmod u+s myprogram
```

The `libvga` library will give up the root privileges after it is initialized.

there is an experimental version of the Graphics library available that uses GGI to do all the drawing, but it is not well tested. It's called `ggigraph` and is distributed in source form only.

Do not use the CRT unit together with the Graph unit: the console may end up in an unusable state. Instead, the `ncurses` unit may function fine.

56.10 Target specific issues: DOS

VESA modes (i.e., anything but 320x200x256 and 640x480x16) do not work under most installations of Windows NT, Windows 2000 and Windows XP. They also do not work for some people under Windows 98 and Windows ME, depending on their graphics drivers. However, the graph unit cannot detect this, because no errors are returned from the system. In such cases, the screen simply turns black, or will show garbage.

Nothing can be done about this, the reason is missing or buggy support in the graphics drivers of the operating system.

56.11 A word about mode selection

The graph unit was implemented for compatibility with the old Turbo Pascal graph unit. For this reason, the mode constants as they were defined in the Turbo Pascal graph unit are retained.

However, since

1. Video cards have evolved very much
2. Free Pascal runs on multiple platforms

it was decided to implement new mode and graphic driver constants, which are more independent of the specific platform the program runs on.

In this section we give a short explanation of the new mode system. the following drivers were defined:

```
D1bit = 11;
D2bit = 12;
```

```

D4bit = 13;
D6bit = 14; { 64 colors Half-brite mode - Amiga }
D8bit = 15;
D12bit = 16; { 4096 color modes HAM mode - Amiga }
D15bit = 17;
D16bit = 18;
D24bit = 19; { not yet supported }
D32bit = 20; { not yet supported }
D64bit = 21; { not yet supported }

lowNewDriver = 11;
highNewDriver = 21;

```

Each of these drivers specifies a desired color-depth.

The following modes have been defined:

```

detectMode = 30000;
m320x200 = 30001;
m320x256 = 30002; { amiga resolution (PAL) }
m320x400 = 30003; { amiga/atari resolution }
m512x384 = 30004; { mac resolution }
m640x200 = 30005; { vga resolution }
m640x256 = 30006; { amiga resolution (PAL) }
m640x350 = 30007; { vga resolution }
m640x400 = 30008;
m640x480 = 30009;
m800x600 = 30010;
m832x624 = 30011; { mac resolution }
m1024x768 = 30012;
m1280x1024 = 30013;
m1600x1200 = 30014;
m2048x1536 = 30015;

lowNewMode = 30001;
highNewMode = 30015;

```

These modes start at 30000 because Borland specified that the mode number should be ascending with increasing X resolution, and the new constants shouldn't interfere with the old ones.

The above constants can be used to set a certain color depth and resolution, as demonstrated in the below example.

If other modes than the ones above are supported by the graphics card, you will not be able to select them with this mechanism.

For this reason, there is also a 'dynamic' mode number, which is assigned at run-time. This number increases with increasing X resolution. It can be queried with the `getmoderange` call. This call will return the range of modes which are valid for a certain graphics driver. The numbers are guaranteed to be consecutive, and can be used to search for a certain resolution, as in the second example below.

Thus, the `getmoderange` function can be used to detect all available modes and drivers, as in the third example below:

Listing: `./graphex/inigraph1.pp`

Program `inigraph1 ;`

```
{ Program to demonstrate static graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue) ';
```

```
var
```

```
  gd, gm, lo, hi, error, tw, th: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }  
  gd := D8bit;  
  gm := m640x480;  
  initgraph(gd, gm, ' ');  
  { Make sure you always check graphresult! }  
  error := graphResult;  
  if (error <> grOk) Then  
    begin  
      writeln( '640x480x256 is not supported!' );  
      halt(1)  
    end;  
  { We are now in 640x480x256 }  
  setColor(cyan);  
  rectangle(0,0,getmaxx,getmaxy);  
  { Write a nice message in the center of the screen }  
  setTextStyle(defaultFont, horizDir, 1);  
  tw := TextWidth(TheLine);  
  th := TextHeight(TheLine);  
  outTextXY((getMaxX - TW) div 2,  
            (getMaxY - TH) div 2, TheLine);  
  { Wait for return }  
  readln;  
  { Back to text mode }  
  closegraph;
```

```
end.
```

Listing: ./graphex/inigraph2.pp

Program inigraph2;

```
{ Program to demonstrate dynamic graphics mode selection }
```

```
uses graph;
```

```
const
```

```
  TheLine = 'We are now in 640 x 480 x 256 colors!' +  
            ' (press <Return> to continue) ';
```

```
var
```

```
  th, tw, gd, gm, lo, hi, error: integer;  
  found: boolean;
```

```
begin
```

```
  { We want an 8 bit mode }
```

```

gd := D8bit;
{ Get all available resolutions for this bitdepth }
getmoderange(gd, lo, hi);
{ If the highest available mode number is -1,
  no resolutions are supported for this bitdepth }
if hi = -1 then
  begin
    writeln('no 8 bit modes supported!');
    halt
  end;
found := false;
{ Search all resolutions for 640x480 }
for gm := lo to hi do
  begin
    initgraph(gd, gm, '');
    { Make sure you always check graphresult! }
    error := graphResult;
    if (error = grOk) and
      (getmaxx = 639) and (getmaxy = 479) then
      begin
        found := true;
        break;
      end;
  end;
if not found then
  CloseGraph();
  begin
    writeln('640x480x256 is not supported!');
    halt(1)
  end;
{ We are now in 640x480x256 }
setColor(cyan);
rectangle(0,0,getmaxx,getmaxy);
{ Write a nice message in the center of the screen }
setTextStyle(defaultFont, horizDir, 1);
TW:=TextWidth(TheLine);
TH:=TextHeight(TheLine);
outTextXY((getMaxX - TW) div 2,
          (getMaxY - TH) div 2, TheLine);
{ Wait for return }
readln;
{ Back to text mode }
closegraph;
end.

```

Listing: ./graphex/modrange.pp

Program GetModeRange_Example;

```
{ This program demonstrates how to find all available graph modes }
```

```
uses graph;
```

```
const
```

```

{ Currently, only 4, 8, 15 and 16 bit modes are supported
  but this may change in the future }
gdnames: array[D4bit..D16bit] of string[6] =
  ('4 bit', '6 bit', '8 bit', '12 bit', '15 bit', '16 bit');
```

```

procedure WriteRes(const depth : integer);
var
    tw, th : integer;
    v, text : String;
begin
    text := 'Current resolution is '; str(getmaxx+1, v);
    text := text + v + 'x'; str(getmaxy+1, v);
    text := text + v + 'x' + gdnames[depth];
    setTextStyle(defaultFont, horizDir, 1);
    TW:=TextWidth(text);
    TH:=TextHeight(text);
    outTextXY((getMaxX - TW) div 2,
              (getMaxY - TH) div 2, text);
end;

var
    t: text;
    line : string;
    gd, c, low, high, res: integer;
begin
    assign(t, 'modes.txt');
    rewrite(t);
    close(t);
    for gd := D4bit to D16bit do
        begin
            { Get the available mode numbers for this driver }
            getModeRange(gd, low, high);
            append(t);
            write(t, gdnames[gd]);
            writeln(t, ': low modenr = ', low, ', high modenr = ', high);
            close(t);
            { If high is -1,
              no resolutions are supported for this bitdepth }
            if high = -1 then
                begin
                    append(t);
                    writeln(t, ' No modes supported!');
                    writeln(t);
                    close(t);
                end
            else
                { Enter all supported resolutions for this bitdepth
                  and write their characteristics to the file }
                for c := low to high do
                    begin
                        append(t);
                        writeln(t, ' testing mode nr ', c);
                        close(t);
                        initgraph(gd, c, '');
                        res := graphresult;
                        append(t);
                        { An error occurred when entering the mode? }
                        if res <> grok then
                            writeln(t, grapherrormsg(res))
                        else
                            begin
                                write(t, 'maxx: ', getmaxx, ', maxy: ', getmaxy);

```

```

        Writeln(t, ', maxcolor: ', getmaxcolor);
        closegraph;
    end;
    writeln(t);
    WriteRes(gd);
    close(t);
    end;
    append(t);
    writeln(t);
    close(t);
    end;
    Writeln('All supported modes are listed in modes.txt files');
end.

```

56.12 Requirements

The unit Graph exports functions and procedures for graphical output. It requires at least a VGA-compatible Card or a VGA-Card with software-driver (min. **512Kb** video memory).

56.13 Constants, types and variables

56.13.1 Constants

AndPut = 3

Draw operation: use AND

```

AnsiToASCIITransTable : TCharsetTransTable = (#$00, #$01, #$02, #
    $03, #$04, #$05, #$06, #$07, #$08, #$09, #$0a, #$0b, #$0c, #$0d,
    #$0e, #$0f, #$10, #$11, #$12, #$13, #$14, #$15, #$16, #$17, #$18,
    #$19, #$1a, #$1b, #$1c, #$1d, #$1e, #$1f, #$20, #$21, #$22, #$23
    , #$24, #$25, #$26, #$27, #$28, #$29, #$2a, #$2b, #$2c, #$2d, #$2e
    , #$2f, #$30, #$31, #$32, #$33, #$34, #$35, #$36, #$37, #$38, #$39
    , #$3a, #$3b, #$3c, #$3d, #$3e, #$3f, #$40, #$41, #$42, #$43, #$44
    , #$45, #$46, #$47, #$48, #$49, #$4a, #$4b, #$4c, #$4d, #$4e, #$4f
    , #$50, #$51, #$52, #$53, #$54, #$55, #$56, #$57, #$58, #$59, #$5a
    , #$5b, #$5c, #$5d, #$5e, #$5f, #$60, #$61, #$62, #$63, #$64, #$65
    , #$66, #$67, #$68, #$69, #$6a, #$6b, #$6c, #$6d, #$6e, #$6f, #$70
    , #$71, #$72, #$73, #$74, #$75, #$76, #$77, #$78, #$79, #$7a, #$7b
    , #$7c, #$7d, #$7e, #$7f, '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?',
    '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '?', '$ff', '$ad
    , '$9b, '$9c, '?', '$9d, '?', '?', '?', '?', '$a6, '$ae, '$aa, '?'
    , '?', '?', '$f8, '$f1, '$fd, '?', '?', '$e6, '?', '$fa, '?', '?'
    , '$a7, '$af, '$ac, '$ab, '?', '$a8, '?', '?', '?', '?', '$8e, '$8f
    , '$92, '$80, '?', '$90, '?', '?', '?', '?', '?', '?', '?', '$a5,
    '?', '?', '?', '?', '$99, '?', '?', '?', '?', '?', '$9a, '?', '?'
    , '$e1, '$85, '$a0, '$83, '?', '$84, '$86, '$91, '$87, '$8a, '$82
    , '$88, '$89, '$8d, '$a1, '$8c, '$8b, '?', '$a4, '$95, '$a2, '$93
    , '?', '$94, '$f6, '?', '$97, '$a3, '$96, '$81, '?', '?', '$98)

```

Default ansi transliteration table.

BkSlashFill = 5

Fill style: Diagonal (backslash) lines

black = 0

Color code: black.

blue = 1

Color code: blue

BoldFont = 10

Font number: Bold font.

BottomText = 0

Vertical text alignment: Align text to bottom

brown = 6

Color code: brown

CenterLn = 2

Line style: centered line

CenterText = 1

Horizontal text alignment: Center text

CGA = 1

Graphic driver for CGA cards

CGAC0 = 0

CGA Graphic driver mode C0

CGAC1 = 1

CGA Graphic driver mode C1

CGAC2 = 2

CGA Graphic driver mode C2

CGAC3 = 3

CGA Graphic driver mode C3

CGAHi = 4

CGA Graphic driver Hi-res mode

ClipOff = False

Viewport clipping off

ClipOn = True

Viewport clipping on

CloseDotFill = 11

Fill style: Closely spaced dotted lines

CopyPut = 0

Draw operation: use Copy

CurrentDriver = -128

Currently used driver

cyan = 3

Color code: Cyan

D12bit = 16

Mode: Depth 12 bit

D15bit = 17

Mode: Depth 15 bit

D16bit = 18

Mode: Depth 16 bit

D1bit = 11

Mode: Depth 1 bit

D24bit = 19

Mode: Depth 24 bit

D2bit = 12

Mode: Depth 2 bit

D32bit = 20

Mode: Depth 32 bit

D4bit = 13

Mode: Depth 4 bit

D64bit = 21

Mode: Depth 64 bit

D6bit = 14

Mode: Depth 6 bit

D8bit = 15

Mode: Depth 8 bit

darkgray = 8

Color code: Dark gray

DashedLn = 3

Line style: dashed line

Default = 0

Default mode

DefaultFont = 0

Font number: Normal font

Detect = 0

Mode: Detect mode.

detectMode = 30000

Mode: Autodetect optimal mode

DottedLn = 1

Line style: Dotted line

DrawTextBackground : Boolean = False

Should the background of texts be drawn or should it be left untouched ?

EGA = 3

Graphic driver for EGA cards

EGA64 = 4

Graphic driver for EGA 64 cards

EGA64Hi = 1

EGA64 graphic driver high resolution mode

EGA64Lo = 0

EGA64 graphic driver low resolution mode

EGABlack = 0

Color code: EGA Black

EGABlue = 1

Color code: EGA blue

EGABrown = 20

Color code: EGA brown

EGACyan = 3

Color code: EGA cyan

EGADarkgray = 56

Color code: EGA dark gray

EGAGreen = 2

Color code: EGA green

EGAHi = 1

EGA graphic driver high resolution mode

EGALightblue = 57

Color code: EGA Light blue

EGALightcyan = 59

Color code: EGA Light cyan

EGALightgray = 7

Color code: EGA Light gray

EGALightgreen = 58

Color code: EGA Light green

EGALightmagenta = 61

Color code: EGA light magenta

EGALightred = 60

Color code: EGA light red

EGALo = 0

EGA graphic driver low resolution mode

EGAMagenta = 5

Color code: EGA magenta

EGAMono = 5

Graphic driver for EGA monochrome cards

EGAMonoHi = 3

EGAMono graphic driver high resolution mode

EGARed = 4

Color code: EGA red

EGAWhite = 63

Color code: EGA white

EGAYellow = 62

Color code: EGA yellow

EmptyFill = 0

Fill style: Do not fill

EuroFont = 9

Font number: ?

```
fillpatternTable : Array[0..12] of FillPatternType = (($00, $00,
    $00, $00, $00, $00, $00, $00), ($ff, $ff, $ff, $ff, $ff, $ff, $ff
    , $ff), ($ff, $ff, $00, $00, $ff, $ff, $00, $00), ($01, $02, $04,
    $08, $10, $20, $40, $80), ($07, $0e, $1c, $38, $70, $e0, $c1, $83
    ), ($07, $83, $c1, $e0, $70, $38, $1c, $0e), ($5a, $2d, $96, $4b,
    $a5, $d2, $69, $b4), ($ff, $88, $88, $88, $ff, $88, $88, $88), (
    $18, $24, $42, $81, $81, $42, $24, $18), ($cc, $33, $cc, $33, $cc
    , $33, $cc, $33), ($80, $00, $08, $00, $80, $00, $08, $00), ($88,
    $00, $22, $00, $88, $00, $22, $00), (0, 0, 0, 0, 0, 0, 0, 0))
```

Table with standard fill patterns

G1024x768x16 = 30

Mode: Resolution 1024x768, 16 colors

G1024x768x16M = 25

Mode: Resolution 1024x768, 16M colors

G1024x768x16M32 = 36

Mode: Resolution 1024x758, 16M 32-bit colors

G1024x768x256 = 12

Mode: Resolution 1024x768, 256 colors

G1024x768x32K = 23

Mode: Resolution 1024x768, 32K colors

G1024x768x64K = 24

Mode: Resolution 1024x768, 64K colors

G1152x864x16 = 38

Mode: Resolution 1152x864, 16 colors

G1152x864x16M = 42

Mode: Resolution 1152x864, 16M colors

G1152x864x16M32 = 43

Mode: Resolution 1152x864, 16M 32-bitcolors

G1152x864x256 = 39

Mode: Resolution 1152x864, 256 colors

G1152x864x32K = 40

Mode: Resolution 1152x864, 32K colors

G1152x864x64K = 41

Mode: Resolution 1152x864, 64K colors

G1280x1024x16 = 31

Mode: Resolution 1280x1024, 16 colors

G1280x1024x16M = 28

Mode: Resolution 1280x1024, 16M colors

G1280x1024x16M32 = 37

Mode: Resolution 1280x1024, 16M 32-bit colors

G1280x1024x256 = 13

Mode: Resolution 1280x1024, 256 colors

G1280x1024x32K = 26

Mode: Resolution 1280x1024, 32K colors

G1280x1024x64K = 27

Mode: Resolution 1280x1024, 64K colors

G1600x1200x16 = 44

Mode: Resolution 1600x1200, 16 colors

G1600x1200x16M = 48

Mode: Resolution 1600x1200, 16M colors

G1600x1200x16M32 = 49

Mode: Resolution 1600x1200, 16M 32-bit colors

G1600x1200x256 = 45

Mode: Resolution 1600x1200, 256 colors

G1600x1200x32K = 46

Mode: Resolution 1600x1200, 32K colors

G1600x1200x64K = 47

Mode: Resolution 1600x1200, 64K colors

G320x200x16 = 1

Mode: Resolution 320x200, 16 colors

G320x200x16M = 16

Mode: Resolution 320x200, 16M colors

G320x200x16M32 = 33

Mode: Resolution 320x200, 16M 32-bit colors

G320x200x256 = 5

Mode: Resolution 320x200, 256 colors

G320x200x32K = 14

Mode: Resolution 320x200, 32K colors

G320x200x64K = 15

Mode: Resolution 320x200, 64K colors

G320x240x256 = 6

Mode: Resolution 320x240, 256 colors

G320x400x256 = 7

Mode: Resolution 320x400, 256 colors

G360x480x256 = 8

Mode: Resolution 360x480, 256 colors

G640x200x16 = 2

Mode: Resolution x, colors

G640x350x16 = 3

Mode: Resolution x, colors

G640x480x16 = 4

Mode: Resolution x, colors

G640x480x16M = 19

Mode: Resolution 640x480, 16M colors

G640x480x16M32 = 34

Mode: Resolution 640x480, 16M 32-bit colors

G640x480x2 = 9

Mode: Resolution 640x480, 2 colors

G640x480x256 = 10

Mode: Resolution 640x480, 256 colors

G640x480x32K = 17

Mode: Resolution 640x480, 32K colors

G640x480x64K = 18

Mode: Resolution 640x480, 64K colors

G720x348x2 = 32

Mode: Resolution 720x348, 2 colors

G800x600x16 = 29

Mode: Resolution 800x600, 16 colors

G800x600x16M = 22

Mode: Resolution 800x600, 16M colors

G800x600x16M32 = 35

Mode: Resolution 800x600, 16M 32-bit colors

G800x600x256 = 11

Mode: Resolution 800x600, 256 colors

G800x600x32K = 20

Mode: Resolution 800x600, 32K colors

G800x600x64K = 21

Mode: Resolution 800x600, 64K colors

GothicFont = 4

Font number: Gothic font

GraphStringTransTable : PCharsetTransTable = Nil

Table used when transliterating strings.

green = 2

Color code: green

grError = -11

Error: Unknown error.

grFileNotFound = -3

Error: File for driver not found.

grFontNotFound = -8

Error: font description file not found.

grInvalidDriver = -4

Error: Invalid driver specified

grInvalidFont = -13

Error: Invalid font description

grInvalidFontNum = -14

Error: Invalid font number

grInvalidMode = -10

Error: Invalid mode specified.

grInvalidVersion = -18

Error: Invalid version.

grIOerror = -12

Error: Unspecified Input/Output error.

grNoFloodMem = -7

Error: Could not allocate memory for flood operation.

`grNoFontMem = -9`

Error: Not enough memory to load font.

`grNoInitGraph = -1`

Error: Graphical system not initialized

`grNoLoadMem = -5`

Error: Memory error.

`grNoScanMem = -6`

Error: Could not allocate memory for scan

`grNotDetected = -2`

Error: Graphics device not detected.

`grOk = 0`

Graphical operation went OK.

`HatchFill = 7`

Fill style: Hatch lines

`HercMono = 7`

Mode: Hercules, mono color

`HercMonoHi = 0`

Mode: Hercules card, monochrome, high resolution

`highNewDriver = 21`

Mode: highest number for new driver

`highNewMode = m2048x1536`

Mode: Highest possible value of the new modes.

`HorizDir = 0`

Text write direction: Horizontal

`InterleaveFill = 9`

Fill style: Interleaving lines

LCOMFont = 8

Font number: ?

LeftText = 0

Horizontal text alignment: Align text left

lightblue = 9

Color code: Light blue

lightcyan = 11

Color code: Light cyan

lightgray = 7

Color code: Light gray

lightgreen = 10

Color code: Light green

lightmagenta = 13

Color code: Light magenta

lightred = 12

Color code: Light red

LineFill = 2

Fill style: Fill using horizontal lines

lowNewDriver = 11

Mode: lowest number for new driver

lowNewMode = m320x200

Mode: Lowest possible value of the new modes.

LowRes = 6

Mode: Low resolution.

LtBkSlashFill = 6

Fill style: Light diagonal (backslash) lines

LtSlashFill = 3

Fill style: Light diagonal (slash) lines

m1024x768 = detectMode + 12

Mode: Resolution 1024x768

m1280x1024 = detectMode + 13

Mode: Resolution 1280x1024

m1600x1200 = detectMode + 14

Mode: Resolution 1600x1200

m2048x1536 = detectMode + 15

Mode: Resolution 2048x1536

m320x200 = detectMode + 1

Mode: Resolution 320x200

m320x256 = detectMode + 2

Mode: Resolution 320x256

m320x400 = detectMode + 3

Mode: Resolution 320x400

m512x384 = detectMode + 4

Mode: Resolution 512x384

m640x200 = detectMode + 5

Mode: Resolution 640x200

m640x256 = detectMode + 6

Mode: Resolution 640x256

m640x350 = detectMode + 7

Mode: Resolution 640x350

m640x400 = detectMode + 8

Mode: Resolution 640x400

`m640x480 = detectMode + 9`

Mode: Resolution 640x480

`m800x600 = detectMode + 10`

Mode: Resolution 800x600

`m832x624 = detectMode + 11`

Mode: Resolution 832x624

`magenta = 5`

Color code: Magenta

`MaxColors = 255`

Max amount of colors in a palette

`maxsmallint = (smallint)`

Maximum value for smallint type

`MCGA = 2`

Graphic driver for MCGA cards

`MCGAC0 = 0`

MCGA Graphic driver mode C0

`MCGAC1 = 1`

MCGA Graphic driver mode C1

`MCGAC2 = 2`

MCGA Graphic driver mode C2

`MCGAC3 = 3`

MCGA Graphic driver mode C3

`MCGAHi = 5`

MCGA Graphic driver high resolution mode

`MCGAMed = 4`

MCGA Graphic driver medium resolution mode

NormalPut = 0

Draw operation: Use Normal (copy) operation

NormWidth = 1

Line width: Normal width

NotPut = 4

Draw operation: use NOT

OrPut = 2

Draw operation: use OR

red = 4

Color code: Red

```
resolutions : Array[lowNewMode..highNewMode] of TResolutionRec =
  ((x: 320; y: 200), (x: 320; y: 256), (x: 320; y: 400), (x: 512; y
   : 384), (x: 640; y: 200), (x: 640; y: 256), (x: 640; y: 350), (x:
   640; y: 400), (x: 640; y: 480), (x: 800; y: 600), (x: 832; y: 624
   ), (x: 1024; y: 768), (x: 1280; y: 1024), (x: 1600; y: 1200), (x:
   2048; y: 1536))
```

Array with actual resolutions of the new modes

RightText = 2

Horizontal text alignment: Align text right

SansSerifFont = 3

Font number: Sans Serif font

ScriptFont = 5

Font number: Script font

SimpleFont = 6

Font number: Simple font

SlashFill = 4

Fill style: Diagonal (slash) lines

SmallFont = 2

Font number: Small font

`SolidFill = 1`

Fill style: Solid fill.

`SolidLn = 0`

Line style: Solid line

`ThickWidth = 3`

Line width: double width

`TopOff = False`

Top off

`TopOn = True`

Top on

`TopText = 2`

Vertical text alignment: Align text to top

`TriplexFont = 1`

Font number: Triplex font

`TSCRFonT = 7`

Font number: Terminal font

`UserBitLn = 4`

Line style: User defined

`UserCharSize = 0`

User character size

`UserFill = 12`

Fill style: User-defined fill.

`VertDir = 1`

Text write direction: Vertical

`VESA = 10`

Mode: VESA graphics adaptor.

VGA = 9

Mode: VGA graphics adaptor.

VGAHi = 2

Mode: VGA high resolution (640x480)

VGAlo = 0

Mode: VGA low resolution (640x200)

VGAMed = 1

Mode: VGA medium resolution (640x350)

white = 15

Color code: White

WideDotFill = 10

Fill style: Widely spaced dotted lines

XHatchFill = 8

Fill style: Heavy hatch lines

XORPut = 1

Draw operation: use XOR

yellow = 14

Color code: Yellow

56.13.2 Types

```
ArcCoordsType = record
  x : SmallInt;
  y : SmallInt;
  xstart :
    SmallInt;
  ystart : SmallInt;
  xend : SmallInt;
  yend : SmallInt
;
end
```

Describe the last arc which was drawn on screen

```
CircleProc = procedure(X: SmallInt; Y: SmallInt; Radius: Word)
```

Standard circle drawing routine prototype.

```
clrviewproc = procedure
```

Standard clearviewport routine prototype

```
defpixelproc = procedure(X: SmallInt; Y: SmallInt)
```

This is the standard putpixel routine used by all function drawing routines, it will use the viewport settings, as well as clip, and use the current foreground color to plot the desired pixel.

```
ellipseproc = procedure(X: SmallInt; Y: SmallInt; XRadius: Word;
    YRadius: Word; stAngle: Word; EndAngle: Word
    ;
    fp: patternlineproc)
```

Standard ellipse drawing routine prototype.

```
FillPatternType = Array[1..8] of Byte
```

Bit pattern used when drawing lines. Set bits are drawn.

```
FillSettingsType = record
    pattern : Word;
    color : Word;
end
```

Record describing fill mode

```
GetBkColorProc = function : Word
```

GetBkColorProc is the procedure prototype for the GetBkColor (814) method handler in TModeInfo (813). The function should return the color code of the background color.

```
getimageproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt
    ;
    Y2: SmallInt; var Bitmap)
```

Standard GetImage (814) procedure prototype.

```
getpixelproc = function(X: SmallInt; Y: SmallInt) : Word
```

Standard pixel fetching routine prototype

```
getrgbpaletteproc = procedure(ColorNum: SmallInt;
    var RedValue: SmallInt;
    var GreenValue: SmallInt;
    var
    BlueValue: SmallInt)
```

This routine prototype is a hook for GetRGBPalette (814)

```
getscanlineproc = procedure(X1: SmallInt; X2: SmallInt; Y: SmallInt
;
                        var data)
```

This routine is used for FloodFill (819) It returns an entire screen scan line with a word for each pixel in the scanline. Also handy for GetImage.

```
graphfreememprc = procedure(var P: Pointer; size: Word)
```

Procedure prototype, used when heap memory is freed by the graph routines.

```
graphgetmemprc = procedure(var P: pointer; size: Word)
```

Procedure prototype, used when heap memory is needed by the graph routines.

```
graph_float = single
```

The platform's preferred floating point size for fast graph operations

```
hlineproc = procedure(x: SmallInt; x2: SmallInt; y: SmallInt)
```

Standard procedure prototype to draw a single horizontal line

```
imagesizeproc = function(X1: SmallInt; Y1: SmallInt; X2: SmallInt
;
                        Y2: SmallInt) : LongInt
```

Standard ImageSize (815) calculation procedure prototype.

```
initmodeproc = procedure
```

Standard routine prototype to initialize a mode.

```
lineproc = procedure(X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt)
```

Standard line drawing routine prototype.

```
LineSettingsType = record
    linestyle : Word;
    pattern : Word;
    thickness : Word;
end
```

Record describing current line drawing mode

```
OutTextXYProc = procedure(x: SmallInt; y: SmallInt;
    const TextString: string)
```

This routine prototype is a hook for OutTextXY (815)

```
PaletteType = record
  Size : LongInt;
  Colors : Array[0..MaxColors
  ] of RGBRec;
end
```

Record describing palette.

```
patternlineproc = procedure(x1: SmallInt; x2: SmallInt; y: SmallInt
)
```

Standard procedure prototype to draw a patterned line

```
PCharsetTransTable = ^TCharsetTransTable
```

Pointer to TCharsetTransTable (812) array.

```
PModeInfo = ^TModeInfo
```

Pointer to TModeInfo (813) record

```
PointType = record
  x : SmallInt;
  y : SmallInt;
end
```

Record describing a point in a 2 dimensional plane

```
putimageproc = procedure(X: SmallInt; Y: SmallInt; var Bitmap;
  BitBlt: Word)
```

Standard PutImage (815) procedure prototype.

```
putpixelproc = procedure(X: SmallInt; Y: SmallInt; Color: Word)
```

Standard pixel drawing routine prototype

```
restorestateproc = procedure
```

Standard routine prototype to restore the graphical state at a closegraph call.

```
RGBRec = packed record
  Red : SmallInt;
  Green : SmallInt;
  Blue
  : SmallInt;
end
```

Record describing palette RGB color

```
savestateproc = procedure
```

Standard routine prototype to save the graphical state before a mode is set.

```
setactivepageproc = procedure(page: Word)
```

Standard SetActivePage (816) procedure prototype.

```
SetAllPaletteProc = procedure(const Palette: PaletteType)
```

This routine prototype is a hook for SetAllPalette (816)

```
SetBkColorProc = procedure(ColorNum: Word)
```

SetBkColorProc is the procedure prototype for the SetBkColor (816) method handler in TModeInfo (813). The procedure gets passed the color code for the color to set as background color.

```
setrgbpaletteproc = procedure(ColorNum: SmallInt; RedValue: SmallInt
;
                                GreenValue: SmallInt; BlueValue:
                                SmallInt)
```

This routine prototype is a hook for SetRGBPalette (816)

```
setvisualpageproc = procedure(page: Word)
```

Standard SetVisualPage (816) procedure prototype.

```
TCharsetTransTable = Array[Char] of Char
```

Character transliteration table, with entries for 256 characters

```
TextSettingsType = record
    font : Word;
    direction : Word;
    charsize
    : Word;
    horiz : Word;
    vert : Word;
end
```

Record describing how texts are drawn.

```
TModeInfo = record
    DriverNumber : SmallInt;
    ModeNumber : SmallInt
;
    internModeNumber : SmallInt;
    MaxColor : LongInt;
    PaletteSize
    : LongInt;
    XAspect : Word;
```

```

YAspect : Word;
MaxX : Word;
MaxY
: Word;
DirectColor : Boolean;
Hardwarepages : Byte;
ModeName
: string;
DirectPutPixel : defpixelproc;
GetPixel : getpixelproc
;
PutPixel : putpixelproc;
SetRGBPalette : setrgbpaletteproc;
GetRGBPalette : getrgbpaletteproc;
SetAllPalette : SetAllPaletteProc
;
SetVisualPage : setvisualpageproc;
SetActivePage : setactivepageproc
;
ClearViewPort : clrviewproc;
PutImage : putimageproc;
GetImage
: getimageproc;
ImageSize : imagesizeproc;
GetScanLine : getscanlineproc
;
Line : lineproc;
InternalEllipse : ellipseproc;
PatternLine
: patternlineproc;
HLine : hlineproc;
VLine : vlineproc;
Circle
: CircleProc;
InitMode : initmodeproc;
OutTextXY : OutTextXYProc
;
SetBKColor : SetBkColorProc;
GetBKColor : GetBkColorProc;
next : PModeInfo;
end

```

Record describing a graphical mode.

```

TResolutionRec = record
  x : LongInt;
  y : LongInt;
end

```

Record describing resolution

```

ViewPortType = record

```

```

x1 : SmallInt;
y1 : SmallInt;
x2 : SmallInt
;
y2 : SmallInt;
Clip : Boolean;
end

```

Record describing a viewport

```
vlineproc = procedure(x: SmallInt; y: SmallInt; y2: SmallInt)
```

Standard procedure prototype to draw a single vertical line

56.13.3 Variables

```
Circle : CircleProc
```

Circle draws a complete circle with center at (X, Y), radius radius.

```
ClearViewPort : clrviewproc
```

Clears the current viewport. The current background color is used as filling color. The pointer is set at (0, 0).

```
DirectPutPixel : defpixelproc
```

Hook to directly draw a pixel on the screen.

```
GetBkColor : GetBkColorProc
```

GetBkColor returns the current background color (the palette entry).

```
GetImage : getimageproc
```

GetImage Places a copy of the screen area (X1, Y1) to X2, Y2 in BitMap

```
GetPixel : getpixelproc
```

GetPixel returns the color of the point at (X, Y)

```
GetRGBPalette : getrgbpaletteproc
```

Hook to set a RGB palette entries.

```
GetScanLine : getscanlineproc
```

Hook to get a scan line from the screen.

```
GraphFreeMemPtr : graphfreememprc
```

Hook to free heap memory.

GraphGetMemPtr : graphgetmemproc

Hook to get heap memory

HLine : hlineproc

Hook to draw a solid horizontal line

ImageSize : imagesizeproc

ImageSize returns the number of bytes needed to store the image in the rectangle defined by (X1,Y1) and (X2,Y2).

InternalEllipse : ellipseproc

Hook to draw an ellipse

Line : lineproc

Line draws a line starting from (X1,Y1 to (X2,Y2), in the current line style and color. The current position is put to (X2,Y2)

OutTextXY : OutTextXYProc

OutText puts TextString on the screen, at position (X,Y), using the current font and text settings. The current position is moved to the end of the text.

PatternLine : patternlineproc

Hook to draw a patterned line

PutImage : putimageproc

PutImage Places the bitmap in Bitmap on the screen at (X1,Y1). How determines how the bitmap will be placed on the screen. Possible values are:

- CopyPut
- XORPut
- ORPut
- AndPut
- NotPut

PutPixel : putpixelproc

Puts a point at (X,Y) using color Color

RestoreVideoState : restorestateproc

Hook to restore a saved video mode

`SaveVideoState : savestateproc`

Hook to save the current video state

`SetActivePage : setactivepageproc`

Sets Page as the active page for all graphical output.

`SetAllPalette : SetAllPaletteProc`

Sets the current palette to `Palette`. `Palette` is an untyped variable, usually pointing to a record of type `PaletteType`

`SetBkColor : SetBkColorProc`

Sets the background color to `Color`.

`SetRGBPalette : setrgbpaletteproc`

`SetRGBPalette` sets the `ColorNr`-th entry in the palette to the color with RGB-values `Red`, `Green` `Blue`.

`SetVisualPage : setvisualpageproc`

`SetVisualPage` sets the video page to page number `Page`.

`VLine : vlineproc`

Hook to draw a solid vertical line

56.14 Procedures and functions

56.14.1 Arc

Synopsis: Draw part of a circle

Declaration: `procedure Arc(X: SmallInt; Y: SmallInt; StAngle: Word; EndAngle: Word;
Radius: Word)`

Visibility: default

Description: `Arc` draws part of a circle with center at `(X,Y)`, radius `radius`, starting from angle `start`, stopping at angle `stop`. These angles are measured counterclockwise.

Errors: None.

See also: [Circle \(814\)](#), [Ellipse \(818\)](#), [GetArcCoords \(819\)](#), [PieSlice \(828\)](#), [Sector \(830\)](#)

56.14.2 Bar

Synopsis: Draw filled rectangle

Declaration: `procedure Bar(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style.

Errors: None.

See also: Bar3D ([817](#)), Rectangle ([829](#))

56.14.3 Bar3D

Synopsis: Draw filled 3-dimensional rectangle

Declaration: `procedure Bar3D(x1: SmallInt; y1: SmallInt; x2: SmallInt; y2: SmallInt; depth: Word; top: Boolean)`

Visibility: default

Description: Bar3d draws a 3-dimensional Bar with corners at (X1,Y1) and (X2,Y2) and fills it with the current color and fill-style. Depth specifies the number of pixels used to show the depth of the bar.

If Top is true; then a 3-dimensional top is drawn.

Errors: None.

See also: Bar ([817](#)), Rectangle ([829](#))

56.14.4 ClearDevice

Synopsis: Clear the complete screen

Declaration: `procedure ClearDevice`

Visibility: default

Description: Clears the graphical screen (with the current background color), and sets the pointer at (0,0).

Errors: None.

See also: ClearViewPort ([814](#)), SetBkColor ([816](#))

56.14.5 Closegraph

Synopsis: Close graphical system.

Declaration: `procedure Closegraph`

Visibility: default

Description: Closes the graphical system, and restores the screen modus which was active before the graphical modus was activated.

Errors: None.

See also: InitGraph ([826](#))

56.14.6 DetectGraph

Synopsis: Detect correct graphical driver to use

Declaration: `procedure DetectGraph(var GraphDriver: SmallInt;
var GraphMode: SmallInt)`

Visibility: default

Description: `DetectGraph` checks the hardware in the PC and determines the driver and screen-modus to be used. These are returned in `Driver` and `Modus`, and can be fed to `InitGraph`. See the `InitGraph` for a list of drivers and modi.

Errors: None.

See also: `InitGraph` ([826](#))

56.14.7 DrawPoly

Synopsis: Draw a polygone

Declaration: `procedure DrawPoly(NumPoints: Word; var polypoints)`

Visibility: default

Description: `DrawPoly` draws a polygone with `NumberOfPoints` corner points, using the current color and line-style. `PolyPoints` is an array of type `PointType` ([811](#)).

Errors: None.

See also: `Bar` ([817](#)), `Bar3D` ([817](#)), `Rectangle` ([829](#))

56.14.8 Ellipse

Synopsis: Draw an ellipse

Declaration: `procedure Ellipse(X: SmallInt; Y: SmallInt; stAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Ellipse` draws part of an ellipse with center at `(X, Y)`. `XRadius` and `Yradius` are the horizontal and vertical radii of the ellipse. `Start` and `Stop` are the starting and stopping angles of the part of the ellipse. They are measured counterclockwise from the X-axis (3 o'clock is equal to 0 degrees). Only positive angles can be specified.

Errors: None.

See also: `Arc` ([816](#)), `Circle` ([814](#)), `FillEllipse` ([818](#))

56.14.9 FillEllipse

Synopsis: Draw and fill an ellipse

Declaration: `procedure FillEllipse(X: SmallInt; Y: SmallInt; XRadius: Word;
YRadius: Word)`

Visibility: default

Description: `Ellipse` draws an ellipse with center at (X, Y) . `XRadii` and `Yradii` are the horizontal and vertical radii of the ellipse. The ellipse is filled with the current color and fill-style.

Errors: None.

See also: `Arc` ([816](#)), `Circle` ([814](#)), `GetArcCoords` ([819](#)), `PieSlice` ([828](#)), `Sector` ([830](#))

56.14.10 `FillPoly`

Synopsis: Draw, close and fill a polygone

Declaration: `procedure FillPoly (NumPoints: Word; var PolyPoints)`

Visibility: default

Description: `FillPoly` draws a polygone with `NumberOfPoints` corner points and fills it using the current color and line-style. `PolyPoints` is an array of type `PointType`.

Errors: None.

See also: `Bar` ([817](#)), `Bar3D` ([817](#)), `Rectangle` ([829](#))

56.14.11 `FloodFill`

Synopsis: Fill an area with a given color

Declaration: `procedure FloodFill (x: SmallInt; y: SmallInt; Border: Word)`

Visibility: default

Description: Fills the area containing the point (X, Y) , bounded by the color `BorderColor`.

Errors: None

See also: `SetColor` ([830](#)), `SetBkColor` ([816](#))

56.14.12 `GetArcCoords`

Synopsis: Return coordinates of last drawn arc or ellipse.

Declaration: `procedure GetArcCoords (var ArcCoords: ArcCoordsType)`

Visibility: default

Description: `GetArcCoords` returns the coordinates of the latest `Arc` or `Ellipse` call.

Errors: None.

See also: `Arc` ([816](#)), `Ellipse` ([818](#))

56.14.13 GetAspectRatio

Synopsis: Return screen resolution

Declaration: `procedure GetAspectRatio (var Xasp: Word; var Yasp: Word)`

Visibility: default

Description: `GetAspectRatio` determines the effective resolution of the screen. The aspect ration can then be calculated as `Xasp/Yasp`.

Errors: None.

See also: `InitGraph` ([826](#)), `SetAspectRatio` ([830](#))

56.14.14 GetColor

Synopsis: Return current drawing color

Declaration: `function GetColor : Word`

Visibility: default

Description: `GetColor` returns the current drawing color (the palette entry).

Errors: None.

See also: `GetColor` ([820](#)), `SetBkColor` ([816](#))

56.14.15 GetDefaultPalette

Synopsis: Return default palette

Declaration: `procedure GetDefaultPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetDefaultPalette` returns the current palette in `Palette`.

Errors: None.

See also: `GetColor` ([820](#)), `GetBkColor` ([814](#))

56.14.16 GetDirectVideo

Synopsis: Determine whether direct video mode is active.

Declaration: `function GetDirectVideo : Boolean`

Visibility: default

Description: Determine whether direct video mode is active.

56.14.17 GetDriverName

Synopsis: Return current driver name

Declaration: `function GetDriverName : string`

Visibility: default

Description: `GetDriverName` returns a string containing the name of the current driver.

Errors: None.

See also: `GetModeName` ([823](#)), `InitGraph` ([826](#))

56.14.18 GetFillPattern

Synopsis: Return current fill pattern

Declaration: `procedure GetFillPattern(var FillPattern: FillPatternType)`

Visibility: default

Description: `GetFillPattern` returns an array with the current fill-pattern in `FillPattern`

Errors: None

See also: `SetFillPattern` ([831](#))

56.14.19 GetFillSettings

Synopsis: Return current fill settings

Declaration: `procedure GetFillSettings(var Fillinfo: FillSettingsType)`

Visibility: default

Description: `GetFillSettings` returns the current fill-settings in `FillInfo`

Errors: None.

See also: `SetFillPattern` ([831](#))

56.14.20 GetGraphMode

Synopsis: Get current graphical modus

Declaration: `function GetGraphMode : SmallInt`

Visibility: default

Description: `GetGraphMode` returns the current graphical modus

Errors: None.

See also: `InitGraph` ([826](#))

56.14.21 GetLineSettings

Synopsis: Get current line drawing settings

Declaration: `procedure GetLineSettings (var ActiveLineInfo: LineSettingsType)`

Visibility: default

Description: `GetLineSettings` returns the current Line settings in `LineInfo`

Errors: None.

See also: `SetLineStyle` ([832](#))

56.14.22 GetMaxColor

Synopsis: return maximum number of colors

Declaration: `function GetMaxColor : Word`

Visibility: default

Description: `GetMaxColor` returns the maximum color-number which can be set with `SetColor`. Contrary to Turbo Pascal, this color isn't always guaranteed to be white (for instance in 256+ color modes).

Errors: None.

See also: `SetColor` ([830](#)), `GetPaletteSize` ([824](#))

56.14.23 GetMaxMode

Synopsis: Return biggest mode for the current driver

Declaration: `function GetMaxMode : SmallInt`

Visibility: default

Description: `GetMaxMode` returns the highest modulus for the current driver.

Errors: None.

See also: `InitGraph` ([826](#))

56.14.24 GetMaxX

Synopsis: Return maximal X coordinate

Declaration: `function GetMaxX : SmallInt`

Visibility: default

Description: `GetMaxX` returns the maximum horizontal screen length

Errors: None.

See also: `GetMaxY` ([823](#))

56.14.25 GetMaxY

Synopsis: Return maximal Y coordinate

Declaration: `function GetMaxY : SmallInt`

Visibility: default

Description: `GetMaxY` returns the maximum number of screen lines

Errors: None.

See also: `GetMaxY` ([823](#))

56.14.26 GetModeName

Synopsis: Return description a modus

Declaration: `function GetModeName (ModeNumber: SmallInt) : string`

Visibility: default

Description: `GetModeName` Returns a string with the name of modus `Modus`

Errors: None.

See also: `GetDriverName` ([821](#)), `InitGraph` ([826](#))

56.14.27 GetModeRange

Synopsis: Return lowest and highest modus of current driver

Declaration: `procedure GetModeRange (GraphDriver: SmallInt; var LoMode: SmallInt;
var HiMode: SmallInt)`

Visibility: default

Description: `GetModeRange` returns the Lowest and Highest modus of the currently installed driver. If no modes are supported for this driver, `HiModus` will be -1.

Errors: None.

See also: `InitGraph` ([826](#))

56.14.28 GetPalette

Synopsis: Return current palette

Declaration: `procedure GetPalette (var Palette: PaletteType)`

Visibility: default

Description: `GetPalette` returns in `Palette` the current palette.

Errors: None.

See also: `GetPaletteSize` ([824](#)), `SetPalette` ([832](#))

56.14.29 GetPaletteSize

Synopsis: Return maximal number of entries in current palette

Declaration: `function GetPaletteSize : SmallInt`

Visibility: default

Description: `GetPaletteSize` returns the maximum number of entries in the current palette.

Errors: None.

See also: `GetPalette` ([823](#)), `SetPalette` ([832](#))

56.14.30 GetTextSettings

Synopsis: Return current text style

Declaration: `procedure GetTextSettings (var TextInfo: TextSettingsType)`

Visibility: default

Description: `GetTextSettings` returns the current text style settings : The font, direction, size and placement as set with `SetTextStyle` and `SetTextJustify`

Errors: None.

See also: `SetTextStyle` ([833](#)), `SetTextJustify` ([833](#))

56.14.31 GetViewSettings

Synopsis: Return current viewport

Declaration: `procedure GetViewSettings (var viewport: ViewPortType)`

Visibility: default

Description: `GetViewSettings` returns the current viewport and clipping settings in `ViewPort`.

Errors: None.

See also: `SetViewPort` ([834](#))

56.14.32 GetX

Synopsis: Return current cursor X position

Declaration: `function GetX : SmallInt`

Visibility: default

Description: `GetX` returns the X-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetY` ([825](#))

56.14.33 GetY

Synopsis: Return current cursor Y position

Declaration: `function GetY : SmallInt`

Visibility: default

Description: `GetY` returns the Y-coordinate of the current position of the graphical pointer

Errors: None.

See also: `GetX` ([824](#))

56.14.34 GraphDefaults

Synopsis: Reset graphical mode to defaults

Declaration: `procedure GraphDefaults`

Visibility: default

Description: `GraphDefaults` resets all settings for viewport, palette, foreground and background pattern, line-style and pattern, filling style, filling color and pattern, font, text-placement and text size.

Errors: None.

See also: `SetViewPort` ([834](#)), `SetFillStyle` ([831](#)), `SetColor` ([830](#)), `SetBkColor` ([816](#)), `SetLineStyle` ([832](#))

56.14.35 GraphErrorMsg

Synopsis: Return a description of an error

Declaration: `function GraphErrorMsg(ErrorCode: SmallInt) : string`

Visibility: default

Description: `GraphErrorMsg` returns a string describing the error `Errorcode`. This string can be used to let the user know what went wrong.

Errors: None.

See also: `GraphResult` ([1](#))

56.14.36 GraphResult

Synopsis: Result of last graphical operation

Declaration: `function GraphResult : SmallInt`

Visibility: default

Description: `GraphResult` returns an error-code for the last graphical operation. If the returned value is zero, all went well. A value different from zero means an error has occurred. besides all operations which draw something on the screen, the following procedures also can produce a `GraphResult` different from zero:

- `InstallUserFont` ([827](#))
- `SetLineStyle` ([832](#))

- SetWriteMode ([834](#))
- SetFillStyle ([831](#))
- SetTextJustify ([833](#))
- SetGraphMode ([832](#))
- SetTextStyle ([833](#))

Errors: None.

See also: GraphErrorMsg ([1](#))

56.14.37 InitGraph

Synopsis: Initialize graphical system

Declaration: `procedure InitGraph(var GraphDriver: SmallInt; var GraphMode: SmallInt; const PathToDriver: string)`

Visibility: default

Description: `InitGraph` initializes the graph package. `GraphDriver` has two valid values: `GraphDriver=0` which performs an auto detect and initializes the highest possible mode with the most colors. 1024x768x64K is the highest possible resolution supported by the driver, if you need a higher resolution, you must edit `MODES.PPI`. If you need another mode, then set `GraphDriver` to a value different from zero and `graphmode` to the mode you wish (VESA modes where 640x480x256 is 101h etc.). `PathToDriver` is only needed, if you use the BGI fonts from Borland. Free Pascal does not offer BGI fonts like Borland, these must be obtained separately.

Example code:

```
var
  gd,gm : integer;
  PathToDriver : string;
begin
  gd:=detect; { highest possible resolution }
  gm:=0; { not needed, auto detection }
  PathToDriver:='C:\PP\BGI'; { path to BGI fonts,
                             drivers aren't needed }
  InitGraph(gd,gm,PathToDriver);
  if GraphResult<>grok then
    halt; ..... { whatever you need }
  CloseGraph; { restores the old graphics mode }
end.
```

Errors: None.

See also: Modes ([786](#)), DetectGraph ([818](#)), CloseGraph ([817](#)), GraphResult ([1](#))

56.14.38 InstallUserDriver

Synopsis: Install a user driver

Declaration: `function InstallUserDriver(Name: string; AutoDetectPtr: Pointer) : SmallInt`

Visibility: default

Description: `InstallUserDriver` adds the device-driver `DriverPath` to the list of .BGI drivers. `AutoDetectPtr` is a pointer to a possible auto-detect function.

Errors: None.

See also: `InitGraph` ([826](#)), `InstallUserFont` ([827](#))

56.14.39 InstallUserFont

Synopsis: Install a user-defined font

Declaration: `function InstallUserFont(const FontFileName: string) : SmallInt`

Visibility: default

Description: `InstallUserFont` adds the font in `FontPath` to the list of fonts of the .BGI system.

Errors: None.

See also: `InitGraph` ([826](#)), `InstallUserDriver` ([826](#))

56.14.40 LineRel

Synopsis: Draw a line starting from current position in given direction

Declaration: `procedure LineRel(Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `LineRel` draws a line starting from the current pointer position to the point (DX, DY) , **relative** to the current position, in the current line style and color. The Current Position is set to the endpoint of the line.

Errors: None.

See also: `Line` ([815](#)), `LineTo` ([827](#))

56.14.41 LineTo

Synopsis: Draw a line starting from current position to a given point

Declaration: `procedure LineTo(X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `LineTo` draws a line starting from the current pointer position to the point (DX, DY) , **relative** to the current position, in the current line style and color. The Current position is set to the end of the line.

Errors: None.

See also: `LineRel` ([827](#)), `Line` ([815](#))

56.14.42 MoveRel

Synopsis: Move cursor relative to current position

Declaration: `procedure MoveRel (Dx: SmallInt; Dy: SmallInt)`

Visibility: default

Description: `MoveRel` moves the pointer to the point (DX, DY), relative to the current pointer position

Errors: None.

See also: `MoveTo` ([828](#))

56.14.43 MoveTo

Synopsis: Move cursor to absolute position.

Declaration: `procedure MoveTo (X: SmallInt; Y: SmallInt)`

Visibility: default

Description: `MoveTo` moves the pointer to the point (X, Y).

Errors: None.

See also: `MoveRel` ([828](#))

56.14.44 OutText

Synopsis: Write text on the screen at the current location.

Declaration: `procedure OutText (const TextString: string)`

Visibility: default

Description: `OutText` puts `TextString` on the screen, at the current pointer position, using the current font and text settings. The current position is moved to the end of the text.

Errors: None.

See also: `OutTextXY` ([815](#))

56.14.45 PieSlice

Synopsis: Draw a pie-slice

Declaration: `procedure PieSlice (X: SmallInt; Y: SmallInt; stangle: SmallInt;
 endAngle: SmallInt; Radius: Word)`

Visibility: default

Description: `PieSlice` draws and fills a sector of a circle with center (X, Y) and radius `Radius`, starting at angle `Start` and ending at angle `Stop`.

Errors: None.

See also: `Arc` ([816](#)), `Circle` ([814](#)), `Sector` ([830](#))

56.14.46 queryadapterinfo

Synopsis: Function called to retrieve the current video adapter settings.

Declaration: `function queryadapterinfo : PModeInfo`

Visibility: default

56.14.47 Rectangle

Synopsis: Draw a rectangle on the screen.

Declaration: `procedure Rectangle(x1: SmallInt; y1: SmallInt; x2: SmallInt;
y2: SmallInt)`

Visibility: default

Description: Draws a rectangle with corners at (X1, Y1) and (X2, Y2), using the current color and style.

Errors: None.

See also: Bar ([817](#)), Bar3D ([817](#))

56.14.48 RegisterBGIDriver

Synopsis: Register a new BGI driver.

Declaration: `function RegisterBGIDriver(driver: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: InstallUserDriver ([826](#)), RegisterBGIFont ([829](#))

56.14.49 RegisterBGIfont

Synopsis: Register a new BGI font

Declaration: `function RegisterBGIFont(font: pointer) : SmallInt`

Visibility: default

Description: Registers a user-defined BGI driver

Errors: None.

See also: InstallUserFont ([827](#)), RegisterBGIDriver ([829](#))

56.14.50 RestoreCrtMode

Synopsis: Restore text screen

Declaration: `procedure RestoreCrtMode`

Visibility: default

Description: Restores the screen modus which was active before the graphical modus was started.

To get back to the graph mode you were last in, you can use `SetGraphMode (GetGraphMode)`

Errors: None.

See also: `InitGraph` ([826](#))

56.14.51 Sector

Synopsis: Draw and fill a sector of an ellipse

Declaration: `procedure Sector(x: SmallInt; y: SmallInt; StAngle: Word;
EndAngle: Word; XRadius: Word; YRadius: Word)`

Visibility: default

Description: `Sector` draws and fills a sector of an ellipse with center (X, Y) and radii XRadius and YRadius, starting at angle Start and ending at angle Stop.

Errors: None.

See also: `Arc` ([816](#)), `Circle` ([814](#)), `PieSlice` ([828](#))

56.14.52 SetAspectRatio

Synopsis: Set aspect ration of the screen

Declaration: `procedure SetAspectRatio(Xasp: Word; Yasp: Word)`

Visibility: default

Description: Sets the aspect ratio of the current screen to Xasp/Yasp.

Errors: None

See also: `InitGraph` ([826](#)), `GetAspectRatio` ([820](#))

56.14.53 SetColor

Synopsis: Set foreground drawing color

Declaration: `procedure SetColor(Color: Word)`

Visibility: default

Description: Sets the foreground color to Color.

Errors: None.

See also: `GetColor` ([820](#)), `SetBkColor` ([816](#)), `SetWriteMode` ([834](#))

56.14.54 SetDirectVideo

Synopsis: Attempt to enter direct video mode.

Declaration: `procedure SetDirectVideo(DirectAccess: Boolean)`

Visibility: default

Description: `SetDirectVideo` attempts to enter direct video mode. In that mode, everything is drawn straight in the video buffer.

56.14.55 SetFillPattern

Synopsis: Set drawing fill pattern

Declaration: `procedure SetFillPattern(Pattern: FillPatternType; Color: Word)`

Visibility: default

Description: `SetFillPattern` sets the current fill-pattern to `FillPattern`, and the filling color to `Color`. The pattern is an 8x8 raster, corresponding to the 64 bits in `FillPattern`.

Errors: None

See also: `GetFillPattern` ([821](#)), `SetFillStyle` ([831](#)), `SetWriteMode` ([834](#))

56.14.56 SetFillStyle

Synopsis: Set drawing fill style

Declaration: `procedure SetFillStyle(Pattern: Word; Color: Word)`

Visibility: default

Description: `SetFillStyle` sets the filling pattern and color to one of the predefined filling patterns. `Pattern` can be one of the following predefined constants :

EmptyFill Uses backgroundcolor.

SolidFill Uses filling color

LineFill Fills with horizontal lines.

LtSlashFill Fills with lines from left-under to top-right.

SlashFill Idem as previous, thick lines.

BkSlashFill Fills with thick lines from left-Top to bottom-right.

LtBkSlashFill Idem as previous, normal lines.

HatchFill Fills with a hatch-like pattern.

XHatchFill Fills with a hatch pattern, rotated 45 degrees.

InterLeaveFill

WideDotFill Fills with dots, wide spacing.

CloseDotFill Fills with dots, narrow spacing.

UserFill Fills with a user-defined pattern.

Errors: None.

See also: `SetFillPattern` ([831](#)), `SetWriteMode` ([834](#))

56.14.57 SetGraphMode

Synopsis: Set graphical mode

Declaration: `procedure SetGraphMode (Mode: SmallInt)`

Visibility: default

Description: `SetGraphMode` sets the graphical mode and clears the screen.

Errors: None.

See also: `InitGraph` ([826](#))

56.14.58 SetLineStyle

Synopsis: Set line drawing style

Declaration: `procedure SetLineStyle (LineStyle: Word; Pattern: Word; Thickness: Word)`

Visibility: default

Description: `SetLineStyle` sets the drawing style for lines. You can specify a `LineStyle` which is one of the following pre-defined constants:

SolidIn Draws a solid line.

DottedIn Draws a dotted line.

CenterIn Draws a non-broken centered line.

DashedIn Draws a dashed line.

UserBitIn Draws a User-defined bit pattern.

If `UserBitIn` is specified then `Pattern` contains the bit pattern. In all other cases, `Pattern` is ignored. The parameter `Width` indicates how thick the line should be. You can specify one of the following pre-defined constants:

NormWidth Normal line width

ThickWidth Double line width

Errors: None.

See also: `GetLineSettings` ([822](#)), `SetWriteMode` ([834](#))

56.14.59 SetPalette

Synopsis: Set palette entry using color constant

Declaration: `procedure SetPalette (ColorNum: Word; Color: ShortInt)`

Visibility: default

Description: `SetPalette` changes the `ColorNr`-th entry in the palette to `NewColor`

Errors: None.

See also: `SetAllPalette` ([816](#)), `SetRGBPalette` ([816](#))

56.14.60 SetTextJustify

Synopsis: Set text placement style

Declaration: `procedure SetTextJustify(horiz: Word; vert: Word)`

Visibility: default

Description: `SetTextJustify` controls the placement of new text, relative to the (graphical) cursor position. `Horizontal` controls horizontal placement, and can be one of the following pre-defined constants:

LeftTextText is set left of the pointer.

CenterTextText is set centered horizontally on the pointer.

RightTextText is set to the right of the pointer.

`Vertical` controls the vertical placement of the text, relative to the (graphical) cursor position. Its value can be one of the following pre-defined constants :

BottomTextText is placed under the pointer.

CenterTextText is placed centered vertically on the pointer.

TopTextText is placed above the pointer.

Errors: None.

See also: `OutText` ([828](#)), `OutTextXY` ([815](#))

56.14.61 SetTextStyle

Synopsis: Set text style

Declaration: `procedure SetTextStyle(font: Word; direction: Word; charsize: Word)`

Visibility: default

Description: `SetTextStyle` controls the style of text to be put on the screen. pre-defined constants for `Font` are:

DefaultFontThe default font

TriplexFontA special font

SmallFontA smaller font

SansSerifFontA sans-serif font (like Arial)

GothicFontA gothic font

ScriptFontA script font

SimpleFontA simple font

TSCRFonTerminal screen font

LCOMFont?

EuroFont?

BoldFontA bold typeface font

Pre-defined constants for `Direction` are :

HorizDirWrite horizontal

VertDirWrite vertical

Errors: None.

See also: `GetTextSettings` ([824](#))

56.14.62 SetUserCharSize

Synopsis: Set user character size for vector font

Declaration: `procedure SetUserCharSize(Multx: Word; Divx: Word; Multy: Word;
Divy: Word)`

Visibility: default

Description: Sets the width and height of vector-fonts. The horizontal size is given by Xasp1/Xasp2, and the vertical size by Yasp1/Yasp2.

Errors: None.

See also: [SetTextStyle \(833\)](#)

56.14.63 SetViewPort

Synopsis: Set the graphical drawing window

Declaration: `procedure SetViewPort(X1: SmallInt; Y1: SmallInt; X2: SmallInt;
Y2: SmallInt; Clip: Boolean)`

Visibility: default

Description: Sets the current graphical viewport (window) to the rectangle defined by the top-left corner (X1, Y1) and the bottom-right corner (X2, Y2). If Clip is true, anything drawn outside the viewport (window) will be clipped (i.e. not drawn). Coordinates specified after this call are relative to the top-left corner of the viewport.

Errors: None.

See also: [GetViewSettings \(824\)](#)

56.14.64 SetWriteMode

Synopsis: Specify binary operation to perform when drawing on screen

Declaration: `procedure SetWriteMode(WriteMode: SmallInt)`

Visibility: default

Description: `SetWriteMode` controls the drawing of lines on the screen. It controls the binary operation used when drawing lines on the screen. Mode can be one of the following pre-defined constants:

CopyPutDraw as specified using current bitmask and color

XORPutDraw XOR-ing current bitmask and color

Errors: None.

See also: [SetColor \(830\)](#), [SetBkColor \(816\)](#), [SetLineStyle \(832\)](#), [SetFillStyle \(831\)](#)

56.14.65 TextHeight

Synopsis: Return height (in pixels) of the given string

Declaration: `function TextHeight(const TextString: string) : Word`

Visibility: default

Description: `TextHeight` returns the height (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextWidth` ([835](#))

56.14.66 TextWidth

Synopsis: Return width (in pixels) of the given string

Declaration: `function TextWidth(const TextString: string) : Word`

Visibility: default

Description: `TextWidth` returns the width (in pixels) of the string `S` in the current font and text-size.

Errors: None.

See also: `TextHeight` ([835](#))

Chapter 57

Reference for unit 'heaptrc'

57.1 Used units

Table 57.1: Used units by unit 'heaptrc'

Name	Page
System	1194

57.2 Overview

This document describes the HEAPTRC unit for Free Pascal. It was written by Pierre Muller. It is system independent, and works on all supported systems.

The HEAPTRC unit can be used to debug your memory allocation/deallocation. It keeps track of the calls to `getmem/freemem`, and, implicitly, of `New/Dispose` statements.

When the program exits, or when you request it explicitly. It displays the total memory used, and then dumps a list of blocks that were allocated but not freed. It also displays where the memory was allocated.

If there are any inconsistencies, such as memory blocks being allocated or freed twice, or a memory block that is released but with wrong size, this will be displayed also.

The information that is stored/displayed can be customized using some constants.

Do not use this unit directly, instead use the `-gh` switch, to let the compiler insert the unit in the uses clause.

57.3 Controlling HeapTrc with environment variables

The `HeapTrc` unit can be controlled with the `HEAPTRC` environment variable. The contents of this variable controls the initial setting of some constants in the unit. `HEAPTRC` consists of one or more of the following strings, separated by spaces:

keepreleased If this string occurs, then the `KeepReleased` ([838](#)) variable is set to `True`

disabled If this string occurs, then the `UseHeapTrace` ([839](#)) variable is set to `False` and the heap trace is disabled. It does not make sense to combine this value with other values.

nohalt If this string occurs, then the `HaltOnError` (838) variable is set to `False`, so the program continues executing even in case of a heap error.

log=filename If this string occurs, then the output of `heaptrc` is sent to the specified `Filename`. (see also `SetHeapTraceOutput` (842))

The following are valid values for the `HEAPTRC` variable:

```
HEAPTRC=disabled
HEAPTRC="keepreleased log=heap.log"
HEAPTRC="log=myheap.log nohalt"
```

Note that these strings are case sensitive, and the name of the variable too.

57.4 HeapTrc Usage

You must use the `-gh` switch, to let the compiler insert the unit by itself, so you don't have to include it in your `uses` clause. In fact, as of version 3.0.0 you may no longer do so.

The below example shows how to use the `heaptrc` unit.

This is the memory dump shown when running this program in a standard way:

```
Marked memory at 0040FA50 invalid
Wrong size : 128 allocated 64 freed
  0x00408708
  0x0040CB49
  0x0040C481
Call trace for block 0x0040FA50 size 128
  0x0040CB3D
  0x0040C481
```

If you use the `lineinfo` unit (or use the `-gl` switch) as well, then `heaptrc` will also give you the filenames and line-numbers of the procedures in the backtrace:

```
Marked memory at 00410DA0 invalid
Wrong size : 128 allocated 64 freed
  0x004094B8
  0x0040D8F9  main,   line 25 of heapex.pp
  0x0040D231
Call trace for block 0x00410DA0 size 128
  0x0040D8ED  main,   line 23 of heapex.pp
  0x0040D231
```

If lines without filename/line-number occur, this means there is a unit which has no debug info included.

Listing: `./heapex/heapex.pp`

Program `heapex`;

```
{
  Program used to demonstrate the usage of heaptrc unit
  Compile this program with the -gh command-line option
}
```

```

Var P1 : ^Longint;
      P2 : Pointer;
      I : longint;

begin
  {$IF NOT DECLARED(heaptrc)}
  {$ERROR You must compile this program with -gh}
  {$ENDIF}
  New(P1);
  // causes previous allocation not to be de-allocated
  New(P1);
  Dispose(P1);
  For I:=1 to 10 do
    begin
      GetMem (P2,128);
      // When I is even, deallocate block. We loose 5 times 128
      // bytes this way.
      If (I mod 2) = 0 Then FreeMem(P2,128);
    end;
    GetMem(P2,128);
    // This will provoke an error and a memory dump
    FreeMem (P2,64);
  end.

```

57.5 Constants, types and variables

57.5.1 Constants

```
add_tail : Boolean = True
```

If `add_tail` is `True` (the default) then a check is also performed on the memory location just behind the allocated memory.

```
GlobalSkipIfNoLeaks : Boolean = False
```

`GlobalSkipIfNoLeaks` will, when set to `true`, disable the output of the `heaptrc` unit if no memory leaks will be detected, i.e. there will only be output if there were actual memory leaks.

```
HaltOnError : Boolean = True
```

If `HaltOnError` is set to `True` then an illegal call to `FreeMem` will cause the memory manager to execute a `halt (1)` instruction, causing a memory dump. By Default it is set to `True`.

```
HaltOnNotReleased : Boolean = False
```

`HaltOnNotReleased` can be set to `True` to make the `DumpHeap` (840) procedure halt (exit code 203) the program if any memory was not released when the dump is made. If it is `False` (the default) then `DumpHeap` just returns.

```
keepreleased : Boolean = False
```

If `keepreleased` is set to `true`, then a list of freed memory blocks is kept. This is useful if you suspect that the same memory block is released twice. However, this option is very memory intensive, so use it sparingly, and only when it's really necessary.

`maxprintedblocklength : Integer = 128`

`maxprintedblocklength` determines the maximum number of bytes written by a memory block dump, as produced when `printleakedblock` (839) or `printfaultyblock` (839) are true. If the size of the memory block is larger than this size, then only the first `maxprintedblocklength` will be included in the dump.

`printfaultyblock : Boolean = False`

`printleakedblock` can be set to `True` to print a memory dump of faulty memory blocks (in case a memory override occurs) The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (839) bytes of the memory block will be printed.

`printleakedblock : Boolean = False`

`printleakedblock` can be set to `True` to print a memory dump of unreleased blocks when the `heaptrc` unit produces a summary of memory leaks. The block is printed as a series of hexadecimal numbers, representing the bytes in the memory block. At most `maxprintedblocklength` (839) bytes of the memory block will be printed.

`quicktrace : Boolean = True`

`Quicktrace` determines whether the memory manager checks whether a block that is about to be released is allocated correctly. This is a rather time consuming search, and slows program execution significantly, so by default it is set to `True`.

`tracesize = 8`

`Tracesize` specifies how many levels of calls are displayed of the call stack during the memory dump. If you specify `keepreleased:=True` then half the `TraceSize` is reserved for the `GetMem` call stack, and the other half is reserved for the `FreeMem` call stack. For example, the default value of 8 will cause eight levels of call frames to be dumped for the `getmem` call if `keepreleased` is `False`. If `KeepReleased` is `true`, then 4 levels of call frames will be dumped for the `GetMem` call and 4 frames will be dumped for the `FreeMem` call. If you want to change this value, you must recode the `heaptrc` unit.

`usecrc : Boolean = True`

If `usecrc` is `True` (the default) then a crc check is performed on locations before and after the allocated memory. This is useful to detect memory overwrites.

`useheaptrace : Boolean = True`

This variable must be set at program startup, through the help of an environment variable.

57.5.2 Types

`tdisplayextrainfoProc = procedure(var ptext: text; p: pointer)`

The `TDisplayExtraInfoType` is a procedural type used in the `SetHeapExtraInfo` (840) call to display a memory location which was previously filled with `TFillExtraInfoProc` (839)

`tFillExtraInfoProc = procedure(p: pointer)`

The `TFillExtraInfoProc` is a procedural type used in the `SetHeapExtraInfo` (840) call to fill a memory location with extra data for displaying.

57.6 Procedures and functions

57.6.1 CheckPointer

Synopsis: Check if a pointer is in the address range of the application

Declaration: `procedure CheckPointer(p: pointer)`

Visibility: default

Description: `CheckPointer` checks if the pointer is in the address range of the application, more specifically, if it is in the heap. if not, it prints an error and stops the program with aruntime error 204.

57.6.2 DumpHeap

Synopsis: Dump memory usage report to stderr.

Declaration: `procedure DumpHeap`
`procedure DumpHeap(SkipIfNoLeaks: Boolean)`

Visibility: default

Description: `DumpHeap` dumps to standard output a summary of memory usage. It is called automatically by the `heaptrc` unit when your program exits (by installing an exit procedure), but it can be called at any time.

Errors: None.

57.6.3 SetHeapExtraInfo

Synopsis: Store extra information in blocks.

Declaration: `procedure SetHeapExtraInfo(size: PtrUInt; fillproc: tFillExtraInfoProc;`
`displayproc: tdisplayextrainfoProc)`

Visibility: default

Description: You can use `SetHeapExtraInfo` to store extra info in the blocks that the `heaptrc` unit reserves when tracing `getmem` calls. `Size` indicates the size (in bytes) that the trace mechanism should reserve for your extra information. For each call to `getmem`, `FillProc` will be called, and passed a pointer to the memory reserved.

When dumping the memory summary, the extra info is shown by calling `displayproc` and passing it the memory location which was filled by `fillproc`. It should write the information in readable form to the text file provided in the call to `displayproc`

Errors: You can only call `SetHeapExtraInfo` if no memroy has been allocated yet. If memory was already allocated prior to the call to `SetHeapExtraInfo`, then an error will be displayed on standard error output, and a `DumpHeap` (840) is executed.

See also: `DumpHeap` (840), `SetHeapTraceOutput` (842)

Listing: `./heapex/setinfo.pp`

Program `heapex`;

{ Program used to demonstrate the usage of heaptrc unit }

Uses heaptrc;

Var P1 : ^Longint;
 P2 : Pointer;
 I : longint;
 Marker : Longint;

Procedure SetMarker (P : pointer);

Type PLongint = ^Longint;

begin
 PLongint(P)^:=Marker;
end;

Procedure Part1;

begin
 // Blocks allocated here are marked with \$FFAAFFAA = -5570646
 Marker := \$FFAAFFAA;
 New(P1);
 New(P1);
 Dispose(P1);
 For I:=1 to 10 do
 begin
 GetMem (P2,128);
 If (I mod 2) = 0 Then FreeMem(P2,128);
 end;
 GetMem(P2,128);
end;

Procedure Part2;

begin
 // Blocks allocated here are marked with \$FAFAFAFA = -84215046
 Marker := \$FAFAFAFA;
 New(P1);
 New(P1);
 Dispose(P1);
 For I:=1 to 10 do
 begin
 GetMem (P2,128);
 If (I mod 2) = 0 Then FreeMem(P2,128);
 end;
 GetMem(P2,128);
end;

begin
 SetExtraInfo (SizeOf(Marker), @SetMarker);
 Writeln ('Part 1');
 part1;
 Writeln ('Part 2');
 part2;
end.

57.6.4 SetHeapTraceOutput

Synopsis: Specify filename for heap trace output.

Declaration: `procedure SetHeapTraceOutput(const name: string); Overload`
`procedure SetHeapTraceOutput(var ATextOutput: Text); Overload`

Visibility: default

Description: `SetHeapTraceOutput` sets the filename into which heap trace info will be written. By default information is written to standard output, this function allows you to redirect the information to a file with full filename name.

Errors: If the file cannot be written to, errors will occur when writing the trace.

See also: `SetHeapExtraInfo` ([840](#))

Chapter 58

Reference for unit 'ipc'

58.1 Used units

Table 58.1: Used units by unit 'ipc'

Name	Page
BaseUnix	124
System	1194
unixtype	1879

58.2 Overview

This document describes the IPC unit for Free Pascal. It was written for Linux by Michael Van Canneyt. It gives all the functionality of System V Inter-Process Communication: shared memory, semaphores and messages. It works only on the Linux operating system.

Many constants here are provided for completeness only, and should under normal circumstances not be used by the programmer.

58.3 Constants, types and variables

58.3.1 Constants

`IPC_CREAT = 1 shl 9`

Create if key is nonexistent

`IPC_EXCL = 2 shl 9`

fail if key exists

`IPC_INFO = 3`

For `ipcs` call

`IPC_NOWAIT = 4 shl 9`

return error on wait

`IPC_PRIVATE = (0)`

`IPC_RMID = 0`

Remove resource

`IPC_SET = 1`

set ipc_perm options

`IPC_STAT = 2`

get ipc_perm options

58.3.2 Types

`key_t = TKey`

Alias for TKey (844) type

`PIPC_Perm = ^TIPC_Perm`

Pointer to TIPC_Perm (843) record.

`TKey = cint`

Type returned by the ftok (843) key generating function.

Chapter 59

Reference for unit 'keyboard'

59.1 Used units

Table 59.1: Used units by unit 'keyboard'

Name	Page
System	1194

59.2 Overview

The **Keyboard** unit implements a keyboard access layer which is system independent. It can be used to poll the keyboard state and wait for certain events. Waiting for a keyboard event can be done with the `GetKeyEvent` ([859](#)) function, which will return a driver-dependent key event. This key event can be translated to a interpretable event by the `TranslateKeyEvent` ([868](#)) function. The result of this function can be used in the other event examining functions.

A custom keyboard driver can be installed using the `SetKeyboardDriver` ([867](#)) function. The current keyboard driver can be retrieved using the `GetKeyboardDriver` ([859](#)) function. The last section of this chapter demonstrates how to make a keyboard driver.

59.3 Unix specific notes

On Unix, applications run on a "terminal", and the application writes to the screen and reads from the keyboard by communicating with the terminal. Unix keyboard handling is mostly backward compatible with the DEC vt100 and vt220 terminals from tens of years ago. The vt100 and vt220 had very different keyboards than todays PC's and this is where the problems start. To make it worse the protocol of both terminals has not been very well designed.

Because of this, the keyboard unit on Unix operating systems does a best effort to provide keyboard functionality. An implementation with full keyboard facilities like on other operating systems is not possible.

The exception is the Linux kernel. The terminal emulation of the Linux kernel is from a PC keyboard viewpoint hopeless as well, but unlike other terminal emulators it is configurable. On the Linux console, the Free Pascal keyboard unit tries to implement full functionality.

Users of applications using the keyboard unit should expect the following:

- Full functionality on the Linux console. It must be the bare console, SSH into another machine will kill the full functionality.
- Limited functionality otherwise.

Notes about Linux full functionality:

- The keyboard is reprogrammed. If the keyboard is for whatever reason not restored in its original state, please load your keymap to reinitialize it.
- Alt+function keys generate keycodes for those keys. To switch virtual consoles, use ctrl+alt+function key.
- Unlike what you're used to with other Unix software, escape works as you intuitively expect, it generates the keycode for an escape key **without a delay**.

The limited functionality does include these quirks:

- Escape must be pressed two times before it has effect.
- On the Linux console, when the users runs the program by logging into another machine:
 - Shift+F1 and Shift+F12 will generate keycodes for F11 and F12.
 - Shift+arrow keys, shift+ins, shift+del, shift+home, shift+end do not work. The same is true about the control and alt combinations.
 - Alt+function keys will switch virtual consoles instead of generating the right key sequences.
 - Ctrl+function keys will generate the keycodes for the function keys without ctrl
- In Xterm:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
- In Konsole:
 - Shift+insert pastes the x clipboard, no keycode will be generated.
 - Shift+arrow keys doesn't work, nor does ctrl+arrow keys

If you have a non-standard terminal, some keys may not work at all. When in limited functionality mode, the user can work around using an escape prefix:

- Esc+1 = F1, Esc+2 = F2.
- Esc before another key is equal to alt+key.

In such cases, if the terminal does output an escape sequence for those keys, please submit a bug report so we can add them.

59.4 Writing a keyboard driver

Writing a keyboard driver means that hooks must be created for most of the keyboard unit functions. The `TKeyboardDriver` record contains a field for each of the possible hooks:

```
TKeyboardDriver = Record
  InitDriver : Procedure;
  DoneDriver : Procedure;
  GetKeyEvent : Function : TKeyEvent;
  PollKeyEvent : Function : TKeyEvent;
  GetShiftState : Function : Byte;
  TranslateKeyEvent : Function (KeyEvent: TKeyEvent): TKeyEvent;
  TranslateKeyEventUniCode: Function (KeyEvent: TKeyEvent): TKeyEvent;
end;
```

The meaning of these hooks is explained below:

InitDriver Called to initialize and enable the driver. Guaranteed to be called only once. This should initialize all needed things for the driver.

DoneDriver Called to disable and clean up the driver. Guaranteed to be called after a call to `initDriver`. This should clean up all things initialized by `InitDriver`.

GetKeyEvent Called by `GetKeyEvent` (859). Must wait for and return the next key event. It should NOT store keys.

PollKeyEvent Called by `PollKeyEvent` (864). It must return the next key event if there is one. Should not store keys.

GetShiftState Called by `PollShiftStateEvent` (865). Must return the current shift state.

TranslateKeyEvent Should translate a raw key event to a `cOrrect` key event, i.e. should fill in the `shiftstate` and convert function key scancodes to function key keycodes. If the `TranslateKeyEvent` is not filled in, a default translation function will be called which converts the known scancodes from the tables in the previous section to a correct keyevent.

TranslateKeyEventUniCode Should translate a key event to a unicode key representation.

Strictly speaking, only the `GetKeyEvent` and `PollKeyEvent` hooks must be implemented for the driver to function correctly.

The example unit demonstrates how a keyboard driver can be installed. It takes the installed driver, and hooks into the `GetKeyEvent` function to register and log the key events in a file. This driver can work on top of any other driver, as long as it is inserted in the `uses` clause *after* the real driver unit, and the real driver unit should set the driver record in its initialization section.

Note that with a simple extension of this unit could be used to make a driver that is capable of recording and storing a set of keyboard strokes, and replaying them at a later time, so a 'keyboard macro' capable driver. This driver could sit on top of any other driver.

Listing: `./kbdex/logkeys.pp`

```
unit logkeys;
```

```
interface
```

```
Procedure StartKeyLogging;
```

```
Procedure StopKeyLogging;
```



```

Function IsKeyLogging : Boolean;
Procedure SetKeyLogFileName (FileName : String);

implementation

uses sysutils , keyboard;

var
    NewKeyBoardDriver ,
    OldKeyBoardDriver : TKeyboardDriver;
    Active , Logging : Boolean;
    LogFileName : String;
    KeyLog : Text;

Function TimeStamp : String;

begin
    TimeStamp:=FormatDateTime( 'hh:nn:ss' , Time());
end;

Procedure StartKeyLogging;

begin
    Logging:=True;
    WriteLn(KeyLog, 'Start logging keystrokes at: ', TimeStamp);
end;

Procedure StopKeyLogging;

begin
    WriteLn(KeyLog, 'Stop logging keystrokes at: ', TimeStamp);
    Logging:=False;
end;

Function IsKeyLogging : Boolean;

begin
    IsKeyLogging:=Logging;
end;

Function LogGetKeyEvent : TKeyEvent;

Var
    K : TKeyEvent;

begin
    K:=OldkeyboardDriver.GetKeyEvent();
    If Logging then
        begin
            Write(KeyLog, TimeStamp, ': Key event: ');
            WriteLn(KeyLog, KeyEventToString(TranslateKeyEvent(K)));
        end;
    LogGetKeyEvent:=K;
end;

Procedure LogInitKeyBoard;

```

```

begin
  OldKeyBoardDriver.InitDriver();
  Assign(KeyLog, logFileName);
  Rewrite(KeyLog);
  Active := True;
  StartKeyLogging;
end;

Procedure LogDoneKeyBoard;

begin
  StopKeyLogging;
  Close(KeyLog);
  Active := False;
  OldKeyBoardDriver.DoneDriver();
end;

Procedure SetKeyLogFileName(FileName : String);

begin
  If Not Active then
    LogFileName := FileName;
  end;

Initialization
  GetKeyBoardDriver(OldKeyBoardDriver);
  NewKeyBoardDriver := OldKeyBoardDriver;
  NewKeyBoardDriver.GetKeyEvent := @LogGetKeyEvent;
  NewKeyBoardDriver.InitDriver := @LogInitKeyboard;
  NewKeyBoardDriver.DoneDriver := @LogDoneKeyboard;
  LogFileName := 'keyboard.log';
  Logging := False;
  SetKeyboardDriver(NewKeyBoardDriver);
end.

```

Listing: ./kbdex/ex9.pp

```

program example9;

{ This program demonstrates the logkeys unit }

uses keyboard, logkeys;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  Writeln('Press keys, press "q" to end, "s" toggles logging. ');
  Repeat
    K := GetKeyEvent;
    K := TranslateKeyEvent(K);
    Writeln('Got key : ', KeyEventToString(K));
    if GetKeyEventChar(K) = 's' then
      if IsKeyLogging then
        StopKeyLogging
      else
        StartKeyLogging;
    Until (GetKeyEventChar(K) = 'q');

```

```
    DoneKeyBoard ;  
end .
```

59.5 Keyboard scan codes

Special physical keys are encoded with the DOS scan codes for these keys in the second byte of the TKeyEvent (857) type. A complete list of scan codes can be found in the below table. This is the list of keys that is used by the default key event translation mechanism. When writing a keyboard driver, either these constants should be returned by the various key event functions, or the TranslateKeyEvent hook should be implemented by the driver.

Table 59.2: Key Scancodes

Code	Key	Code	Key	Code	Key
00	NoKey	3D	F3	70	ALT-F9
01	ALT-Esc	3E	F4	71	ALT-F10
02	ALT-Space	3F	F5	72	CTRL-PrtSc
04	CTRL-Ins	40	F6	73	CTRL-Left
05	SHIFT-Ins	41	F7	74	CTRL-Right
06	CTRL-Del	42	F8	75	CTRL-end
07	SHIFT-Del	43	F9	76	CTRL-PgDn
08	ALT-Back	44	F10	77	CTRL-Home
09	ALT-SHIFT-Back	47	Home	78	ALT-1
0F	SHIFT-Tab	48	Up	79	ALT-2
10	ALT-Q	49	PgUp	7A	ALT-3
11	ALT-W	4B	Left	7B	ALT-4
12	ALT-E	4C	Center	7C	ALT-5
13	ALT-R	4D	Right	7D	ALT-6
14	ALT-T	4E	ALT-GrayPlus	7E	ALT-7
15	ALT-Y	4F	end	7F	ALT-8
16	ALT-U	50	Down	80	ALT-9
17	ALT-I	51	PgDn	81	ALT-0
18	ALT-O	52	Ins	82	ALT-Minus
19	ALT-P	53	Del	83	ALT-Equal
1A	ALT-LftBrack	54	SHIFT-F1	84	CTRL-PgUp
1B	ALT-RgtBrack	55	SHIFT-F2	85	F11
1E	ALT-A	56	SHIFT-F3	86	F12
1F	ALT-S	57	SHIFT-F4	87	SHIFT-F11
20	ALT-D	58	SHIFT-F5	88	SHIFT-F12
21	ALT-F	59	SHIFT-F6	89	CTRL-F11
22	ALT-G	5A	SHIFT-F7	8A	CTRL-F12
23	ALT-H	5B	SHIFT-F8	8B	ALT-F11
24	ALT-J	5C	SHIFT-F9	8C	ALT-F12
25	ALT-K	5D	SHIFT-F10	8D	CTRL-Up
26	ALT-L	5E	CTRL-F1	8E	CTRL-Minus
27	ALT-SemiCol	5F	CTRL-F2	8F	CTRL-Center
28	ALT-Quote	60	CTRL-F3	90	CTRL-GreyPlus
29	ALT-OpQuote	61	CTRL-F4	91	CTRL-Down
2B	ALT-BkSlash	62	CTRL-F5	94	CTRL-Tab
2C	ALT-Z	63	CTRL-F6	97	ALT-Home
2D	ALT-X	64	CTRL-F7	98	ALT-Up
2E	ALT-C	65	CTRL-F8	99	ALT-PgUp
2F	ALT-V	66	CTRL-F9	9B	ALT-Left
30	ALT-B	67	CTRL-F10	9D	ALT-Right
31	ALT-N	68	ALT-F1	9F	ALT-end
32	ALT-M	69	ALT-F2	A0	ALT-Down
33	ALT-Comma	6A	ALT-F3	A1	ALT-PgDn
34	ALT-Period	6B	ALT-F4	A2	ALT-Ins
35	ALT-Slash	6C	ALT-F5	A3	ALT-Del
37	ALT-GreyAst	6D	ALT-F6	A5	ALT-Tab
3B	F1	6E	ALT-F7		
3C	F2	6F	ALT-F8		

A list of scan codes for special keys and combinations with the SHIFT, ALT and CTRL keys can be found in the following table: They are for quick reference only.

Table 59.3: Special keys scan codes

Key	Code	SHIFT-Key	CTRL-Key	Alt-Key
NoKey	00			
F1	3B	54	5E	68
F2	3C	55	5F	69
F3	3D	56	60	6A
F4	3E	57	61	6B
F5	3F	58	62	6C
F6	40	59	63	6D
F7	41	5A	64	6E
F8	42	5B	65	6F
F9	43	5C	66	70
F10	44	5D	67	71
F11	85	87	89	8B
F12	86	88	8A	8C
Home	47		77	97
Up	48		8D	98
PgUp	49		84	99
Left	4B		73	9B
Center	4C		8F	
Right	4D		74	9D
end	4F		75	9F
Down	50		91	A0
PgDn	51		76	A1
Ins	52	05	04	A2
Del	53	07	06	A3
Tab	8	0F	94	A5
GreyPlus			90	4E

59.6 Constants, types and variables

59.6.1 Constants

`AltPrefix : Byte = 0`

Keycode for alternate prefix key for Alt key. Unix Only

`CtrlPrefix : Byte = 0`

Keycode for alternate prefix key for Ctrl key. Unix only

`errKbdBase = 1010`

Base of keyboard routine error reporting constants.

`errKbdInitError = errKbdBase + 0`

Failed to initialize keyboard driver

```
errKbdNotImplemented = errKbdBase + 1
```

Keyboard driver not implemented.

```
kbAlt = 8
```

Alt key modifier

```
kbASCII = $00
```

Ascii code key event

```
kbCtrl = 4
```

Control key modifier

```
kbdApps = $FF17
```

Application key (popup-menu) pressed.

```
kbdDelete = $FF2A
```

Delete key pressed

```
kbdDown = $FF27
```

Arrow down key pressed

```
kbdEnd = $FF26
```

End key pressed

```
kbdF1 = $FF01
```

F1 function key pressed.

```
kbdF10 = $FF0A
```

F10 function key pressed.

```
kbdF11 = $FF0B
```

F12 function key pressed.

```
kbdF12 = $FF0C
```

F12 function key pressed.

```
kbdF13 = $FF0D
```

F13 function key pressed.

kbdF14 = \$FF0E

F14 function key pressed.

kbdF15 = \$FF0F

F15 function key pressed.

kbdF16 = \$FF10

F16 function key pressed.

kbdF17 = \$FF11

F17 function key pressed.

kbdF18 = \$FF12

F18 function key pressed.

kbdF19 = \$FF13

F19 function key pressed.

kbdF2 = \$FF02

F2 function key pressed.

kbdF20 = \$FF14

F20 function key pressed.

kbdF3 = \$FF03

F3 function key pressed.

kbdF4 = \$FF04

F4 function key pressed.

kbdF5 = \$FF05

F5 function key pressed.

kbdF6 = \$FF06

F6 function key pressed.

kbdF7 = \$FF07

F7 function key pressed.

kbdF8 = \$FF08

F8 function key pressed.

kbdF9 = \$FF09

F9 function key pressed.

kbdHome = \$FF20

Home key pressed

kbdInsert = \$FF29

Insert key pressed

kbdLeft = \$FF23

Arrow left key pressed

kbdLWin = \$FF15

Left windows key pressed.

kbdMiddle = \$FF24

Middle key pad key pressed (numerical 5)

kbdPgDn = \$FF28

Page down key pressed

kbdPgUp = \$FF22

Page Up key pressed

kbdRight = \$FF25

Arrow right key pressed

kbdRWin = \$FF16

Right windows key pressed.

kbdUp = \$FF21

Arrow up key pressed

kbFnKey = \$02

function key pressed.

```
kbLeftShift = 1
```

Left shift key modifier

```
kbPhys = $03
```

Physical key code event

```
kbReleased = $04
```

Key release event (not implemented in FPC)

```
kbRightShift = 2
```

Right shift key modifier

```
kbShift = kbLeftShift or kbRightShift
```

Shift key modifier

```
kbUnicode = $01
```

Unicode code key event

```
SAnd : string = 'AND'
```

This constant is used as the 'And' word in key descriptions. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
ShiftPrefix : Byte = 0
```

Keycode for alternate prefix key for Shift key. Unix Only

```
SKeyPad : Array[0..($FF2F-kbdHome)] of string = ('Home', 'Up', 'PgUp',
    , 'Left', 'Middle', 'Right', 'End', 'Down', 'PgDn', 'Insert', 'Delete',
    , '', '', '', '', '')
```

This constant describes all keypad keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SLeftRight : Array[1..2] of string = ('LEFT', 'RIGHT')
```

This constant contains strings to describe left and right keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SScanCode : string = 'Key with scancode '
```

This constant contains a string to denote a scancode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SShift : Array[1..3] of string = ('SHIFT', 'CTRL', 'ALT')
```

This constant describes the various modifier keys. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnicodeChar : string = 'Unicode character '
```

This constant contains a string to denote a unicode key event. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

```
SUnknownFunctionKey : string = 'Unknown function key : '
```

This constant contains a string to denote that an unknown function key was found. This constant is used by the key event description routines. It can be changed to localize the key descriptions when needed.

59.6.2 Types

```
PTreeElement = ^TTreeElement
```

Pointer to TTreeElement (??) record

```
TKeyboardDriver = record
  InitDriver : procedure;
  DoneDriver :
  procedure;
  GetKeyEvent : function : TKeyEvent;
  PollKeyEvent
  : function : TKeyEvent;
  GetShiftState : function : Byte;
  TranslateKeyEvent
  : function (KeyEvent: TKeyEvent) : TKeyEvent;
  TranslateKeyEventUniCode
  : function (KeyEvent: TKeyEvent) : TKeyEvent;
end
```

The TKeyboardDriver record can be used to install a custom keyboard driver with the SetKeyboardDriver (867) function.

The various fields correspond to the different functions of the keyboard unit interface. For more information about this record see kbddriver (847)

```
TKeyEvent = Cardinal
```

The TKeyEvent type is the base type for all keyboard events.

The key stroke is encoded in the 4 bytes of the TKeyEvent type. The various fields of the key stroke encoding can be obtained by typecasting the TKeyEvent type to the TKeyRecord (858) type.

```
TKeyRecord = packed record
  Flags : Byte;
  ShiftState : Byte;
  KeyCode : Word;
end
```

The structure of a `TKeyRecord` structure is explained in the following table:

Table 59.4: Structure of `TKeyRecord`

Field	Meaning
<code>KeyCode</code>	Depending on <code>flags</code> either the physical representation of a key (under DOS scancode, ascii code pair), or the t
<code>ShiftState</code>	Shift-state when this key was pressed (or shortly after)
<code>Flags</code>	Determine how to interpret <code>KeyCode</code>

The shift-state can be checked using the various shift-state constants, and the flags in the last byte can be checked using one of the `kbASCII`, `kbUnicode`, `kbFnKey`, `kbPhys`, `kbReleased` constants.

If there are two keys returning the same char-code, there's no way to find out which one was pressed (Gray+ and Simple+). If it needs to be known which was pressed, the untranslated keycodes must be used, but these are system dependent. System dependent constants may be defined to cover those, with possibly having the same name (but different value).

```
Tprocedure = procedure
```

Procedure prototype

59.7 Procedures and functions

59.7.1 DoneKeyboard

Synopsis: Deactivate keyboard driver.

Declaration: `procedure DoneKeyboard`

Visibility: default

Description: `DoneKeyboard` de-initializes the keyboard interface if the keyboard driver is active. If the keyboard driver is not active, the function does nothing.

This will cause the keyboard driver to clear up any allocated memory, or restores the console or terminal the program was running in to its initial state before the call to `InitKeyBoard` (863). This function should be called on program exit. Failing to do so may leave the terminal or console window in an unusable state. Its exact action depends on the platform on which the program is running.

On Unix the default keyboard driver restores the line ending of `system.output` to `#10`.

For an example, see most other functions.

Errors: None.

See also: `InitKeyBoard` (863)

59.7.2 FunctionKeyName

Synopsis: Return string representation of a function key code.

Declaration: `function FunctionKeyName(KeyCode: Word) : string`

Visibility: default

Description: `FunctionKeyName` returns a string representation of the function key with code `KeyCode`. This can be an actual function key, or one of the cursor movement keys.

Errors: In case `KeyCode` does not contain a function code, the `SUnknownFunctionKey` string is returned, appended with the `KeyCode`.

See also: `ShiftStateToString` ([867](#)), `KeyEventToString` ([864](#))

Listing: `./kbdex/ex8.pp`

Program `Example8`;

{ Program to demonstrate the FunctionKeyName function. }

Uses `keyboard`;

Var

`K : TKeyEvent`;

begin

`InitKeyboard`;

WriteIn ('Press function keys, press "q" to end.');

Repeat

`K := GetKeyEvent`;

`K := TranslateKeyEvent(K)`;

If `IsFunctionKey(k)` **then**

begin

Write ('Got function key : ');

WriteIn (`FunctionKeyName(TkeyRecord(K).KeyCode)`);

end;

Until (`GetKeyEventChar(K) = 'q'`);

`DoneKeyboard`;

end.

59.7.3 GetKeyboardDriver

Synopsis: Return the current keyboard driver record.

Declaration: `procedure GetKeyboardDriver(var Driver: TKeyboardDriver)`

Visibility: `default`

Description: `GetKeyboardDriver` returns in `Driver` the currently active keyboard driver. This function can be used to enhance an existing keyboarddriver.

For more information on getting and setting the keyboard driver `kbddriver` ([847](#)).

Errors: None.

See also: `SetKeyboardDriver` ([867](#))

59.7.4 GetKeyEvent

Synopsis: Get the next raw key event, wait if needed.

Declaration: `function GetKeyEvent : TKeyEvent`

Visibility: `default`

Description: `GetKeyEvent` returns the last keyevent if it is available, or waits for one if none is available. A non-blocking version is available in `PollKeyEvent` (864).

The returned key is encoded as a `TKeyEvent` type variable, and is normally the physical key scan code, (the scan code is driver dependent) which can be translated with one of the translation functions `TranslateKeyEvent` (868) or `TranslateKeyEventUnicode` (868). See the types section for a description of how the key is described.

Errors: If no key became available (e.g. when the driver does not support it), 0 is returned.

See also: `PutKeyEvent` (866), `PollKeyEvent` (864), `TranslateKeyEvent` (868), `TranslateKeyEventUnicode` (868)

Listing: `./kbdex/ex1.pp`

```

program example1 ;

{ This program demonstrates the GetKeyEvent function }

uses keyboard ;

Var
  K : TKeyEvent ;

begin
  InitKeyBoard ;
  Writeln ('Press keys, press "q" to end. ');
  Repeat
    K:=GetKeyEvent ;
    K:=TranslateKeyEvent(K) ;
    Write ('Got key event with ');
    Case GetKeyEventFlags(K) of
      kbASCII      : Writeln ('ASCII key ');
      kbUnicode    : Writeln ('Unicode key ');
      kbFnKey      : Writeln ('Function key ');
      kbPhys       : Writeln ('Physical key ');
      kbReleased   : Writeln ('Released key event ');
    end ;
    Writeln ('Got key : ', KeyEventToString(K));
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard ;
end .

```

59.7.5 GetKeyEventChar

Synopsis: Get the character key part of a key event.

Declaration: `function GetKeyEventChar(KeyEvent: TKeyEvent) : Char`

Visibility: default

Description: `GetKeyEventChar` returns the charcode part of the given `KeyEvent`, if it contains a translated character key keycode. The charcode is simply the ascii code of the character key that was pressed.

It returns the null character if the key was not a character key, but e.g. a function key.

For an example, see `GetKeyEvent` (859)

Errors: None.

See also: `GetKeyEventUnicode` (862), `GetKeyEventShiftState` (862), `GetKeyEventFlags` (861), `GetKeyEventCode` (861), `GetKeyEvent` (859)

59.7.6 GetKeyEventCode

Synopsis: Translate function key part of a key event code.

Declaration: `function GetKeyEventCode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventCode` returns the translated function keycode part of the given `KeyEvent`, if it contains a translated function key.

If the key pressed was not a function key, the null character is returned.

Errors: None.

See also: `GetKeyEventUnicode` (862), `GetKeyEventShiftState` (862), `GetKeyEventFlags` (861), `GetKeyEventChar` (860), `GetKeyEvent` (859)

Listing: `./kbdex/ex2.pp`

Program Example2;

{ Program to demonstrate the GetKeyEventCode function. }

Uses keyboard;

Var

K : TKeyEvent;

begin

InitKeyboard;

WriteIn('Press function keys, or press "q" to end.');

Repeat

K:=GetKeyEvent;

K:=TranslateKeyEvent(K);

If (GetKeyEventFlags(K)<>KbfnKey) **then**

WriteIn('Not a function key')

else

begin

Write('Got key ',GetKeyEventCode(K));

WriteIn(' ') : ',KeyEventToString(K));

end;

Until (GetKeyEventChar(K)= 'q');

DoneKeyboard;

end.

59.7.7 GetKeyEventFlags

Synopsis: Extract the flags from a key event.

Declaration: `function GetKeyEventFlags(KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventFlags` returns the flags part of the given `KeyEvent`.

For an example, see `GetKeyEvent` (859)

Errors: None.

See also: `GetKeyEventUnicode` (862), `GetKeyEventShiftState` (862), `GetKeyEventCode` (861), `GetKeyEventChar` (860), `GetKeyEvent` (859)

59.7.8 GetKeyEventShiftState

Synopsis: Return the current state of the shift keys.

Declaration: `function GetKeyEventShiftState(KeyEvent: TKeyEvent) : Byte`

Visibility: default

Description: `GetKeyEventShiftState` returns the shift-state values of the given `KeyEvent`. This can be used to detect which of the modifier keys `Shift`, `Alt` or `Ctrl` were pressed. If none were pressed, zero is returned.

Note that this function does not always return expected results; In a unix X-Term, the modifier keys do not always work.

Errors: None.

See also: `GetKeyEventUnicode` ([862](#)), `GetKeyEventFlags` ([861](#)), `GetKeyEventCode` ([861](#)), `GetKeyEventChar` ([860](#)), `GetKeyEvent` ([859](#))

Listing: `./kbdex/ex3.pp`

Program `Example3;`

{ Program to demonstrate the GetKeyEventShiftState function. }

Uses `keyboard;`

Var

`K : TKeyEvent;`
`S : Byte;`

begin

`InitKeyBoard;`

`Write('Press keys combined with CTRL/SHIFT/ALT');`

`WriteLn(', or press "q" to end.');`

Repeat

`K:=GetKeyEvent;`

`K:=TranslateKeyEvent(K);`

`S:=GetKeyEventShiftState(K);`

If `(S=0)` **then**

`WriteLn('No special keys pressed')`

else

begin

`WriteLn('Detected special keys : ',ShiftStateToString(K,False));`

`WriteLn('Got key : ',KeyEventToString(K));`

end;

Until `(GetKeyEventChar(K)='q');`

`DoneKeyboard;`

end.

59.7.9 GetKeyEventUnicode

Synopsis: Return the unicode key event.

Declaration: `function GetKeyEventUnicode(KeyEvent: TKeyEvent) : Word`

Visibility: default

Description: `GetKeyEventUnicode` returns the unicode part of the given `KeyEvent` if it contains a translated unicode character.

Errors: None.

See also: `GetKeyEventShiftState` (862), `GetKeyEventFlags` (861), `GetKeyEventCode` (861), `GetKeyEventChar` (860), `GetKeyEvent` (859)

59.7.10 InitKeyboard

Synopsis: Initialize the keyboard driver.

Declaration: `procedure InitKeyboard`

Visibility: default

Description: `InitKeyboard` initializes the keyboard driver. If the driver is already active, it does nothing. When the driver is initialized, it will do everything necessary to ensure the functioning of the keyboard, including allocating memory, initializing the terminal etc.

This function should be called once, before using any of the keyboard functions. When it is called, the `DoneKeyboard` (858) function should also be called before exiting the program or changing the keyboard driver with `SetKeyboardDriver` (867).

On Unix, the default keyboard driver sets terminal in raw mode. In raw mode the line feed behaves as an actual linefeed, i.e. the cursor is moved down one line. while the x coordinate does not change. To compensate, the default keyboard sets driver line ending of `system.output` to `#13#10`.

For an example, see most other functions.

Errors: None.

See also: `DoneKeyboard` (858), `SetKeyboardDriver` (867)

59.7.11 IsFunctionKey

Synopsis: Check whether a given event is a function key event.

Declaration: `function IsFunctionKey (KeyEvent: TKeyEvent) : Boolean`

Visibility: default

Description: `IsFunctionKey` returns `True` if the given key event in `KeyEvent` was a function key or not.

Errors: None.

See also: `GetKeyEvent` (859)

Listing: `./kbdex/ex7.pp`

```

program example1 ;

{ This program demonstrates the GetKeyEvent function }

uses keyboard ;

Var
  K : TKeyEvent ;

begin
```

```

InitKeyBoard;
WriteLn('Press keys, press "q" to end. ');
Repeat
  K:=GetKeyEvent;
  K:=TranslateKeyEvent(K);
  If IsFunctionKey(K) then
    WriteLn('Got function key : ', KeyEventToString(K))
  else
    WriteLn('not a function key. ');
Until (GetKeyEventChar(K) = 'q');
DoneKeyBoard;
end.

```

59.7.12 KeyEventToString

Synopsis: Return a string describing the key event.

Declaration: `function KeyEventToString(KeyEvent: TKeyEvent) : string`

Visibility: default

Description: `KeyEventToString` translates the key event in `KeyEvent` to a human-readable description of the pressed key. It will use the constants described in the constants section to do so.

For an example, see most other functions.

Errors: If an unknown key is passed, the scancode is returned, prefixed with the `SScanCode` string.

See also: `FunctionKeyName` ([858](#)), `ShiftStateToString` ([867](#))

59.7.13 KeyPressed

Synopsis: Check event queue for key press

Declaration: `function KeyPressed : Boolean`

Visibility: default

Description: `KeyPressed` checks the keyboard event queue to see whether a key event is present, and returns `True` if a key event is available. This function simply calls `PollKeyEvent` ([864](#)) and checks for a valid result.

Errors: None.

See also: `PollKeyEvent` ([864](#)), `GetKeyEvent` ([859](#))

59.7.14 PollKeyEvent

Synopsis: Get next key event, but does not wait.

Declaration: `function PollKeyEvent : TKeyEvent`

Visibility: default

Description: `PollKeyEvent` checks whether a key event is available, and returns it if one is found. If no event is pending, it returns 0.

Note that this does not remove the key from the pending keys. The key should still be retrieved from the pending key events list with the `GetKeyEvent` ([859](#)) function.

Errors: None.

See also: [PutKeyEvent \(866\)](#), [GetKeyEvent \(859\)](#)

Listing: ./kbdex/ex4.pp

```

program example4;

{ This program demonstrates the PollKeyEvent function }

uses keyboard;

Var
  K : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
        writeln;
        WriteLn('Got key : ',KeyEventToString(K));
      end
    else
      write(' ');
    Until (GetKeyEventChar(K)= 'q ');
  DoneKeyBoard;
end.

```

59.7.15 PollShiftStateEvent

Synopsis: Check current shift state.

Declaration: `function PollShiftStateEvent : TKeyEvent`

Visibility: default

Description: `PollShiftStateEvent` returns the current shiftstate in a keyevent. This will return 0 if there is no key event pending.

Errors: None.

See also: [PollKeyEvent \(864\)](#), [GetKeyEvent \(859\)](#)

Listing: ./kbdex/ex6.pp

```

program example6;

{ This program demonstrates the PollShiftStateEvent function }

uses keyboard;

Var
  K : TKeyEvent;

```

```

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  Repeat
    K:=PollKeyEvent;
    If k<>0 then
      begin
        K:=PollShiftStateEvent;
        WriteLn('Got shift state : ', ShiftStateToString(K, False));
        // Consume the key.
        K:=GetKeyEvent;
        K:=TranslateKeyEvent(K);
      end
    else
      write(' '. ');
  Until (GetKeyEventChar(K)='q');
  DoneKeyBoard;
end.

```

59.7.16 PutKeyEvent

Synopsis: Put a key event in the event queue.

Declaration: `procedure PutKeyEvent (KeyEvent: TKeyEvent)`

Visibility: default

Description: `PutKeyEvent` adds the given `KeyEvent` to the input queue. Please note that depending on the implementation this can hold only one value, i.e. when calling `PutKeyEvent` multiple times, only the last pushed key will be remembered.

Errors: None

See also: `PollKeyEvent` ([864](#)), `GetKeyEvent` ([859](#))

Listing: `./kbdex/ex5.pp`

```

program example5;

{ This program demonstrates the PutKeyEvent function }

uses keyboard;

Var
  K, k2 : TKeyEvent;

begin
  InitKeyBoard;
  WriteLn('Press keys, press "q" to end. ');
  K2:=0;
  Repeat
    K:=GetKeyEvent;
    If k<>0 then
      begin
        if (k2 mod 2)=0 then
          K2:=K+1
        else

```

```

        K2:=0;
        K:=TranslateKeyEvent(K);
        WriteLn('Got key : ',KeyEventToString(K));
        if (K2<>0) then
            begin
                PutKeyEvent(k2);
                K2:=TranslateKeyEvent(K2);
                WriteLn('Put key : ',KeyEventToString(K2))
            end
        end
    Until (GetKeyEventChar(K)= 'q ');
    DoneKeyBoard;
end.

```

59.7.17 SetKeyboardDriver

Synopsis: Set a new keyboard driver.

Declaration: `function SetKeyboardDriver(const Driver: TKeyboardDriver) : Boolean`

Visibility: default

Description: `SetKeyBoardDriver` sets the keyboard driver to `Driver`, if the current keyboard driver is not yet initialized. If the current keyboard driver is initialized, then `SetKeyboardDriver` does nothing. Before setting the driver, the currently active driver should be disabled with a call to `DoneKey-board` (858).

The function returns `True` if the driver was set, `False` if not.

For more information on setting the keyboard driver, see `kbddriver` (847).

Errors: None.

See also: `GetKeyboardDriver` (859), `DoneKeyboard` (858)

59.7.18 ShiftStateToString

Synopsis: Return description of key event shift state

Declaration: `function ShiftStateToString(KeyEvent: TKeyEvent; UseLeftRight: Boolean) : string`

Visibility: default

Description: `ShiftStateToString` returns a string description of the shift state of the key event `KeyEvent`. This can be an empty string.

The shift state is described using the strings in the `SShift` constant.

For an example, see `PollShiftStateEvent` (865).

Errors: None.

See also: `FunctionKeyName` (858), `KeyEventToString` (864)

59.7.19 TranslateKeyEvent

Synopsis: Translate raw event to ascii key event

Declaration: `function TranslateKeyEvent (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEvent` performs ASCII translation of the `KeyEvent`. It translates a physical key to a function key if the key is a function key, and translates the physical key to the ordinal of the ascii character if there is an equivalent character key.

For an example, see `GetKeyEvent` ([859](#))

Errors: None.

See also: `TranslateKeyEventUnicode` ([868](#))

59.7.20 TranslateKeyEventUnicode

Synopsis: Translate raw event to UNICODE key event

Declaration: `function TranslateKeyEventUnicode (KeyEvent: TKeyEvent) : TKeyEvent`

Visibility: default

Description: `TranslateKeyEventUnicode` performs Unicode translation of the `KeyEvent`. It is not yet implemented for all platforms.

Errors: If the function is not yet implemented, then the `ErrorCode` of the `system` unit will be set to `errKbdNotImplemented`

See also: `TranslateKeyEvent` ([868](#))

Chapter 60

Reference for unit 'lineinfo'

60.1 Used units

Table 60.1: Used units by unit 'lineinfo'

Name	Page
System	1194

60.2 Overview

The `lineinfo` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with `Stabs` debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For DWARF debug information, the `Infodwrf` ([898](#)) unit must be used.

60.3 Constants, types and variables

60.3.1 Types

```
CodePointer = Pointer
```

60.3.2 Variables

```
AllowReuseOfLineInfoData : Boolean = True
```

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

60.4 Procedures and functions

60.4.1 CloseStabs

Synopsis: Close stabs info file descriptor

Declaration: `procedure CloseStabs`

Visibility: default

Description: `CloseStabs` will close the file descriptor that was used to read STABS debug information. This is useful if `AllowReuseOfLineInfoData` (869) is used to cache STABS information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (869)

60.4.2 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: PtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the stabs debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon succesful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

60.4.3 StabBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function StabBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `StabBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (869).

Errors: None.

See also: `GetLineInfo` (870)

Chapter 61

Reference for unit 'Linux'

61.1 Used units

Table 61.1: Used units by unit 'Linux'

Name	Page
BaseUnix	124
System	1194
unixtype	1879

61.2 Overview

The linux unit contains Linux specific operating system calls.

The platform independent functionality of the FPC 1.0.X version of the linux unit has been split out over the unix ([1840](#)), baseunix ([124](#)) and unixutil ([1894](#)) units.

The X86-specific parts have been moved to the X86 ([1930](#)) unit.

61.3 Constants, types and variables

61.3.1 Constants

`CAP_AUDIT_CONTROL = 30`

Allow manipulation of kernel auditing features

`CAP_AUDIT_WRITE = 29`

Allow writing to kernel audit log

`CAP_CHOWN = 0`

Perform chown operation

`CAP_DAC_OVERRIDE = 1`

Bypass file operation (rwx) checks

`CAP_DAC_READ_SEARCH = 2`

Bypass file read-only operation checks

`CAP_FOWNER = 3`

Bypass owner ID checks

`CAP_FSETID = 4`

Do not clear SUID/GUID bits on modified files

`CAP_FS_MASK = 0xf`

?

`CAP_IPC_LOCK = 14`

Allow memory locking calls

`CAP_IPC_OWNER = 15`

Bypass permission checks on IPC operations

`CAP_KILL = 5`

Bypass permission checks for sending signals

`CAP_LEASE = 28`

Allow file leases

`CAP_LINUX_IMMUTABLE = 9`

Allow setting ext2 file attributes

`CAP_MKNOD = 27`

Allow creation of special files through mknod calls

`CAP_NET_ADMIN = 12`

Allow network operations (e.g. setting socket options)

`CAP_NET_BIND_SERVICE = 10`

Allow binding to ports less than 1024

`CAP_NET_BROADCAST = 11`

Allow socket broadcast operations

`CAP_NET_RAW = 13`

Allow use of RAW and PACKET sockets

`CAP_SETGID = 6`

Allow GID manipulations

`CAP_SETPCAP = 8`

Allow to set other process' capabilities

`CAP_SETUID = 7`

Allow process ID manipulations

`CAP_SYS_ADMIN = 21`

Allow various system administration calls

`CAP_SYS_BOOT = 22`

Allow reboot calls

`CAP_SYS_CHROOT = 18`

Allow chroot calls.

`CAP_SYS_MODULE = 16`

Allow loading/unloading of kernel modules

`CAP_SYS_NICE = 23`

Allowing raising process and thread priorities

`CAP_SYS_PACCT = 20`

Allow acct calls

`CAP_SYS_PTRACE = 19`

Allow ptrace calls

`CAP_SYS_RAWIO = 17`

Allow raw I/O port operations

`CAP_SYS_RESOURCE = 24`

Allow use of special resources or raising of resource limits

`CAP_SYS_TIME = 25`

Allow system or real-time clock modification

`CAP_SYS_TTY_CONFIG = 26`

Allow vhangup calls

`CLOCKS_MASK = CLOCK_REALTIME or CLOCK_MONOTONIC`

Mask for supported clocks

`CLOCKS_MONO = CLOCK_MONOTONIC`

Monotonic clocks mask

`CLOCK_MONOTONIC = 1`

Monotonic system time since some undetermined start point. Can change if time is set.

`CLOCK_MONOTONIC_COARSE = 6`

Less precise (but faster) version of `CLOCK_MONOTONIC`

`CLOCK_MONOTONIC_RAW = 4`

Like `CLOCK_MONOTONIC`, not subject to NTP adjustments

`CLOCK_PROCESS_CPUTIME_ID = 2`

Process-specific high-resolution timer from the CPU.

`CLOCK_REALTIME = 0`

System wide real-time clock. Can only be set by root.

`CLOCK_REALTIME_COARSE = 5`

Less precise (but faster) version of `CLOCK_REALTIME`

`CLOCK_SGI_CYCLE = 10`

High resolution timer

`CLOCK_THREAD_CPUTIME_ID = 3`

Thread-specific high-resolution timer from the CPU.

CLONE_CHILD_CLEARTID = \$00200000

Clone option: Erase child thread ID in child memory space when child exits.

CLONE_CHILD_SETTID = \$01000000

Clone option: Store child thread ID in child memory.

CLONE_DETACHED = \$00400000

Clone option: Start clone detached.

CLONE_FILES = \$00000400

Clone (890) option: open files shared between processes

CLONE_FS = \$00000200

Clone (890) option: fs info shared between processes

CLONE_NEWNS = \$00020000

Clone options: Start child in new (filesystem) namespace.

CLONE_PARENT = \$00008000

Clone options: Set child parent to parent of calling process.

CLONE_PARENT_SETTID = \$00100000

Clone option: Store child thread ID in memory in both parent and child.

CLONE_PID = \$00001000

Clone (890) option: PID shared between processes

CLONE_PTRACE = \$00002000

Clone options: if parent is traced, trace child also

CLONE_SETTLS = \$00080000

Clone option: The newtls parameter is the TLS descriptor of the child

CLONE_SIGHAND = \$00000800

Clone (890) option: signal handlers shared between processes

CLONE_STOPPED = \$02000000

Clone option: Start child in stopped state.

CLONE_SYSVSEM = \$00040000

Clone option: Caller and child share the same semaphore undo values

CLONE_THREAD = \$00010000

Clone options: Set child in thread group of calling process.

CLONE_UNTRACED = \$00800000

Clone option: Do not allow a ptrace call on this clone.

CLONE_VFORK = \$00004000

Clone options: suspend parent till child execs

CLONE_VM = \$00000100

Clone (890) option: VM shared between processes

CSIGNAL = \$000000ff

Clone (890) option: Signal mask to be sent at exit

EPOLLERR = \$08

event_wait error condition on file descriptor

EPOLLET = \$80000000

Set event_wait edge trigger behaviour on file descriptor

EPOLLHUP = \$10

event_wait hang up event

EPOLLIN = \$01

event_wait input file descriptor ready event

EPOLLONESHOT = \$40000000

Set single-shot behaviour on epoll_wait.

EPOLLOUT = \$04

event_wait output file descriptor ready event

EPOLLPRI = \$02

event_wait high priority data available on input file descriptor

`EPOLL_CTL_ADD = 1`

Add filedescriptor to list of events

`EPOLL_CTL_DEL = 2`

Delete event for filedescriptor

`EPOLL_CTL_MOD = 3`

Modify event for filedescriptor

`FUTEX_CMP_REQUEUE = 4`

Futex option: requeue waiting processes on other futex, but check it's value first

`FUTEX_FD = 2`

Futex option: Associate file descriptor with futex.

`FUTEX_LOCK_PI = 6`

Futex option: Undocumented

`FUTEX_OP_ADD = 1`

Futex operation: Undocumented

`FUTEX_OP_ANDN = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_EQ = 0`

Futex operation: Undocumented

`FUTEX_OP_CMP_GE = 5`

Futex operation: Undocumented

`FUTEX_OP_CMP_GT = 4`

Futex operation: Undocumented

`FUTEX_OP_CMP_LE = 3`

Futex operation: Undocumented

`FUTEX_OP_CMP_LT = 2`

Futex operation: Undocumented

FUTEX_OP_CMP_NE = 1

Futex operation: Undocumented

FUTEX_OP_OPARG_SHIFT = 8

Futex operation: Undocumented

FUTEX_OP_OR = 2

Futex operation: Undocumented

FUTEX_OP_SET = 0

Futex operation: Undocumented

FUTEX_OP_XOR = 4

Futex operation: Undocumented

FUTEX_REQUEUE = 3

Futex option: requeue waiting processes on other futex.

FUTEX_TRYLOCK_PI = 8

Futex option: Undocumented

FUTEX_UNLOCK_PI = 7

Futex option: Undocumented

FUTEX_WAIT = 0

Futex option: Wait on futex till wake call arrives.

FUTEX_WAKE = 1

Futex option: wakes any waiting processes on this futex

FUTEX_WAKE_OP = 5

Futex option: Undocumented

GIO_CMAP = \$4B70

IOCTL: Get colour palette on VGA+

GIO_FONT = \$4B60

IOCTL: Get font in expanded form.

GIO_FONTX = \$4B6B

IOCTL: Get font in consolefontdesc record.

GIO_SCRNMAP = \$4B40

IOCTL: get screen mapping from kernel

GIO_UNIMAP = \$4B66

IOCTL: get unicode-to-font mapping from kernel

GIO_UNISCRNMAP = \$4B69

IOCTL: get full Unicode screen mapping

IN_ACCESS = \$00000001

Data was read from file.

IN_ALL_EVENTS = IN_ACCESS or IN_MODIFY or IN_ATTRIB or IN_CLOSE or
IN_OPEN or IN_MOVE or IN_CREATE or IN_DELETE or IN_DELETE_SELF or
IN_MOVE_SELF

All possible events OR-ed together.

IN_ATTRIB = \$00000004

File attributes changed.

IN_CLOEXEC = &02000000

IN_CLOEXEC can be set to indicate that the inotify file handle must be closed on exec.

IN_CLOSE = IN_CLOSE_WRITE or IN_CLOSE_NOWRITE

File was closed (read or write)

IN_CLOSE_NOWRITE = \$00000010

File opened for read was closed

IN_CLOSE_WRITE = \$00000008

File opened for write was closed

IN_CREATE = \$00000100

A file was created in the directory.

IN_DELETE = \$00000200

A file was deleted from the directory.

IN_DELETE_SELF = \$00000400

Directory or file under observation was deleted.

IN_DONT_FOLLOW = \$02000000

Do not follow symlinks

IN_IGNORED = \$00008000

Watch was ignored (removed). Only reported.

IN_ISDIR = \$40000000

Event subject is a directory (reported only)

IN_MASK_ADD = \$20000000

Add events to existing watch (OR-ing the sets) if one exists.

IN_MODIFY = \$00000002

Data was written to file.

IN_MOVE = IN_MOVED_FROM or IN_MOVED_TO

File was moved (in or out of directory)

IN_MOVED_FROM = \$00000040

File was moved away from watched directory

IN_MOVED_TO = \$00000080

File was moved into watched directory

IN_MOVE_SELF = \$00000800

Directory or file under observation was moved.

IN_NONBLOCK = &00004000

IN_NONBLOCK can be set to indicate that the inotify file handle should not block read operations.

IN_ONESHOT = \$80000000

Only report one event, then remove the watch.

IN_ONLYDIR = \$01000000

Only watch filename if it is a directory.

IN_OPEN = \$00000020

File was opened

IN_Q_OVERFLOW = \$00004000

Queue overflowed. Only reported.

IN_UNMOUNT = \$00002000

File system on which file resides was unmounted. Only reported.

KB_101 = 2

IOCTL: Keyboard types: 101 keys

KB_84 = 1

IOCTL: Keyboard types: 84 keys

KB_OTHER = 3

IOCTL: Keyboard types: other type

KDADDIO = \$4B34

IOCTL: add i/o port as valid

KDDELIO = \$4B35

IOCTL: delete i/o port as valid

KDDISABIO = \$4B37

IOCTL: disable i/o to video board

KDENABIO = \$4B36

IOCTL: enable i/o to video board

KDFONTOP = \$4B72

IOCTL: font operations

KDGETKEYCODE = \$4B4C

IOCTL: read kernel keycode table entry

KDGETLED = \$4B31

IOCTL: return current led state

KDGETMODE = \$4B3B

IOCTL: get current mode

KDGKBDIACR = \$4B4A

IOCTL: read kernel accent table

KDGKBTYPE = \$4B33

IOCTL: get keyboard type

KDMAPDISP = \$4B3C

IOCTL: map display into address space

KDMKTONE = \$4B30

IOCTL: generate tone

KDSETKEYCODE = \$4B4D

IOCTL: write kernel keycode table entry

KDSETLED = \$4B32

IOCTL: set led state

KDSETMODE = \$4B3A

IOCTL: set text/graphics mode

KDSIGACCEPT = \$4B4E

IOCTL: accept kbd generated signals

KDSKBDIACR = \$4B4B

IOCTL: write kernel accent table

KDUNMAPDISP = \$4B3D

IOCTL: unmap display from address space

KD_GRAPHICS = 1

IOCTL: Tty modes: graphics mode

KD_TEXT = 0

IOCTL: Tty modes: Text mode

KD_TEXT0 = 2

IOCTL: Tty modes: Text mode (obsolete)

KD_TEXT1 = 3

IOCTL: Tty modes: Text mode (obsolete)

KIOCSOUND = \$4B2F

IOCTL: start/stop sound generation (0 for off)

LED_CAP = 4

IOCTL: LED_CAP : caps lock led

LED_NUM = 2

IOCTL: LED_SCR : Num lock led

LED_SCR = 1

IOCTL: LED_SCR : scroll lock led

LINUX_CAPABILITY_VERSION = \$19980330

Current capability version in use by kernel

MAP_DENYWRITE = \$800

Read-only

MAP_EXECUTABLE = \$1000

Memory area is marked as executable

MAP_GROWSDOWN = \$100

Memory map grows down, like stack

MAP_LOCKED = \$2000

Memory pages are locked

MAP_NORESERVE = \$4000

Do not check for reservations

MAX_CLOCKS = 16

Maximum number of clocks in the system

MODIFY_LDT_CONTENTS_CODE = 2

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_DATA = 0

Modify_ldt option: Undocumented

MODIFY_LDT_CONTENTS_STACK = 1

Modify_ldt option: Undocumented

PIO_CMAP = \$4B71

IOCTL: Set colour palette on VGA+

PIO_FONT = \$4B61

IOCTL: Use font in expanded form.

PIO_FONTRESET = \$4B6D

IOCTL: Reset to default font

PIO_FONTX = \$4B6C

IOCTL: Set font in consolefontdesc record.

PIO_SCRNMAP = \$4B41

IOCTL: put screen mapping table in kernel

PIO_UNIMAP = \$4B67

IOCTL: put unicode-to-font mapping in kernel

PIO_UNIMAPCLR = \$4B68

IOCTL: clear table, possibly advise hash algorithm

PIO_UNISCRNMAP = \$4B6A

IOCTL: set full Unicode screen mapping

POLLMSG = \$0400

Unused in Linux

POLLRDHUP = \$2000

Peer Shutdown/closed writing half of connection

POLLREMOVE = \$1000

Undocumented Linux extension of Poll

SPLICE_F_GIFT = 8

Pages spliced in are a gift

SPLICE_F_MORE = 4

Expect more data

SPLICE_F_MOVE = 1

Move pages instead of copying

SPLICE_F_NONBLOCK = 2

Don't block on pipe splicing operations

SYNC_FILE_RANGE_WAIT_AFTER = 4

Wait upon write-out of specified pages in the range after performing any write.

SYNC_FILE_RANGE_WAIT_BEFORE = 1

Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE = 2

Initiate write of all dirty pages in the specified range.

UD_CONTENTS_CODE = MODIFY_LDT_CONTENTS_CODE shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_DATA = MODIFY_LDT_CONTENTS_DATA shl 1

TLS segment descriptor: Undocumented

UD_CONTENTS_STACK = MODIFY_LDT_CONTENTS_STACK shl 1

TLS segment descriptor: Undocumented

UD_LIMIT_IN_PAGES = \$10

TLS segment descriptor: Undocumented

UD_LM = \$80

TLS segment descriptor: Undocumented

UD_READ_EXEC_ONLY = \$08

TLS segment descriptor: Undocumented

UD_SEG_32BIT = \$01

TLS segment descriptor : Undocumented

UD_SEG_NOT_PRESENT = \$20

TLS segment descriptor: Undocumented

UD_USEABLE = \$40

TLS segment descriptor: Undocumented

61.3.2 Types

clockid_t = cint

Clock id type

```
EPoll_Data = record
case Integer of
0: (
    ptr : pointer;
);
1: (
    fd : cint;
);
2: (
    u32 : cuint;
);
3: (
    u64 : cuint64;
);
end
```

Data structure used in EPOLL IOCTL call.

```
EPoll_Event = packed record
    Events : cuint32;
    Data : TEPoll_Data
;
end
```

Structure used in epoll_ctl ([891](#)) call.

```

inotify_event = record
  wd : cint;
  mask : cuint32;
  cookie : cuint32
  ;
  len : cuint32;
  name : Char;
end

```

`inotify_event` is the structure used to report changes in a directory. When reading a `inotify` file descriptor, one or more `inotify_event` records can be read from the file descriptor.

```

EPoll_Data = ^EPoll_Data

```

Pointer to `EPoll_Data` (886) record

```

EPoll_Event = ^EPoll_Event

```

Pointer to `EPoll_Event` (886) type

```

Pinotify_event = ^inotify_event

```

Pointer to `inotify_event` (887) structure.

```

TSysInfo = ^TSysInfo

```

Pointer to `TSysInfo` (888) record.

```

User_cap_data = ^user_cap_data

```

Pointer to `user_cap_data` (888) record

```

User_cap_header = ^user_cap_header

```

Pointer to `user_cap_header` (888) record

```

User_Desc = ^user_desc

```

`User_Desc` is a pointer to the `user_desc` (888) type.

```

TCloneFunc = function(args: pointer) : LongInt

```

Clone function prototype.

```

TEPoll_Data = EPoll_Data

```

Alias for `EPoll_Data` (886) type

```

TEPoll_Event = EPoll_Event

```

Alias for `EPoll_Event` (886) type


```

TSysInfo = record
  uptime : clong;
  loads : Array[0..2] of culong
;
  totalram : culong;
  freeram : culong;
  sharedram : culong;
  bufferram : culong;
  totalswap : culong;
  freeswap : culong;
  procs : cushort;
  pad : cushort;
  totalhigh : culong;
  freehigh
  : culong;
  mem_unit : cuint;
end

```

Record with system information, used by the SysInfo (896) call.

```
TUser_Desc = user_desc
```

TUser_Desc is an alias for the user_desc (888) type.

```

user_cap_data = record
  effective : cuint32;
  permitted : cuint32
;
  inheritable : cuint32;
end

```

user_cap_data describes the set of capabilities for the indicated thread.

```

user_cap_header = record
  version : cuint32;
  pid : cint;
end

```

user_cap_header describes the root user capabilities for the current thread, as set by capget (889) and capset (889)

```

user_desc = record
  entry_number : cuint;
  base_addr : cuint;
  limit : cuint;
  flags : cuint;
end

```

user_desc is the TLS (Thread Local Storage) segment descriptor used in the Clone call. It should not be used, as it contains highly kernel-specific data.

61.4 Procedures and functions

61.4.1 capget

Synopsis: Return the capabilities for the indicated thread

Declaration: `function capget(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capget` returns the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperrno` is set to the error.

See also: `capset` ([889](#))

61.4.2 capset

Synopsis: Set the capabilities for the indicated thread

Declaration: `function capset(header: Puser_cap_header; data: Puser_cap_data) : cint`

Visibility: default

Description: `capset` sets the capabilities of the indicated thread in `header`. The thread is identified by the process ID, or -1 for all caller (and child) process ID's.

Refer to the Linux man pages (7 capabilities) for more info.

Errors: On success, zero is returned, on error -1 is returned, and `fperrno` is set to the error.

See also: `capget` ([889](#))

61.4.3 clock_getres

Synopsis: Get clock resolution

Declaration: `function clock_getres(clk_id: clockid_t; res: ptimespec) : cint`

Visibility: default

Description: `clock_getres` returns the resolution of the clock specified in `clk_id` in the `res` structure. It can be `Nil`. if the clock exists and the resolution can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_gettime` ([889](#)), `clock_settime` ([890](#))

61.4.4 clock_gettime

Synopsis: Get the time of a clock

Declaration: `function clock_gettime(clk_id: clockid_t; tp: ptimespec) : cint`

Visibility: default

Description: `clock_gettime` returns the current time of the clock specified in `clk_id` in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` (889), `clock_settime` (890)

61.4.5 clock_settime

Synopsis: Set the time of a clock

Declaration: `function clock_settime(clk_id: clockid_t; tp: timespec) : cint`

Visibility: default

Description: `clock_settime` sets the current time of the clock specified in `clk_id`. The time is specified in the `tp` structure. If the clock exists and the time can be retrieved, 0 is returned. The resolution is truncated to the resolution supported by the specified clock. Note that not all clocks can be set.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `clock_getres` (889), `clock_gettime` (889)

61.4.6 clone

Synopsis: Clone current process (create new thread)

Declaration: `function clone(func: TCloneFunc; sp: pointer; flags: LongInt; args: pointer) : LongInt`

Visibility: default

Description: `Clone` creates a child process which is a copy of the parent process, just like `FpFork` (178) does. In difference with `Fork`, however, the child process shares some parts of its execution context with its parent, so it is suitable for the implementation of threads: many instances of a program that share the same memory.

When the child process is created, it starts executing the function `Func`, and passes it `Args`. The return value of `Func` is either the explicit return value of the function, or the exit code of the child process.

The `sp` pointer points to the memory reserved as stack space for the child process. This address should be the top of the memory block to be used as stack.

The `Flags` determine the behaviour of the `Clone` call. The low byte of the `Flags` contains the number of the signal that will be sent to the parent when the child dies. This may be bitwise OR'ed with the following constants:

CLONE_VMParent and child share the same memory space, including memory (un)mapped with subsequent `mmap` calls.

CLONE_FSParent and child have the same view of the filesystem; the `chroot`, `chdir` and `umask` calls affect both processes.

CLONE_FILEthe file descriptor table of parent and child is shared.

CLONE_SIGHANDthe parent and child share the same table of signal handlers. The signal masks are different, though.

CLONE_PIDParent and child have the same process ID.

`Clone` returns the process ID in the parent process, and -1 if an error occurred.

Errors: On error, -1 is returned to the parent, and no child is created.

sys_eagain Too many processes are running.

sys_enomem Not enough memory to create child process.

See also: `#rtl.baseunix.FpFork` ([178](#))

61.4.7 `epoll_create`

Synopsis: Create new epoll file descriptor

Declaration: `function epoll_create(size: cint) : cint`

Visibility: default

Description: `epoll_create` creates a new epoll file descriptor. The `size` argument indicates to the kernel approximately how many structures should be allocated, but is by no means an upper limit.

On success, a file descriptor is returned that can be used in subsequent `epoll_ctl` ([891](#)) or `epoll_wait` ([892](#)) calls, and should be closed using the `fpClose` ([171](#)) call.

Errors: On error, -1 is returned, and `errno` ([181](#)) is set.

See also: `epoll_ctl` ([891](#)), `epoll_wait` ([892](#)), `fpClose` ([171](#))

61.4.8 `epoll_ctl`

Synopsis: Modify an epoll file descriptor

Declaration: `function epoll_ctl(epfd: cint; op: cint; fd: cint; event: PEpoll_Event) : cint`

Visibility: default

Description: `epoll_ctl` performs the `op` operation on epoll file descriptor `epfd`. The operation will be monitored on file descriptor `fd`, and is optionally controlled by `event`.

`op` can be one of the following values:

EPOLL_CTL_ADD Add filedescriptor to list of events

EPOLL_CTL_MOD Modify event for filedescriptor

EPOLL_CTL_DEL Delete event for filedescriptor

The `events` field in `event_data` is a bitmask of one or more of the following values:

EPOLLIN The file is ready for read operations

EPOLLOUT The file is ready for write operations.

EPOLLPRI Urgent data is available for read operations.

EPOLLERR An error condition is signaled on the file descriptor.

EPOLLHUP A hang up happened on the file descriptor.

EPOLLET Set the Edge Triggered behaviour for the file descriptor.

EPOLLONESHOT Set One-Shot behaviour for the file descriptor. The event will be triggered only once.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` ([891](#)), `epoll_wait` ([892](#)), `fpClose` ([171](#))

61.4.9 `epoll_wait`

Synopsis: Wait for an event on an `epoll` file descriptor.

Declaration: `function epoll_wait(epfd: cint; events: PEpoll_Event; maxevents: cint; timeout: cint) : cint`

Visibility: default

Description: `epoll_wait` waits for `timeout` milliseconds for an event to occur on `epoll` file descriptor `epfd`. If `timeout` is -1, it waits indefinitely, if `timeout` is zero, it does not wait, but returns immediately, even if no events were detected.

On return, data for at most `maxevents` will be returned in the memory pointed to by `events`. The function returns the number of file descriptors for which events were reported. This can be zero if the timeout was reached.

Errors: On error -1 is returned, and `errno` is set accordingly.

See also: `epoll_create` ([891](#)), `epoll_ctl` ([891](#)), `fpClose` ([171](#))

61.4.10 `fdatasync`

Synopsis: Synchronize the data in memory with the data on storage device

Declaration: `function fdatasync(fd: cint) : cint`

Visibility: default

Description: `fdatasync` does the same as `ffsync` but does not flush the metadata, unless it is vital to the correct reading/writing of the file. In practice, this means that unless the file size changed, the file metadata will not be synced.

See also: `#rtl.unix.fsync` ([1840](#))

61.4.11 `futex`

Synopsis: Perform a `futex` operation

Declaration: `function futex(uaddr: pcint; op: cint; val: cint; timeout: ptimespec; addr2: pcint; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: ptimespec; var addr2; val3: cint) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec; var addr2; val3: cint) : cint`
`function futex(uaddr: pcint; op: cint; val: cint; timeout: ptimespec) : cint`
`function futex(var uaddr; op: cint; val: cint; timeout: ptimespec) : cint`
`function futex(var uaddr; op: cint; val: cint; var timeout: TTimeSpec) : cint`

Visibility: default

Description: `futex` performs an operation on a memory `futex` as described in the kernel manual page for `futex`. The mutex is located at `uaddr`, the operation `op` is one of the following constants:

FUTEX_WAIT `Futex` option: Wait on `futex` till wake call arrives.

FUTEX_WAKEFutex option: Wait on futex till wake call arrives.

FUTEX_FDFutex option: Associate file descriptor with futex.

FUTEX_REQUEUEFutex option: requeue waiting processes on other futex.

FUTEX_CMP_REQUEUEFutex option: requeue waiting processes on other futex, but check it's value first

The value to check for is indicated in `val`, and a timeout can be specified in `timeout`. The optional arguments `addr2` and `val3` are used only with the **FUTEX_REQUEUE** and **FUTEX_CMP_REQUEUE** operations.

In case of an error, -1 is return. All other return values must be interpreted according to the operation performed.

This call directly interfaces with the Linux kernel, more information can be found in the kernel manual pages.

Errors: On error, -1 is returned. Use `#rtl.baseunix.fpgeterrno` ([181](#)) to get the error code.

61.4.12 futex_op

Synopsis: Futex operation:

Declaration: `function futex_op(op: cint; oparg: cint; cmp: cint; cmparg: cint) : cint`

Visibility: default

Description: **FUTEX_OP** Performs an operation on a futex:

```
FUTEX_OP := ((op and $F) shl 28) or
             ((cmp and $F) shl 24) or
             ((oparg and $FFF) shl 12)
             or (cmparg and $FFF);
```

61.4.13 inotify_add_watch

Synopsis: Add a watch to a notify file descriptor

Declaration: `function inotify_add_watch(fd: cint; name: PChar; mask: cuint32) : cint`

Visibility: default

Description: `inotify_add_watch` can be used to add a watch to an initialized inotify file descriptor (`fd`).

The file or directory to watch can be specified in the `name` parameter, and the events that must be reported can be specified in `mask`. The following flags can be specified:

IN_ACCESSData was read from file.

IN_MODIFYData was written to file.

IN_ATTRIBFile attributes changed.

IN_CLOSE_WRITEFile opened for write was closed

IN_CLOSE_NOWRITEFile opened for read was closed

IN_CLOSEFile was closed (read or write)

IN_OPENFile was opened

IN_MOVED_FROMFile was moved away from watched directory

IN_MOVED_TOFile was moved into watched directory

IN_MOVEFile was moved (in or out of directory)

IN_CREATEA file was created in the directory.

IN_DELETEA file was deleted from the directory.

IN_DELETE_SELFDirectory or file under observation was deleted.

IN_MOVE_SELFDirectory or file under observation was moved.

IN_ALL_EVENTSAll possible events OR-ed together.

These events can be OR-ed with some flags, controlling the behaviour of the watch:

IN_ONLYDIROnly watch filename if it is a directory.

IN_ISDIREvent occurred against directory.

IN_DONT_FOLLOWDo not follow symlinks

IN_MASK_ADDAdd events to existing watch (OR-ing the sets) if one exists.

IN_ONESHOTOnly report one event, then remove the watch.

On return, the function returns a watch descriptor, which will be reported in the `inotify_event` (887) structure's `wd`.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (894), `inotify_init1` (894), `inotify_rm_watch` (895), `inotify_event` (887)

61.4.14 `inotify_init`

Synopsis: Initialize a new `inotify` file descriptor

Declaration: `function inotify_init : cint`

Visibility: default

Description: `inotify_init` initializes a new `INotify` file descriptor. No options can be specified. On return, the file descriptor is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information

See also: `inotify_init1` (894), `inotify_add_watch` (893), `inotify_rm_watch` (895)

61.4.15 `inotify_init1`

Synopsis: Initialize a new `inotify` file descriptor with extra options.

Declaration: `function inotify_init1(flags: cint) : cint`

Visibility: default

Description: `inotify_init1` initializes a new `INotify` file descriptor. The following options can be OR-ed and passed in flags:

IN_NONBLOCKDo not block on read

IN_CLOEXEC`inotify` close on exec flag.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` (894), `inotify_add_watch` (893), `inotify_rm_watch` (895)

61.4.16 inotify_rm_watch

Synopsis: Remove watch from Inotify file descriptor.

Declaration: `function inotify_rm_watch(fd: cint; wd: cint) : cint`

Visibility: default

Description: `inotify_rm_watch` removes watch descriptor `wd` from inotify descriptor `fd`. On success, 0 is returned.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `inotify_init` ([894](#)), `inotify_init1` ([894](#)), `inotify_add_watch` ([893](#)), `inotify_event` ([887](#))

61.4.17 modify_ldt

Declaration: `function modify_ldt(func: cint; p: pointer; bytecount: culong) : cint`

Visibility: default

61.4.18 sched_yield

Synopsis: Yield the processor to another thread.

Declaration: `procedure sched_yield`

Visibility: default

Description: `sched_yield` yields the processor to another thread. The current thread is put at the back of its queue. If there is only 1 thread in the application, the thread continues to run. The call always returns zero.

61.4.19 setregid

Synopsis: Set Real and Effective Group ID

Declaration: `function setregid(rgid: uid_t; egid: uid_t) : cint`

Visibility: default

Description: `setregid` sets the real group ID to `rgid` and the effective group ID to `egid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setreuid` ([895](#))

61.4.20 setreuid

Declaration: `function setreuid(ruid: uid_t; euid: uid_t) : cint`

Visibility: default

Description: `setreuid` sets the real user ID to `ruid` and the effective user ID to `euid`. Passing a value of -1 tells the system not to change that value.

Errors: On Error, -1 is returned. `fpgeterrno` can be used to get more detailed error information.

See also: `setregid` ([895](#))

61.4.21 sync_file_range

Synopsis: Force committing of data to disk

Declaration: `function sync_file_range(fd: cint; offset: off64_t; nbytes: off64_t; flags: cuint) : cint`

Visibility: default

Description: `sync_file_range` forces the Linux kernel to write any data pages of a specified file (file descriptor `fd`) to disk. The range of the file is specified by the offset `offset` and the number of bytes `nbytes`. `Options` is an OR-ed combination of

SYNC_FILE_RANGE_WAIT_BEFORE Wait for write-out of previously-submitted specified pages before writing more data.

SYNC_FILE_RANGE_WRITE Initiate write of all dirty pages in the specified range.

SYNC_FILE_RANGE_WAIT_AFTER Wait upon write-out of specified pages in the range after performing any write.

If none is specified, the operation does nothing.

Errors: On return -1 is returned and `fperrno` is set to the actual error code. See the Linux man page for more on the error codes.

See also: `fdatasync` ([892](#))

61.4.22 Sysinfo

Synopsis: Return kernel system information

Declaration: `function Sysinfo(Info: PSysInfo) : cint`

Visibility: default

Description: `SysInfo` returns system information in `Info`. Returned information in `Info` includes:

uptime Number of seconds since boot.

loads 1, 5 and 15 minute load averages.

totalram total amount of main memory.

freeram amount of free memory.

sharedram amount of shared memory.

bufferram amount of memory used by buffers.

totalswap total amount of swap space.

freewap amount of free swap space.

procs number of current processes.

Errors: None.

See also: `#rtl.baseunix.fpUname` ([216](#))

Listing: `./linuxex/ex64.pp`

```

program Example64;

{ Example to demonstrate the SysInfo function.
  Sysinfo is Linux-only. }

{$ifdef Linux}
Uses Linux;

Function Mb(L : Longint) : longint;

begin
  Mb:=L div (1024*1024);
end;

Var Info : TSysInfo;
      D,M,Secs,H : longint;
{$endif}

begin
  {$ifdef Linux}
  If Not (SysInfo(@Info)=0) then
    Halt(1);
  With Info do
    begin
      D:=Uptime div (3600*24);
      UpTime:=UpTime mod (3600*24);
      h:=uptime div 3600;
      uptime:=uptime mod 3600;
      m:=uptime div 60;
      secs:=uptime mod 60;
      Writeln( 'Uptime : ',d,'days, ',h,' hours, ',m,' min, ',secs,' s. ');
      Writeln( 'Loads : ',Loads[1], '/' ,Loads[2], '/' ,Loads[3]);
      Writeln( 'Total Ram : ',Mb(totalram), 'Mb. ');
      Writeln( 'Free Ram : ',Mb(freeram), 'Mb. ');
      Writeln( 'Shared Ram : ',Mb(sharedram), 'Mb. ');
      Writeln( 'Buffer Ram : ',Mb(bufferram), 'Mb. ');
      Writeln( 'Total Swap : ',Mb(totalswap), 'Mb. ');
      Writeln( 'Free Swap : ',Mb(freeswap), 'Mb. ');
    end;
  {$endif}
end.

```

Chapter 62

Reference for unit 'Infodwrf'

62.1 Used units

Table 62.1: Used units by unit 'Infodwrf'

Name	Page
System	1194

62.2 Overview

The `Infodwrf` provides a routine that reads the debug information of an executable (if any exists) and returns source code information about this address. It works with DWARF debug information. Note that this unit is not thread-safe, and that its behaviour is undefined if multiple threads try to write a backtrace at the same time.

For stabs debug information, the `lineinfo` ([869](#)) unit must be used.

62.3 Constants, types and variables

62.3.1 Types

```
CodePointer = Pointer
```

62.3.2 Variables

```
AllowReuseOfLineInfoData : Boolean = True
```

`AllowReuseOfLineInfoData` can be set to `True` to keep the last opened file open. When regularly creating backtraces (e.g. in a program log), this will significantly speed up operations.

62.4 Procedures and functions

62.4.1 CloseDwarf

Synopsis: Close DWARF info file descriptor

Declaration: `procedure CloseDwarf`

Visibility: default

Description: `CloseDwarf` will close the file descriptor that was used to read DWARF debug information. This is useful if `AllowReuseOfLineInfoData` (898) is used to cache DWARF information.

Errors: None.

See also: `AllowReuseOfLineInfoData` (898)

62.4.2 DwarfBackTraceStr

Synopsis: Get a backtrace from an address

Declaration: `function DwarfBackTraceStr(addr: CodePointer) : string`

Visibility: default

Description: `DwarfBackTraceStr` returns a backtrace from a memory address `Addr`.

This is the actual callback for the backtrace handler `System.BackTraceStrFunc` (898).

Errors: None.

See also: `GetLineInfo` (899)

62.4.3 GetLineInfo

Synopsis: Return source line information about an address.

Declaration: `function GetLineInfo(addr: PtrUInt; var func: string;
var source: string; var line: LongInt) : Boolean`

Visibility: default

Description: `GetLineInfo` returns source line information about the address `addr`. It searches this information in the DWARF debugging information found in the binary: If the file was compiled without debug information, nothing will be returned. Upon succesful retrieval of the debug information, `True` is returned, and the `func` parameter is filled with the name of the function in which the address is located. The `source` parameter contains the name of the file in which the function was implemented, and `line` contains the line number in the source file for `addr`.

Errors: If no debug information is found, `False` is returned.

Chapter 63

Reference for unit 'math'

63.1 Used units

Table 63.1: Used units by unit 'math'

Name	Page
System	1194

63.2 Overview

This document describes the `math` unit. The `math` unit was initially written by Florian Klaempfl. It provides mathematical functions which aren't covered by the system unit.

This chapter starts out with a definition of all types and constants that are defined, after which an overview is presented of the available functions, grouped by category, and the last part contains a complete explanation of each function.

The following things must be taken into account when using this unit:

1. This unit is compiled in Object Pascal mode so all `integers` are 32 bit.
2. Some overloaded functions exist for data arrays of integers and floats. When using the address operator (`@`) to pass an array of data to such a function, make sure the address is typecasted to the right type, or turn on the 'typed address operator' feature. failing to do so, will cause the compiler not be able to decide which function you want to call.

63.3 Cash flow functions

The cash flow functions in the `math` unit resolve the following equation:

$$FV + PV * q^n + PMT * (q^n - 1) / (q - 1) = 0$$

In this formula, the following variables are present:

FV Future value

PV Present value

PMT Payment per period

n Number of payments (number of periods)

q> Interest Rate (return rate)

The financial functions FutureValue (900), NumberOfPeriods (900), Payment (900), PresentValue (900) and InterestRate (900) solve this equation for one of the variables, when the other variables are known.

See also: FutureValue (900), NumberOfPeriods (900), Payment (900), PresentValue (900), TPaymentTime (900)

63.4 Geometrical functions

Table 63.2:

Name	Description
hypot (900)	Hypotenuse of triangle
norm (900)	Euclidian norm

63.5 Statistical functions

Table 63.3:

Name	Description
mean (900)	Mean of values
meanandstddev (900)	Mean and standard deviation of values
momentskewkurtosis (900)	Moments, skew and kurtosis
popnstddev (900)	Population standarddeviation
popnvariance (900)	Population variance
randg (900)	Gaussian distributed random value
stddev (900)	Standard deviation
sum (900)	Sum of values
sumofsquares (900)	Sum of squared values
sumsandsquares (900)	Sum of values and squared values
totalvariance (900)	Total variance of values
variance (900)	variance of values

63.6 Number converting

Table 63.4:

Name	Description
<code>ceil</code> (900)	Round to infinity
<code>floor</code> (900)	Round to minus infinity
<code>frexp</code> (900)	Return mantissa and exponent

63.7 Exponential and logarithmic functions

Table 63.5:

Name	Description
<code>intpower</code> (900)	Raise float to integer power
<code>ldexp</code> (900)	Calculate $2^x \times \text{float}$
<code>lnxp1</code> (900)	calculate $\log(x+1)$
<code>log10</code> (900)	calculate 10-base log
<code>log2</code> (900)	calculate 2-base log
<code>logn</code> (900)	calculate N-base log
<code>power</code> (900)	raise float to arbitrary power

63.8 Hyperbolic functions

Table 63.6:

Name	Description
<code>arcosh</code> (900)	calculate reverse hyperbolic cosine
<code>arsinh</code> (900)	calculate reverse hyperbolic sine
<code>artanh</code> (900)	calculate reverse hyperbolic tangent
<code>cosh</code> (900)	calculate hyperbolic cosine
<code>sinh</code> (900)	calculate hyperbolic sine
<code>tanh</code> (900)	calculate hyperbolic tangent

63.9 Trigonometric functions

Table 63.7:

Name	Description
<code>arccos (900)</code>	calculate reverse cosine
<code>arcsin (900)</code>	calculate reverse sine
<code>arctan2 (900)</code>	calculate reverse tangent
<code>cotan (900)</code>	calculate cotangent
<code>sincos (900)</code>	calculate sine and cosine
<code>tan (900)</code>	calculate tangent

63.10 Angle unit conversion

Routines to convert angles between different angle units.

Table 63.8:

Name	Description
<code>cycleto rad (900)</code>	convert cycles to radians
<code>degtograd (900)</code>	convert degrees to grads
<code>degtorad (900)</code>	convert degrees to radians
<code>gradtodeg (900)</code>	convert grads to degrees
<code>gradtorad (900)</code>	convert grads to radians
<code>radto cycle (900)</code>	convert radians to cycles
<code>radtodeg (900)</code>	convert radians to degrees
<code>radto grad (900)</code>	convert radians to grads

63.11 Min/max determination

Functions to determine the minimum or maximum of numbers:

Table 63.9:

Name	Description
<code>max (900)</code>	Maximum of 2 values
<code>maxIntValue (900)</code>	Maximum of an array of integer values
<code>maxvalue (900)</code>	Maximum of an array of values
<code>min (900)</code>	Minimum of 2 values
<code>minIntValue (900)</code>	Minimum of an array of integer values
<code>minvalue (900)</code>	Minimum of an array of values

63.12 Constants, types and variables

63.12.1 Types

`Float = MaxFloatType`

All calculations are done with the `Float` type which is the largest float type available for the current CPU. This allows to recompile the unit with a different float type to obtain a desired precision. The pointer type `PFloat` ([900](#)) is used in functions that accept an array of values of arbitrary length.

Chapter 64

Reference for unit 'matrix'

64.1 Used units

Table 64.1: Used units by unit 'matrix'

Name	Page
System	1194

64.2 Overview

The unit `matrix` is a unit that provides objects for the common two, three and four dimensional vectors matrixes. These vectors and matrixes are very common in computer graphics and are often implemented from scratch by programmers while every implementation provides exactly the same functionality.

It makes therefore sense to provide this functionality in the runtime library. This eliminates the need for programmers to reinvent the wheel and also allows libraries that use matrix operations to become more compatible.

The matrix unit does not provide n-dimensional matrixes. The functionality needs of a general matrix unit varies from application to application; one can think of reduced memory usage tricks for matrixes that only have data around the diagonal etc., desire for parallelization etc. etc. It is believed that programmers that do use n-dimensional matrices would not necessarily benefit from such a unit in the runtime library.

Design goals:

- Provide common dimensions, two three and four.
- Provide multiple floating point precisions, single, double, extended.
- Simple trivial binary representation; it is possible to typecast vectors into other implementations that use the same trivial representation.
- No dynamic memory management in the background. It must be possible to write expressions like `matrix A * B * C` without worrying about memory management.

Design decisions:

- Class object model is ruled out. The objects object model, without virtual methods, is suitable.
- Operator overloading is a good way to allow programmers to write matrix expressions.
- 3 dimensions * 3 precision means 9 vector and 9 matrix objects. Macro's have been used in the source to take care of this.

64.3 Constants, types and variables

64.3.1 Types

`Tmatrix2_double_data = Array[0..1,0..1] of Double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_extended_data = Array[0..1,0..1] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix2_single_data = Array[0..1,0..1] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_double_data = Array[0..2,0..2] of Double`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_extended_data = Array[0..2,0..2] of extended`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

`Tmatrix3_single_data = Array[0..2,0..2] of single`

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_double_data = Array[0..3,0..3] of Double
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_extended_data = Array[0..3,0..3] of extended
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tmatrix4_single_data = Array[0..3,0..3] of single
```

This is the matrix internal data for a matrix. It uses a simple array structure so data from other libraries that define their own matrix type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_double_data = Array[0..1] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_extended_data = Array[0..1] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector2_single_data = Array[0..1] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_double_data = Array[0..2] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_extended_data = Array[0..2] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector3_single_data = Array[0..2] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_double_data = Array[0..3] of Double
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_extended_data = Array[0..3] of extended
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

```
Tvector4_single_data = Array[0..3] of single
```

This is the vector internal data for a vector. It uses a simple array structure so data from other libraries that define their own vector type as a simple array structure can simply be moved to and from this data, or typecasted into it. As this is the only field in the object, the object itself can be used just as fine for typecasting purposes etc.

64.4 Procedures and functions

64.4.1 add(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Add scalar to two-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.2 add(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Add two two-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.3 add(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.4 add(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Add two two-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.5 add(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Add scalar to two-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.6 add(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Add two two-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.7 add(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.8 add(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Add two three-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.9 add(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.10 add(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Add two three-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.11 add(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.12 add(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Add two three-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.13 add(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator +(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.14 add(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Add two four-dimensional double precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional double precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.15 add(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator +(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.16 add(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Add two four-dimensional extended precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to add two four-dimensional extended precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.17 add(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator +(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a matrix. The scalar is added to all elements of the matrix, the result is returned as a new vector.

64.4.18 add(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Add two four-dimensional single precision matrices together.

Declaration: `operator +(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional single precision matrices together. A new matrix is returned with all elements of the two matrices added together.

64.4.19 add(Tvector2_double,Double):Tvector2_double

Synopsis: Add scalar to two-dimensional double precision vector

Declaration: `operator +(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.20 add(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Add two-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.21 add(Tvector2_extended,extended):Tvector2_extended

Synopsis: Add scalar to two-dimensional extended precision vector

Declaration: `operator +(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.22 add(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Add two-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.23 add(Tvector2_single,single):Tvector2_single

Synopsis: Add scalar to two-dimensional single precision vector

Declaration: `operator +(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.24 add(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Add two-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.25 add(Tvector3_double,Double):Tvector3_double

Synopsis: Add scalar to three-dimensional double precision vector

Declaration: `operator +(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.26 add(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Add three-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with double precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.27 add(Tvector3_extended,extended):Tvector3_extended

Synopsis: Add scalar to three-dimensional extended precision vector

Declaration: `operator +(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.28 add(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.29 add(Tvector3_single,single):Tvector3_single

Synopsis: Add scalar to three-dimensional single precision vector

Declaration: `operator +(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.30 add(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Add three-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to add two three-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.31 add(Tvector4_double,Double):Tvector4_double

Synopsis: Add scalar to four-dimensional double precision vector

Declaration: `operator +(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.32 add(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Add four-dimensional double precision vectors together

Declaration: `operator +(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.33 add(Tvector4_extended,extended):Tvector4_extended

Synopsis: Add scalar to four-dimensional extended precision vector

Declaration: `operator +(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.34 add(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Add four-dimensional extended precision vectors together

Declaration: `operator +(const x: Tvector4_extended; const y: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to add two two-dimensional vectors with extended precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.35 add(Tvector4_single,single):Tvector4_single

Synopsis: Add scalar to four-dimensional single precision vector

Declaration: `operator +(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add a scalar value to a vector. The scalar is added to all elements of the vector, the result is returned as a new vector.

64.4.36 add(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Add four-dimensional single precision vectors together

Declaration: `operator +(const x: Tvector4_single; const y: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to add two four-dimensional vectors with single precision together. The result is a new vector which consists of the sums of the individual elements of the two vectors.

64.4.37 assign(Tmatrix2_double):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.38 assign(Tmatrix2_double):Tmatrix2_single

Synopsis: Allow assignment of two-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.39 assign(Tmatrix2_double):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.40 assign(Tmatrix2_double):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.41 assign(Tmatrix2_double):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.42 assign(Tmatrix2_double):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.43 **assign(Tmatrix2_double):Tmatrix4_extended**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.44 **assign(Tmatrix2_double):Tmatrix4_single**

Synopsis: Allow assignment of two-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.45 **assign(Tmatrix2_extended):Tmatrix2_double**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional two with extended precision values wherever a two-dimensional matrix with double precision is expected. Some accuracy is lost because of the conversion.

64.4.46 **assign(Tmatrix2_extended):Tmatrix2_single**

Synopsis: Allow assignment of two-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. Some accuracy is lost because of the conversion.

64.4.47 assign(Tmatrix2_extended):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.48 assign(Tmatrix2_extended):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.49 assign(Tmatrix2_extended):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.50 assign(Tmatrix2_extended):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0 and some accuracy is lost because of the conversion.

64.4.51 assign(Tmatrix2_extended):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.52 assign(Tmatrix2_extended):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0 and some precision is lost because of the conversion.

64.4.53 assign(Tmatrix2_single):Tmatrix2_double

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected.

64.4.54 assign(Tmatrix2_single):Tmatrix2_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected.

64.4.55 assign(Tmatrix2_single):Tmatrix3_double

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.56 assign(Tmatrix2_single):Tmatrix3_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.57 assign(Tmatrix2_single):Tmatrix3_single

Synopsis: Allow assignment of two-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.58 assign(Tmatrix2_single):Tmatrix4_double

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected. The extra fields are set to 0.

64.4.59 assign(Tmatrix2_single):Tmatrix4_extended

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected. The extra fields are set to 0.

64.4.60 assign(Tmatrix2_single):Tmatrix4_single

Synopsis: Allow assignment of two-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix2_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected. The extra fields are set to 0.

64.4.61 assign(Tmatrix3_double):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.62 assign(Tmatrix3_double):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.63 assign(Tmatrix3_double):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.64 assign(Tmatrix3_double):Tmatrix3_extended

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.65 assign(Tmatrix3_double):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.66 **assign(Tmatrix3_double):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with double precision is expected.

64.4.67 **assign(Tmatrix3_double):Tmatrix4_extended**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.68 **assign(Tmatrix3_double):Tmatrix4_single**

Synopsis: Allow assignment of three-dimensional double precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.69 **assign(Tmatrix3_extended):Tmatrix2_double**

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some accuracy is lost because of the conversion.

64.4.70 assign(Tmatrix3_extended):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.71 assign(Tmatrix3_extended):Tmatrix2_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.72 assign(Tmatrix3_extended):Tmatrix3_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.73 assign(Tmatrix3_extended):Tmatrix3_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.74 assign(Tmatrix3_extended):Tmatrix4_double

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected. Some precision is lost because of the conversion.

64.4.75 assign(Tmatrix3_extended):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.76 assign(Tmatrix3_extended):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.77 assign(Tmatrix3_single):Tmatrix2_double

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.78 assign(Tmatrix3_single):Tmatrix2_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.79 **assign(Tmatrix3_single):Tmatrix2_single**

Synopsis: Allow assignment of three-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.80 **assign(Tmatrix3_single):Tmatrix3_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected.

64.4.81 **assign(Tmatrix3_single):Tmatrix3_extended**

Synopsis: Allow assignment of three-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected.

64.4.82 **assign(Tmatrix3_single):Tmatrix4_double**

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.83 assign(Tmatrix3_single):Tmatrix4_extended

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.84 assign(Tmatrix3_single):Tmatrix4_single

Synopsis: Allow assignment of three-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix3_single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional matrix with single precision values wherever a four-dimensional matrix with single precision is expected.

64.4.85 assign(Tmatrix4_double):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.86 assign(Tmatrix4_double):Tmatrix2_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.87 assign(Tmatrix4_double):Tmatrix2_single

Synopsis: Allow assignment of four-dimensional double precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.88 assign(Tmatrix4_double):Tmatrix3_double

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.89 assign(Tmatrix4_double):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.90 assign(Tmatrix4_double):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional double precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.91 assign(Tmatrix4_double):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional double precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.92 assign(Tmatrix4_double):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_double) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with double precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.93 **assign(Tmatrix4_extended):Tmatrix2_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.94 **assign(Tmatrix4_extended):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.95 **assign(Tmatrix4_extended):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional extended precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost in the conversion.

64.4.96 **assign(Tmatrix4_extended):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.97 assign(Tmatrix4_extended):Tmatrix3_extended

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.98 assign(Tmatrix4_extended):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away and some precision is lost because of the conversion.

64.4.99 assign(Tmatrix4_extended):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with double precision is expected.

64.4.100 assign(Tmatrix4_extended):Tmatrix4_single

Synopsis: Allow assignment of four-dimensional extended precision matrix to four-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_extended) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with extended precision values wherever a four-dimensional matrix with single precision is expected. Some precision is lost because of the conversion.

64.4.101 assign(Tmatrix4_single):Tmatrix2_double

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.102 **assign(Tmatrix4_single):Tmatrix2_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.103 **assign(Tmatrix4_single):Tmatrix2_single**

Synopsis: Allow assignment of four-dimensional single precision matrix to two-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a two-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.104 **assign(Tmatrix4_single):Tmatrix3_double**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with double precision is expected. The surplus fields are thrown away.

64.4.105 **assign(Tmatrix4_single):Tmatrix3_extended**

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with extended precision is expected. The surplus fields are thrown away.

64.4.106 assign(Tmatrix4_single):Tmatrix3_single

Synopsis: Allow assignment of four-dimensional single precision matrix to three-dimensional single precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a three-dimensional matrix with single precision is expected. The surplus fields are thrown away.

64.4.107 assign(Tmatrix4_single):Tmatrix4_double

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional double precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with double precision is expected.

64.4.108 assign(Tmatrix4_single):Tmatrix4_extended

Synopsis: Allow assignment of four-dimensional single precision matrix to four-dimensional extended precision matrix

Declaration: `operator :=(const v: Tmatrix4_single) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional matrix with single precision values wherever a four-dimensional matrix with extended precision is expected.

64.4.109 assign(Tvector2_double):Tvector2_extended

Synopsis: Allow assignment of double precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever an extended precision vector is expected.

64.4.110 assign(Tvector2_double):Tvector2_single

Synopsis: Allow assignment of double precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with double precision values wherever a single precision vector is expected, at the cost of loosing some precision.

64.4.111 assign(Tvector2_double):Tvector3_double

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.112 assign(Tvector2_double):Tvector3_extended

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.113 assign(Tvector2_double):Tvector3_single

Synopsis: Allow assignment of two-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.114 assign(Tvector2_double):Tvector4_double

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.115 assign(Tvector2_double):Tvector4_extended

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.116 `assign(Tvector2_double):Tvector4_single`

Synopsis: Allow assignment of two-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.117 `assign(Tvector2_extended):Tvector2_double`

Synopsis: Allow assignment of extended precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a double precision vector is expected, at the cost of losing some precision.

64.4.118 `assign(Tvector2_extended):Tvector2_single`

Synopsis: Allow assignment of extended precision vector to single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a vector with extended precision values wherever a single precision vector is expected, at the cost of losing some precision.

64.4.119 `assign(Tvector2_extended):Tvector3_double`

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.120 assign(Tvector2_extended):Tvector3_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.121 assign(Tvector2_extended):Tvector3_single

Synopsis: Allow assignment of two-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third dimension is set to 0.0.

64.4.122 assign(Tvector2_extended):Tvector4_double

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.123 assign(Tvector2_extended):Tvector4_extended

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.124 assign(Tvector2_extended):Tvector4_single

Synopsis: Allow assignment of two-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion and the third and fourth dimensions are set to 0.0.

64.4.125 assign(Tvector2_single):Tvector2_double

Synopsis: Allow assignment of single precision vector to double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever a double precision vector is expected.

64.4.126 assign(Tvector2_single):Tvector2_extended

Synopsis: Allow assignment of single precision vector to extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a vector with single precision values wherever an extended precision vector is expected.

64.4.127 assign(Tvector2_single):Tvector3_double

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The third dimension is set to 0.0.

64.4.128 assign(Tvector2_single):Tvector3_extended

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The third dimension is set to 0.0.

64.4.129 assign(Tvector2_single):Tvector3_single

Synopsis: Allow assignment of two-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The third dimension is set to 0.0.

64.4.130 assign(Tvector2_single):Tvector4_double

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The third and fourth dimensions are set to 0.0.

64.4.131 assign(Tvector2_single):Tvector4_extended

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The third and fourth dimensions are set to 0.0.

64.4.132 assign(Tvector2_single):Tvector4_single

Synopsis: Allow assignment of two-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector2_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a two-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The third and fourth dimensions are set to 0.0.

64.4.133 assign(Tvector3_double):Tvector2_double

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.134 assign(Tvector3_double):Tvector2_extended

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.135 assign(Tvector3_double):Tvector2_single

Synopsis: Allow assignment of three-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.136 assign(Tvector3_double):Tvector3_extended

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected.

64.4.137 assign(Tvector3_double):Tvector3_single

Synopsis: Allow assignment of three-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. Some precision is lost because of the conversion.

64.4.138 **assign(Tvector3_double):Tvector4_double**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.139 **assign(Tvector3_double):Tvector4_extended**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.140 **assign(Tvector3_double):Tvector4_single**

Synopsis: Allow assignment of three-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some precision is lost because of the conversion.

64.4.141 **assign(Tvector3_extended):Tvector2_double**

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.142 assign(Tvector3_extended):Tvector2_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.143 assign(Tvector3_extended):Tvector2_single

Synopsis: Allow assignment of three-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away and some precision is lost because of the conversion.

64.4.144 assign(Tvector3_extended):Tvector3_double

Synopsis: Allow assignment of three-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.145 assign(Tvector3_extended):Tvector3_single

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. Some precision is lost because of the conversion.

64.4.146 assign(Tvector3_extended):Tvector4_double

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.147 assign(Tvector3_extended):Tvector4_extended

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.148 assign(Tvector3_extended):Tvector4_single

Synopsis: Allow assignment of three-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0 and some accuracy is lost because of the conversion.

64.4.149 assign(Tvector3_single):Tvector2_double

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third dimension is thrown away.

64.4.150 assign(Tvector3_single):Tvector2_extended

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third dimension is thrown away.

64.4.151 **assign(Tvector3_single):Tvector2_single**

Synopsis: Allow assignment of three-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third dimension is thrown away.

64.4.152 **assign(Tvector3_single):Tvector3_double**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected.

64.4.153 **assign(Tvector3_single):Tvector3_extended**

Synopsis: Allow assignment of three-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected.

64.4.154 **assign(Tvector3_single):Tvector4_double**

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected. The fourth dimension is set to 0.

64.4.155 assign(Tvector3_single):Tvector4_extended

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected. The fourth dimension is set to 0.

64.4.156 assign(Tvector3_single):Tvector4_single

Synopsis: Allow assignment of three-dimensional single precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector3_single) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a three-dimensional vector with single precision values wherever a four-dimensional vector with single precision is expected. The fourth dimension is set to 0.

64.4.157 assign(Tvector4_double):Tvector2_double

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.158 assign(Tvector4_double):Tvector2_extended

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.159 assign(Tvector4_double):Tvector2_single

Synopsis: Allow assignment of four-dimensional double precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.160 **assign(Tvector4_double):Tvector3_double**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.161 **assign(Tvector4_double):Tvector3_extended**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.162 **assign(Tvector4_double):Tvector3_single**

Synopsis: Allow assignment of four-dimensional double precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.163 **assign(Tvector4_double):Tvector4_extended**

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with extended precision is expected.

64.4.164 assign(Tvector4_double):Tvector4_single

Synopsis: Allow assignment of four-dimensional double precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_double) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with double precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.165 assign(Tvector4_extended):Tvector2_double

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.166 assign(Tvector4_extended):Tvector2_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.167 assign(Tvector4_extended):Tvector2_single

Synopsis: Allow assignment of four-dimensional extended precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away and some accuracy is lost because of the conversion.

64.4.168 assign(Tvector4_extended):Tvector3_double

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.169 assign(Tvector4_extended):Tvector3_extended

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimensions are thrown away.

64.4.170 assign(Tvector4_extended):Tvector3_single

Synopsis: Allow assignment of four-dimensional extended precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away and some accuracy is lost because of the conversion.

64.4.171 assign(Tvector4_extended):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with double precision is expected. Some accuracy is lost because of the conversion.

64.4.172 assign(Tvector4_extended):Tvector4_single

Synopsis: Allow assignment of four-dimensional extended precision vector to four-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_extended) : Tvector4_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with extended precision values wherever a four-dimensional vector with single precision is expected. Some accuracy is lost because of the conversion.

64.4.173 assign(Tvector4_single):Tvector2_double

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with double precision is expected. The third and fourth dimensions are thrown away.

64.4.174 assign(Tvector4_single):Tvector2_extended

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with extended precision is expected. The third and fourth dimensions are thrown away.

64.4.175 assign(Tvector4_single):Tvector2_single

Synopsis: Allow assignment of four-dimensional single precision vector to two-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector2_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a two-dimensional vector with single precision is expected. The third and fourth dimensions are thrown away.

64.4.176 assign(Tvector4_single):Tvector3_double

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with double precision is expected. The fourth dimension is thrown away.

64.4.177 assign(Tvector4_single):Tvector3_extended

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with extended precision is expected. The fourth dimension is thrown away.

64.4.178 assign(Tvector4_single):Tvector3_single

Synopsis: Allow assignment of four-dimensional single precision vector to three-dimensional single precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector3_single`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a three-dimensional vector with single precision is expected. The fourth dimension is thrown away.

64.4.179 assign(Tvector4_single):Tvector4_double

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional double precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_double`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with double precision is expected.

64.4.180 assign(Tvector4_single):Tvector4_extended

Synopsis: Allow assignment of four-dimensional single precision vector to four-dimensional extended precision vector

Declaration: `operator :=(const v: Tvector4_single) : Tvector4_extended`

Visibility: default

Description: This operator allows you to use a four-dimensional vector with single precision values wherever a four-dimensional vector with extended precision is expected.

64.4.181 divide(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.182 divide(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_extended; const x: extended) : Tmatrix2_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.183 divide(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.184 divide(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.185 divide(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_extended; const x: extended) : Tmatrix3_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.186 divide(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.187 divide(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.188 divide(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_extended; const x: extended) : Tmatrix4_extended`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.189 divide(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Divide a two-dimensional single precision matrix by a scalar

Declaration: `operator /(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to divide a matrix by a scalar. All elements in the matrix are divided by the scalar, the result is returned as a new matrix.

64.4.190 divide(Tvector2_double,Double):Tvector2_double

Synopsis: Divide a two-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.191 divide(Tvector2_extended,extended):Tvector2_extended

Synopsis: Divide a two-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.192 divide(Tvector2_single,single):Tvector2_single

Synopsis: Divide a two-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.193 divide(Tvector3_double,Double):Tvector3_double

Synopsis: Divide a three-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.194 divide(Tvector3_extended,extended):Tvector3_extended

Synopsis: Divide a three-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.195 divide(Tvector3_single,single):Tvector3_single

Synopsis: Divide a three-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.196 divide(Tvector4_double,Double):Tvector4_double

Synopsis: Divide a four-dimensional double precision vector by a scalar

Declaration: `operator /(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.197 divide(Tvector4_extended,extended):Tvector4_extended

Synopsis: Divide a four-dimensional extended precision vector by a scalar

Declaration: `operator /(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.198 divide(Tvector4_single,single):Tvector4_single

Synopsis: Divide a four-dimensional single precision vector by a scalar

Declaration: `operator /(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to divide a vector by a scalar value. Each vector element is divided by the scalar value; the result is returned as a new vector.

64.4.199 multiply(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Multiply a two-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.200 multiply(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Give product of two two-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.201 multiply(Tmatrix2_double,Tvector2_double):Tvector2_double

Synopsis: Give product of a two-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_double; const v: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a two-dimensional double precision matrices with a two dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.202 multiply(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Multiply a two-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.203 multiply(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Give product of two two-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.204 multiply(Tmatrix2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Give product of a two-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_extended; const v: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a two-dimensional extended precision matrices with a two dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.205 multiply(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Multiply a two-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.206 multiply(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Give product of two two-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.207 multiply(Tmatrix2_single,Tvector2_single):Tvector2_single

Synopsis: Give product of a two-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix2_single; const v: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a two-dimensional single precision matrices with a two dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.208 multiply(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Multiply a three-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.209 multiply(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Give product of two three-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.210 multiply(Tmatrix3_double,Tvector3_double):Tvector3_double

Synopsis: Give product of a three-dimensional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_double; const v: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a three-dimensional double precision matrices with a three dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.211 multiply(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Multiply a three-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.212 multiply(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Give product of two three-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.213 multiply(Tmatrix3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Give product of a three-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_extended; const v: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a three-dimensional extended precision matrices with a three dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.214 multiply(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Multiply a three-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.215 multiply(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Give product of two three-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.216 multiply(Tmatrix3_single,Tvector3_single):Tvector3_single

Synopsis: Give product of a three-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix3_single; const v: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a three-dimensional single precision matrices with a three dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.217 multiply(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Multiply a four-dimensional double precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.218 multiply(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Give product of two four-dimensional double precision matrices

Declaration: `operator *(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.219 multiply(Tmatrix4_double,Tvector4_double):Tvector4_double

Synopsis: Give product of a four-dimendional double precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_double; const v: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a four-dimensional double precision matrices with a four dimensional double precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.220 multiply(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Multiply a four-dimensional extended precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.221 multiply(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Give product of two four-dimensional extended precision matrices

Declaration: `operator *(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.222 multiply(Tmatrix4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Give product of a four-dimensional extended precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_extended; const v: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a four-dimensional extended precision matrices with a four dimensional extended precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.223 multiply(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Multiply a four-dimensional single precision matrix by a scalar

Declaration: `operator *(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply a matrix with a scalar. All elements in the matrix are multiplied by the scalar, the result is returned as a new matrix.

64.4.224 multiply(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Give product of two four-dimensional single precision matrices

Declaration: `operator *(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to multiply two two-dimensional single precision matrices. A new matrix is returned which is the product of both matrices. The product is calculated using the well known matrix multiplication algorithm.

64.4.225 multiply(Tmatrix4_single,Tvector4_single):Tvector4_single

Synopsis: Give product of a four-dimendional single precision matrix and vector

Declaration: `operator *(const m: Tmatrix4_single; const v: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a four-dimensional single precision matrices with a four dimensional single precision vector. A new vector is returned which is the product of the matrix and the vector. The product is calculated using the well known matrix-vector multiplication algorithm.

64.4.226 multiply(Tvector2_double,Double):Tvector2_double

Synopsis: Multiply a two-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.227 multiply(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.228 multiply(Tvector2_extended,extended):Tvector2_extended

Synopsis: Multiply a two-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.229 multiply(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_extended; const y: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.230 multiply(Tvector2_single,single):Tvector2_single

Synopsis: Multiply a two-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.231 multiply(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector2_single; const y: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.232 multiply(Tvector3_double,Double):Tvector3_double

Synopsis: Multiply a three-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.233 multiply(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.234 multiply(Tvector3_extended,extended):Tvector3_extended

Synopsis: Multiply a three-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.235 multiply(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.236 multiply(Tvector3_single,single):Tvector3_single

Synopsis: Multiply a three-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.237 multiply(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.238 multiply(Tvector4_double,Double):Tvector4_double

Synopsis: Multiply a four-dimensional double precision vector by a scalar

Declaration: `operator *(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.239 multiply(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.240 multiply(Tvector4_extended,extended):Tvector4_extended

Synopsis: Multiply a four-dimensional extended precision vector by a scalar

Declaration: `operator *(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.241 multiply(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.242 multiply(Tvector4_single,single):Tvector4_single

Synopsis: Multiply a four-dimensional single precision vector by a scalar

Declaration: `operator *(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to multiply a vector by a scalar value. Each vector element is multiplied by the scalar value; the result is returned as a new vector.

64.4.243 multiply(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Multiply two vectors element wise

Declaration: `operator *(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator returns a vector that contains the element by element multiplication of the two multiplied vectors.

64.4.244 negative(Tmatrix2_double):Tmatrix2_double

Synopsis: Negate two-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix2_double) : Tmatrix2_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.245 negative(Tmatrix2_extended):Tmatrix2_extended

Synopsis: Negate two-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix2_extended) : Tmatrix2_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.246 negative(Tmatrix2_single):Tmatrix2_single

Synopsis: Negate two-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.247 negative(Tmatrix3_double):Tmatrix3_double

Synopsis: Negate three-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix3_double) : Tmatrix3_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.248 negative(Tmatrix3_extended):Tmatrix3_extended

Synopsis: Negate three-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix3_extended) : Tmatrix3_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.249 negative(Tmatrix3_single):Tmatrix3_single

Synopsis: Negate three-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix3_single) : Tmatrix3_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.250 negative(Tmatrix4_double):Tmatrix4_double

Synopsis: Negate four-dimensional double precision matrix.

Declaration: `operator -(const m1: Tmatrix4_double) : Tmatrix4_double`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.251 negative(Tmatrix4_extended):Tmatrix4_extended

Synopsis: Negate four-dimensional extended precision matrix.

Declaration: `operator -(const m1: Tmatrix4_extended) : Tmatrix4_extended`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.252 negative(Tmatrix4_single):Tmatrix4_single

Synopsis: Negate four-dimensional single precision matrix.

Declaration: `operator -(const m1: Tmatrix4_single) : Tmatrix4_single`

Visibility: default

Description: This operation returns a matrix with all elements negated.

64.4.253 negative(Tvector2_double):Tvector2_double

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_double) : Tvector2_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.254 negative(Tvector2_extended):Tvector2_extended

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_extended) : Tvector2_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.255 negative(Tvector2_single):Tvector2_single

Synopsis: Negate two-dimensional vector.

Declaration: `operator -(const x: Tvector2_single) : Tvector2_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.256 negative(Tvector3_double):Tvector3_double

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_double) : Tvector3_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.257 negative(Tvector3_extended):Tvector3_extended

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_extended) : Tvector3_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.258 negative(Tvector3_single):Tvector3_single

Synopsis: Negate three-dimensional vector.

Declaration: `operator -(const x: Tvector3_single) : Tvector3_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.259 negative(Tvector4_double):Tvector4_double

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_double) : Tvector4_double`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.260 negative(Tvector4_extended):Tvector4_extended

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_extended) : Tvector4_extended`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.261 negative(Tvector4_single):Tvector4_single

Synopsis: Negate four-dimensional vector.

Declaration: `operator -(const x: Tvector4_single) : Tvector4_single`

Visibility: default

Description: This operation returns a vector in the opposite direction of the vector that is passed. In order to do so, all values in the vector are negated.

64.4.262 power(Tvector2_double,Tvector2_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_double; const y: Tvector2_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.263 power(Tvector2_extended,Tvector2_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_extended; const y: Tvector2_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.264 power(Tvector2_single,Tvector2_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector2_single; const y: Tvector2_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.265 power(Tvector3_double,Tvector3_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_double; const y: Tvector3_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.266 power(Tvector3_extended,Tvector3_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_extended; const y: Tvector3_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.267 power(Tvector3_single,Tvector3_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector3_single; const y: Tvector3_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.268 power(Tvector4_double,Tvector4_double):Double

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_double; const y: Tvector4_double) : Double`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.269 power(Tvector4_extended,Tvector4_extended):extended

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_extended; const y: Tvector4_extended)
: extended`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.270 power(Tvector4_single,Tvector4_single):single

Synopsis: Calculate the internal product of two vectors.

Declaration: `operator ** (const x: Tvector4_single; const y: Tvector4_single) : single`

Visibility: default

Description: This operator returns the internal product of the two vectors, that is, the elements of the two vectors are element-wise multiplied, and then added together.

64.4.271 subtract(Tmatrix2_double,Double):Tmatrix2_double

Synopsis: Subtract scalar to two-dimensional double precision matrix

Declaration: `operator - (const m: Tmatrix2_double; const x: Double) : Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.272 subtract(Tmatrix2_double,Tmatrix2_double):Tmatrix2_double

Synopsis: Subtract a two-dimensional double precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_double; const m2: Tmatrix2_double)
: Tmatrix2_double`

Visibility: default

Description: This operator allows you to subtract a two-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.273 subtract(Tmatrix2_extended,extended):Tmatrix2_extended

Synopsis: Add scalar to two-dimensional extended precision matrix

Declaration: `operator - (const m: Tmatrix2_extended; const x: extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.274 subtract(Tmatrix2_extended,Tmatrix2_extended):Tmatrix2_extended

Synopsis: Subtract a two-dimensional extended precision matrix from another.

Declaration: `operator - (const m1: Tmatrix2_extended; const m2: Tmatrix2_extended)
: Tmatrix2_extended`

Visibility: default

Description: This operator allows you to subtract a two-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.275 subtract(Tmatrix2_single,single):Tmatrix2_single

Synopsis: Subtract scalar to two-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix2_single; const x: single) : Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.276 subtract(Tmatrix2_single,Tmatrix2_single):Tmatrix2_single

Synopsis: Subtract a two-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix2_single; const m2: Tmatrix2_single)
: Tmatrix2_single`

Visibility: default

Description: This operator allows you to subtract a two-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.277 subtract(Tmatrix3_double,Double):Tmatrix3_double

Synopsis: Add scalar to three-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix3_double; const x: Double) : Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.278 subtract(Tmatrix3_double,Tmatrix3_double):Tmatrix3_double

Synopsis: Subtract a three-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_double; const m2: Tmatrix3_double)
: Tmatrix3_double`

Visibility: default

Description: This operator allows you to subtract a three-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.279 subtract(Tmatrix3_extended,extended):Tmatrix3_extended

Synopsis: Add scalar to three-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix3_extended; const x: extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.280 subtract(Tmatrix3_extended,Tmatrix3_extended):Tmatrix3_extended

Synopsis: Subtract a three-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_extended; const m2: Tmatrix3_extended)
: Tmatrix3_extended`

Visibility: default

Description: This operator allows you to subtract a three-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.281 subtract(Tmatrix3_single,single):Tmatrix3_single

Synopsis: Add scalar to three-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix3_single; const x: single) : Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.282 subtract(Tmatrix3_single,Tmatrix3_single):Tmatrix3_single

Synopsis: Subtract a three-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix3_single; const m2: Tmatrix3_single)
: Tmatrix3_single`

Visibility: default

Description: This operator allows you to subtract a three-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.283 subtract(Tmatrix4_double,Double):Tmatrix4_double

Synopsis: Add scalar to four-dimensional double precision matrix

Declaration: `operator -(const m: Tmatrix4_double; const x: Double) : Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.284 subtract(Tmatrix4_double,Tmatrix4_double):Tmatrix4_double

Synopsis: Subtract a four-dimensional double precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_double; const m2: Tmatrix4_double)
: Tmatrix4_double`

Visibility: default

Description: This operator allows you to subtract a four-dimensional double precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.285 subtract(Tmatrix4_extended,extended):Tmatrix4_extended

Synopsis: Add scalar to four-dimensional extended precision matrix

Declaration: `operator -(const m: Tmatrix4_extended; const x: extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.286 subtract(Tmatrix4_extended,Tmatrix4_extended):Tmatrix4_extended

Synopsis: Subtract a four-dimensional extended precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_extended; const m2: Tmatrix4_extended)
: Tmatrix4_extended`

Visibility: default

Description: This operator allows you to subtract a four-dimensional extended precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.287 subtract(Tmatrix4_single,single):Tmatrix4_single

Synopsis: Add scalar to four-dimensional single precision matrix

Declaration: `operator -(const m: Tmatrix4_single; const x: single) : Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a matrix. The scalar is subtracted from all elements of the matrix, the result is returned as a new matrix.

64.4.288 subtract(Tmatrix4_single,Tmatrix4_single):Tmatrix4_single

Synopsis: Subtract a four-dimensional single precision matrix from another.

Declaration: `operator -(const m1: Tmatrix4_single; const m2: Tmatrix4_single)
: Tmatrix4_single`

Visibility: default

Description: This operator allows you to subtract a four-dimensional single precision matrix from another. A new matrix is returned with all elements of the two matrices subtracted from each other.

64.4.289 subtract(Tvector2_double,Double):Tvector2_double

Synopsis: Subtract scalar from two-dimensional double precision vector

Declaration: `operator -(const x: Tvector2_double; y: Double) : Tvector2_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.290 subtract(Tvector2_double,Tvector2_double):Tvector2_double

Synopsis: Subtract two-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector2_double; const y: Tvector2_double)
: Tvector2_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.291 subtract(Tvector2_extended,extended):Tvector2_extended

Synopsis: Subtract scalar from two-dimensional extended precision vector

Declaration: `operator -(const x: Tvector2_extended; y: extended) : Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.292 subtract(Tvector2_extended,Tvector2_extended):Tvector2_extended

Synopsis: Subtract two-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector2_extended; const y: Tvector2_extended)
: Tvector2_extended`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.293 subtract(Tvector2_single,single):Tvector2_single

Synopsis: Subtract scalar from two-dimensional single precision vector

Declaration: `operator -(const x: Tvector2_single; y: single) : Tvector2_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.294 subtract(Tvector2_single,Tvector2_single):Tvector2_single

Synopsis: Subtract two-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector2_single; const y: Tvector2_single)
: Tvector2_single`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.295 subtract(Tvector3_double,Double):Tvector3_double

Synopsis: Subtract scalar from three-dimensional double precision vector

Declaration: `operator -(const x: Tvector3_double; y: Double) : Tvector3_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.296 subtract(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Subtract three-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator allows you to subtract two two-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.297 subtract(Tvector3_extended,extended):Tvector3_extended

Synopsis: Subtract scalar from three-dimensional extended precision vector

Declaration: `operator -(const x: Tvector3_extended; y: extended) : Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.298 subtract(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Subtract three-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.299 subtract(Tvector3_single,single):Tvector3_single

Synopsis: Subtract scalar from three-dimensional single precision vector

Declaration: `operator -(const x: Tvector3_single; y: single) : Tvector3_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.300 subtract(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Subtract three-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator allows you to subtract two three-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.301 subtract(Tvector4_double,Double):Tvector4_double

Synopsis: Subtract scalar from four-dimensional double precision vector

Declaration: `operator -(const x: Tvector4_double; y: Double) : Tvector4_double`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.302 subtract(Tvector4_double,Tvector4_double):Tvector4_double

Synopsis: Subtract four-dimensional double precision vectors from each other

Declaration: `operator -(const x: Tvector4_double; const y: Tvector4_double)
: Tvector4_double`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with double precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.303 subtract(Tvector4_extended,extended):Tvector4_extended

Synopsis: Subtract scalar from four-dimensional extended precision vector

Declaration: `operator -(const x: Tvector4_extended; y: extended) : Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.304 subtract(Tvector4_extended,Tvector4_extended):Tvector4_extended

Synopsis: Subtract four-dimensional extended precision vectors from each other

Declaration: `operator -(const x: Tvector4_extended; const y: Tvector4_extended)
: Tvector4_extended`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with extended precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.305 subtract(Tvector4_single,single):Tvector4_single

Synopsis: Subtract scalar from four-dimensional single precision vector

Declaration: `operator -(const x: Tvector4_single; y: single) : Tvector4_single`

Visibility: default

Description: This operator allows you to subtract a scalar value from a vector. The scalar is subtracted from all elements of the vector, the result is returned as a new vector.

64.4.306 subtract(Tvector4_single,Tvector4_single):Tvector4_single

Synopsis: Subtract four-dimensional single precision vectors from each other

Declaration: `operator -(const x: Tvector4_single; const y: Tvector4_single)
: Tvector4_single`

Visibility: default

Description: This operator allows you to subtract two four-dimensional vectors with single precision from each other. The result is a new vector which consists of the difference of the individual elements of the two vectors.

64.4.307 symmetricaldifference(Tvector3_double,Tvector3_double):Tvector3_double

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_double; const y: Tvector3_double)
: Tvector3_double`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.308 symmetricaldifference(Tvector3_extended,Tvector3_extended):Tvector3_extended

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_extended; const y: Tvector3_extended)
: Tvector3_extended`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.4.309 symmetricaldifference(Tvector3_single,Tvector3_single):Tvector3_single

Synopsis: Calculate the external product of two three-dimensional vectors

Declaration: `operator ><(const x: Tvector3_single; const y: Tvector3_single)
: Tvector3_single`

Visibility: default

Description: This operator returns the external product of two three dimensional vector. It is a vector orthonormal to the two multiplied vectors. The length of that vector is equal to the surface area of a parallelogram with the two vectors as sides.

The external product is often used to get a vector orthonormal to two other vectors, but of a predefined length. In order to do so, the result vector from the external product, is divided by its length, and then multiplied by the desired size.

64.5 Tmatrix2_double**64.5.1 Description**

The `Tmatrix2_double` object provides a matrix of 2*2 double precision scalars.

64.5.2 Method overview

Page	Method	Description
975	determinant	Calculates the determinant of the matrix.
975	get_column	Returns the c-th column of the matrix as vector.
975	get_row	Returns the r-th row of the matrix as vector.
975	init	Initializes the matrix, setting its elements to the values passed to the constructor.
974	init_identity	Initializes the matrix and sets its elements to the identity matrix.
974	init_zero	Initializes the matrix and sets its elements to zero
976	inverse	Calculates the inverse of the matrix.
975	set_column	Sets c-th column of the matrix with a vector.
975	set_row	Sets r-th row of the matrix with a vector.
976	transpose	Returns the transposition of the matrix.

64.5.3 Tmatrix2_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.5.4 Tmatrix2_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.5.5 Tmatrix2_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ba: Double; bb: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.5.6 Tmatrix2_double.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.5.7 Tmatrix2_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.5.8 Tmatrix2_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.5.9 Tmatrix2_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.5.10 Tmatrix2_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.5.11 Tmatrix2_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.5.12 Tmatrix2_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.6 Tmatrix2_extended

64.6.1 Description

The `Tmatrix2_extended` object provides a matrix of 2*2 extended precision scalars.

64.6.2 Method overview

Page	Method	Description
978	<code>determinant</code>	Calculates the determinant of the matrix.
977	<code>get_column</code>	Returns the c-th column of the matrix as vector.
977	<code>get_row</code>	Returns the r-th row of the matrix as vector.
977	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
977	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
976	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
978	<code>inverse</code>	Calculates the inverse of the matrix.
977	<code>set_column</code>	Sets c-th column of the matrix with a vector.
977	<code>set_row</code>	Sets r-th row of the matrix with a vector.
978	<code>transpose</code>	Returns the transposition of the matrix.

64.6.3 Tmatrix2_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.6.4 Tmatrix2_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.6.5 Tmatrix2_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ba: extended; bb: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.6.6 Tmatrix2_extended.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.6.7 Tmatrix2_extended.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_extended`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.6.8 Tmatrix2_extended.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.6.9 Tmatrix2_extended.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_extended)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.6.10 Tmatrix2_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.6.11 Tmatrix2_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.6.12 Tmatrix2_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.7 Tmatrix2_single

64.7.1 Description

The `Tmatrix2_single` object provides a matrix of 2*2 single precision scalars.

64.7.2 Method overview

Page	Method	Description
980	<code>determinant</code>	Calculates the determinant of the matrix.
979	<code>get_column</code>	Returns the c-th column of the matrix as vector.
979	<code>get_row</code>	Returns the r-th row of the matrix as vector.
979	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
979	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
979	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
980	<code>inverse</code>	Calculates the inverse of the matrix.
979	<code>set_column</code>	Sets c-th column of the matrix with a vector.
980	<code>set_row</code>	Sets r-th row of the matrix with a vector.
980	<code>transpose</code>	Returns the transposition of the matrix.

64.7.3 Tmatrix2_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.7.4 Tmatrix2_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.7.5 Tmatrix2_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ba: single; bb: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.7.6 Tmatrix2_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector2_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.7.7 Tmatrix2_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector2_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.7.8 Tmatrix2_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.7.9 Tmatrix2_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector2_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.7.10 Tmatrix2_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.7.11 Tmatrix2_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A: Tmatrix2_single) : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.7.12 Tmatrix2_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix2_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.8 Tmatrix3_double

64.8.1 Description

The `Tmatrix3_double` object provides a matrix of 3*3 double precision scalars.

64.8.2 Method overview

Page	Method	Description
982	determinant	Calculates the determinant of the matrix.
981	get_column	Returns the c-th column of the matrix as vector.
982	get_row	Returns the r-th row of the matrix as vector.
981	init	Initializes the matrix, setting its elements to the values passed to the constructor.
981	init_identity	Initializes the matrix and sets its elements to the identity matrix.
981	init_zero	Initializes the matrix and sets its elements to zero
982	inverse	Calculates the inverse of the matrix.
982	set_column	Sets c-th column of the matrix with a vector.
982	set_row	Sets r-th row of the matrix with a vector.
982	transpose	Returns the transposition of the matrix.

64.8.3 Tmatrix3_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.8.4 Tmatrix3_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.8.5 Tmatrix3_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ba: Double; bb: Double; bc: Double; ca: Double; cb: Double; cc: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.8.6 Tmatrix3_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.8.7 Tmatrix3_double.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_double`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.8.8 Tmatrix3_double.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.8.9 Tmatrix3_double.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_double)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.8.10 Tmatrix3_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix.

64.8.11 Tmatrix3_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(A_determinant: Double) : Tmatrix3_double`

Visibility: default

Description: `Tmatrix3_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.8.12 Tmatrix3_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the *x* and *y* coordinates of the values swapped.

64.9 Tmatrix3_extended

64.9.1 Description

The `Tmatrix3_extended` object provides a matrix of 3*3 extended precision scalars.

64.9.2 Method overview

Page	Method	Description
984	<code>determinant</code>	Calculates the determinant of the matrix.
984	<code>get_column</code>	Returns the c-th column of the matrix as vector.
984	<code>get_row</code>	Returns the r-th row of the matrix as vector.
983	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
983	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
983	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
984	<code>inverse</code>	Calculates the inverse of the matrix.
984	<code>set_column</code>	Sets r-th column of the matrix with a vector.
984	<code>set_row</code>	Sets r-th row of the matrix with a vector.
985	<code>transpose</code>	Returns the transposition of the matrix.

64.9.3 Tmatrix3_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.9.4 Tmatrix3_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.9.5 Tmatrix3_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ba: extended; bb: extended; bc: extended; ca: extended;
cb: extended; cc: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.9.6 Tmatrix3_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.9.7 Tmatrix3_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.9.8 Tmatrix3_extended.set_column

Synopsis: Sets *r*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.9.9 Tmatrix3_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.9.10 Tmatrix3_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix.

64.9.11 Tmatrix3_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: extended) : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix3_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.9.12 Tmatrix3_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.10 Tmatrix3_single

64.10.1 Description

The `Tmatrix3_single` object provides a matrix of 3*3 single precision scalars.

64.10.2 Method overview

Page	Method	Description
987	<code>determinant</code>	Calculates the determinant of the matrix.
986	<code>get_column</code>	Returns the c-th column of the matrix as vector.
986	<code>get_row</code>	Returns the r-th row of the matrix as vector.
986	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
985	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
985	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
987	<code>inverse</code>	Calculates the inverse of the matrix.
986	<code>set_column</code>	Sets c-th column of the matrix with a vector.
986	<code>set_row</code>	Sets r-th row of the matrix with a vector.
987	<code>transpose</code>	Returns the transposition of the matrix.

64.10.3 Tmatrix3_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.10.4 Tmatrix3_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.10.5 Tmatrix3_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ba: single;
bb: single; bc: single; ca: single; cb: single;
cc: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.10.6 Tmatrix3_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector3_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.10.7 Tmatrix3_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector3_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.10.8 Tmatrix3_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.10.9 Tmatrix3_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector3_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.10.10 Tmatrix3_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix.

64.10.11 Tmatrix3_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: single) : Tmatrix3_single`

Visibility: default

Description: `Tmatrix3_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter.

64.10.12 Tmatrix3_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix3_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.11 Tmatrix4_double**64.11.1 Description**

The `Tmatrix4_double` object provides a matrix of 4*4 double precision scalars.

64.11.2 Method overview

Page	Method	Description
989	<code>determinant</code>	Calculates the determinant of the matrix.
988	<code>get_column</code>	Returns the c-th column of the matrix as vector.
988	<code>get_row</code>	Returns the r-th row of the matrix as vector.
988	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
988	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
988	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
989	<code>inverse</code>	Calculates the inverse of the matrix.
989	<code>set_column</code>	Sets c-th column of the matrix with a vector.
989	<code>set_row</code>	Sets r-th row of the matrix with a vector.
989	<code>transpose</code>	Returns the transposition of the matrix.

64.11.3 Tmatrix4_double.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.11.4 Tmatrix4_double.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.11.5 Tmatrix4_double.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: Double; ab: Double; ac: Double; ad: Double;
ba: Double; bb: Double; bc: Double; bd: Double;
ca: Double; cb: Double; cc: Double; cd: Double;
da: Double; db: Double; dc: Double; dd: Double)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.11.6 Tmatrix4_double.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_double`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.11.7 Tmatrix4_double.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_double`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.11.8 Tmatrix4_double.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.11.9 Tmatrix4_double.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_double)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.11.10 Tmatrix4_double.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : Double`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.11.11 Tmatrix4_double.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: Double) : Tmatrix4_double`

Visibility: default

Description: `Tmatrix4_double.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.11.12 Tmatrix4_double.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_double`

Visibility: default

Description: `Tmatrix2_double.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.12 Tmatrix4_extended

64.12.1 Description

The Tmatrix4_extended object provides a matrix of 4*4 extended precision scalars.

64.12.2 Method overview

Page	Method	Description
991	determinant	Calculates the determinant of the matrix.
991	get_column	Returns the c-th column of the matrix as vector.
991	get_row	Returns the r-th row of the matrix as vector.
990	init	Initializes the matrix, setting its elements to the values passed to the constructor.
990	init_identity	Initializes the matrix and sets its elements to the identity matrix.
990	init_zero	Initializes the matrix and sets its elements to zero
992	inverse	Calculates the inverse of the matrix.
991	set_column	Sets c-th column of the matrix with a vector.
991	set_row	Sets r-th row of the matrix with a vector.
992	transpose	Returns the transposition of the matrix.

64.12.3 Tmatrix4_extended.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.12.4 Tmatrix4_extended.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.12.5 Tmatrix4_extended.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: extended; ab: extended; ac: extended;
ad: extended; ba: extended; bb: extended; bc: extended;
bd: extended; ca: extended; cb: extended; cc: extended;
cd: extended; da: extended; db: extended; dc: extended;
dd: extended)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.12.6 Tmatrix4_extended.get_column

Synopsis: Returns the *c*-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *c*-th column of the matrix as vector. The column numbering starts at 0.

64.12.7 Tmatrix4_extended.get_row

Synopsis: Returns the *r*-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_extended`

Visibility: default

Description: Returns the *r*-th row of the matrix as vector. The row numbering starts at 0.

64.12.8 Tmatrix4_extended.set_column

Synopsis: Sets *c*-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *c*-th column of the matrix with vector *v*. The column numbering starts at 0.

64.12.9 Tmatrix4_extended.set_row

Synopsis: Sets *r*-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_extended)`

Visibility: default

Description: Replaces the *r*-th row of the matrix with vector *v*. The row numbering starts at 0.

64.12.10 Tmatrix4_extended.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : extended`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.12.11 Tmatrix4_extended.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse (Adeterminant: extended) : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix4_extended.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.12.12 Tmatrix4_extended.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_extended`

Visibility: default

Description: `Tmatrix2_extended.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.13 Tmatrix4_single

64.13.1 Description

The `Tmatrix4_single` object provides a matrix of 4*4 single precision scalars.

64.13.2 Method overview

Page	Method	Description
994	<code>determinant</code>	Calculates the determinant of the matrix.
993	<code>get_column</code>	Returns the c-th column of the matrix as vector.
993	<code>get_row</code>	Returns the r-th row of the matrix as vector.
993	<code>init</code>	Initializes the matrix, setting its elements to the values passed to the constructor.
993	<code>init_identity</code>	Initializes the matrix and sets its elements to the identity matrix.
992	<code>init_zero</code>	Initializes the matrix and sets its elements to zero
994	<code>inverse</code>	Calculates the inverse of the matrix.
993	<code>set_column</code>	Sets c-th column of the matrix with a vector.
994	<code>set_row</code>	Sets r-th row of the matrix with a vector.
994	<code>transpose</code>	Returns the transposition of the matrix.

64.13.3 Tmatrix4_single.init_zero

Synopsis: Initializes the matrix and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.13.4 Tmatrix4_single.init_identity

Synopsis: Initializes the matrix and sets its elements to the identity matrix.

Declaration: `constructor init_identity`

Visibility: default

Description: Initializes the matrix and sets its elements to the identity matrix, that is, elements to 1 on the left-upper to right-lower diagonal, the rest zero.

64.13.5 Tmatrix4_single.init

Synopsis: Initializes the matrix, setting its elements to the values passed to the constructor.

Declaration: `constructor init(aa: single; ab: single; ac: single; ad: single;
ba: single; bb: single; bc: single; bd: single;
ca: single; cb: single; cc: single; cd: single;
da: single; db: single; dc: single; dd: single)`

Visibility: default

Description: Initializes the matrix, setting its elements to the values passed to the constructor. The order of the values is left to right, then top to bottom.

64.13.6 Tmatrix4_single.get_column

Synopsis: Returns the c-th column of the matrix as vector.

Declaration: `function get_column(c: Byte) : Tvector4_single`

Visibility: default

Description: Returns the c-th column of the matrix as vector. The column numbering starts at 0.

64.13.7 Tmatrix4_single.get_row

Synopsis: Returns the r-th row of the matrix as vector.

Declaration: `function get_row(r: Byte) : Tvector4_single`

Visibility: default

Description: Returns the r-th row of the matrix as vector. The row numbering starts at 0.

64.13.8 Tmatrix4_single.set_column

Synopsis: Sets c-th column of the matrix with a vector.

Declaration: `procedure set_column(c: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the c-th column of the matrix with vector v. The column numbering starts at 0.

64.13.9 Tmatrix4_single.set_row

Synopsis: Sets r-th row of the matrix with a vector.

Declaration: `procedure set_row(r: Byte; const v: Tvector4_single)`

Visibility: default

Description: Replaces the r-th row of the matrix with vector v. The row numbering starts at 0.

64.13.10 Tmatrix4_single.determinant

Synopsis: Calculates the determinant of the matrix.

Declaration: `function determinant : single`

Visibility: default

Description: Returns the determinant of the matrix. Note: Calculating the determinant of a 4*4 matrix requires quite a few operations.

64.13.11 Tmatrix4_single.inverse

Synopsis: Calculates the inverse of the matrix.

Declaration: `function inverse(Adeterminant: single) : Tmatrix4_single`

Visibility: default

Description: `Tmatrix4_single.inverse` returns a new matrix that is the inverse of the matrix. You must pass the determinant of the matrix as parameter. Note: Calculating the inverse of a 4*4 matrix requires quite a few operations.

64.13.12 Tmatrix4_single.transpose

Synopsis: Returns the transposition of the matrix.

Declaration: `function transpose : Tmatrix4_single`

Visibility: default

Description: `Tmatrix2_single.transpose` returns a new matrix that is the transposition of the matrix, that is, the matrix with the x and y coordinates of the values swapped.

64.14 Tvector2_double**64.14.1 Description**

The `Tvector2_double` object provides a vector of two double precision scalars.

64.14.2 Method overview

Page	Method	Description
995	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
995	<code>init_one</code>	Initializes the vector and sets its elements to one
995	<code>init_zero</code>	Initializes the vector and sets its elements to zero
995	<code>length</code>	Calculates the length of the vector.
995	<code>squared_length</code>	Calculates the squared length of the vector.

64.14.3 Tvector2_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.14.4 Tvector2_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.14.5 Tvector2_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double)`

Visibility: default

64.14.6 Tvector2_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([995](#)) if you are able to, as it is faster.

64.14.7 Tvector2_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.15 Tvector2_extended

64.15.1 Description

The `Tvector2_extended` object provides a vector of two extended precision scalars.

64.15.2 Method overview

Page	Method	Description
996	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
996	<code>init_one</code>	Initializes the vector and sets its elements to one
996	<code>init_zero</code>	Initializes the vector and sets its elements to zero
996	<code>length</code>	Calculates the length of the vector.
997	<code>squared_length</code>	Calculates the squared length of the vector.

64.15.3 Tvector2_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.15.4 Tvector2_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.15.5 Tvector2_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended)`

Visibility: default

64.15.6 Tvector2_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` ([997](#)) if you are able to, as it is faster.

64.15.7 Tvector2_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.16 Tvector2_single

64.16.1 Description

The `Tvector2_single` object provides a vector of two single precision scalars.

64.16.2 Method overview

Page	Method	Description
997	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
997	<code>init_one</code>	Initializes the vector and sets its elements to one
997	<code>init_zero</code>	Initializes the vector and sets its elements to zero
998	<code>length</code>	Calculates the length of the vector.
998	<code>squared_length</code>	Calculates the squared length of the vector.

64.16.3 Tvector2_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.16.4 Tvector2_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.16.5 Tvector2_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single)`

Visibility: default

64.16.6 Tvector2_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2)`. Try to use `squared_length` (998) if you are able to, as it is faster.

64.16.7 Tvector2_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2`.

64.17 Tvector3_double

64.17.1 Description

The `Tvector3_double` object provides a vector of three double precision scalars.

64.17.2 Method overview

Page	Method	Description
999	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
998	<code>init_one</code>	Initializes the vector and sets its elements to one
998	<code>init_zero</code>	Initializes the vector and sets its elements to zero
999	<code>length</code>	Calculates the length of the vector.
999	<code>squared_length</code>	Calculates the squared length of the vector.

64.17.3 Tvector3_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.17.4 Tvector3_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.17.5 Tvector3_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double)`

Visibility: default

64.17.6 Tvector3_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (999) if you are able to, as it is faster.

64.17.7 Tvector3_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.18 Tvector3_extended

64.18.1 Description

The `Tvector3_extended` object provides a vector of three extended precision scalars.

64.18.2 Method overview

Page	Method	Description
1000	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1000	<code>init_one</code>	Initializes the vector and sets its elements to one
999	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1000	<code>length</code>	Calculates the length of the vector.
1000	<code>squared_length</code>	Calculates the squared length of the vector.

64.18.3 Tvector3_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.18.4 Tvector3_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.18.5 Tvector3_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended)`

Visibility: default

64.18.6 Tvector3_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2)`. Try to use `squared_length` (1000) if you are able to, as it is faster.

64.18.7 Tvector3_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2`.

64.19 Tvector3_single

64.19.1 Description

The `Tvector3_single` object provides a vector of three single precision scalars.

64.19.2 Method overview

Page	Method	Description
1001	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1001	<code>init_one</code>	Initializes the vector and sets its elements to one
1001	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1001	<code>length</code>	Calculates the length of the vector.
1001	<code>squared_length</code>	Calculates the squared length of the vector.

64.19.3 Tvector3_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.19.4 Tvector3_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.19.5 Tvector3_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single)`

Visibility: default

64.19.6 Tvector3_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: $\text{length} = \sqrt{\text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2}$. Try to use `squared_length` ([1001](#)) if you are able to, as it is faster.

64.19.7 Tvector3_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: $\text{squared_length} = \text{data}[0]**2 + \text{data}[1]**2 + \text{data}[2]**2$.

64.20 Tvector4_double

64.20.1 Description

The `Tvector4_double` object provides a vector of four double precision scalars.

64.20.2 Method overview

Page	Method	Description
1002	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1002	<code>init_one</code>	Initializes the vector and sets its elements to one
1002	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1002	<code>length</code>	Calculates the length of the vector.
1002	<code>squared_length</code>	Calculates the squared length of the vector.

64.20.3 Tvector4_double.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.20.4 Tvector4_double.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.20.5 Tvector4_double.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: Double; b: Double; c: Double; d: Double)`

Visibility: default

64.20.6 Tvector4_double.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : Double`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1002](#)) if you are able to, as it is faster.

64.20.7 Tvector4_double.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : Double`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.21 Tvector4_extended

64.21.1 Description

The `Tvector4_extended` object provides a vector of four extended precision scalars.

64.21.2 Method overview

Page	Method	Description
1003	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1003	<code>init_one</code>	Initializes the vector and sets its elements to one
1003	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1003	<code>length</code>	Calculates the length of the vector.
1004	<code>squared_length</code>	Calculates the squared length of the vector.

64.21.3 Tvector4_extended.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.21.4 Tvector4_extended.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.21.5 Tvector4_extended.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: extended; b: extended; c: extended; d: extended)`

Visibility: default

64.21.6 Tvector4_extended.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : extended`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1004](#)) if you are able to, as it is faster.

64.21.7 Tvector4_extended.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : extended`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

64.22 Tvector4_single

64.22.1 Description

The `Tvector4_single` object provides a vector of four single precision scalars.

64.22.2 Method overview

Page	Method	Description
1004	<code>init</code>	Initializes the vector, setting its elements to the values passed to the constructor.
1004	<code>init_one</code>	Initializes the vector and sets its elements to one
1004	<code>init_zero</code>	Initializes the vector and sets its elements to zero
1005	<code>length</code>	Calculates the length of the vector.
1005	<code>squared_length</code>	Calculates the squared length of the vector.

64.22.3 Tvector4_single.init_zero

Synopsis: Initializes the vector and sets its elements to zero

Declaration: `constructor init_zero`

Visibility: default

64.22.4 Tvector4_single.init_one

Synopsis: Initializes the vector and sets its elements to one

Declaration: `constructor init_one`

Visibility: default

64.22.5 Tvector4_single.init

Synopsis: Initializes the vector, setting its elements to the values passed to the constructor.

Declaration: `constructor init(a: single; b: single; c: single; d: single)`

Visibility: default

64.22.6 Tvector4_single.length

Synopsis: Calculates the length of the vector.

Declaration: `function length : single`

Visibility: default

Description: Calculate the length of the vector: `length=sqrt(data[0]**2+data[1]**2+data[2]**2+data[3]**2)`. Try to use `squared_length` ([1005](#)) if you are able to, as it is faster.

64.22.7 Tvector4_single.squared_length

Synopsis: Calculates the squared length of the vector.

Declaration: `function squared_length : single`

Visibility: default

Description: Calculate the squared length of the vector: `squared_length=data[0]**2+data[1]**2+data[2]**2+data[3]**2`.

Chapter 65

Reference for unit 'mmx'

65.1 Used units

Table 65.1: Used units by unit 'mmx'

Name	Page
System	1194

65.2 Overview

This document describes the MMX unit. This unit allows you to use the MMX capabilities of the Free Pascal compiler. It was written by Florian Klaempfl for the I386 processor. It should work on all platforms that use the Intel processor.

65.3 Constants, types and variables

65.3.1 Constants

```
is_amd_3d_cpu : Boolean = False
```

The `is_amd_3d_cpu` initialized constant allows you to determine if the computer has the AMD 3D extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_dsp_cpu : Boolean = False
```

The `is_amd_3d_dsp_cpu` initialized constant allows you to determine if the computer has the AMD 3D DSP extensions. It is set correctly in the unit's initialization code.

```
is_amd_3d_mmx_cpu : Boolean = False
```

The `is_amd_3d_mmx_cpu` initialized constant allows you to determine if the computer has the AMD 3D MMX extensions. It is set correctly in the unit's initialization code.

```
is_mmx_cpu : Boolean = False
```

The `is_mmx_cpu` initialized constant allows you to determine if the computer has MMX extensions. It is set correctly in the unit's initialization code.

```
is_sse2_cpu : Boolean = False
```

The `is_sse2_cpu` initialized constant allows you to determine if the computer has the SSE2 extensions. It is set correctly in the unit's initialization code.

```
is_sse_cpu : Boolean = False
```

The `is_sse_cpu` initialized constant allows you to determine if the computer has the SSE extensions. It is set correctly in the unit's initialization code.

65.3.2 Types

```
pmmxbyte = ^tmmxbyte
```

Pointer to `tmmxbyte` (1007) array type

```
pmmxcardinal = ^tmmxcardinal
```

Pointer to `tmmxcardinal` (1007) array type

```
pmmxinteger = ^tmmxinteger
```

Pointer to `tmmxinteger` (1008) array type

```
pmmxlongint = ^tmmxlongint
```

Pointer to `tmmxlongint` (1008) array type

```
pmmxshortint = ^tmmxshortint
```

Pointer to `tmmxshortint` (1008) array type

```
pmmxsingle = ^tmmxsingle
```

Pointer to `tmmxsingle` (1008) array type

```
pmmxword = ^tmmxword
```

Pointer to `tmmxword` (1008) array type

```
tmmxbyte = Array[0..7] of Byte
```

Array of bytes, 64 bits in size

```
tmmxcardinal = Array[0..1] of Cardinal
```

Array of cardinals, 64 bits in size


```
tmmxinteger = Array[0..3] of Integer
```

Array of integers, 64 bits in size

```
tmmxlongint = Array[0..1] of LongInt
```

Array of longint, 64 bits in size

```
tmmxshortint = Array[0..7] of ShortInt
```

Array of shortints, 64 bits in size

```
tmmxsingle = Array[0..1] of single
```

Array of singles, 64 bits in size

```
tmmxword = Array[0..3] of Word
```

Array of words, 64 bits in size

65.4 Procedures and functions

65.4.1 emms

Synopsis: Reset floating point registers

Declaration: `procedure emms`

Visibility: `default`

Description: `Emms` sets all floating point registers to empty. This procedure must be called after you have used any MMX instructions, if you want to use floating point arithmetic. If you just want to move floating point data around, it isn't necessary to call this function, the compiler doesn't use the FPU registers when moving data. Only when doing calculations, you should use this function. The following code demonstrates this:

```
Program MMXDemo;
uses mmx;
var
  dl : double;
  a : array[0..10000] of double;
  i : longint;
begin
  dl:=1.0;
  {$mmx+}
  { floating point data is used, but we do _no_ arithmetic }
  for i:=0 to 10000 do
    a[i]:=d2; { this is done with 64 bit moves }
  {$mmx-}
  emms; { clear fpu }
  { now we can do floating point arithmetic again }
end.
```

See also: `femms` ([1009](#))

65.4.2 femms

Synopsis: Reset floating point registers - AMD version

Declaration: `procedure femms`

Visibility: `default`

Description: `femms` executes the `femms` assembler instruction for AMD processors. it is not supported by all assemblers, hence it is coded as byte codes.

See also: `emms` ([1008](#))

Chapter 66

Reference for unit 'Mouse'

66.1 Used units

Table 66.1: Used units by unit 'Mouse'

Name	Page
System	1194

66.2 Overview

The `Mouse` unit implements a platform independent mouse handling interface. It is implemented identically on all platforms supported by Free Pascal and can be enhanced with custom drivers, should this be needed. It is intended to be used only in text-based screens, for instance in conjunction with the keyboard and video unit. No support for graphical screens is implemented, and there are (currently) no plans to implement this.

66.3 Writing a custom mouse driver

The `mouse` unit has support for adding a custom mouse driver. This can be used to add support for mice not supported by the standard Free Pascal driver, but also to enhance an existing driver for instance to log mouse events or to implement a record and playback function.

The following unit shows how a mouse driver can be enhanced by adding some logging capabilities to the driver.

Listing: `./mouseex/logmouse.pp`

```
unit logmouse ;
```

```
interface
```

```
Procedure StartMouseLogging ;
```

```
Procedure StopMouseLogging ;
```

```
Function IsMouseLogging : Boolean ;
```

```
Procedure SetMouseLogFileName ( FileName : String ) ;
```

implementation

```
uses sysutils ,Mouse;
```

var

```
  NewMouseDriver ,
  OldMouseDriver : TMouseDriver;
  Active ,Logging : Boolean;
  LogFileName : String;
  MouseLog : Text;
```

```
Function TimeStamp : String;
```

begin

```
  TimeStamp:=FormatDateTime( 'hh:nn:ss' ,Time());
end;
```

```
Procedure StartMouseLogging;
```

begin

```
  Logging:=True;
  WriteLn(MouseLog,'Start logging mouse events at: ',TimeStamp);
end;
```

```
Procedure StopMouseLogging;
```

begin

```
  WriteLn(MouseLog,'Stop logging mouse events at: ',TimeStamp);
  Logging:=False;
end;
```

```
Function IsMouseLogging : Boolean;
```

begin

```
  IsMouseLogging:=Logging;
end;
```

```
Procedure LogGetMouseEvent(Var Event : TMouseEvent);
```

Var

```
  M : TMouseEvent;
```

begin

```
  OldMouseDriver.GetMouseEvent(M);
  If Logging then
  begin
    Write(MouseLog,TimeStamp,' : Mouse ');
    With M do
    begin
      Case Action of
        MouseActionDown : Write(MouseLog,'down');
        MouseActionUp : Write(MouseLog,'up');
        MouseActionMove : Write(MouseLog,'move');
      end;
    Write(MouseLog,' event at ',X,', ',Y);
    If (Buttons<>0) then
    begin
```

```

    Write(MouseLog, ' for buttons: ');
    If (Buttons and MouseLeftbutton)<>0 then
        Write(MouseLog, ' Left ');
    If (Buttons and MouseRightbutton)<>0 then
        Write(MouseLog, ' Right ');
    If (Buttons and MouseMiddlebutton)<>0 then
        Write(MouseLog, ' Middle ');
    end;
    WriteLn(MouseLog);
end;
end;
end;

Procedure LogInitMouse;

begin
    OldMouseDriver.InitDriver();
    Assign(MouseLog, logFileName);
    Rewrite(MouseLog);
    Active := True;
    StartMouseLogging;
end;

Procedure LogDoneMouse;

begin
    StopMouseLogging;
    Close(MouseLog);
    Active := False;
    OldMouseDriver.DoneDriver();
end;

Procedure SetMouseLogFileName(FileName : String);

begin
    If Not Active then
        LogFileName := FileName;
end;

Initialization
    GetMouseDriver(OldMouseDriver);
    NewMouseDriver := OldMouseDriver;
    NewMouseDriver.GetMouseEvent := @LogGetMouseEvent;
    NewMouseDriver.InitDriver := @LogInitMouse;
    NewMouseDriver.DoneDriver := @LogDoneMouse;
    LogFileName := 'Mouse.log';
    Logging := False;
    SetMouseDriver(NewMouseDriver);
end.

```

66.4 Constants, types and variables

66.4.1 Constants

```
errMouseBase = 1030
```

Base for mouse error codes.

`errMouseInitError = errMouseBase + 0`

Mouse initialization error

`errMouseNotImplemented = errMouseBase + 1`

Mouse driver not implemented.

`MouseActionDown = $0001`

Mouse button down event signal.

`MouseActionMove = $0004`

Mouse cursor move event signal.

`MouseActionUp = $0002`

Mouse button up event signal.

`MouseButton4 = $08`

4th mouse button event

`MouseButton5 = $10`

5th mouse button event

`MouseEventBufSize = 16`

The mouse unit has a mechanism to buffer mouse events. This constant defines the size of the event buffer.

`MouseLeftButton = $01`

Left mouse button event.

`MouseMiddleButton = $04`

Middle mouse button event.

`MouseRightButton = $02`

Right mouse button event.

66.4.2 Types

```
PMouseEvent = ^TMouseEvent
```

Pointer to TMouseEvent (1014) record.

```
TMouseDriver = record
  UseDefaultQueue : Boolean;
  InitDriver :
  procedure;
  DoneDriver : procedure;
  DetectMouse : function : Byte
  ;
  ShowMouse : procedure;
  HideMouse : procedure;
  GetMouseX :
  function : Word;
  GetMouseY : function : Word;
  GetMouseButtons
  : function : Word;
  SetMouseXY : procedure(x: Word; y: Word);
  GetMouseEvent : procedure(var MouseEvent: TMouseEvent);
  PollMouseEvent
  : function(var MouseEvent: TMouseEvent) : Boolean;
  PutMouseEvent
  : procedure(const MouseEvent: TMouseEvent);
end
```

The TMouseDriver record is used to implement a mouse driver in the SetMouseDriver (1020) function. Its fields must be filled in before calling the SetMouseDriver (1020) function.

```
TMouseEvent = packed record
  buttons : Word;
  x : Word;
  y : Word
  ;
  Action : Word;
end
```

The TMouseEvent is the central type of the mouse unit, it is used to describe all mouse events.

The Buttons field describes which buttons were down when the event occurred. The x, y fields describe where the event occurred on the screen. The Action describes what action was going on when the event occurred. The Buttons and Action field can be examined using the constants defined in the unit interface.

66.4.3 Variables

```
MouseButtons : Byte
```

This variable keeps track of the last known mouse button state. Do not use.

```
MouseIntFlag : Byte
```

This variable keeps track of the last known internal mouse state. Do not use.

MouseWhereX : Word

This variable keeps track of the last known cursor position. Do not use.

MouseWhereY : Word

This variable keeps track of the last known cursor position. Do not use.

66.5 Procedures and functions

66.5.1 DetectMouse

Synopsis: Detect the presence of a mouse.

Declaration: `function DetectMouse : Byte`

Visibility: default

Description: `DetectMouse` detects whether a mouse is attached to the system or not. If there is no mouse, then zero is returned. If a mouse is attached, then the number of mouse buttons is returned.

This function should be called after the mouse driver was initialized.

Errors: None.

See also: `InitMouse` ([1019](#)), `DoneMouse` ([1015](#))

Listing: `./mouseex/ex1.pp`

Program `Example1`;

{ Program to demonstrate the DetectMouse function. }

Uses `mouse`;

Var

Buttons : Byte;

begin

InitMouse;

Buttons:=DetectMouse;

If Buttons=0 **then**

Writeln('No mouse present. ')

else

Writeln('Found mouse with ',Buttons, ' buttons. ');

DoneMouse;

end.

66.5.2 DoneMouse

Synopsis: Deinitialize mouse driver.

Declaration: `procedure DoneMouse`

Visibility: default

Description: `DoneMouse` De-initializes the mouse driver. It cleans up any memory allocated when the mouse was initialized, or removes possible mouse hooks from memory. The mouse functions will not work after `DoneMouse` was called. If `DoneMouse` is called a second time, it will exit at once. `InitMouse` should be called before `DoneMouse` can be called again.

For an example, see most other mouse functions.

Errors: None.

See also: `DetectMouse` ([1015](#)), `InitMouse` ([1019](#))

66.5.3 GetMouseButtons

Synopsis: Get the state of the mouse buttons

Declaration: `function GetMouseButtons : Word`

Visibility: default

Description: `GetMouseButtons` returns the current button state of the mouse, i.e. it returns a or-ed combination of the following constants:

MouseLeftButton When the left mouse button is held down.

MouseRightButton When the right mouse button is held down.

MouseMiddleButton When the middle mouse button is held down.

Errors: None.

See also: `GetMouseEvent` ([1017](#)), `GetMouseX` ([1017](#)), `GetMouseY` ([1018](#))

Listing: `./mouseex/ex2.pp`

Program `Example2;`

{ Program to demonstrate the GetMouseButtons function. }

Uses `mouse;`

begin

`InitMouse;`

`WriteLn('Press right mouse button to exit program');`

`While (GetMouseButtons<>MouseRightButton) do ;`

`DoneMouse;`

end.

66.5.4 GetMouseDriver

Synopsis: Get a copy of the currently active mouse driver.

Declaration: `procedure GetMouseDriver(var Driver: TMouseDriver)`

Visibility: default

Description: `GetMouseDriver` returns the currently set mouse driver. It can be used to retrieve the current mouse driver, and override certain callbacks.

A more detailed explanation about getting and setting mouse drivers can be found in `mousedrv` (1010).

For an example, see the section on writing a custom mouse driver, `mousedrv` (1010)

Errors: None.

See also: `SetMouseDriver` (1020)

66.5.5 GetMouseEvent

Synopsis: Get next mouse event from the queue.

Declaration: `procedure GetMouseEvent (var MouseEvent : TMouseEvent)`

Visibility: default

Description: `GetMouseEvent` returns the next mouse event (a movement, button press or button release), and waits for one if none is available in the queue.

Some mouse drivers can implement a mouse event queue which can hold multiple events till they are fetched. Others don't, and in that case, a one-event queue is implemented for use with `PollMouseEvent` (1019).

Errors: None.

See also: `GetMouseButtons` (1016), `GetMouseX` (1017), `GetMouseY` (1018)

66.5.6 GetMouseX

Synopsis: Query the current horizontal position of the mouse cursor.

Declaration: `function GetMouseX : Word`

Visibility: default

Description: `GetMouseX` returns the current X position of the mouse. X is measured in characters, starting at 0 for the left side of the screen.

Errors: None.

See also: `GetMouseButtons` (1016), `GetMouseEvent` (1017), `GetMouseY` (1018)

Listing: `./mouseex/ex4.pp`

Program Example4;

{ Program to demonstrate the GetMouseX,GetMouseY functions. }

Uses mouse;

Var

X,Y : Word;

begin

InitMouse;

WriteLn('Move mouse cursor to square 10,10 to end');

```

Repeat
  X:=GetMouseX;
  Y:=GetMouseY;
  WriteLn( 'X,Y= ( ',X, ', ',Y, ' ) ' );
Until (X=9) and (Y=9);
DoneMouse;
end.

```

66.5.7 GetMouseY

Synopsis: Query the current vertical position of the mouse cursor.

Declaration: `function GetMouseY : Word`

Visibility: default

Description: `GetMouseY` returns the current Y position of the mouse. Y is measured in characters, starting at 0 for the top of the screen.

For an example, see `GetMouseX` ([1017](#))

Errors: None.

See also: `GetMouseButtons` ([1016](#)), `GetMouseEvent` ([1017](#)), `GetMouseX` ([1017](#))

66.5.8 HideMouse

Synopsis: Hide the mouse cursor.

Declaration: `procedure HideMouse`

Visibility: default

Description: `HideMouse` hides the mouse cursor. This may or may not be implemented on all systems, and depends on the driver.

Errors: None.

See also: `ShowMouse` ([1021](#))

Listing: `./mouseex/ex5.pp`

Program `Example5;`

{ Program to demonstrate the HideMouse function. }

Uses `mouse;`

Var

`Event : TMouseEvent;`
`Visible : Boolean;`

begin

`InitMouse;`
`ShowMouse;`
`Visible:=True;`
`WriteLn('Press left mouse button to hide/show, right button quits');`
Repeat

```

GetMouseEvent(Event);
With Event do
  If (Buttons=MouseLeftbutton) and
    (Action=MouseDown) then
    begin
      If Visible then
        HideMouse;
      else
        ShowMouse;
        Visible:=Not Visible;
      end;
    Until (Event.Buttons=MouseRightButton) and
      (Event.Action=MouseDown);
  DoneMouse;
end.

```

66.5.9 InitMouse

Synopsis: Initialize the FPC mouse driver.

Declaration: `procedure InitMouse`

Visibility: default

Description: `InitMouse` initializes the mouse driver. This will allocate any data structures needed for the mouse to function. All mouse functions can be used after a call to `InitMouse`.

A call to `InitMouse` must always be followed by a call to `DoneMouse` (1015) at program exit. Failing to do so may leave the mouse in an unusable state, or may result in memory leaks.

For an example, see most other functions.

Errors: None.

See also: `DoneMouse` (1015), `DetectMouse` (1015)

66.5.10 PollMouseEvent

Synopsis: Query next mouse event. Do not wait if none available.

Declaration: `function PollMouseEvent(var MouseEvent: TMouseEvent) : Boolean`

Visibility: default

Description: `PollMouseEvent` checks whether a mouse event is available, and returns it in `MouseEvent` if one is found. The function result is `True` in that case. If no mouse event is pending, the function result is `False`, and the contents of `MouseEvent` is undefined.

Note that after a call to `PollMouseEvent`, the event should still be removed from the mouse event queue with a call to `GetMouseEvent`.

Errors: None.

See also: `GetMouseEvent` (1017), `PutMouseEvent` (1020)

66.5.11 PutMouseEvent

Synopsis: Put a mouse event in the venet queue.

Declaration: `procedure PutMouseEvent (const MouseEvent: TMouseEvent)`

Visibility: default

Description: `PutMouseEvent` adds `MouseEvent` to the input queue. The next call to `GetMouseEvent` (1017) or `PollMouseEvent` will then return `MouseEvent`.

Please note that depending on the implementation the mouse event queue can hold only one value.

Errors: None.

See also: `GetMouseEvent` (1017), `PollMouseEvent` (1019)

66.5.12 SetMouseDriver

Synopsis: Set a new mouse driver.

Declaration: `procedure SetMouseDriver (const Driver: TMouseDriver)`

Visibility: default

Description: `SetMouseDriver` sets the mouse driver to `Driver`. This function should be called before `InitMouse` (1019) is called, or after `DoneMouse` is called. If it is called after the mouse has been initialized, it does nothing.

For more information on setting the mouse driver, `mousedrv` (1010).

For an example, see `mousedrv` (1010)

See also: `InitMouse` (1019), `DoneMouse` (1015), `GetMouseDriver` (1016)

66.5.13 SetMouseXY

Synopsis: Set the mouse cursor position.

Declaration: `procedure SetMouseXY (x: Word; y: Word)`

Visibility: default

Description: `SetMouseXY` places the mouse cursor on `X`, `Y`. `X` and `Y` are zero based character coordinates: 0, 0 is the top-left corner of the screen, and the position is in character cells (i.e. not in pixels).

Errors: None.

See also: `GetMouseX` (1017), `GetMouseY` (1018)

Listing: `./mouseex/ex7.pp`

Program `Example7`;

{ Program to demonstrate the SetMouseXY function. }

Uses `mouse`;

begin

`InitMouse`;

`WriteLn`('Click right mouse button to quit.');

```
SetMouseXY (40 , 12);  
Repeat  
  WriteIn ( GetMouseX , ' ' , GetMouseY );  
  If ( GetMouseX > 70 ) then  
    SetMouseXY (10 , GetMouseY );  
  If ( GetMouseY > 20 ) then  
    SetMouseXY ( GetMouseX , 5 );  
  Until ( GetMouseButtons = MouseRightButton );  
DoneMouse;  
end.
```

66.5.14 ShowMouse

Synopsis: Show the mouse cursor.

Declaration: `procedure ShowMouse`

Visibility: `default`

Description: `ShowMouse` shows the mouse cursor if it was previously hidden. The capability to hide or show the mouse cursor depends on the driver.

For an example, see `HideMouse` ([1018](#))

Errors: None.

See also: `HideMouse` ([1018](#))

Chapter 67

Reference for unit 'Objects'

67.1 Used units

Table 67.1: Used units by unit 'Objects'

Name	Page
System	1194

67.2 Overview

This document documents the `objects` unit. The unit was implemented by many people, and was mainly taken from the FreeVision sources. It has been ported to all supported platforms.

The methods and fields that are in a `Private` part of an object declaration have been left out of this documentation.

67.3 Constants, types and variables

67.3.1 Constants

`coIndexError = -1`

Collection list error: Index out of range

`coOverflow = -2`

Collection list error: Overflow

`DefaultTPCompatible : Boolean = False`

`DefaultTPCompatible` is used to initialize `tstream.tpcompatible` (??).

`MaxBytes = 128 * 1024 * 128`

Maximum data size (in bytes)

```
MaxCollectionSize = MaxBytes div (Pointer)
```

Maximum collection size (in items)

```
MaxPtrs = MaxBytes div (Pointer)
```

Maximum data size (in pointers)

```
MaxReadBytes = $7fffffff
```

Maximum data that can be read from a stream (not used)

```
MaxTPCompatibleCollectionSize = 65520 div 4
```

Maximum collection size (in items, same value as in TP)

```
MaxWords = MaxBytes div (Word)
```

Maximum data size (in words)

```
RCollection : TStreamRec = (ObjType: 50; VmtLink: (^TCollection)
); Load: @TCollection.Load; Store: @TCollection.Store; Next: Nil)
```

Default stream record for the TCollection ([1039](#)) object.

```
RStrCollection : TStreamRec = (ObjType: 69; VmtLink: (^TStrCollection
)); Load: @TStrCollection.Load; Store: @TStrCollection.Store; Next
: Nil)
```

Default stream record for the TStrCollection ([1078](#)) object.

```
RStringCollection : TStreamRec = (ObjType: 51; VmtLink: (^TStringCollection
)); Load: @TStringCollection.Load; Store: @TStringCollection.Store
; Next: Nil)
```

Default stream record for the TStringCollection ([1088](#)) object.

```
RStringList : TStreamRec = (ObjType: 52; VmtLink: (^TStringList)
); Load: @TStringList.Load; Store: Nil; Next: Nil)
```

Default stream record for the TStringList ([1090](#)) object.

```
RStrListMaker : TStreamRec = (ObjType: 52; VmtLink: (^TStrListMaker
)); Load: Nil; Store: @TStrListMaker.Store; Next: Nil)
```

Default stream record for the TStrListMaker ([1092](#)) object.

```
stCreate = $3C00
```


Stream initialization mode: Create new file

`stError = -1`

Stream error codes: Access error

`stGetError = -5`

Stream error codes: Get object error

`stInitError = -2`

Stream error codes: Initialize error

`stOk = 0`

Stream error codes: No error

`stOpen = $3D02`

Stream initialization mode: Read/write access

`stOpenError = -8`

Stream error codes: Error opening stream

`stOpenRead = $3D00`

Stream initialization mode: Read access only

`stOpenWrite = $3D01`

Stream initialization mode: Write access only

`stPutError = -6`

Stream error codes: Put object error

`stReadError = -3`

Stream error codes: Stream read error

`StreamError : CodePointer = Nil`

Pointer to default stream error handler.

`stSeekError = -7`

Stream error codes: Seek error in stream

`stWriteError = -4`

Stream error codes: Stream write error

`vmtHeaderSize = 8`

Size of the VMT header in an object (not used).

67.3.2 Types

AsciiZ = Array[0..255] of Char

Filename - null terminated array of characters.

FNameStr = String

Filename - shortstring version.

```
LongRec = packed record
  Hi : Word;
  Lo : Word;
end
```

Record describing a longint (in Words)

PBufStream = ^TBufStream

Pointer to TBufStream ([1035](#)) object.

PByteArray = ^TByteArray

Pointer to TByteArray ([1027](#))

PCharSet = ^TCharSet

Pointer to TCharSet ([1027](#)).

PCollection = ^TCollection

Pointer to TCollection ([1039](#)) object.

PDosStream = ^TDosStream

Pointer to TDosStream ([1053](#)) object.

PItemList = ^TItemList

Pointer to TItemList ([1027](#)) object.

PMemoryStream = ^TMemoryStream

Pointer to TMemoryStream ([1058](#)) object.

PObject = ^TObject

Pointer to TObject ([1060](#)) object.

PPoint = ^TPoint

Pointer to TPoint (1062) record.

`PPointerArray = ^TPointerArray`

Pointer to TPointerArray (1027)

`PRect = ^TRect`

Pointer to TRect (1062) object.

`PResourceCollection = ^TResourceCollection`

Pointer to TResourceCollection (1068) object.

`PResourceFile = ^TResourceFile`

Pointer to TResourceFile (1069) object.

`PSortedCollection = ^TSortedCollection`

Pointer to TSortedCollection (1072) object.

`PStrCollection = ^TStrCollection`

Pointer to TStrCollection (1078) object.

`PStream = ^TStream`

Pointer type to TStream (1080)

`PStreamRec = ^TStreamRec`

Pointer to TStreamRec (1028)

`PStrIndex = ^TStrIndex`

Pointer to TStrIndex (1028) array.

`PString = PShortString`

Pointer to a shortstring.

`PStringCollection = ^TStringCollection`

Pointer to TStringCollection (1088) object.

`PStringList = ^TStringList`

Pointer to TStringList (1090) object.

`PStrListMaker = ^TStrListMaker`

Pointer to TStrListMaker ([1092](#)) object.

```
PtrRec = packed record
  Ofs : Word;
  Seg : Word;
end
```

Record describing a pointer to a memory location.

```
PUnSortedStrCollection = ^TUnSortedStrCollection
```

Pointer to TUnSortedStrCollection ([1093](#)) object.

```
PWordArray = ^TWordArray
```

Pointer to TWordArray ([1028](#))

```
Sw_Integer = LongInt
```

Alias for longint

```
Sw_Word = Cardinal
```

Alias for Cardinal

```
TByteArray = Array[0..MaxBytes-1] of Byte
```

Array with maximum allowed number of bytes.

```
TCharSet = Set of Char
```

Generic set of characters type.

```
TItemList = Array[0..MaxCollectionSize-1] of Pointer
```

Pointer array type used in a TCollection ([1039](#))

```
TPointerArray = Array[0..MaxPtrs-1] of Pointer
```

Array with maximum allowed number of pointers

```
TStreamRec = packed record
  ObjType : Sw_Word;
  VmtLink : pointer
;
  Load : CodePointer;
  Store : CodePointer;
  Next : PStreamRec
;
end
```

TStreamRec is used by the **Objects** unit streaming mechanism: when an object is registered, a TStreamRec record is added to a list of records. This list is used when objects need to be streamed from/streamed to a stream. It contains all the information needed to stream the object.

```
TStrIndex = Array[0..9999] of TStrIndexRec
```

Pointer array type used in a TStringList ([1090](#))

```
TStrIndexRec = packed record
  Key : Sw_Word;
  Count : Word;
  Offset
    : Word;
end
```

Record type used in a TStringList ([1090](#)) to store the strings

```
TWordArray = Array[0..MaxWords-1] of Word
```

Array with maximum allowed number of words.

```
WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end
```

Record describing a Word (in bytes)

67.3.3 Variables

```
invalidhandle : THandle
```

Value for invalid handle. Initial value for file stream handles or when the stream is closed.

67.4 Procedures and functions

67.4.1 Abstract

Synopsis: Abstract error handler.

Declaration: `procedure Abstract`

Visibility: `default`

Description: When implementing abstract methods, do not declare them as `abstract`. Instead, define them simply as `virtual`. In the implementation of such abstract methods, call the `Abstract` procedure. This allows explicit control of what happens when an abstract method is called.

The current implementation of `Abstract` terminates the program with a run-time error 211.

Errors: None.

67.4.2 CallPointerConstructor

Synopsis: Call a constructor with a pointer argument.

Declaration: `function CallPointerConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. `Param1` is passed to the constructor. The return value is a pointer to the instance.

Note that this can only be used on constructors that require a pointer as the sole argument. It can also be used to call a constructor with a single argument by reference.

Errors: If the constructor expects other arguments than a pointer, the stack may be corrupted.

See also: `CallVoidConstructor` (1030), `CallPointerMethod` (1029), `CallVoidLocal` (1030), `CallPointerLocal` (1029), `CallVoidMethodLocal` (1031), `CallPointerMethodLocal` (1030)

67.4.3 CallPointerLocal

Synopsis: Call a local nested function with a pointer argument

Declaration: `function CallPointerLocal(Func: CodePointer; Frame: Pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1029), `CallVoidMethod` (1031), `CallVoidLocal` (1030), `CallVoidMethodLocal` (1031), `CallPointerMethodLocal` (1030), `CallVoidConstructor` (1030), `CallPointerConstructor` (1029)

67.4.4 CallPointerMethod

Synopsis: Call a method with a single pointer argument

Declaration: `function CallPointerMethod(Method: CodePointer; Obj: pointer;
Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethod` calls the method with address `Method` for instance `Obj`. It passes `Param1` to the method as the single argument. It returns a pointer to the instance.

Errors: If the method expects other parameters than a single pointer, the stack may become corrupted.

See also: `CallVoidMethod` (1031), `CallVoidLocal` (1030), `CallPointerLocal` (1029), `CallVoidMethodLocal` (1031), `CallPointerMethodLocal` (1030), `CallVoidConstructor` (1030), `CallPointerConstructor` (1029)

67.4.5 CallPointerMethodLocal

Synopsis: Call a local procedure of a method with a pointer argument

Declaration: `function CallPointerMethodLocal(Func: CodePointer; Frame: Pointer;
Obj: pointer; Param1: pointer) : pointer`

Visibility: default

Description: `CallPointerMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method. It passes `Param1` to the local function.

Errors: If the local function expects other parameters than a pointer, the stack may become corrupted.

See also: `CallPointerMethod` (1029), `CallVoidMethod` (1031), `CallPointerLocal` (1029), `CallVoidLocal` (1030), `CallVoidMethodLocal` (1031), `CallVoidConstructor` (1030), `CallPointerConstructor` (1029)

67.4.6 CallVoidConstructor

Synopsis: Call a constructor with no arguments

Declaration: `function CallVoidConstructor(Ctor: CodePointer; Obj: pointer;
VMT: pointer) : pointer`

Visibility: default

Description: `CallVoidConstructor` calls the constructor of an object. `Ctor` is the address of the constructor, `Obj` is a pointer to the instance. If it is `Nil`, then a new instance is allocated. `VMT` is a pointer to the object's VMT. The return value is a pointer to the instance.

Note that this can only be used on constructors that require no arguments.

Errors: If the constructor expects arguments, the stack may be corrupted.

See also: `CallPointerConstructor` (1029), `CallPointerMethod` (1029), `CallVoidLocal` (1030), `CallPointerLocal` (1029), `CallVoidMethodLocal` (1031), `CallPointerMethodLocal` (1030)

67.4.7 CallVoidLocal

Synopsis: Call a local nested procedure.

Declaration: `function CallVoidLocal(Func: CodePointer; Frame: Pointer) : pointer`

Visibility: default

Description: `CallVoidLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping function.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` (1029), `CallVoidMethod` (1031), `CallPointerLocal` (1029), `CallVoidMethodLocal` (1031), `CallPointerMethodLocal` (1030), `CallVoidConstructor` (1030), `CallPointerConstructor` (1029)

67.4.8 CallVoidMethod

Synopsis: Call an object method

Declaration: `function CallVoidMethod(Method: CodePointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethod` calls the method with address `Method` for instance `Obj`. It returns a pointer to the instance.

Errors: If the method expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1029](#)), `CallVoidLocal` ([1030](#)), `CallPointerLocal` ([1029](#)), `CallVoidMethodLocal` ([1031](#)), `CallPointerMethodLocal` ([1030](#)), `CallVoidConstructor` ([1030](#)), `CallPointerConstructor` ([1029](#))

67.4.9 CallVoidMethodLocal

Synopsis: Call a local procedure of a method

Declaration: `function CallVoidMethodLocal(Func: CodePointer; Frame: Pointer; Obj: pointer) : pointer`

Visibility: default

Description: `CallVoidMethodLocal` calls the local procedure with address `Func`, where `Frame` is the frame of the wrapping method.

Errors: If the local function expects parameters, the stack may become corrupted.

See also: `CallPointerMethod` ([1029](#)), `CallVoidMethod` ([1031](#)), `CallPointerLocal` ([1029](#)), `CallVoidLocal` ([1030](#)), `CallPointerMethodLocal` ([1030](#)), `CallVoidConstructor` ([1030](#)), `CallPointerConstructor` ([1029](#))

67.4.10 DisposeStr

Synopsis: Dispose of a shortstring which was allocated on the heap.

Declaration: `procedure DisposeStr(P: PString)`

Visibility: default

Description: `DisposeStr` removes a dynamically allocated string from the heap.

For an example, see `NewStr` ([1032](#)).

Errors: None.

See also: `NewStr` ([1032](#)), `SetStr` ([1034](#))

67.4.11 LongDiv

Synopsis: Overflow safe divide

Declaration: `function LongDiv(X: LongInt; Y: Integer) : Integer`

Visibility: default

Description: `LongDiv` divides `X` by `Y`. The result is of type `Integer` instead of type `Longint`, as you would get normally.

Errors: If Y is zero, a run-time error will be generated.

See also: LongMul ([1032](#))

67.4.12 LongMul

Synopsis: Overflow safe multiply.

Declaration: `function LongMul(X: Integer; Y: Integer) : LongInt`

Visibility: default

Description: LongMul multiplies X with Y. The result is of type LongInt. This avoids possible overflow errors you would normally get when multiplying X and Y that are too big.

Errors: None.

See also: LongDiv ([1031](#))

67.4.13 NewStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `function NewStr(const S: string) : PString`

Visibility: default

Description: NewStr makes a copy of the string S on the heap, and returns a pointer to this copy. If the string is empty then Nil is returned.

The allocated memory is not based on the declared size of the string passed to NewStr, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: DisposeStr ([1031](#)), SetStr ([1034](#))

Listing: ./objectex/ex40.pp

```

Program ex40;

{ Program to demonstrate the NewStr function }

Uses Objects;

Var S : String;
    P : PString;

begin
  S := 'Some really cute string';
  P := NewStr(S);
  If P^ <> S then
    Writeln ('Oh-oh... Something is wrong !!');
  DisposeStr(P);
end.

```

67.4.14 RegisterObjects

Synopsis: Register standard objects.

Declaration: `procedure RegisterObjects`

Visibility: `default`

Description: `RegisterObjects` registers the following objects for streaming:

1. `TCollection`, see `TCollection` (1039).
2. `TStringCollection`, see `TStringCollection` (1088).
3. `TStrCollection`, see `TStrCollection` (1078).

Errors: None.

See also: `RegisterType` (1033)

67.4.15 RegisterType

Synopsis: Register new object for streaming.

Declaration: `procedure RegisterType (var S: TStreamRec)`

Visibility: `default`

Description: `RegisterType` registers a new type for streaming. An object cannot be streamed unless it has been registered first. The stream record `S` needs to have the following fields set:

ObjType: `Sw_Word` This should be a unique identifier. Each possible type should have it's own identifier.

VmtLink: `pointer` This should contain a pointer to the VMT (Virtual Method Table) of the object you try to register.

Load : `Pointer` is a pointer to a method that initializes an instance of that object, and reads the initial values from a stream. This method should accept as it's sole argument a `PStream` type variable.

Store: `Pointer` is a pointer to a method that stores an instance of the object to a stream. This method should accept as it's sole argument a `PStream` type variable.

The VMT of the object can be retrieved with the following expression:

```
VmtLink: ofs (TypeOf (MyType) ^) ;
```

Errors: In case of error (if a object with the same `ObjType`) is already registered), run-time error 212 occurs.

Listing: `./objectex/myobject.pp`

```
Unit MyObject;
```

```
Interface
```

```
Uses Objects;
```

```
Type
```

```

PMyObject = ^TMyObject;
TMyObject = Object(TObject)
  Field : Longint;
  Constructor Init;
  Constructor Load (Var Stream : TStream);
  Destructor Done;
  Procedure Store (Var Stream : TStream);
  Function GetField : Longint;
  Procedure SetField (Value : Longint);
end;

```

Implementation

```

Constructor TMyobject.Init;

begin
  Inherited Init;
  Field := -1;
end;

Constructor TMyobject.Load (Var Stream : TStream);

begin
  Stream.Read(Field, Sizeof(Field));
end;

Destructor TMyObject.Done;

begin
end;

Function TMyObject.GetField : Longint;

begin
  GetField := Field;
end;

Procedure TMyObject.SetField (Value : Longint);

begin
  Field := Value;
end;

Procedure TMyObject.Store (Var Stream : TStream);

begin
  Stream.Write(Field, SizeOf(Field));
end;

Const MyObjectRec : TStreamRec = (
  Objtype : 666;
  vmtlink : Ofs(TypeOf(TMyObject)^);
  Load : @TMyObject.Load;
  Store : @TMyObject.Store;
);

begin
  RegisterObjects;

```

```
RegisterType (MyObjectRec);
end.
```

67.4.16 SetStr

Synopsis: Allocate a copy of a shortstring on the heap.

Declaration: `procedure SetStr(var p: PString; const s: string)`

Visibility: default

Description: `SetStr` makes a copy of the string `s` on the heap and returns the pointer to this copy in `p`. If `p` pointed to another string (i.e. was not `Nil`, the memory is released first. Contrary to `NewStr` (1032), if the string is empty then a pointer to an empty string is returned.

The allocated memory is not based on the declared size of the string passed to `NewStr`, but is based on the actual length of the string.

Errors: If not enough memory is available, an 'out of memory' error will occur.

See also: `DisposeStr` (1031), `NewStr` (1032)

67.5 TBufStream

67.5.1 Description

`TBufStream` implements a buffered file stream. That is, all data written to the stream is written to memory first. Only when the buffer is full, or on explicit request, the data is written to disk.

Also, when reading from the stream, first the buffer is checked if there is any unread data in it. If so, this is read first. If not the buffer is filled again, and then the data is read from the buffer.

The size of the buffer is fixed and is set when constructing the file.

This is useful if you need heavy throughput for your stream, because it speeds up operations.

67.5.2 Method overview

Page	Method	Description
1036	<code>Close</code>	Flush data and Close the file.
1036	<code>Done</code>	Close the file and cleans up the instance.
1036	<code>Flush</code>	FLush data from buffer, and write it to stream.
1035	<code>Init</code>	Initialize an instance of <code>TBufStream</code> and open the file.
1038	<code>Open</code>	Open the file if it is closed.
1038	<code>Read</code>	Read data from the file to a buffer in memory.
1037	<code>Seek</code>	Set current position in file.
1037	<code>Truncate</code>	Flush buffer, and truncate the file at current position.
1038	<code>Write</code>	Write data to the file from a buffer in memory.

67.5.3 TBufStream.Init

Synopsis: Initialize an instance of `TBufStream` and open the file.

Declaration: `constructor Init(FileName: FNameStr; Mode: Word; Size: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TBufStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

`stCreate`Creates a new file.

`stOpenRead`Read access only.

`stOpenWrite`Write access only.

`stOpen`Read and write access.

The `Size` parameter determines the size of the buffer that will be created. It should be different from zero.

For an example see `TBufStream.Flush` (1036).

Errors: On error, `Status` is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Init` (1054), `TBufStream.Done` (1036)

67.5.4 TBufStream.Done

Synopsis: Close the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` flushes and closes the file if it was open and cleans up the instance of `TBufStream`.

For an example see `TBufStream.Flush` (1036).

Errors: None.

See also: `TDosStream.Done` (1054), `TBufStream.Init` (1035), `TBufStream.Close` (1036)

67.5.5 TBufStream.Close

Synopsis: Flush data and Close the file.

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` flushes and closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (1036) it does not clean up the instance of `TBufStream`

For an example see `TBufStream.Flush` (1036).

Errors: None.

See also: `TStream.Close` (1084), `TBufStream.Init` (1035), `TBufStream.Done` (1036)

67.5.6 TBufStream.Flush

Synopsis: Flush data from buffer, and write it to stream.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: When the stream is in write mode, the contents of the buffer are written to disk, and the buffer position is set to zero. When the stream is in read mode, the buffer position is set to zero.

Errors: Write errors may occur if the file was in write mode. see Write (1038) for more info on the errors.

See also: TStream.Close (1084), TBufStream.Init (1035), TBufStream.Done (1036)

Listing: ./objectex/ex15.pp

Program ex15;

{ Program to demonstrate the TStream.Flush method }

Uses Objects;

Var L : String;
 P : PString;
 S : TBufStream; *{ Only one with Flush implemented. }*

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(TBufStream, Init('test.dat', stcreate, 100));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
{ At this moment, there is no data on disk yet. }
S^.Flush;
{ Now there is. }
S^.WriteStr(@L);
{ Close calls flush first }
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);
end.
```

67.5.7 TBufStream.Truncate

Synopsis: Flush buffer, and truncate the file at current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: If the status of the stream is stOK, then Truncate tries to flush the buffer, and then truncates the stream size to the current file position.

For an example, see TDosStream.Truncate (1055).

Errors: Errors can be those of Flush (1036) or TDosStream.Truncate (1055).

See also: TStream.Truncate (1085), TDosStream.Truncate (1055), TStream.GetSize (1082)

67.5.8 TBufStream.Seek

Synopsis: Set current position in file.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

For an example, see `TStream.Seek` (1086);

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` (1086), `TStream.GetPos` (1082)

67.5.9 TBufStream.Open

Synopsis: Open the file if it is closed.

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (1036) call.

For an example, see `TDosStream.Open` (1057).

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (1084), `TBufStream.Close` (1036)

67.5.10 TBufStream.Read

Synopsis: Read data from the file to a buffer in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

`Read` will first try to read the data from the stream's internal buffer. If insufficient data is available, the buffer will be filled before continuing to read. This process is repeated until all needed data has been read.

For an example, see `TStream.Read` (1087).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (1087), `TBufStream.Write` (1038)

67.5.11 TBufStream.Write

Synopsis: Write data to the file from a buffer in memory.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

`Write` will first try to write the data to the stream's internal buffer. When the internal buffer is full, then the contents will be written to disk. This process is repeated until all data has been written.

For an example, see `TStream.Read` (1087).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` (1087), `TBufStream.Read` (1038)

67.6 TCollection

67.6.1 Description

The `TCollection` object manages a collection of pointers or objects. It also provides a series of methods to manipulate these pointers or objects.

Whether or not objects are used depends on the kind of calls you use. All kinds come in 2 flavors, one for objects, one for pointers.

67.6.2 Method overview

Page	Method	Description
1041	<code>At</code>	Return the item at a certain index.
1050	<code>AtDelete</code>	Delete item at certain position.
1049	<code>AtFree</code>	Free an item at the indicates position, calling it's destructor.
1052	<code>AtInsert</code>	Insert an element at a certain position in the collection.
1052	<code>AtPut</code>	Set collection item, overwriting an existing value.
1048	<code>Delete</code>	Delete an item from the collection, but does not destroy it.
1046	<code>DeleteAll</code>	Delete all elements from the collection. Objects are not destroyed.
1041	<code>Done</code>	Clean up collection, release all memory.
1051	<code>Error</code>	Set error code.
1044	<code>FirstThat</code>	Return first item which matches a test.
1050	<code>ForEach</code>	Execute procedure for each item in the list.
1047	<code>Free</code>	Free item from collection, calling it's destructor.
1045	<code>FreeAll</code>	Release all objects from the collection.
1049	<code>FreeItem</code>	Destroy a non-nil item.
1042	<code>GetItem</code>	Read one item off the stream.
1042	<code>IndexOf</code>	Find the position of a certain item.
1039	<code>Init</code>	Instantiate a new collection.
1048	<code>Insert</code>	Insert a new item in the collection at the end.
1043	<code>LastThat</code>	Return last item which matches a test.
1040	<code>Load</code>	Initialize a new collection and load collection from a stream.
1044	<code>Pack</code>	Remove all <code>>Nil</code> pointers from the collection.
1053	<code>PutItem</code>	Put one item on the stream
1051	<code>SetLimit</code>	Set maximum number of elements in the collection.
1053	<code>Store</code>	Write collection to a stream.

67.6.3 TCollection.Init

Synopsis: Instantiate a new collection.

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` initializes a new instance of a collection. It sets the (initial) maximum number of items in the collection to `ALimit`. `ADelta` is the increase size : The number of memory places that will be allocated in case `ALimit` is reached, and another element is added to the collection.

For an example, see `TCollection.ForEach` ([1050](#)).

Errors: None.

See also: `TCollection.Load` ([1040](#)), `TCollection.Done` ([1041](#))

67.6.4 TCollection.Load

Synopsis: Initialize a new collection and load collection from a stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` initializes a new instance of a collection. It reads from stream `S` the item count, the item limit count, and the increase size. After that, it reads the specified number of items from the stream.

Errors: Errors returned can be those of `GetItem` ([1042](#)).

See also: `TCollection.Init` ([1039](#)), `TCollection.GetItem` ([1042](#)), `TCollection.Done` ([1041](#))

Listing: `./objectex/ex22.pp`

```

Program ex22;

{ Program to demonstrate the TCollection.Load method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
    M : PMyObject;
    I : Longint;
    S : PMemoryStream;

begin
  C:=New( PCollection , Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject , Init );
      M^. SetField(100-I);
      C^. Insert (M);
    end;
  WriteLn ( 'Inserted ', C^.Count, ' objects ');
  S:=New( PMemoryStream, Init(1000,10));
  C^. Store (S^);
  C^. FreeAll;
  // Dispose (C, Done);
  S^. Seek (0);

```

```

C^.Load(S^);
WriteLn ('Read ',C^.Count, ' objects from stream. ');
Dispose(S,Done);
Dispose(C,Done);
end.

```

67.6.5 TCollection.Done

Synopsis: Clean up collection, release all memory.

Declaration: destructor Done; Virtual

Visibility: default

Description: Done frees all objects in the collection, and then releases all memory occupied by the instance.

For an example, see TCollection.ForEach ([1050](#)).

Errors: None.

See also: TCollection.Init ([1039](#)), TCollection.FreeAll ([1045](#))

67.6.6 TCollection.At

Synopsis: Return the item at a certain index.

Declaration: function At(Index: Sw_Integer) : Pointer

Visibility: default

Description: At returns the item at position Index.

Errors: If Index is less than zero or larger than the number of items in the collection, seepl{Error}{TCollection.Error} is called with coIndexError and Index as arguments, resulting in a run-time error.

See also: TCollection.Insert ([1048](#))

Listing: ./objectex/ex23.pp

Program ex23;

{ Program to demonstrate the TCollection.At method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M : PMyObject;
I : Longint;

begin

C:=New(PCollection,Init(100,10));

For I:=1 **to** 100 **do**

begin

M:=New(PMyObject,Init);

M^.SetField(100-I);

C^.Insert(M);

end;

For I:=0 **to** C^.Count-1 **do**

```

begin
M:=C^.At(I);
Writeln ('Object ',i,' has field : ',M^.GetField);
end;
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.7 TCollection.IndexOf

Synopsis: Find the position of a certain item.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. If `Item` isn't present in the collection, -1 is returned.

Errors: If the item is not present, -1 is returned.

See also: `TCollection.At` ([1041](#)), `TCollection.GetItem` ([1042](#)), `TCollection.Insert` ([1048](#))

Listing: ./objectex/ex24.pp

Program ex24;

{ Program to demonstrate the TCollection.IndexOf method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
M,Keep : PMyObject;
I : Longint;

```

begin
Randomize;
C:=New(PCollection,Init(100,10));
Keep:=Nil;
For I:=1 to 100 do
begin
M:=New(PMyObject,Init);
M^.SetField(I-1);
If Random<0.1 then
Keep:=M;
C^.Insert(M);
end;
If Keep=Nil then
begin
Writeln ('Please run again. No object selected');
Halt(1);
end;
Writeln ('Selected object has field : ',Keep^.GetField);
Write ('Selected object has index : ',C^.IndexOf(Keep));
Writeln (' should match it's field. ');
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.8 TCollection.GetItem

Synopsis: Read one item off the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a single item off the stream `S`, and returns a pointer to this item. This method is used internally by the `Load` method, and should not be used directly.

Errors: Possible errors are the ones from `TStream.Get` ([1080](#)).

See also: `TStream.Get` ([1080](#)), `TCollection.Store` ([1053](#))

67.6.9 TCollection.LastThat

Synopsis: Return last item which matches a test.

Declaration: `function LastThat(Test: CodePointer) : Pointer`

Visibility: default

Description: This function returns the last item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.FirstThat` ([1044](#))

Listing: `./objectex/ex25.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.Foreach method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C : PCollection`;
 `M : PMyObject`;
 `I : Longint`;

Function `CheckField (Dummy: Pointer; P : PMyObject) : Longint`;

begin
 if `P^.GetField < 56` **then**
 `Checkfield := 1`
 else
 `CheckField := 0`;
end;

begin
 `C := New(PCollection, Init(100, 10));`
 for `I := 1 to 100` **do**
 begin
 `M := New(PMyObject, Init);`
 `M^.SetField(I);`
 `C^.Insert(M);`
 end;
 Writeln ('Inserted ', `C^.Count`, ' objects ');

```

WriteLn ( 'Last one for which Field<56 has index (should be 54) : ',
          C^.IndexOf(C^.LastThat(@CheckField)));
C^.FreeAll;
Dispose(C,Done);
end.

```

67.6.10 TCollection.FirstThat

Synopsis: Return first item which matches a test.

Declaration: `function FirstThat(Test: CodePointer) : Pointer`

Visibility: default

Description: This function returns the first item in the collection for which `Test` returns a non-nil result. `Test` is a function that accepts 1 argument: a pointer to an object, and that returns a pointer as a result.

Errors: None.

See also: `TCollection.LastThat` ([1043](#))

Listing: ./objectex/ex26.pp

Program ex21;

{ Program to demonstrate the TCollection.FirstThat method }

Uses Objects,MyObject; *{ For TMyObject definition and registration }*

Var C : PCollection;
 M : PMyObject;
 I : Longint;

Function CheckField (Dummy: Pointer;P : PMyObject) : Longint;

begin

If P^.GetField>56 **then**
 Checkfield:=1

else
 CheckField:=0;

end;

begin

 C:=**New**(PCollection,Init(100,10));

For I:=1 **to** 100 **do**

begin

 M:=**New**(PMyObject,Init);

 M^.SetField(I);

 C^.Insert(M);

end;

WriteLn ('Inserted ',C^.Count,' objects');

WriteLn ('first one for which Field>56 has index (should be 56) : ',
 C^.IndexOf(C^.FirstThat(@CheckField)));

 C^.FreeAll;

Dispose(C,Done);

end.

67.6.11 TCollection.Pack

Synopsis: Remove all >Nil pointers from the collection.

Declaration: `procedure Pack`

Visibility: default

Description: `Pack` removes all `Nil` pointers from the collection, and adjusts `Count` to reflect this change. No memory is freed as a result of this call. In order to free any memory, you can call `SetLimit` with an argument of `Count` after a call to `Pack`.

Errors: None.

See also: `TCollection.SetLimit` ([1051](#))

Listing: `./objectex/ex26.pp`

Program `ex21`;

{ Program to demonstrate the TCollection.FirstThat method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

Function `CheckField` (`Dummy`: `Pointer`; `P` : `PMMyObject`) : `Longint`;

begin
 If `P^.GetField > 56` **then**
 `Checkfield := 1`
 else
 `CheckField := 0`;
end;

begin
 `C := New(PCollection, Init(100, 10));`
 For `I := 1` **to** `100` **do**
 begin
 `M := New(PMyObject, Init);`
 `M^.SetField(I);`
 `C^.Insert(M);`
 end;
 WriteLn ('Inserted ', `C^.Count`, ' objects');
 WriteLn ('first one for which Field > 56 has index (should be 56) : ',
 `C^.IndexOf(C^.FirstThat(@CheckField))`);
 `C^.FreeAll`;
 Dispose(`C`, `Done`);
end.

67.6.12 TCollection.FreeAll

Synopsis: Release all objects from the collection.

Declaration: `procedure FreeAll`

Visibility: default

Description: `FreeAll` calls the destructor of each object in the collection. It doesn't release any memory occupied by the collection itself, but it does set `Count` to zero.

See also: `TCollection.DeleteAll` ([1046](#)), `TCollection.FreeItem` ([1049](#))

Listing: `./objectex/ex28.pp`

Program `ex28`;

{ Program to demonstrate the TCollection.FreeAll method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New(PCollection, Init(120,10));`
 For `I:=1 to 100 do`
 begin
 `M:=New(PMyObject, Init);`
 `M^.SetField(I-1);`
 `C^.Insert(M);`
 end;
 WriteLn ('Added 100 Items.');
 `C^.FreeAll`;
 WriteLn ('Freed all objects.');
 Dispose(`C`, `Done`);
end.

67.6.13 TCollection.DeleteAll

Synopsis: Delete all elements from the collection. Objects are not destroyed.

Declaration: `procedure DeleteAll`

Visibility: `default`

Description: `DeleteAll` deletes all elements from the collection. It just sets the `Count` variable to zero. Contrary to `FreeAll` ([1045](#)), `DeleteAll` doesn't call the destructor of the objects.

Errors: None.

See also: `TCollection.FreeAll` ([1045](#)), `TCollection.Delete` ([1048](#))

Listing: `./objectex/ex29.pp`

Program `ex29`;

{
 Program to demonstrate the TCollection.DeleteAll method
 Compare with example 28, where FreeAll is used.
}

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

```

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  C^.DeleteAll;
  WriteLn ('Deleted all objects. ');
  Dispose(C,Done);
end.

```

67.6.14 TCollection.Free

Synopsis: Free item from collection, calling it's destructor.

Declaration: `procedure Free(Item: Pointer)`

Visibility: default

Description: `Free` Deletes `Item` from the collection, and calls the destructor `Done` of the object.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.FreeItem` ([1049](#))

Listing: ./objectex/ex30.pp

```

Program ex30;

{ Program to demonstrate the TCollection.Free method }

Uses Objects,MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  WriteLn ('Added 100 Items. ');
  With C^ do
    While Count>0 do Free(At(Count-1));
  WriteLn ('Freed all objects. ');

```

```
Dispose (C, Done);
end.
```

67.6.15 TCollection.Insert

Synopsis: Insert a new item in the collection at the end.

Declaration: `procedure Insert (Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts `Item` in the collection. `TCollection` inserts this item at the end, but descendent objects may insert it at another place.

Errors: None.

See also: `TCollection.AtInsert` ([1052](#)), `TCollection.AtPut` ([1052](#))

67.6.16 TCollection.Delete

Synopsis: Delete an item from the collection, but does not destroy it.

Declaration: `procedure Delete (Item: Pointer)`

Visibility: default

Description: `Delete` deletes `Item` from the collection. It doesn't call the item's destructor, though. For this the `Free` ([1047](#)) call is provided.

Errors: If the `Item` is not in the collection, `Error` will be called with `coIndexError`.

See also: `TCollection.AtDelete` ([1050](#)), `TCollection.Free` ([1047](#))

Listing: `./objectex/ex31.pp`

Program `ex31`;

{ Program to demonstrate the TCollection.Delete method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New`(`PCollection`, `Init`(120,10));
 For `I:=1` **to** 100 **do**
 begin
 `M:=New`(`PMMyObject`, `Init`);
 `M^.SetField`(`I-1`);
 `C^.Insert`(`M`);
 end;
 WriteLn ('Added 100 Items.');
 With `C^` **do**
 While `Count>0` **do** `Delete`(`At`(`Count-1`));
 WriteLn ('Freed all objects');
end

```

    Dispose(C, Done);
end.

```

67.6.17 TCollection.AtFree

Synopsis: Free an item at the indicates position, calling it's destructor.

Declaration: `procedure AtFree(Index: Sw_Integer)`

Visibility: default

Description: `AtFree` deletes the item at position `Index` in the collection, and calls the item's destructor if it is not `Nil`.

Errors: If `Index` isn't valid then `Error (1051)` is called with `CoIndexError`.

See also: `TCollection.Free (1047)`, `TCollection.AtDelete (1050)`

Listing: `./objectex/ex32.pp`

Program `ex32;`

{ Program to demonstrate the TCollection.AtFree method }

Uses `Objects, MyObject; { For TMyObject definition and registration }`

Var `C : PCollection;`
 `M : PMyObject;`
 `I : Longint;`

```

begin
  Randomize;
  C:=New(PCollection, Init(120,10));
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(I-1);
      C^.Insert(M);
    end;
  Writeln ('Added 100 Items');
  With C^ do
    While Count>0 do AtFree(Count-1);
  Writeln ('Freed all objects. ');
  Dispose(C, Done);
end.

```

67.6.18 TCollection.FreeItem

Synopsis: Destroy a non-nil item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` calls the destructor of `Item` if it is not nil.

Remark: This function is used internally by the `TCollection` object, and should not be called directly.

Errors: None.

See also: `TCollection.Free` ([1047](#)), `TCollection.AtFree` ([1049](#))

67.6.19 TCollection.AtDelete

Synopsis: Delete item at certain position.

Declaration: `procedure AtDelete(Index: Sw_Integer)`

Visibility: default

Description: `AtDelete` deletes the pointer at position `Index` in the collection. It doesn't call the object's destructor.

Errors: If `Index` isn't valid then `Error` ([1051](#)) is called with `CoIndexError`.

See also: `TCollection.Delete` ([1048](#))

Listing: `./objectex/ex33.pp`

Program `ex33`;

{ Program to demonstrate the TCollection.AtDelete method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C` : `PCollection`;
 `M` : `PMMyObject`;
 `I` : `Longint`;

begin
 Randomize;
 `C:=New(PCollection, Init(120,10));`
 For `I:=1 to 100 do`
 begin
 `M:=New(PMyObject, Init);`
 `M^.SetField(I-1);`
 `C^.Insert(M);`
 end;
 WriteLn ('Added 100 Items.');
 With `C^ do`
 While `Count>0 do AtDelete(Count-1);`
 WriteLn ('Freed all objects.');
 Dispose(`C`, `Done`);
end.

67.6.20 TCollection.ForEach

Synopsis: Execute procedure for each item in the list.

Declaration: `procedure ForEach(Action: CodePointer)`

Visibility: default

Description: `ForEach` calls `Action` for each element in the collection, and passes the element as an argument to `Action`.

`Action` is a procedural type variable that accepts a pointer as an argument.

Errors: None.

See also: `TCollection.FirstThat` ([1044](#)), `TCollection.LastThat` ([1043](#))

Listing: `./objectex/ex21.pp`

```

Program ex21;

  { Program to demonstrate the TCollection.Foreach method }

Uses Objects, MyObject; { For TMyObject definition and registration }

Var C : PCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  C:=New( PCollection, Init(100,10));
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField(100-I);
      C^.Insert(M);
    end;
    Writeln ( 'Inserted ', C^.Count, ' objects ' );
    C^.ForEach( @PrintField );
    C^.FreeAll;
    Dispose(C, Done);
end.

```

67.6.21 TCollection.SetLimit

Synopsis: Set maximum number of elements in the collection.

Declaration: `procedure SetLimit(ALimit: Sw_Integer); Virtual`

Visibility: default

Description: `SetLimit` sets the maximum number of elements in the collection. `ALimit` must not be less than `Count`, and should not be larger than `MaxCollectionSize`

For an example, see `Pack` ([1044](#)).

Errors: None.

See also: `TCollection.Init` ([1039](#))

67.6.22 TCollection.Error

Synopsis: Set error code.

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` is called by the various `TCollection` methods in case of an error condition. The default behaviour is to make a call to `RunError` with an error of 212-Code.

This method can be overridden by descendent objects to implement a different error-handling.

See also: Abstract ([1028](#))

67.6.23 TCollection.AtPut

Synopsis: Set collection item, overwriting an existing value.

Declaration: `procedure AtPut (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtPut` sets the element at position `Index` in the collection to `Item`. Any previous value is overwritten.

For an example, see `Pack` ([1044](#)).

Errors: If `Index` isn't valid then `Error` ([1051](#)) is called with `CoIndexError`.

67.6.24 TCollection.AtInsert

Synopsis: Insert an element at a certain position in the collection.

Declaration: `procedure AtInsert (Index: Sw_Integer; Item: Pointer)`

Visibility: default

Description: `AtInsert` inserts `Item` in the collection at position `Index`, shifting all elements by one position. In case the current limit is reached, the collection will try to expand with a call to `SetLimit`

Errors: If `Index` isn't valid then `Error` ([1051](#)) is called with `CoIndexError`. If the collection fails to expand, then `coOverflow` is passed to `Error`.

See also: `TCollection.Insert` ([1048](#))

Listing: `./objectex/ex34.pp`

Program `ex34`;

{ Program to demonstrate the TCollection.AtInsert method }

Uses `Objects, MyObject`; *{ For TMyObject definition and registration }*

Var `C : PCollection`;
`M : PMyObject`;
`I : Longint`;

Procedure `PrintField` (`Dummy: Pointer`; `P : PMyObject`);

begin
`WriteLn ('Field : ', P^.GetField);`
end;

begin

```

Randomize;
C:=New(PCollection, Init(120,10));
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    M:=New(PMyObject, Init);
    M^.SetField(I-1);
    If I=1 then
      C^.Insert(M)
    else
      With C^ do
        AtInsert(Random(Count),M);
      end;
    WriteLn ('Values : ');
    C^.Foreach(@PrintField);
    Dispose(C,Done);
  end.

```

67.6.25 TCollection.Store

Synopsis: Write collection to a stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by writing the current `Count`, `Limit` and `Delta` to the stream, and then writing each item to the stream.

The contents of the stream are then suitable for instantiating another collection with `Load` (1040).

For an example, see `TCollection.Load` (1040).

Errors: Errors returned are those by `TStream.Put` (1085).

See also: `TCollection.Load` (1040), `TCollection.PutItem` (1053)

67.6.26 TCollection.PutItem

Synopsis: Put one item on the stream

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to stream `S`. This method is used internally by the `TCollection` object, and should not be called directly.

Errors: Errors are those returned by `TStream.Put` (1085).

See also: `Store` (1053), `GetItem` (1042)

67.7 TDosStream

67.7.1 Description

`TDosStream` is a stream that stores its contents in a file. it overrides a couple of methods of `TStream` (1080) for this.

In addition to the fields inherited from `TStream` (see `TStream` (1080)), there are some extra fields, that describe the file. (mainly the name and the OS file handle)

No buffering in memory is done when using `TDosStream`. All data are written directly to the file. For a stream that buffers in memory, see `TBufStream` (1035).

67.7.2 Method overview

Page	Method	Description
1055	<code>Close</code>	Close the file.
1054	<code>Done</code>	Closes the file and cleans up the instance.
1054	<code>Init</code>	Instantiate a new instance of <code>TDosStream</code> .
1057	<code>Open</code>	Open the file stream
1057	<code>Read</code>	Read data from the stream to a buffer.
1056	<code>Seek</code>	Set file position.
1055	<code>Truncate</code>	Truncate the file on the current position.
1058	<code>Write</code>	Write data from a buffer to the stream.

67.7.3 TDosStream.Init

Synopsis: Instantiate a new instance of `TDosStream`.

Declaration: `constructor Init (FileName: FNameStr; Mode: Word)`

Visibility: default

Description: `Init` instantiates an instance of `TDosStream`. The name of the file that contains (or will contain) the data of the stream is given in `FileName`. The `Mode` parameter determines whether a new file should be created and what access rights you have on the file. It can be one of the following constants:

stCreateCreates a new file.

stOpenReadRead access only.

stOpenWriteWrite access only.

stOpenRead and write access.

For an example, see `TDosStream.Truncate` (1055).

Errors: On error, `Status` (??) is set to `stInitError`, and `ErrorInfo` is set to the dos error code.

See also: `TDosStream.Done` (1054)

67.7.4 TDosStream.Done

Synopsis: Closes the file and cleans up the instance.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` closes the file if it was open and cleans up the instance of `TDosStream`.
for an example, see e.g. `TDosStream.Truncate` (1055).

Errors: None.

See also: `TDosStream.Init` (1054), `TDosStream.Close` (1055)

67.7.5 TDosStream.Close

Synopsis: Close the file.

Declaration: `procedure Close; Virtual`

Visibility: `default`

Description: `Close` closes the file if it was open, and sets `Handle` to -1. Contrary to `Done` (1054) it does not clean up the instance of `TDosStream`

For an example, see `TDosStream.Open` (1057).

Errors: None.

See also: `TStream.Close` (1084), `TDosStream.Init` (1054), `TDosStream.Done` (1054)

67.7.6 TDosStream.Truncate

Synopsis: Truncate the file on the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: If the status of the stream is `stOK`, then `Truncate` tries to truncate the stream size to the current file position.

Errors: If an error occurs, the stream's status is set to `stError` and `ErrorInfo` is set to the OS error code.

See also: `TStream.Truncate` (1085), `TStream.GetSize` (1082)

Listing: `./objectex/ex16.pp`

```

Program ex16;

{ Program to demonstrate the TStream.Truncate method }

Uses Objects;

Var L : String;
    P : PString;
    S : PDosStream; { Only one with Truncate implemented. }

begin
  L := 'Some constant string';
  { Buffer size of 100 }
  S := New(PDosStream, Init('test.dat', stcreate));
  Writeln ('Writing "', L, '" to stream with handle ', S^.Handle);
  S^.WriteStr(@L);
  S^.WriteStr(@L);
  { Close calls flush first }
  S^.Close;
  S^.Open (stOpen);
  Writeln ('Size of stream is : ', S^.GetSize);
  P := S^.ReadStr;
  L := P^;
  DisposeStr(P);
  Writeln ('Read "', L, '" from stream with handle ', S^.Handle);

```

```

S^.Truncate;
Writeln ('Truncated stream. Size is : ',S^.GetSize);
S^.Close;
Dispose (S,Done);
end.

```

67.7.7 TDosStream.Seek

Synopsis: Set file position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, then `Seek` sets the file position to `Pos`. `Pos` is a zero-based offset, counted from the beginning of the file.

Errors: In case an error occurs, the stream's status is set to `stSeekError`, and the OS error code is stored in `ErrorInfo`.

See also: `TStream.Seek` ([1086](#)), `TStream.GetPos` ([1082](#))

Listing: `./objectex/ex17.pp`

Program `ex17;`

{ Program to demonstrate the TStream.Seek method }

Uses `Objects;`

Var `L : String;`
 `Marker : Word;`
 `P : PString;`
 `S : PDosStream;`

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PDosStream, Init('test.dat', stcreate));
Writeln ('Writing "',L,'" to stream. ');
S^.WriteStr(@L);
Marker:=S^.GetPos;
Writeln ('Set marker at ',Marker);
L:= 'Some other constant String';
Writeln ('Writing "',L,'" to stream. ');
S^.WriteStr(@L);
S^.Close;
S^.Open (stOpenRead);
Writeln ('Size of stream is : ',S^.GetSize);
Writeln ('Seeking to marker');
S^.Seek(Marker);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
Writeln ('Read "',L,'" from stream. ');
S^.Close;
Dispose (S,Done);
end.

```

67.7.8 TDosStream.Open

Synopsis: Open the file stream

Declaration: `procedure Open (OpenMode: Word); Virtual`

Visibility: default

Description: If the stream's status is `stOK`, and the stream is closed then `Open` re-opens the file stream with mode `OpenMode`. This call can be used after a `Close` (1055) call.

Errors: If an error occurs when re-opening the file, then `Status` is set to `stOpenError`, and the OS error code is stored in `ErrorInfo`

See also: `TStream.Open` (1084), `TDosStream.Close` (1055)

Listing: `./objectex/ex14.pp`

Program `ex14;`

{ Program to demonstrate the TStream.Close method }

Uses `Objects;`

Var `L : String;`
 `P : PString;`
 `S : PDosStream; { Only one with Close implemented. }`

begin

```

L:= 'Some constant string';
S:=New(PDosStream, Init('test.dat', stcreate));
WriteLn ('Writing "', L, '" to stream with handle ', S^.Handle);
S^.WriteStr(@L);
S^.Close;
WriteLn ('Closed stream. File handle is ', S^.Handle);
S^.Open (stOpenRead);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
WriteLn ('Read "', L, '" from stream with handle ', S^.Handle);
S^.Close;
Dispose (S, Done);

```

end.

67.7.9 TDosStream.Read

Synopsis: Read data from the stream to a buffer.

Declaration: `procedure Read (var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Read` will read `Count` bytes from the stream and place them in `Buf`.

For an example, see `TStream.Read` (1087).

Errors: In case of an error, `Status` is set to `StReadError`, and `ErrorInfo` gets the OS specific error, or 0 when an attempt was made to read beyond the end of the stream.

See also: `TStream.Read` (1087), `TDosStream.Write` (1058)

67.7.10 TDosStream.Write

Synopsis: Write data from a buffer to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: If the Stream is open and the stream status is `stOK` then `Write` will write `Count` bytes from `Buf` and place them in the stream.

For an example, see `TStream.Read` ([1087](#)).

Errors: In case of an error, `Status` is set to `StWriteError`, and `ErrorInfo` gets the OS specific error.

See also: `TStream.Write` ([1087](#)), `TDosStream.Read` ([1057](#))

67.8 TMemoryStream

67.8.1 Description

The `TMemoryStream` object implements a stream that stores its data in memory. The data is stored on the heap, with the possibility to specify the maximum amount of data, and the size of the memory blocks being used.

See also: `TStream` ([1080](#))

67.8.2 Method overview

Page	Method	Description
1059	<code>Done</code>	Clean up memory and destroy the object instance.
1058	<code>Init</code>	Initialize memory stream, reserves memory for stream data.
1060	<code>Read</code>	Read data from the stream to a location in memory.
1059	<code>Truncate</code>	Set the stream size to the current position.
1060	<code>Write</code>	Write data to the stream.

67.8.3 TMemoryStream.Init

Synopsis: Initialize memory stream, reserves memory for stream data.

Declaration: `constructor Init(ALimit: LongInt; ABlockSize: Word)`

Visibility: default

Description: `Init` instantiates a new `TMemoryStream` object. The `memorystreamobject` will initially allocate at least `ALimit` bytes memory, divided into memory blocks of size `ABlockSize`. The number of blocks needed to get to `ALimit` bytes is rounded up.

By default, the number of blocks is 1, and the size of a block is 8192. This is selected if you specify 0 as the blocksize.

For an example, see e.g. `TStream.CopyFrom` ([1088](#)).

Errors: If the stream cannot allocate the initial memory needed for the memory blocks, then the stream's status is set to `stInitError`.

See also: `TMemoryStream.Done` ([1059](#))

67.8.4 TMemoryStream.Done

Synopsis: Clean up memory and destroy the object instance.

Declaration: `destructor Done; Virtual`

Visibility: `default`

Description: `Done` releases the memory blocks used by the stream, and then cleans up the memory used by the stream object itself.

For an example, see e.g `TStream.CopyFrom` ([1088](#)).

Errors: `None`.

See also: `TMemoryStream.Init` ([1058](#))

67.8.5 TMemoryStream.Truncate

Synopsis: Set the stream size to the current position.

Declaration: `procedure Truncate; Virtual`

Visibility: `default`

Description: `Truncate` sets the size of the memory stream equal to the current position. It de-allocates any memory-blocks that are no longer needed, so that the new size of the stream is the current position in the stream, rounded up to the first multiple of the stream blocksize.

Errors: If an error occurs during memory de-allocation, the stream's status is set to `stError`

See also: `TStream.Truncate` ([1085](#))

Listing: `./objectex/ex20.pp`

Program `ex20;`

{ Program to demonstrate the TMemoryStream.Truncate method }

Uses `Objects;`

Var `L : String;`
`P : PString;`
`S : PMemoryStream;`
`I : Longint;`

begin

```

L:= 'Some constant string';
{ Buffer size of 100 }
S:=New(PMemoryStream, Init(1000,100));
Writeln ( 'Writing 100 times "',L,'" to stream.' );
For I:=1 to 100 do
  S^. WriteStr(@L);
Writeln ( 'Finished.' );
S^.Seek(100);
S^.Truncate;
Writeln ( 'Truncated at byte 100.' );
Dispose (S,Done);
Writeln ( 'Finished.' );

```

end.

67.8.6 TMemoryStream.Read

Synopsis: Read data from the stream to a location in memory.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read reads Count bytes from the stream to Buf. It updates the position of the stream.

For an example, see TStream.Read (1087).

Errors: If there is not enough data available, no data is read, and the stream's status is set to `stReadError`.

See also: TStream.Read (1087), TMemoryStream.Write (1060)

67.8.7 TMemoryStream.Write

Synopsis: Write data to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write copies Count bytes from Buf to the stream. It updates the position of the stream.

If not enough memory is available to hold the extra Count bytes, then the stream will try to expand, by allocating as much blocks with size `BlkSize` (as specified in the constructor call `Init` (1058)) as needed.

For an example, see TStream.Read (1087).

Errors: If the stream cannot allocate more memory, then the status is set to `stWriteError`

See also: TStream.Write (1087), TMemoryStream.Read (1060)

67.9 TObject

67.9.1 Description

This type serves as the basic object for all other objects in the Objects unit.

67.9.2 Method overview

Page	Method	Description
1062	Done	Destroy an object.
1061	Free	Destroy an object and release all memory.
1060	Init	Construct (initialize) a new object
1061	Is_Object	Check whether a pointer points to an object.

67.9.3 TObject.Init

Synopsis: Construct (initialize) a new object

Declaration: `constructor Init`

Visibility: default

Description: Instantiates a new object of type `TObject`. It fills the instance up with Zero bytes.

For an example, see `Free` (1061)

Errors: None.

See also: `TObject.Free` (1061), `TObject.Done` (1062)

67.9.4 TObject.Free

Synopsis: Destroy an object and release all memory.

Declaration: `procedure Free`

Visibility: default

Description: `Free` calls the destructor of the object, and releases the memory occupied by the instance of the object.

Errors: No checking is performed to see whether `self` is `nil` and whether the object is indeed allocated on the heap.

See also: `TObject.Init` (1060), `TObject.Done` (1062)

Listing: `./objectex/ex7.pp`

```

program ex7;

  { Program to demonstrate the TObject.Free call }

Uses Objects;

Var O : TObject;

begin
  // Allocate memory for object.
  O:=New(TObject, Init);
  // Free memory of object.
  O^.free;
end.

```

67.9.5 TObject.Is_Object

Synopsis: Check whether a pointer points to an object.

Declaration: `function Is_Object(P: Pointer) : Boolean`

Visibility: default

Description: `Is_Object` returns `True` if the pointer `P` points to an instance of a `TObject` descendent, it returns `false` otherwise.

67.9.6 TObject.Done

Synopsis: Destroy an object.

Declaration: destructor Done; Virtual

Visibility: default

Description: Done, the destructor of TObject does nothing. It is mainly intended to be used in the TObject.Free (1061) method.

The destructore Done does not free the memory occupied by the object.

Errors: None.

See also: TObject.Free (1061), TObject.Init (1060)

Listing: ./objectex/ex8.pp

```

program ex8;

  { Program to demonstrate the TObject.Done call }

Uses Objects;

Var O : PObject;

begin
  // Allocate memory for object.
  O:=New(PObject, Init);
  O^.Done;
end.

```

67.10 TPoint

67.10.1 Description

Record describing a point in a 2 dimensional plane.

67.11 TRect

67.11.1 Description

Describes a rectangular region in a plane.

67.11.2 Method overview

Page	Method	Description
1067	Assign	Set rectangle corners.
1064	Contains	Determine if a point is inside the rectangle
1064	Copy	Copy cornerpoints from another rectangle.
1063	Empty	Is the surface of the rectangle zero
1064	Equals	Do the corners of the rectangles match
1067	Grow	Expand rectangle with certain size.
1065	Intersect	Reduce rectangle to intersection with another rectangle
1066	Move	Move rectangle along a vector.
1065	Union	Enlarges rectangle to encompass another rectangle.

67.11.3 TRect.Empty

Synopsis: Is the surface of the rectangle zero

Declaration: `function Empty : Boolean`

Visibility: default

Description: `Empty` returns `True` if the rectangle defined by the corner points A, B has zero or negative surface.

Errors: None.

See also: `TRect.Equals` ([1064](#)), `TRect.Contains` ([1064](#))

Listing: `./objectex/ex1.pp`

Program `ex1`;

{ Program to demonstrate TRect.Empty }

Uses `objects`;

Var `ARect,BRect : TRect`;
 `P : TPoint`;

begin

With `ARect.A` **do**

begin

`X:=10`;

`Y:=10`;

end;

With `ARect.B` **do**

begin

`X:=20`;

`Y:=20`;

end;

{ Offset B by (5,5) }

With `BRect.A` **do**

begin

`X:=15`;

`Y:=15`;

end;

With `BRect.B` **do**

begin

`X:=25`;

`Y:=25`;

end;

{ Point }

With `P` **do**

begin

`X:=15`;

`Y:=15`;

end;

Writeln ('A empty : ',`ARect.Empty`);

Writeln ('B empty : ',`BRect.Empty`);

Writeln ('A Equals B : ',`ARect.Equals(BRect)`);

Writeln ('A Contains (15,15) : ',`ARect.Contains(P)`);

end.

67.11.4 TRect.Equals

Synopsis: Do the corners of the rectangles match

Declaration: `function Equals(R: TRect) : Boolean`

Visibility: default

Description: `Equals` returns `True` if the rectangle has the same corner points A, B as the rectangle R, and `False` otherwise.

For an example, see `TRect.Empty` (1063)

Errors: None.

See also: `TRect.Empty` (1063), `TRect.Contains` (1064)

67.11.5 TRect.Contains

Synopsis: Determine if a point is inside the rectangle

Declaration: `function Contains(P: TPoint) : Boolean`

Visibility: default

Description: `Contains` returns `True` if the point P is contained in the rectangle (including borders), `False` otherwise.

Errors: None.

See also: `TRect.Intersect` (1065), `TRect.Equals` (1064)

67.11.6 TRect.Copy

Synopsis: Copy cornerpoints from another rectangle.

Declaration: `procedure Copy(R: TRect)`

Visibility: default

Description: Assigns the rectangle R to the object. After the call to `Copy`, the rectangle R has been copied to the object that invoked `Copy`.

Errors: None.

See also: `TRect.Assign` (1067)

Listing: `./objectex/ex2.pp`

Program `ex2`;

{ Program to demonstrate TRect.Copy }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

`ARect.Assign(10,10,20,20);`

`BRect.Assign(15,15,25,25);`

```

CRect.Copy(ARect);
If ARect.Equals(CRect) Then
  Writeln ('ARect equals CRect')
Else
  Writeln ('ARect does not equal CRect !');
end.

```

67.11.7 TRect.Union

Synopsis: Enlarges rectangle to encompass another rectangle.

Declaration: `procedure Union(R: TRect)`

Visibility: default

Description: `Union` enlarges the current rectangle so that it becomes the union of the current rectangle with the rectangle `R`.

Errors: None.

See also: `TRect.Intersect` ([1065](#))

Listing: `./objectex/ex3.pp`

Program `ex3`;

{ Program to demonstrate TRect.Union }

Uses `objects`;

Var `ARect, BRect, CRect : TRect`;

begin

```

  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is union of ARect and BRect }

```

```

  CRect.Assign(10,10,25,25);
  { Calculate it explicitly }

```

```

  ARect.Union(BRect);

```

```

  If ARect.Equals(CRect) Then
    Writeln ('ARect equals CRect')

```

```

  Else

```

```

    Writeln ('ARect does not equal CRect !');

```

```

end.

```

67.11.8 TRect.Intersect

Synopsis: Reduce rectangle to intersection with another rectangle

Declaration: `procedure Intersect(R: TRect)`

Visibility: default

Description: `Intersect` makes the intersection of the current rectangle with `R`. If the intersection is empty, then the rectangle is set to the empty rectangle at coordinate (0,0).

Errors: None.

See also: `TRect.Union` ([1065](#))

Listing: ./objectex/ex4.pp

```

Program ex4;

{ Program to demonstrate TRect.Intersect }

Uses objects;

Var ARect, BRect, CRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  BRect.Assign(15,15,25,25);
  { CRect is intersection of ARect and BRect }
  CRect.Assign(15,15,20,20);
  { Calculate it explicitly }
  ARect.Intersect(BRect);
  If ARect.Equals(CRect) Then
    Writeln ( 'ARect equals CRect' )
  Else
    Writeln ( 'ARect does not equal CRect !' );
  BRect.Assign(25,25,30,30);
  ARect.Intersect(BRect);
  If ARect.Empty Then
    Writeln ( 'ARect is empty' );
end.

```

67.11.9 TRect.Move

Synopsis: Move rectangle along a vector.

Declaration: `procedure Move(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Move` moves the current rectangle along a vector with components (ADX, ADY). It adds ADX to the X-coordinate of both corner points, and ADY to both end points.

Errors: None.

See also: `TRect.Grow` ([1067](#))

Listing: ./objectex/ex5.pp

```

Program ex5;

{ Program to demonstrate TRect.Move }

Uses objects;

Var ARect, BRect : TRect;

```

```

begin
  ARect.Assign(10,10,20,20);
  ARect.Move(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(15,15,25,25);
  If ARect.Equals(BRect) Then
    Writeln ('ARect equals BRect')
  Else
    Writeln ('ARect does not equal BRect !');
end.

```

67.11.10 TRect.Grow

Synopsis: Expand rectangle with certain size.

Declaration: `procedure Grow(ADX: Sw_Integer; ADY: Sw_Integer)`

Visibility: default

Description: `Grow` expands the rectangle with an amount `ADX` in the `X` direction (both on the left and right side of the rectangle, thus adding a length `2*ADX` to the width of the rectangle), and an amount `ADY` in the `Y` direction (both on the top and the bottom side of the rectangle, adding a length `2*ADY` to the height of the rectangle).

`ADX` and `ADY` can be negative. If the resulting rectangle is empty, it is set to the empty rectangle at `(0,0)`.

Errors: None.

See also: `TRect.Move` ([1066](#))

Listing: `./objectex/ex6.pp`

```

Program ex6;

{ Program to demonstrate TRect.Grow }

Uses objects;

Var ARect,BRect : TRect;

begin
  ARect.Assign(10,10,20,20);
  ARect.Grow(5,5);
  // Brect should be where new ARect is.
  BRect.Assign(5,5,25,25);
  If ARect.Equals(BRect) Then
    Writeln ('ARect equals BRect')
  Else
    Writeln ('ARect does not equal BRect !');
end.

```

67.11.11 TRect.Assign

Synopsis: Set rectangle corners.

Declaration: `procedure Assign(XA: Sw_Integer; YA: Sw_Integer; XB: Sw_Integer;
YB: Sw_Integer)`

Visibility: default

Description: `Assign` sets the corner points of the rectangle to `(XA, YA)` and `(Xb, Yb)`.

For an example, see `TRect.Copy` ([1064](#)).

Errors: None.

See also: `TRect.Copy` ([1064](#))

67.12 TResourceCollection

67.12.1 Description

A `TResourceCollection` manages a collection of resource names. It stores the position and the size of a resource, as well as the name of the resource. It stores these items in records that look like this:

```
TYPE
  TResourceItem = packed RECORD
    Posn: LongInt;
    Size: LongInt;
    Key : String;
  End;
  PResourceItem = ^TResourceItem;
```

It overrides some methods of `TStringCollection` in order to accomplish this.

Remark: Remark that the `TResourceCollection` manages the names of the resources and their associated positions and sizes, it doesn't manage the resources themselves.

67.12.2 Method overview

Page	Method	Description
1069	<code>FreeItem</code>	Release memory occupied by item.
1069	<code>GetItem</code>	Read an item from the stream.
1068	<code>KeyOf</code>	Return the key of an item in the collection.
1069	<code>PutItem</code>	Write an item to the stream.

67.12.3 TResourceCollection.KeyOf

Synopsis: Return the key of an item in the collection.

Declaration: `function KeyOf(Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key of an item in the collection. For resources, the key is a pointer to the string with the resource name.

Errors: None.

See also: `TStringCollection.Compare` ([1089](#))

67.12.4 TResourceCollection.GetItem

Synopsis: Read an item from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a resource item from the stream `S`. It reads the position, size and name from the stream, in that order. It DOES NOT read the resource itself from the stream.

The resulting item is not inserted in the collection. This call is mainly for internal use by the `TCollection.Load (1040)` method.

Errors: Errors returned are those by `TStream.Read (1087)`

See also: `TCollection.Load (1040)`, `TStream.Read (1087)`

67.12.5 TResourceCollection.FreeItem

Synopsis: Release memory occupied by item.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `FreeItem` releases the memory occupied by `Item`. It de-allocates the name, and then the resource item record.

It does NOT remove the item from the collection.

Errors: None.

See also: `TCollection.FreeItem (1049)`

67.12.6 TResourceCollection.PutItem

Synopsis: Write an item to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes `Item` to the stream `S`. It does this by writing the position and size and name of the resource item to the stream.

This method is used primarily by the `Store (1053)` method.

Errors: Errors returned are those by `TStream.Write (1087)`.

See also: `TCollection.Store (1053)`

67.13 TResourceFile

67.13.1 Description

`TResourceFile (1069)` represents the resources in a binary file image.

67.13.2 Method overview

Page	Method	Description
1070	Count	Number of resources in the file
1072	Delete	Delete a resource from the file
1070	Done	Destroy the instance and remove it from memory.
1071	Flush	Writes the resources to the stream.
1071	Get	Return a resource by key name.
1070	Init	Instantiate a new instance.
1071	KeyAt	Return the key of the item at a certain position.
1072	Put	Set a resource by key name.
1071	SwitchTo	Write resources to a new stream.

67.13.3 TResourceFile.Init

Synopsis: Instantiate a new instance.

Declaration: `constructor Init (AStream: PStream)`

Visibility: default

Description: `Init` instantiates a new instance of a `TResourceFile` object. If `AStream` is not nil then it is considered as a stream describing an executable image on disk.

`Init` will try to position the stream on the start of the resources section, and read all resources from the stream.

Errors: None.

See also: `TResourceFile.Done` ([1070](#))

67.13.4 TResourceFile.Done

Synopsis: Destroy the instance and remove it from memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: `Done` cleans up the instance of the `TResourceFile` Object. If `Stream` was specified at initialization, then `Stream` is disposed of too.

Errors: None.

See also: `TResourceFile.Init` ([1070](#))

67.13.5 TResourceFile.Count

Synopsis: Number of resources in the file

Declaration: `function Count : Sw_Integer`

Visibility: default

Description: `Count` returns the number of resources. If no resources were read, zero is returned.

Errors: None.

See also: `TResourceFile.Init` ([1070](#))

67.13.6 TResourceFile.KeyAt

Synopsis: Return the key of the item at a certain position.

Declaration: `function KeyAt (I: Sw_Integer) : string`

Visibility: default

Description: `KeyAt` returns the key (the name) of the `I`-th resource.

Errors: In case `I` is invalid, `TCollection.Error` will be executed.

See also: `TResourceFile.Get` ([1071](#))

67.13.7 TResourceFile.Get

Synopsis: Return a resource by key name.

Declaration: `function Get (Key: string) : PObject`

Visibility: default

Description: `Get` returns a pointer to a instance of a resource identified by `Key`. If `Key` cannot be found in the list of resources, then `Nil` is returned.

Errors: Errors returned may be those by `TStream.Get`

67.13.8 TResourceFile.SwitchTo

Synopsis: Write resources to a new stream.

Declaration: `function SwitchTo (AStream: PStream; Pack: Boolean) : PStream`

Visibility: default

Description: `SwitchTo` switches to a new stream to hold the resources in. `AStream` will be the new stream after the call to `SwitchTo`.

If `Pack` is true, then all the known resources will be copied from the current stream to the new stream (`AStream`). If `Pack` is False, then only the current resource is copied.

The return value is the value of the original stream: `Stream`.

The `Modified` flag is set as a consequence of this call.

Errors: Errors returned can be those of `TStream.Read` ([1087](#)) and `TStream.Write` ([1087](#)).

See also: `TResourceFile.Flush` ([1071](#))

67.13.9 TResourceFile.Flush

Synopsis: Writes the resources to the stream.

Declaration: `procedure Flush`

Visibility: default

Description: If the `Modified` flag is set to `True`, then `Flush` writes the resources to the stream `Stream`. It sets the `Modified` flag to true after that.

Errors: Errors can be those by `TStream.Seek` ([1086](#)) and `TStream.Write` ([1087](#)).

See also: `TResourceFile.SwitchTo` ([1071](#))

67.13.10 TResourceFile.Delete

Synopsis: Delete a resource from the file

Declaration: `procedure Delete(Key: string)`

Visibility: `default`

Description: `Delete` deletes the resource identified by `Key` from the collection. It sets the `Modified` flag to `true`.

Errors: `None`.

See also: `TResourceFile.Flush` ([1071](#))

67.13.11 TResourceFile.Put

Synopsis: Set a resource by key name.

Declaration: `procedure Put(Item: PObject; Key: string)`

Visibility: `default`

Description: `Put` sets the resource identified by `Key` to `Item`. If no such resource exists, a new one is created. The item is written to the stream.

Errors: Errors returned may be those by `TStream.Put` ([1085](#)) and `TStream.Seek`

See also: `Get` ([1071](#))

67.14 TSortedCollection

67.14.1 Description

`TSortedCollection` is an abstract class, implementing a sorted collection. You should never use an instance of `TSortedCollection` directly, instead you should declare a descendent type, and override the `Compare` ([1074](#)) method.

Because the collection is ordered, `TSortedCollection` overrides some `TCollection` methods, to provide faster routines for lookup.

The `Compare` ([1074](#)) method decides how elements in the collection should be ordered. Since `TCollection` has no way of knowing how to order pointers, you must override the compare method.

Additionally, `TCollection` provides a means to filter out duplicates. if you set `Duplicates` to `False` (the default) then duplicates will not be allowed.

The example below defines a descendent of `TSortedCollection` which is used in the examples.

67.14.2 Method overview

Page	Method	Description
1074	Compare	Compare two items in the collection.
1074	IndexOf	Return index of an item in the collection.
1073	Init	Instantiates a new instance of a <code>TSortedCollection</code>
1076	Insert	Insert new item in collection.
1073	KeyOf	Return the key of an item
1073	Load	Instantiates a new instance of a <code>TSortedCollection</code> and loads it from stream.
1075	Search	Search for item with given key.
1077	Store	Write the collection to the stream.

67.14.3 TSortedCollection.Init

Synopsis: Instantiates a new instance of a `TSortedCollection`

Declaration: `constructor Init (ALimit: Sw_Integer; ADelta: Sw_Integer)`

Visibility: default

Description: `Init` calls the inherited constructor (see `TCollection.Init` ([1039](#))) and sets the `Duplicates` flag to `false`.

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

Errors: None.

See also: `TSortedCollection.Load` ([1073](#)), `TCollection.Done` ([1041](#))

67.14.4 TSortedCollection.Load

Synopsis: Instantiates a new instance of a `TSortedCollection` and loads it from stream.

Declaration: `constructor Load (var S: TStream)`

Visibility: default

Description: `Load` calls the inherited constructor (see `TCollection.Load` ([1040](#))) and reads the `Duplicates` flag from the stream..

You should not call this method directly, since `TSortedCollection` is a abstract class. Instead, the descendent classes should call it via the `inherited` keyword.

For an example, see `TCollection.Load` ([1040](#)).

Errors: None.

See also: `TSortedCollection.Init` ([1073](#)), `TCollection.Done` ([1041](#))

67.14.5 TSortedCollection.KeyOf

Synopsis: Return the key of an item

Declaration: `function KeyOf (Item: Pointer) : Pointer; Virtual`

Visibility: default

Description: `KeyOf` returns the key associated with `Item`. `TSortedCollection` returns the item itself as the key, descendent objects can override this method to calculate a (unique) key based on the item passed (such as hash values).

`Keys` are used to sort the objects, they are used to search and sort the items in the collection. If descendent types override this method then it allows possibly for faster search/sort methods based on keys rather than on the objects themselves.

Errors: None.

See also: `TSortedCollection.IndexOf` ([1074](#)), `TSortedCollection.Compare` ([1074](#))

67.14.6 `TSortedCollection.IndexOf`

Synopsis: Return index of an item in the collection.

Declaration: `function IndexOf(Item: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `IndexOf` returns the index of `Item` in the collection. It searches for the object based on it's key. If duplicates are allowed, then it returns the index of last object that matches `Item`.

In case `Item` is not found in the collection, -1 is returned.

For an example, see `TCollection.IndexOf` ([1042](#))

Errors: None.

See also: `TSortedCollection.Search` ([1075](#)), `TSortedCollection.Compare` ([1074](#))

67.14.7 `TSortedCollection.Compare`

Synopsis: Compare two items in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `Compare` is an abstract method that should be overridden by descendent objects in order to compare two items in the collection. This method is used in the `Search` ([1075](#)) method and in the `Insert` ([1076](#)) method to determine the ordering of the objects.

The function should compare the two keys of items and return the following function results:

Result < 0 If `Key1` is logically before `Key2` (`Key1 < Key2`)

Result = 0 If `Key1` and `Key2` are equal. (`Key1 = Key2`)

Result > 0 If `Key1` is logically after `Key2` (`Key1 > Key2`)

Errors: An 'abstract run-time error' will be generated if you call `TSortedCollection.Compare` directly.

See also: `TSortedCollection.IndexOf` ([1074](#)), `TSortedCollection.Search` ([1075](#))

Listing: `./objectex/mysortc.pp`

Unit MySortC;

Interface

Uses Objects;

Type

```

PMySortedCollection = ^TMySortedCollection;
TMySortedCollection = Object(TSortedCollection)
    Function Compare (Key1,Key2 : Pointer): Sw_integer; virtual;
    end;

```

Implementation

Uses MyObject;

Function TMySortedCollection.Compare (Key1,Key2 : Pointer) :sw_integer;

begin

```

    Compare:=PMyobject(Key1)^.GetField - PMyObject(Key2)^.GetField;

```

end;

end.

67.14.8 TSortedCollection.Search

Synopsis: Search for item with given key.

Declaration: `function Search(Key: Pointer; var Index: Sw_Integer) : Boolean; Virtual`

Visibility: default

Description: Search looks for the item with key Key and returns the position of the item (if present) in the collection in Index.

Instead of a linear search as TCollection does, TSortedCollection uses a binary search based on the keys of the objects. It uses the Compare (1074) function to implement this search.

If the item is found, Search returns True, otherwise False is returned.

Errors: None.

See also: TCollection.IndexOf (1042)

Listing: ./objectex/ex36.pp

Program ex36;

```

{ Program to demonstrate the TSortedCollection.Insert method }

```

Uses Objects, MyObject, MySortC;

```

{ For TMyObject, TMySortedCollection definition and registration }

```

Var C : PSortedCollection;

```

    M : PMyObject;
```

```

    I : Longint;
```

Procedure PrintField (Dummy: Pointer;P : PMyObject);

```

begin
  Writeln ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  C^.Duplicates:=True;
  Writeln ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New(PMyObject, Init);
      M^.SetField(Random(100));
      C^.Insert(M)
    end;
  M:=New(PMyObject, Init);
  Repeat;
    Write ( 'Value to search for (-1 stops) : ' );
    read ( I );
    If I<>-1 then
      begin
        M^.SetField(i);
        If Not C^.Search (M,I) then
          Writeln ( 'No such value found' )
        else
          begin
            Write ( 'Value ', PMyObject(C^.At(I))^ .GetField );
            Writeln ( ' present at position ', I );
          end;
      end;
    Until I=-1;
    Dispose (M, Done );
    Dispose (C, Done );
  end.

```

67.14.9 TSortedCollection.Insert

Synopsis: Insert new item in collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts an item in the collection at the correct position, such that the collection is ordered at all times. You should never use `Atinsert` ([1052](#)), since then the collection ordering is not guaranteed.

If `Item` is already present in the collection, and `Duplicates` is `False`, the item will not be inserted.

Errors: None.

See also: `TCollection.AtInsert` ([1052](#))

Listing: `./objectex/ex35.pp`

```

Program ex35;

{ Program to demonstrate the TSortedCollection.Insert method }

Uses Objects, MyObject, MySortC;
{ For TMyObject, TMySortedCollection definition and registration }

Var C : PSortedCollection;
      M : PMyObject;
      I : Longint;

Procedure PrintField (Dummy: Pointer; P : PMyObject);

begin
  WriteLn ( 'Field : ', P^.GetField );
end;

begin
  Randomize;
  C:=New( PMySortedCollection, Init(120,10));
  WriteLn ( 'Inserting 100 records at random places.' );
  For I:=1 to 100 do
    begin
      M:=New( PMyObject, Init );
      M^.SetField( Random(100));
      C^.Insert( M )
    end;
  WriteLn ( 'Values : ' );
  C^.Foreach( @PrintField );
  Dispose( C, Done );
end.

```

67.14.10 TSortedCollection.Store

Synopsis: Write the collection to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection to the stream `S`. It does this by calling the inherited `TCollection.Store` ([1053](#)), and then writing the `Duplicates` flag to the stream.

After a `Store`, the collection can be loaded from the stream with the constructor `Load` ([1073](#))

For an example, see `TCollection.Load` ([1040](#)).

Errors: Errors can be those of `TStream.Put` ([1085](#)).

See also: `TSortedCollection.Load` ([1073](#))

67.15 TStrCollection

67.15.1 Description

The `TStrCollection` object manages a sorted collection of null-terminated strings (pchar strings). To this end, it overrides the `Compare` (1074) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.15.2 Method overview

Page	Method	Description
1078	<code>Compare</code>	Compare two strings in the collection.
1079	<code>FreeItem</code>	Free null-terminated string from the collection.
1079	<code>GetItem</code>	Read a null-terminated string from the stream.
1079	<code>PutItem</code>	Write a null-terminated string to the stream.

67.15.3 TStrCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStrCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` (1074)

Listing: `./objectex/ex38.pp`

Program `ex38;`

{ Program to demonstrate the TStrCollection.Compare method }

Uses `Objects , Strings ;`

Var `C : PStrCollection ;`

`S : String ;`

`I : longint ;`

`P : Pchar ;`

begin

`Randomize ;`

`C:=New(PStrCollection , Init(120,10));`

`C^.Duplicates:=True; { Duplicates allowed }`

`WriteLn ('Inserting 100 records at random places.');`

For `I:=1 to 100 do`

`begin`

`Str(Random(100),S);`

```

S:= 'String with value '+S;
P:= StrAlloc (Length(S)+1);
C^.Insert(StrPCopy(P,S));
end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(I),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',I);
    Dispose(C,Done);
  end.

```

67.15.4 TStrCollection.GetItem

Synopsis: Read a null-terminated string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a null-terminated string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.StrRead` ([1081](#)).

See also: `TStrCollection.PutItem` ([1079](#))

67.15.5 TStrCollection.FreeItem

Synopsis: Free null-terminated string from the collection.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStrCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1049](#))

67.15.6 TStrCollection.PutItem

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.StrWrite` ([1086](#)).

See also: `TStrCollection.GetItem` ([1079](#))

67.16 TStream

67.16.1 Description

The `TStream` object is the ancestor for all streaming objects, i.e. objects that have the capability to store and retrieve data.

It defines a number of methods that are common to all objects that implement streaming, many of them are virtual, and are only implemented in the descendent types.

Programs should not instantiate objects of type `TStream` directly, but instead instantiate a descendant type, such as `TDosStream`, `TMemoryStream`.

See also: `PStream` ([1026](#)), `TDosStream` ([1053](#)), `TMemoryStream` ([1058](#))

67.16.2 Method overview

Page	Method	Description
1084	<code>Close</code>	Close the stream
1088	<code>CopyFrom</code>	Copy data from another stream.
1086	<code>Error</code>	Set stream status
1085	<code>Flush</code>	Flush the stream data from the buffer, if any.
1080	<code>Get</code>	Read an object definition from the stream.
1082	<code>GetPos</code>	Return current position in the stream
1082	<code>GetSize</code>	Return the size of the stream.
1080	<code>Init</code>	Constructor for <code>TStream</code> instance
1084	<code>Open</code>	Open the stream
1085	<code>Put</code>	Write an object to the stream.
1087	<code>Read</code>	Read data from stream to buffer.
1083	<code>ReadStr</code>	Read a shortstring from the stream.
1084	<code>Reset</code>	Reset the stream
1086	<code>Seek</code>	Set stream position.
1081	<code>StrRead</code>	Read a null-terminated string from the stream.
1086	<code>StrWrite</code>	Write a null-terminated string to the stream.
1085	<code>Truncate</code>	Truncate the stream size on current position.
1087	<code>Write</code>	Write a number of bytes to the stream.
1086	<code>WriteStr</code>	Write a pascal string to the stream.

67.16.3 TStream.Init

Synopsis: Constructor for `TStream` instance

Declaration: `constructor Init`

Visibility: `default`

Description: `Init` initializes a `TStream` instance. Descendent streams should always call the inherited `Init`.

67.16.4 TStream.Get

Synopsis: Read an object definition from the stream.

Declaration: `function Get : PObject`

Visibility: `default`

Description: `Get` reads an object definition from a stream, and returns a pointer to an instance of this object.

Errors: On error, `TStream.Status` (??) is set, and `NIL` is returned.

See also: `TStream.Put` ([1085](#))

Listing: `./objectex/ex9.pp`

Program `ex9`;

{ Program to demonstrate TStream.Get and TStream.Put }

Uses `Objects, MyObject`; *{ Definition and registration of TMyObject }*

Var `Obj : PMyObject`;
 `S : PStream`;

begin
 `Obj:=New(PMyObject, Init);`
 `Obj^.SetField($1111);`
 `WriteLn ('Field value : ',Obj^.GetField);`
 { Since Stream is an abstract type, we instantiate a TMemoryStream }
 `S:=New(PMemoryStream, Init(100,10));`
 `S^.Put(Obj);`
 `WriteLn ('Disposing object');`
 `S^.Seek(0);`
 `Dispose(Obj, Done);`
 `WriteLn ('Reading object');`
 `Obj:=PMyObject(S^.Get);`
 `WriteLn ('Field Value : ',Obj^.GetField);`
 `Dispose(Obj, Done);`
end.

67.16.5 TStream.StrRead

Synopsis: Read a null-terminated string from the stream.

Declaration: `function StrRead : PChar`

Visibility: `default`

Description: `StrRead` reads a string from the stream, allocates memory for it, and returns a pointer to a null-terminated copy of the string on the heap.

Errors: On error, `Nil` is returned.

See also: `TStream.StrWrite` ([1086](#)), `TStream.ReadStr` ([1083](#))

Listing: `./objectex/ex10.pp`

Program `ex10`;

{
Program to demonstrate the TStream.StrRead TStream.StrWrite functions
}

Uses `objects`;

```

Var P : PChar;
      S : PStream;

begin
  P:= 'Constant Pchar string';
  Writeln ('Writing to stream : "',P,'"');
  S:=New(PMemoryStream, Init(100,10));
  S^.StrWrite(P);
  S^.Seek(0);
  P:= Nil;
  P:=S^.StrRead;
  Dispose (S,Done);
  Writeln ('Read from stream : "',P,'"');
  Freemem(P, Strlen(P)+1);
end.

```

67.16.6 TStream.GetPos

Synopsis: Return current position in the stream

Declaration: `function GetPos : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk`, `GetPos` returns the current position in the stream. Otherwise it returns `-1`

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1086](#)), `TStream.GetSize` ([1082](#))

Listing: `./objectex/ex11.pp`

```

Program ex11;

{ Program to demonstrate the TStream.GetPos function }

Uses objects;

Var L : String;
      S : PStream;

begin
  L:= 'Some kind of string';
  S:=New(PMemoryStream, Init(100,10));
  Writeln ('Stream position before write : ',S^.GetPos);
  S^.WriteStr(@L);
  Writeln ('Stream position after write : ',S^.GetPos);
  Dispose(S,Done);
end.

```

67.16.7 TStream.GetSize

Synopsis: Return the size of the stream.

Declaration: `function GetSize : LongInt; Virtual`

Visibility: default

Description: If the stream's status is `stOk` then `GetSize` returns the size of the stream, otherwise it returns `-1`.

Errors: `-1` is returned if the status is an error condition.

See also: `TStream.Seek` ([1086](#)), `TStream.GetPos` ([1082](#))

Listing: `./objectex/ex12.pp`

```
Program ex12;

{ Program to demonstrate the TStream.GetSize function }

Uses objects;

Var L : String;
    S : PStream;

begin
  L := 'Some kind of string';
  S := New(PMemoryStream, Init(100,10));
  WriteLn ('Stream size before write: ', S^.GetSize);
  S^.WriteStr(@L);
  WriteLn ('Stream size after write: ', S^.GetSize);
  Dispose(S, Done);
end.
```

67.16.8 TStream.ReadStr

Synopsis: Read a shortstring from the stream.

Declaration: `function ReadStr : PString`

Visibility: default

Description: `ReadStr` reads a string from the stream, copies it to the heap and returns a pointer to this copy. The string is saved as a pascal string, and hence is NOT null terminated.

Errors: On error (e.g. not enough memory), `Nil` is returned.

See also: `TStream.StrRead` ([1081](#))

Listing: `./objectex/ex13.pp`

```
Program ex13;

{
  Program to demonstrate the TStream.ReadStr TStream.WriteStr functions
}

Uses objects;

Var P : PString;
    L : String;
    S : PStream;

begin
```

```

L:= 'Constant string line';
WriteIn ('Writing to stream : "',L,'"');
S:=New(PMemoryStream, Init(100,10));
S^.WriteStr(@L);
S^.Seek(0);
P:=S^.ReadStr;
L:=P^;
DisposeStr(P);
DisPose (S,Done);
WriteIn ('Read from stream : "',L,'"');
end.

```

67.16.9 TStream.Open

Synopsis: Open the stream

Declaration: `procedure Open(OpenMode: Word); Virtual`

Visibility: default

Description: `Open` is an abstract method, that should be overridden by descendent objects. Since opening a stream depends on the stream's type this is not surprising.

For an example, see `TDosStream.Open` ([1057](#)).

Errors: None.

See also: `TStream.Close` ([1084](#)), `TStream.Reset` ([1084](#))

67.16.10 TStream.Close

Synopsis: Close the stream

Declaration: `procedure Close; Virtual`

Visibility: default

Description: `Close` is an abstract method, that should be overridden by descendent objects. Since Closing a stream depends on the stream's type this is not surprising.

for an example, see `TDosStream.Open` ([1057](#)).

Errors: None.

See also: `TStream.Open` ([1084](#)), `TStream.Reset` ([1084](#))

67.16.11 TStream.Reset

Synopsis: Reset the stream

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` sets the stream's status to 0, as well as the `ErrorInfo`

Errors: None.

See also: `TStream.Open` ([1084](#)), `TStream.Close` ([1084](#))

67.16.12 TStream.Flush

Synopsis: Flush the stream data from the buffer, if any.

Declaration: `procedure Flush; Virtual`

Visibility: default

Description: `Flush` is an abstract method that should be overridden by descendent objects. It serves to enable the programmer to tell streams that implement a buffer to clear the buffer.

for an example, see `TBufStream.Flush` ([1036](#)).

Errors: None.

See also: `TStream.Truncate` ([1085](#))

67.16.13 TStream.Truncate

Synopsis: Truncate the stream size on current position.

Declaration: `procedure Truncate; Virtual`

Visibility: default

Description: `Truncate` is an abstract procedure that should be overridden by descendent objects. It serves to enable the programmer to truncate the size of the stream to the current file position.

For an example, see `TDosStream.Truncate` ([1055](#)).

Errors: None.

See also: `TStream.Seek` ([1086](#))

67.16.14 TStream.Put

Synopsis: Write an object to the stream.

Declaration: `procedure Put (P: PObject)`

Visibility: default

Description: `Put` writes the object pointed to by `P`. `P` should be non-nil. The object type must have been registered with `RegisterType` ([1033](#)).

After the object has been written, it can be read again with `Get` ([1080](#)).

For an example, see `TStream.Get` ([1080](#));

Errors: No check is done whether `P` is `Nil` or not. Passing `Nil` will cause a run-time error 216 to be generated. If the object has not been registered, the status of the stream will be set to `stPutError`.

See also: `TStream.Get` ([1080](#))

67.16.15 TStream.StrWrite

Synopsis: Write a null-terminated string to the stream.

Declaration: `procedure StrWrite(P: PChar)`

Visibility: default

Description: `StrWrite` writes the null-terminated string `P` to the stream. `P` can only be 65355 bytes long.

For an example, see `TStream.StrRead` ([1081](#)).

Errors: None.

See also: `TStream.WriteString` ([1086](#)), `TStream.StrRead` ([1081](#)), `TStream.ReadStr` ([1083](#))

67.16.16 TStream.WriteString

Synopsis: Write a pascal string to the stream.

Declaration: `procedure WriteStr(P: PString)`

Visibility: default

Description: `StrWrite` writes the pascal string pointed to by `P` to the stream.

For an example, see `TStream.ReadStr` ([1083](#)).

Errors: None.

See also: `TStream.StrWrite` ([1086](#)), `TStream.StrRead` ([1081](#)), `TStream.ReadStr` ([1083](#))

67.16.17 TStream.Seek

Synopsis: Set stream position.

Declaration: `procedure Seek(Pos: LongInt); Virtual`

Visibility: default

Description: `Seek` sets the position to `Pos`. This position is counted from the beginning, and is zero based. (i.e. `seek(0)` sets the position pointer on the first byte of the stream)

For an example, see `TDosStream.Seek` ([1056](#)).

Errors: If `Pos` is larger than the stream size, `Status` is set to `StSeekError`.

See also: `TStream.GetPos` ([1082](#)), `TStream.GetSize` ([1082](#))

67.16.18 TStream.Error

Synopsis: Set stream status

Declaration: `procedure Error(Code: Integer; Info: Integer); Virtual`

Visibility: default

Description: `Error` sets the stream's status to `Code` and `ErrorInfo` to `Info`. If the `StreamError` procedural variable is set, `Error` executes it, passing `Self` as an argument.

This method should not be called directly from a program. It is intended to be used in descendent objects.

Errors: None.

67.16.19 TStream.Read

Synopsis: Read data from stream to buffer.

Declaration: `procedure Read(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Read is an abstract method that should be overridden by descendent objects.

Read reads Count bytes from the stream into Buf. It updates the position pointer, increasing it's value with Count. Buf must be large enough to contain Count bytes.

Errors: No checking is done to see if Buf is large enough to contain Count bytes.

See also: TStream.Write (1087), TStream.ReadStr (1083), TStream.StrRead (1081)

Listing: ./objectex/ex18.pp

```

program ex18;

{ Program to demonstrate the TStream.Read method }

Uses Objects;

Var Buf1, Buf2 : Array[1..1000] of Byte;
    I : longint;
    S : PMemoryStream;

begin
    For I:=1 to 1000 do
        Buf1[I]:=Random(1000);
    Buf2:=Buf1;
    S:=New(PMemoryStream, Init(100,10));
    S^.Write(Buf1, SizeOf(Buf1));
    S^.Seek(0);
    For I:=1 to 1000 do
        Buf1[I]:=0;
    S^.Read(Buf1, SizeOf(Buf1));
    For I:=1 to 1000 do
        If Buf1[I]<>Buf2[I] then
            WriteLn('Buffer differs at position ',I);
    Dispose(S,Done);
end.

```

67.16.20 TStream.Write

Synopsis: Write a number of bytes to the stream.

Declaration: `procedure Write(var Buf; Count: LongInt); Virtual`

Visibility: default

Description: Write is an abstract method that should be overridden by descendent objects.

Write writes Count bytes to the stream from Buf. It updates the position pointer, increasing it's value with Count.

For an example, see TStream.Read (1087).

Errors: No checking is done to see if Buf actually contains Count bytes.

See also: TStream.Read (1087), TStream.WriteString (1086), TStream.StrWrite (1086)

67.16.21 TStream.CopyFrom

Synopsis: Copy data from another stream.

Declaration: `procedure CopyFrom(var S: TStream; Count: LongInt)`

Visibility: default

Description: `CopyFrom` reads `Count` bytes from stream `S` and stores them in the current stream. It uses the `Read` (1087) method to read the data, and the `Write` (1087) method to write in the current stream.

Errors: None.

See also: `Read` (1087), `Write` (1087)

Listing: `./objectex/ex19.pp`

Program `ex19;`

{ Program to demonstrate the TStream.CopyFrom function }

Uses `objects;`

Var `P : PString;`
 `L : String;`
 `S1,S2 : PStream;`

begin
 `L:= 'Constant string line';`
 `Writeln ('Writing to stream 1 : ',L, '');`
 `S1:=New(PMemoryStream, Init(100,10));`
 `S2:=New(PMemoryStream, Init(100,10));`
 `S1^.WriteStr(@L);`
 `S1^.Seek(0);`
 `Writeln ('Copying contents of stream 1 to stream 2');`
 `S2^.Copyfrom(S1^,S1^.GetSize);`
 `S2^.Seek(0);`
 `P:=S2^.ReadStr;`
 `L:=P^;`
 `DisposeStr(P);`
 `Dispose (S1,Done);`
 `Dispose (S2,Done);`
 `Writeln ('Read from stream 2 : ',L, '');`
end.

67.17 TStringCollection**67.17.1 Description**

The `TStringCollection` object manages a sorted collection of pascal strings. To this end, it overrides the `Compare` (1074) method of `TSortedCollection`, and it introduces methods to read/write strings from a stream.

67.17.2 Method overview

Page	Method	Description
1089	Compare	Compare two strings in the collection.
1090	FreeItem	Dispose a string in the collection from memory.
1089	GetItem	Get string from the stream.
1090	PutItem	Write a string to the stream.

67.17.3 TStringCollection.GetItem

Synopsis: Get string from the stream.

Declaration: `function GetItem(var S: TStream) : Pointer; Virtual`

Visibility: default

Description: `GetItem` reads a string from the stream `S` and returns a pointer to it. It doesn't insert the string in the collection.

This method is primarily introduced to be able to load and store the collection from and to a stream.

Errors: The errors returned are those of `TStream.ReadStr` ([1083](#)).

See also: `TStringCollection.PutItem` ([1090](#))

67.17.4 TStringCollection.Compare

Synopsis: Compare two strings in the collection.

Declaration: `function Compare(Key1: Pointer; Key2: Pointer) : Sw_Integer; Virtual`

Visibility: default

Description: `TStringCollection` overrides the `Compare` function so it compares the two keys as if they were pointers to strings. The compare is done case sensitive. It returns the following results:

-1 if the first string is alphabetically earlier than the second string.

0 if the two strings are equal.

1 if the first string is alphabetically later than the second string.

Errors: None.

See also: `TSortedCollection.Compare` ([1074](#))

Listing: `./objectex/ex37.pp`

Program `ex37`;

{ Program to demonstrate the TStringCollection.Compare method }

Uses `Objects`;

Var `C : PStringCollection`;
 `S : String`;
 `I : longint`;

begin
 `Randomize`;

```

C:=New(PStringCollection, Init(120,10));
C^.Duplicates:=True; { Duplicates allowed }
WriteLn ('Inserting 100 records at random places. ');
For I:=1 to 100 do
  begin
    Str(Random(100),S);
    S:='String with value '+S;
    C^.Insert(NewStr(S));
  end;
For I:=0 to 98 do
  With C^ do
    If Compare (At(i),At(I+1))=0 then
      WriteLn ('Duplicate string found at position ',i);
Dispose(C,Done);
end.

```

67.17.5 TStringCollection.FreeItem

Synopsis: Dispose a string in the collection from memory.

Declaration: `procedure FreeItem(Item: Pointer); Virtual`

Visibility: default

Description: `TStringCollection` overrides `FreeItem` so that the string pointed to by `Item` is disposed from memory.

Errors: None.

See also: `TCollection.FreeItem` ([1049](#))

67.17.6 TStringCollection.PutItem

Synopsis: Write a string to the stream.

Declaration: `procedure PutItem(var S: TStream; Item: Pointer); Virtual`

Visibility: default

Description: `PutItem` writes the string pointed to by `Item` to the stream `S`.

This method is primarily used in the `Load` and `Store` methods, and should not be used directly.

Errors: Errors are those of `TStream.WriteString` ([1086](#)).

See also: `TStringCollection.GetItem` ([1089](#))

67.18 TStringList

67.18.1 Description

A `TStringList` object can be used to read a collection of strings stored in a stream. If you register this object with the `RegisterType` ([1033](#)) function, you cannot register the `TStrListMaker` object.

67.18.2 Method overview

Page	Method	Description
1091	Done	Clean up the instance
1091	Get	Return a string by key name
1091	Load	Load stringlist from stream.

67.18.3 TStringList.Load

Synopsis: Load stringlist from stream.

Declaration: `constructor Load(var S: TStream)`

Visibility: default

Description: The `Load` constructor reads the `TStringList` object from the stream `S`. It also reads the descriptions of the strings from the stream. The string descriptions are stored as an array of `TStrIndexrec` records, where each record describes a string on the stream. These records are kept in memory.

Errors: If an error occurs, a stream error is triggered.

See also: `TStringList.Done` ([1091](#))

67.18.4 TStringList.Done

Synopsis: Clean up the instance

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor frees the memory occupied by the string descriptions, and destroys the object.

Errors: None.

See also: `Load` ([1091](#)), `TObject.Done` ([1062](#))

67.18.5 TStringList.Get

Synopsis: Return a string by key name

Declaration: `function Get(Key: Sw_Word) : string`

Visibility: default

Description: `Get` reads the string with key `Key` from the list of strings on the stream, and returns this string. If there is no string with such a key, an empty string is returned.

Errors: If no string with key `Key` is found, an empty string is returned. A stream error may result if the stream doesn't contain the needed strings.

See also: `TStrListMaker.Put` ([1092](#))

67.19 TStrListMaker

67.19.1 Description

The `TStrListMaker` object can be used to generate a stream with strings, which can be read with the `TStringList` object. If you register this object with the `RegisterType` (1033) function, you cannot register the `TStringList` object.

67.19.2 Method overview

Page	Method	Description
1092	<code>Done</code>	Clean up the instance and free all related memory.
1092	<code>Init</code>	Instantiate a new instance of <code>TStrListMaker</code>
1092	<code>Put</code>	Add a new string to the list with associated key.
1093	<code>Store</code>	Write the strings to the stream.

67.19.3 TStrListMaker.Init

Synopsis: Instantiate a new instance of `TStrListMaker`

Declaration: `constructor Init (AStrSize: Sw_Word; AIndexSize: Sw_Word)`

Visibility: default

Description: The `Init` constructor creates a new instance of the `TstrListMaker` object. It allocates `AStrSize` bytes on the heap to hold all the strings you wish to store. It also allocates enough room for `AIndexSize` key description entries (of the type `TStrIndexrec`).

`AStrSize` must be large enough to contain all the strings you wish to store. If not enough memory is allocated, other memory will be overwritten. The same is true for `AIndexSize` : maximally `AIndexSize` strings can be written to the stream.

Errors: None.

See also: `TObject.Init` (1060), `TStrListMaker.Done` (1092)

67.19.4 TStrListMaker.Done

Synopsis: Clean up the instance and free all related memory.

Declaration: `destructor Done; Virtual`

Visibility: default

Description: The `Done` destructor de-allocates the memory for the index description records and the string data, and then destroys the object.

Errors: None.

See also: `TObject.Done` (1062), `TStrListMaker.Init` (1092)

67.19.5 TStrListMaker.Put

Synopsis: Add a new string to the list with associated key.

Declaration: `procedure Put (Key: Sw_Word; S: string)`

Visibility: default

Description: `Put` adds the string `S` with key `Key` to the collection of strings. This action doesn't write the string to a stream. To write the strings to the stream, see the `Store` (1093) method.

Errors: None.

See also: `TStrListMaker.Store` (1093)

67.19.6 TStrListMaker.Store

Synopsis: Write the strings to the stream.

Declaration: `procedure Store(var S: TStream)`

Visibility: default

Description: `Store` writes the collection of strings to the stream `S`. The collection can then be read with the `TStringList` object.

Errors: A stream error may occur when writing the strings to the stream.

See also: `TStringList.Load` (1091), `TStrListMaker.Put` (1092)

67.20 TUnSortedStrCollection

67.20.1 Description

The `TUnSortedStrCollection` object manages an unsorted list of strings. To this end, it overrides the `TSortedCollection.Insert` (1076) method to add strings at the end of the collection, rather than in the alphabetically correct position.

Take care, the `Search` (1075) and `IndexOf` (1042) methods will not work on an unsorted string collection.

67.20.2 Method overview

Page	Method	Description
1093	<code>Insert</code>	Insert a new string in the collection.

67.20.3 TUnSortedStrCollection.Insert

Synopsis: Insert a new string in the collection.

Declaration: `procedure Insert(Item: Pointer); Virtual`

Visibility: default

Description: `Insert` inserts a string at the end of the collection, instead of on its alphabetical place, resulting in an unsorted collection of strings.

Errors: None.

See also: `TCollection.Insert` (1048)

Listing: `./objectex/ex39.pp`

Program ex39;

{ Program to demonstrate the TUnsortedStrCollection.Insert method }

Uses Objects, Strings;

Var C : PUnsortedStrCollection;
 S : **String**;
 I : longint;
 P : Pchar;

begin

Randomize;

 C:=**New**(PUnsortedStrCollection, Init(120,10));

Writeln ('Inserting 100 records at random places.');

For I:=1 **to** 100 **do**

begin

Str(**Random**(100),S);

 S:= 'String with value ' + S;

 C^. **Insert**(**NewStr**(S));

end;

For I:=0 **to** 99 **do**

Writeln (I:2, ': ', PString(C^. **At**(i))^);

Dispose(C, Done);

end.

Chapter 68

Reference for unit 'objpas'

68.1 Used units

Table 68.1: Used units by unit 'objpas'

Name	Page
System	1194

68.2 Overview

The `objpas` unit is meant for compatibility with Object Pascal as implemented by Delphi. The unit is loaded automatically by the Free Pascal compiler whenever the `Delphi` or `objfpc` mode is entered, either through the command line switches `-Sd` or `-Sh` or with the `{ $MODE DELPHI }` or `{ $MODE OBJFPC }` directives.

It redefines some basic pascal types, introduces some functions for compatibility with Delphi's system unit, and introduces some methods for the management of the resource string tables.

68.3 Constants, types and variables

68.3.1 Constants

`MaxInt` = `MaxLongint`

Maximum value for Integer ([1095](#)) type.

68.3.2 Types

`Integer` = `LongInt`

In `OBJPAS` mode and in `DELPHI` mode, an `Integer` has a size of 32 bit. In `TP` or regular `FPC` mode, an integer is 16 bit.

`IntegerArray` = `Array[0..$efffffff] of Integer`

Generic array of integer (1095)

`PInteger = ^Integer`

Pointer to Integer (1095) type.

`PIntegerArray = ^IntegerArray`

Pointer to TIntegerArray (1096) type.

`PointerArray = Array[0..512*1024*1024-2] of Pointer`

Generic Array of pointers.

`PPointerArray = ^PointerArray`

Pointer to PointerArray (1096)

`PString = PAnsiString`

Pointer to ansistring type.

`TBoundArray = Array of Integer`

Array of integer, used in interfaces.

`TIntegerArray = IntegerArray`

Alias for IntegerArray (1096)

`TPointerArray = PointerArray`

Alias for PointerArray (1096)

Chapter 69

Reference for unit 'ports'

69.1 Used units

Table 69.1: Used units by unit 'ports'

Name	Page
System	1194

69.2 Overview

The ports unit implements the `port` constructs found in Turbo Pascal. It uses classes and default array properties to do this.

The unit exists on Linux, OS/2 and Dos. It is implemented only for compatibility with Turbo Pascal. Its usage is discouraged, because using ports is not portable programming, and the operating system may not even allow it (for instance Windows).

Under Linux, your program must be run as root, or the `IOPerm` call must be set in order to set appropriate permissions on the port access.

69.3 Constants, types and variables

69.3.1 Variables

```
port : tport
```

Default instance of type `TPort` ([1098](#)). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
port[221]:=12;
```

Will result in the integer 12 being written to port 221, if port is defined as a variable of type `tport`

```
portb : tport
```

Default instance of type `TPort` (1098). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portb[221]:=12;
```

Will result in the byte 12 being written to port 221, if port is defined as a variable of type `tport`

```
portl : tportl
```

Default instance of type `TPortL` (1099). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portl[221]:=12;
```

Will result in the longint 12 being written to port 221, if port is defined as a variable of type `tport`

```
portw : tportw
```

Default instance of type `TPortW` (1099). Do not free. This variable is initialized in the unit initialization code, and freed at finalization.

Since there is a default property for a variable of this type, a sentence as

```
portw[221]:=12;
```

Will result in the word 12 being written to port 221, if port is defined as a variable of type `tport`

69.4 tport

69.4.1 Description

The `TPort` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `port` (1097), `TPortW` (1099), `TPortL` (1099)

69.4.2 Property overview

Page	Properties	Access	Description
1098	pp	rw	Access integer-sized port by port number

69.4.3 tport.pp

Synopsis: Access integer-sized port by port number

Declaration: `Property pp[w: LongInt]: Byte; default`

Visibility: `public`

Access: Read,Write

Description: Access integer-sized port by port number

69.5 tportl

69.5.1 Description

The `TPortL` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1098](#)), `TPort` ([1098](#)), `TPortL` ([1099](#))

69.5.2 Property overview

Page	Properties	Access	Description
1099	pp	rw	Access Longint-sized port by port number

69.5.3 tportl.pp

Synopsis: Access Longint-sized port by port number

Declaration: `Property pp[w: LongInt]: LongInt; default`

Visibility: public

Access: Read,Write

Description: Access Longint-sized port by port number

69.6 tportw

69.6.1 Description

The `TPortW` type is implemented specially for access to the ports in a TP compatible manner. There is no need to create an instance of this type: the standard TP variables are instantiated at unit initialization.

See also: `portw` ([1098](#)), `TPort` ([1098](#)), `TPortL` ([1099](#))

69.6.2 Property overview

Page	Properties	Access	Description
1099	pp	rw	Access word-sized port by port number

69.6.3 tportw.pp

Synopsis: Access word-sized port by port number

Declaration: `Property pp[w: LongInt]: Word; default`

Visibility: public

Access: Read,Write

Description: Access word-sized port by port number

Chapter 70

Reference for unit 'printer'

70.1 Used units

Table 70.1: Used units by unit 'printer'

Name	Page
System	1194

70.2 Overview

This chapter describes the `printer` unit for Free Pascal. It was written for DOS by Florian Klaempfl, and it was written for Linux by Michael Van Canneyt, and has been ported to Windows and OS/2 as well. Its basic functionality is the same for all supported systems, although there are minor differences on Linux and UNIX.

70.3 Constants, types and variables

70.3.1 Variables

`Lst` : `text`

`Lst` is the standard printing device.

On Linux, `Lst` is set up using `AssignLst ('/tmp/PID.lst')`.

70.4 Procedures and functions

70.4.1 AssignLst

Synopsis: Assign text file to printing device

Declaration: `procedure AssignLst (var F: text; ToFile: string)`

Visibility: default

Description: AssignLst assigns to F a printing device - *UNIX only*. ToFile is a string with the following form:

- '|filename options': This sets up a pipe with the program filename, with the given options, such as in the popen() call.
- 'filename': Prints to file filename. Filename can contain the string 'PID' (No Quotes), which will be replaced by the PID of your program. When closing lst, the file will be sent to lpr and deleted. (lpr should be in PATH)
- {'filename|'}: Same as previous, only the file is *not* sent to lpr, nor is it deleted. (useful for opening /dev/printer or for later printing)

See also: lst ([1100](#))

Listing: ./printex/printex.pp

```

program testprn;

uses printer;

var i : integer;
    f : text;

begin
  writeln ('Test of printer unit');
  writeln ('Writing to lst...');
  for i:=1 to 80 do writeln (lst, 'This is line ', i, '.' #13);
  close (lst);
  writeln ('Done. ');
  { $ifdef Unix }
  writeln ('Writing to pipe...');
  assignlst (f, '|usr/bin/lpr -m');
  rewrite (f);
  for i:=1 to 80 do writeln (f, 'This is line ', i, '.' #13);
  close (f);
  writeln ('Done. ')
  { $endif }
end.

```

70.4.2 InitPrinter

Synopsis: Initialize the printer

Declaration: `procedure InitPrinter(const PrinterName: string)`

Visibility: default

Description: Initialize the printer

70.4.3 IsLstAvailable

Synopsis: Determine whether printer is available.

Declaration: `function IsLstAvailable : Boolean`

Visibility: default

Description: Determine whether printer is available.

Chapter 71

Reference for unit 'sharemem'

71.1 Used units

Table 71.1: Used units by unit 'sharemem'

Name	Page
System	1194

71.2 Overview

`sharemem` implements a shared memory manager. Including this unit will replace the standard memory manager with a memory manager which uses shared memory. This means the memory allocated by this unit can be managed by a program and a DLL if they both use the shared memory manager: it allows, amongst other things, to pass ansistrings or unicode strings from a program to a DLL and vice versa.

This unit does not implement any routines: all actions to replace the memory manager are performed in the initialization section of the unit. The unit should be placed as the first unit in a program or DLL's uses section, memory corruption may occur if the unit is not placed first.

This unit requires the `fpcmemdll.dll` library to be distributed with both program and dll that use this unit. This DLL is distributed with the windows Free Pascal distribution.

Chapter 72

Reference for unit 'Sockets'

72.1 Used units

Table 72.1: Used units by unit 'Sockets'

Name	Page
BaseUnix	124
System	1194
unixtype	1879

72.2 Overview

This document describes the SOCKETS unit for Free Pascal. it was written for Linux by Michael Van Canneyt, and ported to Windows by Florian Klaempfl.

72.3 Constants, types and variables

72.3.1 Constants

`AF_APPLETALK = 5`

Address family Appletalk DDP

`AF_ASH = 18`

Address family: Ash

`AF_ATMPVC = 8`

Address family: ATM PVCs

`AF_ATMSVC = 20`

Address family: ATM SVCs

AF_AX25 = 3

Address family Amateur Radio AX.25

AF_BLUETOOTH = 31

Address family: Bluetooth sockets

AF_BRIDGE = 7

Address family Multiprotocol bridge

AF_DECnet = 12

Address family: Reserved for DECnet project.

AF_ECONET = 19

Address family: Acorn Econet

AF_INET = 2

Address family Internet IP Protocol

AF_INET6 = 10

Address family IP version 6

AF_IPX = 4

Address family Novell IPX

AF_IRDA = 23

Address family: IRDA sockets

AF_KEY = 15

Address family: PF_KEY key management API

AF_LLC = 26

Address family: Linux LLC

AF_LOCAL = 1

Address family: Unix socket

AF_MAX = 32

Address family Maximum value

AF_NETBEUI = 13

Address family: Reserved for 802.2LLC project

AF_NETLINK = 16

Address family: ?

AF_NETROM = 6

Address family Amateur radio NetROM

AF_PACKET = 17

Address family: Packet family

AF_PPPOX = 24

Address family: PPPoX sockets

AF_ROSE = 11

Address family: Amateur Radio X.25 PLP

AF_ROUTE = AF_NETLINK

Address family: Alias to emulate 4.4BSD.

AF_SECURITY = 14

Address family: Security callback pseudo AF

AF_SNA = 22

Address family: Linux SNA project

AF_TIPC = 30

Address family: TIPC sockets

AF_UNIX = 1

Address family Unix domain sockets

AF_UNSPEC = 0

Address family Not specified

AF_WANPIPE = 25

Address family: Wanpipe API Sockets

`AF_X25 = 9`

Address family Reserved for X.25 project

`EsockADDRINUSE = ESysEADDRINUSE`

`EsockADDRINUSE` is the error reported by `fpBind` ([1133](#)) when the socket is already in use.

`EsockEACCESS = ESysEAcces`

Access forbidden error

`EsockEBADF = ESysEBADF`

Alias: bad file descriptor

`EsockEFAULT = ESysEFAULT`

Alias: an error occurred

`EsockEINTR = ESysEINTR`

Alias : operation interrupted

`EsockEINVAL = ESysEINVAL`

Alias: Invalid value specified

`EsockEMFILE = ESysEmfile`

Error code ?

`EsockEMSGSIZE = ESysEMsgSize`

Wrong message size error

`EsockENOBUFFS = ESysENoBufs`

No buffer space available error

`EsockENOTCONN = ESysENotConn`

Not connected error

`EsockENOTSOCK = ESysENotSock`

File descriptor is not a socket error

`EsockEPROTONOSUPPORT = ESysEProtoNoSupport`

Protocol not supported error

`EsockEWOULDBLOCK = ESysEWouldBlock`

Operation would block error

`INADDR_ANY = (0)`

A bitmask matching any IP address on the local machine.

`INADDR_NONE = ($FFFFFFFF)`

A bitmask matching no valid IP address

`IPPROTO_AH = 51`

authentication header.

`IPPROTO_COMP = 108`

Compression Header Protocol.

`IPPROTO_DSTOPTS = 60`

IPv6 destination options.

`IPPROTO_EGP = 8`

Exterior Gateway Protocol.

`IPPROTO_ENCAP = 98`

Encapsulation Header.

`IPPROTO_ESP = 50`

encapsulating security payload.

`IPPROTO_FRAGMENT = 44`

IPv6 fragmentation header.

`IPPROTO_GRE = 47`

General Routing Encapsulation.

`IPPROTO_HOPOPTS = 0`

IPv6 Hop-by-Hop options.

`IPPROTO_ICMP = 1`

Internet Control Message Protocol.

IPPROTO_ICMPV6 = 58

ICMPv6.

IPPROTO_IDP = 22

XNS IDP protocol.

IPPROTO_IGMP = 2

Internet Group Management Protocol.

IPPROTO_IP = 0

Dummy protocol for TCP.

IPPROTO_IPIP = 4

IPIP tunnels (older KA9Q tunnels use 94).

IPPROTO_IPV6 = 41

IPv6 header.

IPPROTO_MAX = 255

Maximum value for IPPROTO options

IPPROTO_MTP = 92

Multicast Transport Protocol.

IPPROTO_NONE = 59

IPv6 no next header.

IPPROTO_PIM = 103

Protocol Independent Multicast.

IPPROTO_PUP = 12

PUP protocol.

IPPROTO_RAW = 255

Raw IP packets.

IPPROTO_ROUTING = 43

IPv6 routing header.

IPPROTO_RSVP = 46

Reservation Protocol.

IPPROTO_SCTP = 132

Stream Control Transmission Protocol.

IPPROTO_TCP = 6

Transmission Control Protocol.

IPPROTO_TP = 29

SO Transport Protocol Class 4.

IPPROTO_UDP = 17

User Datagram Protocol.

IPV6_ADDRFORM = 1

Change the IPV6 address into a different address family. Deprecated

IPV6_ADD_MEMBERSHIP = IPV6_JOIN_GROUP

Undocumented Getsockopt option ?

IPV6_AUTHHDR = 10

GetSockOpt/SetSockopt: Deliver authentication header messages

IPV6_CHECKSUM = 7

Undocumented Getsockopt option ?

IPV6_DROP_MEMBERSHIP = IPV6_LEAVE_GROUP

Undocumented Getsockopt option ?

IPV6_DSTOPTS = 4

Deliver destination option control messages

IPV6_HOPLIMIT = 8

Deliver an integer containing the HOP count

IPV6_HOPOPTS = 3

Deliver hop option control messages

IPV6_IPSEC_POLICY = 34

Undocumented Getsockopt option ?

IPV6_JOIN_ANYCAST = 27

Undocumented Getsockopt option ?

IPV6_JOIN_GROUP = 20

GetSockOpt/SetSockopt: Control membership (join group) in multicast groups

IPV6_LEAVE_ANYCAST = 28

Undocumented Getsockopt option ?

IPV6_LEAVE_GROUP = 21

GetSockOpt/SetSockopt: Control membership (leave group) in multicast groups

IPV6_MTU = 24

GetSockOpt/SetSockopt: Get/Set the MTU for the socket

IPV6_MTU_DISCOVER = 23

GetSockOpt/SetSockopt: Get/Set Control path MTU Discovery on the socket

IPV6_MULTICAST_HOPS = 18

GetSockOpt/SetSockopt: Get/Set the multicast hop limit.

IPV6_MULTICAST_IF = 17

GetSockOpt/SetSockopt: Get/Set device for multicast packages on the socket.

IPV6_MULTICAST_LOOP = 19

GetSockOpt/SetSockopt: Control whether socket sees multicast packages that it has sent itself

IPV6_NEXTHOP = 9

sendmsg: set next hop for IPV6 datagram

IPV6_PKTINFO = 2

Change delivery options for incoming IPV6 datagrams

IPV6_PKTOPTIONS = 6

Undocumented Getsockopt option ?

IPV6_PMTUDISC_DO = 2

Always DF.

IPV6_PMTUDISC_DONT = 0

Never send DF frames.

IPV6_PMTUDISC_WANT = 1

Use per route hints.

IPV6_RECVERR = 25

GetSockOpt/SetSockopt: Control receiving of asynchronous error options

IPV6_ROUTER_ALERT = 22

GetSockOpt/SetSockopt: Get/Set Pass all forwarded packets containing router alert option

IPV6_RTHDR = 5

Deliver routing header control messages

IPV6_RTHDR_LOOSE = 0

Hop doesn't need to be neighbour.

IPV6_RTHDR_STRICT = 1

Hop must be a neighbour.

IPV6_RTHDR_TYPE_0 = 0

IPv6 Routing header type 0.

IPV6_RXDSTOPTS = IPV6_DSTOPTS

Undocumented Getsockopt option ?

IPV6_RXHOPOPTS = IPV6_HOPOPTS

Undocumented Getsockopt option ?

IPV6_RXSRCRT = IPV6_RTHDR

Undocumented Getsockopt option ?

IPV6_UNICAST_HOPS = 16

GetSockOpt/SetSockopt: Get/Set unicast hop limit

IPV6_V6ONLY = 26

GetSockOpt/SetSockopt: Handle IPV6 connections only

IPV6_XFRM_POLICY = 35

Undocumented Getsockopt option ?

IP_ADD_MEMBERSHIP = 35

add an IP group membership

IP_ADD_SOURCE_MEMBERSHIP = 39

join source group

IP_BLOCK_SOURCE = 38

block data from source

IP_DEFAULT_MULTICAST_LOOP = 1

Undocumented ?

IP_DEFAULT_MULTICAST_TTL = 1

Undocumented ?

IP_DROP_MEMBERSHIP = 36

drop an IP group membership

IP_DROP_SOURCE_MEMBERSHIP = 40

leave source group

IP_HDRINCL = 3

Header is included with data.

IP_MAX_MEMBERSHIPS = 20

Maximum group memberships for multicast messages

IP_MSFILTER = 41

Undocumented ?

IP_MTU_DISCOVER = 10

Undocumented ?

IP_MULTICAST_IF = 32

set/get IP multicast i/f

IP_MULTICAST_LOOP = 34

set/get IP multicast loopback

IP_MULTICAST_TTL = 33

set/get IP multicast ttl

IP_OPTIONS = 4

IP per-packet options.

IP_PKTINFO = 8

Undocumented ?

IP_PKTOPTIONS = 9

Undocumented ?

IP_PMTUDISC = 10

Undocumented ?

IP_PMTUDISC_DO = 2

Always DF.

IP_PMTUDISC_DONT = 0

Never send DF frames.

IP_PMTUDISC_WANT = 1

Use per route hints.

IP_RECVERR = 11

Undocumented ?

IP_RECVOPTS = 6

Receive all IP options w/datagram.

IP_RECVRETOPTS = IP_RETOPTS

Receive IP options for response.

IP_RECVTOS = 13

Undocumented ?

IP_RECVTTL = 12

Undocumented ?

IP_RETOPTS = 7

Set/get IP per-packet options.

IP_ROUTER_ALERT = 5

Undocumented ?

IP_TOS = 1

IP type of service and precedence.

IP_TTL = 2

IP time to live.

IP_UNBLOCK_SOURCE = 37

unblock data from source

MCAST_BLOCK_SOURCE = 43

block from given group

MCAST_EXCLUDE = 0

Undocumented ?

MCAST_INCLUDE = 1

Undocumented ?

MCAST_JOIN_GROUP = 42

join any-source group

MCAST_JOIN_SOURCE_GROUP = 46

join source-spec group

MCAST_LEAVE_GROUP = 45

leave any-source group

MCAST_LEAVE_SOURCE_GROUP = 47

leave source-spec group

MCAST_MSFILTER = 48

Undocumented ?

MCAST_UNBLOCK_SOURCE = 44

unblock from given group

MSG_CONFIRM = \$0800

Send flags: Conform connection

MSG_CTRUNC = \$0008

Receive flags: Control Data was discarded (buffer too small)

MSG_DONTROUTE = \$0004

Send flags: don't use gateway

MSG_DONTWAIT = \$0040

Receive flags: Non-blocking operation request.

MSG_EOF = MSG_FIN

Alias for MSG_FIN

MSG_EOR = \$0080

Receive flags: End of record

MSG_ERRQUEUE = \$2000

Receive flags: ?

MSG_FIN = \$0200

Receive flags: ?

MSG_MORE = \$8000

Receive flags: ?

MSG_NOSIGNAL = \$4000

Receive flags: Suppress SIG_PIPE signal.

MSG_OOB = \$0001

Receive flags: receive out-of-band data.

MSG_PEEK = \$0002

Receive flags: peek at data, don't remove from buffer.

MSG_PROXY = \$0010

Receive flags: ?

MSG_RST = \$1000

Receive flags: ?

MSG_SYN = \$0400

Receive flags: ?

MSG_TRUNC = \$0020

Receive flags: packet Data was discarded (buffer too small)

MSG_TRYHARD = MSG_DONTROUTE

Receive flags: ?

MSG_WAITALL = \$0100

Receive flags: Wait till operation completed.

NoAddress : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoAddress6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

NoNet : in_addr = (s_addr: 0)

Constant indicating invalid (no) network address.

NoNet6 : in6_addr = (u6_addr16: (0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0, 0))

Constant indicating invalid (no) IPV6 network address.

PF_APPLETALK = AF_APPLETALK

Protocol family: Appletalk DDP

PF_ASH = AF_ASH

Protocol family: Ash

PF_ATMPVC = AF_ATMPVC

Protocol family: ATM PVCs

PF_ATMSVC = AF_ATMSVC

Protocol family: ATM SVCs

PF_AX25 = AF_AX25

Protocol family: Amateur Radio AX.25

PF_BLUETOOTH = AF_BLUETOOTH

Protocol family: Bluetooth sockets

PF_BRIDGE = AF_BRIDGE

Protocol family: Multiprotocol bridge

PF_DECnet = AF_DECnet

Protocol Family: DECNET project

PF_ECONET = AF_ECONET

Protocol family: Acorn Econet

PF_INET = AF_INET

Protocol family: Internet IP Protocol

PF_INET6 = AF_INET6

Protocol family: IP version 6

PF_IPX = AF_IPX

Protocol family: Novell IPX

PF_IRDA = AF_IRDA

Protocol family: IRDA sockets

PF_KEY = AF_KEY

Protocol family: Key management API

PF_LLCC = AF_LLCC

Protocol family: Linux LLC

PF_LOCAL = AF_LOCAL

Protocol family: Unix socket

PF_MAX = AF_MAX

Protocol family: Maximum value

PF_NETBEUI = AF_NETBEUI

Protocol family: Reserved for 802.2LLC project

PF_NETLINK = AF_NETLINK

Protocol family: ?

PF_NETROM = AF_NETROM

Protocol family:Amateur radio NetROM

PF_PACKET = AF_PACKET

Protocol family: Packet family

PF_PPPOX = AF_PPPOX

Protocol family: PPPoX sockets

PF_ROSE = AF_ROSE

Protocol family: Amateur Radio X.25 PLP

PF_ROUTE = AF_ROUTE

Protocol Family: ?

PF_SECURITY = AF_SECURITY

Protocol family: Security callback pseudo PF

PF_SNA = AF_SNA

Protocol Family: Linux SNA project

PF_TIPC = AF_TIPC

Protocol family: TIPC sockets

PF_UNIX = AF_UNIX

Protocol family: Unix domain sockets

PF_UNSPEC = AF_UNSPEC

Protocol family: Unspecified

PF_WANPIPE = AF_WANPIPE

Protocol family: Wanpipe API Sockets

PF_X25 = AF_X25

Protocol family: Reserved for X.25 project

SCM_SRCRT = IPV6_RXSRCRT

Undocumented Getsockopt option ?

SCM_TIMESTAMP = SO_TIMESTAMP

Socket option: ?

SHUT_RD = 0

Shutdown read part of full duplex socket

SHUT_RDWR = 2

Shutdown read and write part of full duplex socket

SHUT_WR = 1

Shutdown write part of full duplex socket

SOCK_DGRAM = 2

Type of socket: datagram (conn.less) socket (UDP)

SOCK_MAXADDRLLEN = 255

Maximum socket address length for Bind ([1130](#)) call.

SOCK_RAW = 3

Type of socket: raw socket

SOCK_RDM = 4

Type of socket: reliably-delivered message

SOCK_SEQPACKET = 5

Type of socket: sequential packet socket

SOCK_STREAM = 1

Type of socket: stream (connection) type socket (TCP)

SOL_ICMPV6 = 58

Socket level values for IPv6: ICMPV6

SOL_IP = 0

Undocumented ?

SOL_IPV6 = 41

Socket level values for IPv6: IPV6

SOL_SOCKET = 1

Socket option level: Socket level

SOMAXCONN = 128

Maximum queue length specifiable by listen.

SO_ACCEPTCONN = 30

Socket option: ?

SO_ATTACH_FILTER = 26

Socket option: ?

SO_BINDTODEVICE = 25

Socket option: ?

SO_BROADCAST = 6

Socket option: Broadcast

SO_BSDCOMPAT = 14

Socket option: ?

SO_DEBUG = 1

Socket option level: debug

SO_DETACH_FILTER = 27

Socket option: ?

SO_DONTROUTE = 5

Socket option: Don't route

SO_ERROR = 4

Socket option: Error

SO_KEEPAIVE = 9

Socket option: keep alive

SO_LINGER = 13

Socket option: ?

SO_NO_CHECK = 11

Socket option: ?

SO_OOBNLINE = 10

Socket option: ?

SO_PASSCRED = 16

Socket option: ?

SO_PEERCREC = 17

Socket option: ?

SO_PEERNAME = 28

Socket option: ?

SO_PRIORITY = 12

Socket option: ?

SO_RCVBUF = 8

Socket option: receive buffer

SO_RCVLOWAT = 18

Socket option: ?

SO_RCVTIMEO = 20

Socket option: ?

SO_REUSEADDR = 2

Socket option: Reuse address

SO_SECURITY_AUTHENTICATION = 22

Socket option: ?

SO_SECURITY_ENCRYPTION_NETWORK = 24

Socket option: ?

SO_SECURITY_ENCRYPTION_TRANSPORT = 23

Socket option: ?

SO_SNDBUF = 7

Socket option: Send buffer

SO_SNDLOWAT = 19

Socket option: ?

SO_SNDTIMEO = 21

Socket option: ?

SO_TIMESTAMP = 29

Socket option: ?

SO_TYPE = 3

Socket option: Type

S_IN = 0

Input socket in socket pair.

S_OUT = 1

Output socket in socket pair

TCP_CONGESTION = 13

Get/set the congestion-control algorithm for this socket

TCP_CORK = 3

Get/Set CORK algorithm: Send only complete packets

TCP_DEFER_ACCEPT = 9

Get/Set deferred accept on server socket

TCP_INFO = 11

Get TCP connection information (Linux only)

TCP_KEEPCNT = 6

Get/Set retry count for unacknowledged KEEPALIVE transmissions.

TCP_KEEPIDL = 4

Get/Set inactivity interval between KEEPALIVE transmissions.

TCP_KEEPINTVL = 5

Get/Set retry interval for unacknowledged KEEPALIVE transmissions.

TCP_LINGER2 = 8

Get/Set Linger2 flag

TCP_MAXSEG = 2

Get/Set Maximum segment size

TCP_MD5SIG = 14

Get/Set TCP MD5 signature option

TCP_NODELAY = 1

Get/Set No delay flag: disable Nagle algorithm

TCP_QUICKACK = 12

Get/Set quick ACK packet option.

TCP_SYNCNT = 7

Get/Set number of SYN packets to send before giving up on connection establishment

TCP_WINDOW_CLAMP = 10

Get/Set maximum packet size

UDP_CORK = 1

Get/Set UDP CORK algorithm on datagram sockets

UDP_ENCAP = 100

Get/Set UDP encapsulation flag for IPSec datagram sockets

UDP_ENCAP_ESPINUDP = 2

? Undocumented datagram option, IPSec related

UDP_ENCAP_ESPINUDP_NON_IKE = 1

? Undocumented datagram option, IPSec related

UDP_ENCAP_L2TPINUDP = 3

? Undocumented datagram option, IPSec related

72.3.2 Types

```
in6_addr = packed record
case Byte of
0: (
  u6_addr8 : Array[0..15
  ] of Byte;
);
1: (
  u6_addr16 : Array[0..7] of Word;
);
2: (
  u6_addr32
  : Array[0..3] of Cardinal;
);
3: (
  s6_addr8 : Array[0..15] of ShortInt
  ;
);
4: (
  s6_addr : Array[0..15] of ShortInt;
);
5: (
  s6_addr16
  : Array[0..7] of SmallInt;
);
6: (
  s6_addr32 : Array[0..3] of LongInt
  ;
);
end
```

Record used to describe a general IPV6 address.

```
in_addr = packed record
case Boolean of
True: (
  s_addr : cuint32
  ;
);
False: (
  s_bytes : packed Array[1..4] of Byte;
);
end
```

General inet socket address.

```
linger = packed record
  l_onoff : cint;
  l_linger : cint;
end
```

This record is used in the `fpsetsockopt` ([1139](#)) call to specify linger options.

```
PIn6Addr = pin6_addr
```

Pointer to `in6_addr` ([1124](#)) type.

```
pin6_addr = ^in6_addr
```

Pointer to `Tin6_addr` ([1127](#))

```
PInAddr = pin_addr
```

Alias for `pin_addr` ([1125](#))

```
PInetSockAddr = psockaddr_in
```

Pointer to `sockaddr_in` ([1126](#))

```
PInetSockAddr6 = psockaddr_in6
```

Pointer to `sockaddr_in6` ([1127](#)) type

```
pin_addr = ^in_addr
```

Pointer to `in_addr` ([1125](#)) record.

```
plinger = ^linger
```

Pointer to `linger` ([1125](#)) type.

```
psockaddr = ^sockaddr
```

Pointer to TSocketAddr (1127)

```
PSockAddr6 = ^TSockAddr6
```

PSockAddr6 is a pointer to a record of type TSocketAddr6 (1128).

```
psockaddr_in = ^sockaddr_in
```

Pointer to sockaddr_in (1126)

```
psockaddr_in6 = ^sockaddr_in6
```

Pointer to sockaddr_in6 (1127)

```
psockaddr_un = ^sockaddr_un
```

Pointer to sockaddr_un (1127) type.

```
sa_family_t = cushort
```

Address family type

```
sockaddr = packed record
case Integer of
0: (
  sa_family : sa_family_t
  ;
  sa_data : packed Array[0..13] of cuint8;
);
1: (
  sin_family
  : sa_family_t;
  sin_port : cushort;
  sin_addr : in_addr;
  sin_zero
  : packed Array[0..7] of cuint8;
);
end
```

sockaddr is used to store a general socket address for the FPBind (1133), FRecv (1137) and FSend (1138) calls.

```
sockaddr_in = packed record
  sin_family : sa_family_t;
  sin_port
  : cushort;
  sin_addr : in_addr;
  xpad : Array[0..7] of Char;
end
```

sockaddr_in is used to store a INET socket address for the FPBind (1133), FRecv (1137) and FSend (1138) calls.

```

sockaddr_in6 = packed record
  sin6_family : sa_family_t;
  sin6_port
  : cuint16;
  sin6_flowinfo : cuint32;
  sin6_addr : in6_addr;
  sin6_scope_id
  : cuint32;
end

```

Alias for `sockaddr_in6` ([1127](#))

```

sockaddr_un = packed record
  sun_family : sa_family_t;
  sun_path
  : Array[0..107] of Char;
end

```

`sockaddr_un` is used to store a UNIX socket address for the `FPBind` ([1133](#)), `FPRecv` ([1137](#)) and `FPSend` ([1138](#)) calls.

```
TIn6Addr = in6_addr
```

Alias for `in6_addr` ([1124](#)) type.

```
Tin6_addr = in6_addr
```

Alias for `sockaddr_in6` ([1127](#))

```
TInAddr = in_addr
```

Alias for `in_addr` ([1125](#)) record type.

```
TInetSockAddr = sockaddr_in
```

Alias for `sockaddr_in` ([1126](#))

```
TInetSockAddr6 = sockaddr_in6
```

Alias for `sockaddr_in6` ([1127](#))

```
TIn_addr = in_addr
```

Alias for `in_addr` ([1125](#)) record type.

```
TLinger = linger
```

Alias for `linger` ([1125](#))

```
TSockAddr = sockaddr
```


`TSockAddr6 = sockaddr_in6`

`TSockAddr6` is an alias for `sockaddr6_in` (1103)

`TSockArray = Array[1..2] of LongInt`

Type returned by the `FPSocketPair` (1141) call.

`Tsocket = LongInt`

Alias for easy kyllix porting

`TSockLen = BaseUnix.TSocklen`

The actual type of `TSockLen` depends on the platform.

`TSockPairArray = Array[0..1] of LongInt`

Array of sockets, used in `FPSocketPair` (1141) call.

```
TUnixSockAddr = packed record
  family : sa_family_t;
  path : Array
    [0..107] of Char;
end
```

Alias for `sockaddr_un` (1127)

72.4 Procedures and functions

72.4.1 Accept

Synopsis: Accept a connection from a socket (deprecated).

Declaration:

```
function Accept(Sock: LongInt; var addr: TInetSockAddr;
               var SockIn: File; var SockOut: File) : Boolean
function Accept(Sock: LongInt; var addr: TInetSockAddr;
               var SockIn: text; var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: text;
               var SockOut: text) : Boolean
function Accept(Sock: LongInt; var addr: string; var SockIn: File;
               var SockOut: File) : Boolean
```

Visibility: default

Description: `Accept` accepts a connection from a socket `Sock`, which was listening for a connection. If a connection is accepted, a file descriptor is returned. On error `-1` is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The `Accept` call fills the address of the connecting entity in `Addr`, and sets its length in `AddrLen`. `Addr` should be pointing to enough space, and `AddrLen` should be set to the amount of space available, prior to the call.

The alternate forms of the `Accept` (1128) command, with the `Text` or `File` parameters are equivalent to subsequently calling the regular `Accept` (1128) function and the `Sock2Text` (1144) or `Sock2File` (1144) functions. These functions return `True` if successful, `False` otherwise.

Errors: On error, -1 is returned, and errors are reported in `SocketError`, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOTSOCK (1106)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the `Listen` operation.

ESockEFAULT (1106)`Addr` points outside your address space.

ESockEWOULDBLOCK (1107)The requested operation would block the process.

See also: `FPListen` (1137), `Connect` (1130), `FPConnect` (1134), `FPBind` (1133)

Listing: `./sockex/socksvr.pp`

```

Program server ;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets ;

Var
  FromName : string ;
  Buffer    : string[255] ;
  S         : Longint ;
  Sin, Sout : Text ;
  SAddr     : TInetSockAddr ;

procedure perror (const S:string) ;
begin
  writeln (S, SocketError) ;
  halt(100) ;
end ;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0) ;
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET ;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000) ;
  SAddr.sin_addr.s_addr:=0 ;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    Perror ('Server : Bind : ');
  if fpListen (S,1)=-1 then
    Perror ('Server : Listen : ');
  Writeln ('Waiting for Connect from Client, run now sock_cli in an other tty');
  if Accept(S, FromName, Sin, Sout) then
    Perror ('Server : Accept : '+fromname) ;
  Reset(Sin) ;
  Rewrite(Sout) ;
  Writeln(Sout, 'Message From Server') ;
  Flush(SOut) ;
  while not eof(sin) do
    begin
      Readln(Sin, Buffer) ;
    
```

```

    WriteLn('Server : read : ',buffer);
end;
end.

```

72.4.2 Bind

Synopsis: Alias for `fpBind`.

Declaration: `function Bind(Sock: LongInt; const addr: string) : Boolean`

Visibility: default

Description: `Bind` is an alias for `fpBind` (1133) which binds to either a socket struct (`Addr`) or a string indicating a unix socket file (unix socket).

This function is deprecated, use `fpBind` instead.

See also: `FPBind` (1133)

72.4.3 CloseSocket

Synopsis: Closes a socket handle.

Declaration: `function CloseSocket(Sock: LongInt) : LongInt`

Visibility: default

Description: `CloseSocket` closes a socket handle. It returns 0 if the socket was closed successfully, -1 if it failed.

Errors: On error, -1 is returned.

See also: `FPSocket` (1140)

72.4.4 Connect

Synopsis: Open a connection to a server socket (deprecated).

Declaration: `function Connect(Sock: LongInt; const addr: TInetSockAddr;`
 `var SockIn: text; var SockOut: text) : Boolean`
 `function Connect(Sock: LongInt; const addr: TInetSockAddr;`
 `var SockIn: File; var SockOut: File) : Boolean`
 `function Connect(Sock: LongInt; const addr: string; var SockIn: text;`
 `var SockOut: text) : Boolean`
 `function Connect(Sock: LongInt; const addr: string; var SockIn: File;`
 `var SockOut: File) : Boolean`

Visibility: default

Description: `Connect` opens a connection to a peer, whose address is described by `Addr`. `AddrLen` contains the length of the address. The type of `Addr` depends on the kind of connection you're trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The forms of the `Connect` (1130) command with the `Text` or `File` arguments are equivalent to subsequently calling the regular `Connect` function and the `Sock2Text` (1144) or `Sock2File` (1144) functions. These functions return `True` if successful, `False` otherwise.

The `Connect` function returns a file descriptor if the call was successful, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `FPListen` (1137), `FPBind` (1133), `Accept` (1128), `FPAccept` (1132)

Listing: ./sockex/sockcli.pp

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

procedure PError(const S : string);

begin

writeln(S, SocketError);

halt(100);

end;

Var

 SAddr : TInetSockAddr;

 Buffer : string [255];

 S : Longint;

 Sin, Sout : Text;

 i : integer;

begin

 S:=fpSocket (AF_INET, SOCK_STREAM, 0);

if s=-1 **then**

 PError('Client : Socket : ');

 SAddr.sin_family:=AF_INET;

 { port 50000 in network order }

 SAddr.sin_port:=htons(5000);

 { localhost : 127.0.0.1 in network order }

 SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);

if not Connect (S, SAddr, Sin, Sout) **then**

 PError('Client : Connect : ');

Reset(Sin);

ReWrite(Sout);

 Buffer:='This is a textstring sent by the Client.';

for i:=1 **to** 10 **do**

Writeln(Sout, Buffer);

Flush(Sout);

Readln(Sin, Buffer);

WriteLn(Buffer);

 Close(sout);

end.

Listing: ./sockex/pfinger.pp

program pfinger;

uses sockets, errors;

Var

```

Addr : TInetSockAddr;
S : Longint;
Sin, Sout : Text;
Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
    rewrite (sout);
    reset(sin);
    writeln (sout,paramstr(1));
    flush(sout);
    while not eof(sin) do
      begin
        readln (Sin,line);
        writeln (line);
      end;
    fpShutdown(s,2);
    close (sin);
    close (sout);
end.

```

72.4.5 fpaccept

Synopsis: Accept a connection from a socket.

Declaration: function fpaccept(s: cint; addrx: psockaddr; addrlen: pSockLen) : cint

Visibility: default

Description: **Accept** accepts a connection from a socket **S**, which was listening for a connection. If a connection is accepted, a file descriptor is returned (positive number). On error **-1** is returned. The returned socket may NOT be used to accept more connections. The original socket remains open.

The **Accept** call fills the address of the connecting entity in **Addrx**, and sets its length in **Addrlen**. **Addrx** should be pointing to enough space, and **Addrlen** should be set to the amount of space available, prior to the call.

Errors: On error, **-1** is returned, and errors are reported in **SocketError**, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOTSOCK (1106)The descriptor is not a socket.

SYS_EOPNOTSUPPThe socket type doesn't support the **Listen** operation.

ESockEFAULT (1106)**Addr** points outside your address space.

ESockEWOULDBLOCK (1107)The requested operation would block the process.

See also: [fpListen \(1137\)](#), [fpConnect \(1134\)](#), [fpBind \(1133\)](#)

Listing: ./sockex/socksvr.pp

```

Program server;

{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Server Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
{$mode fpc}
uses Sockets;

Var
  FromName : string;
  Buffer    : string[255];
  S         : Longint;
  Sin, Sout : Text;
  SAddr     : TInetSockAddr;

procedure perror (const S:string);
begin
  writeln (S, SocketError);
  halt(100);
end;

begin
  S:=fpSocket (AF_INET, SOCK_STREAM, 0);
  if SocketError<>0 then
    Perror ('Server : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  SAddr.sin_addr.s_addr:=0;
  if fpBind(S, @SAddr, sizeof(saddr))=-1 then
    Perror ('Server : Bind : ');
  if fpListen (S, 1)=-1 then
    Perror ('Server : Listen : ');
  Writeln ('Waiting for Connect from Client, run now sock_cli in an other tty');
  if Accept(S, FromName, Sin, Sout) then
    Perror ('Server : Accept : '+fromname);
  Reset(Sin);
  ReWrite(Sout);
  Writeln(Sout, 'Message From Server');
  Flush(SOut);
  while not eof(sin) do
    begin
      Readln(Sin, Buffer);
      Writeln('Server : read : ', buffer);
    end;
end.

```

72.4.6 fpbind

Synopsis: Bind a socket to an address.

Declaration: `function fpbind(s: cint; addrx: psockaddr; addrlen: TSockLen) : cint`

Visibility: default

Description: `fpBind` binds the socket `s` to address `Addrx`. `Addrx` has length `AddrLen`. The function returns 0 if the call was succesful, -1 if not.

Errors: Errors are returned in `SocketError` and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockEINVAL (1106)The socket is already bound to an address,

ESockEACCESS (1106)Address is protected and you don't have permission to open it.

More errors can be found in the Unix man pages.

See also: `FPsocket` (1140)

72.4.7 fpconnect

Synopsis: Open a connection to a server socket.

Declaration: `function fpconnect(s: cint; name: psockaddr; namelen: TSockLen) : cint`

Visibility: default

Description: `fpConnect` uses the socket `s` to open a connection to a peer, whose address is described by `Name`. `NameLen` contains the length of the address. The type of `Name` depends on the kind of connection you are trying to make, but is generally one of `TSockAddr` or `TUnixSockAddr`.

The `fpConnect` function returns zero if the call was successfull, -1 in case of error.

Errors: On error, -1 is returned and errors are reported in `SocketError`.

See also: `fpListen` (1137), `fpBind` (1133), `fpAccept` (1132)

Listing: `./sockex/sockcli.pp`

Program Client;

```
{
  Program to test Sockets unit by Michael van Canneyt and Peter Vreman
  Client Version, First Run sock_svr to let it create a socket and then
  sock_cli to connect to that socket
}
```

uses Sockets;

```
procedure PError(const S : string);
begin
  writeln(S, SocketError);
  halt(100);
end;
```

Var

```
SAddr    : TInetSockAddr;
Buffer   : string [255];
S         : Longint;
Sin, Sout : Text;
i         : integer;
```

```

begin
  S:=fpSocket (AF_INET,SOCK_STREAM,0);
  if s=-1 then
    Perror('Client : Socket : ');
  SAddr.sin_family:=AF_INET;
  { port 50000 in network order }
  SAddr.sin_port:=htons(5000);
  { localhost : 127.0.0.1 in network order }
  SAddr.sin_addr.s_addr:=HostToNet((127 shl 24) or 1);
  if not Connect (S,SAddr,Sin,Sout) then
    Perror('Client : Connect : ');
  Reset(Sin);
  Rewrite(Sout);
  Buffer:='This is a textstring sent by the Client.';
  for i:=1 to 10 do
    Writeln(Sout,Buffer);
  Flush(Sout);
  Readln(Sin,Buffer);
  Writeln(Buffer);
  Close(sout);
end.

```

Listing: ./sockex/pfinger.pp

```

program pfinger;

uses sockets,errors;

Var
  Addr : TInetSockAddr;
  S : Longint;
  Sin,Sout : Text;
  Line : string;

begin
  Addr.sin_family:=AF_INET;
  { port 79 in network order }
  Addr.sin_port:=79 shl 8;
  { localhost : 127.0.0.1 in network order }
  Addr.sin_addr.s_addr:=((1 shl 24) or 127);
  S:=fpSocket(AF_INET,SOCK_STREAM,0);
  If Not Connect (S,ADDR,SIN,SOUT) Then
    begin
      Writeln ('Couldn't connect to localhost');
      Writeln ('Socket error : ',strerror(SocketError));
      halt(1);
    end;
  rewrite (sout);
  reset(sin);
  writeln (sout,paramstr(1));
  flush(sout);
  while not eof(sin) do
    begin
      readln (Sin,line);
      writeln (line);
    end;
  fpShutdown(s,2);
  close (sin);
  close (sout);

```

`end.`

72.4.8 `fpgetpeername`

Synopsis: Return the name (address) of the connected peer.

Declaration: `function fpgetpeername(s: cint; name: psockaddr; namelen: pSockLen)
: cint`

Visibility: `default`

Description: `fpGetPeerName` returns the name of the entity connected to the specified socket `S`. The Socket must be connected for this call to work.

`Name` should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, `Name` will be filled with the name, and `Name` will be set to the length of `Name`.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOBUFS (1106)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1106)The descriptor is not a socket.

ESockEFAULT (1106)`Addr` points outside your address space.

ESockENOTCONN (1106)The socket isn't connected.

See also: `fpConnect` (1134), `fpSocket` (1140)

72.4.9 `fpgetsockname`

Synopsis: Return name of socket.

Declaration: `function fpgetsockname(s: cint; name: psockaddr; namelen: pSockLen)
: cint`

Visibility: `default`

Description: `fpGetSockName` returns the current name of the specified socket `S`. `Name` should point to enough space to store the name, the amount of space pointed to should be set in `Namelen`. When the function returns successfully, `Name` will be filled with the name, and `Namelen` will be set to the length of `Name`.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOBUFS (1106)The system doesn't have enough buffers to perform the operation.

ESockENOTSOCK (1106)The descriptor is not a socket.

ESockEFAULT (1106)`Addr` points outside your address space.

See also: `fpBind` (1133)

72.4.10 fpgetsockopt

Synopsis: Get current socket options

Declaration: `function fpgetsockopt(s: cint; level: cint; optname: cint;
optval: pointer; optlen: pSockLen) : cint`

Visibility: default

Description: `fpGetSockOpt` gets the connection option `optname`, for socket `S`. The socket may be obtained from different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKET From the socket itself.

XXX set `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The options are stored in the memory location pointed to by `optval`. `optlen` should point to the initial length of `optval`, and on return will contain the actual length of the stored data.

On success, 0 is returned. On Error, -1 is returned.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106) The socket descriptor is invalid.

ESockENOTSOCK (1106) The descriptor is not a socket.

ESockEFAULT (1106) `OptVal` points outside your address space.

See also: `fpSetSockOpt` (1139)

72.4.11 fplisten

Synopsis: Listen for connections on a socket.

Declaration: `function fplisten(s: cint; backlog: cint) : cint`

Visibility: default

Description: `fpListen` listens for up to `backlog` connections from socket `S`. The socket `S` must be of type `SOCK_STREAM` or `Sock_SEQPACKET`.

The function returns 0 if a connection was accepted, -1 if an error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106) The socket descriptor is invalid.

ESockENOTSOCK (1106) The descriptor is not a socket.

SYS_EOPNOTSUPP The socket type doesn't support the `Listen` operation.

See also: `fpSocket` (1140), `fpBind` (1133), `fpConnect` (1134)

72.4.12 fprecv

Synopsis: Receive data on socket

Declaration: `function fprecv(s: cint; buf: pointer; len: size_t; flags: cint)
: ssize_t`

Visibility: default

Description: `fpRecv` reads at most `len` bytes from socket `S` into address `buf`. The socket must be in a connected state. `Flags` can be one of the following:

- 1**Process out-of band data.
- 4**Bypass routing, use a direct interface.
- ??**Wait for full request or report an error.

The function returns the number of bytes actually read from the socket, or -1 if a detectable error occurred.

Errors: Errors are reported in `SocketError`, and include the following:

- ESockEBADF (1106)**The socket descriptor is invalid.
- ESockENOTCONN (1106)**The socket isn't connected.
- ESockENOTSOCK (1106)**The descriptor is not a socket.
- ESockEFAULT (1106)**The address is outside your address space.
- ESockEMSGSIZE (1106)**The message cannot be sent atomically.
- ESockEWOULDBLOCK (1107)**The requested operation would block the process.
- ESockENOBUFS (1106)**The system doesn't have enough free buffers available.

See also: `FPSend` (1138)

72.4.13 `fprecvfrom`

Synopsis: Receive data from an unconnected socket

Declaration: `function fprecvfrom(s: cint; buf: pointer; len: size_t; flags: cint; from: psockaddr; fromlen: pSockLen) : ssize_t`

Visibility: default

Description: `fpRecvFrom` receives data in buffer `Buf` with maximum length `Len` from socket `S`. Receipt is controlled by options in `Flags`. The location pointed to by `from` will be filled with the address from the sender, and its length will be stored in `fromlen`. The function returns the number of bytes received, or -1 on error. `AddrLen`.

Errors: On error, -1 is returned.

See also: `fpSocket` (1140), `fprecv` (1137)

72.4.14 `fpsend`

Synopsis: Send data through socket

Declaration: `function fpsend(s: cint; msg: pointer; len: size_t; flags: cint) : ssize_t`

Visibility: default

Description: `fpSend` sends `Len` bytes starting from address `Msg` to socket `S`. `S` must be in a connected state. Options can be passed in `Flags`.

The function returns the number of bytes sent, or -1 if a detectable error occurred.

`Flags` can be one of the following:

1Process out-of band data.

4Bypass routing, use a direct interface.

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOTSOCK (1106)The descriptor is not a socket.

ESockEFAULT (1106)The address is outside your address space.

ESockEMSGSIZE (1106)The message cannot be sent atomically.

ESockEWOULDBLOCK (1107)The requested operation would block the process.

ESockENOBUFS (1106)The system doesn't have enough free buffers available.

See also: `fpRecv` (1137)

72.4.15 `fpsendto`

Synopsis: Send data through an unconnected socket to an address.

Declaration: `function fpSendto(s: cint; msg: pointer; len: size_t; flags: cint; tox: psockaddr; tolen: TSocketLen) : ssize_t`

Visibility: default

Description: `fpSendto` sends data from buffer `Msg` with length `len` through socket `S` with options `Flags`. The data is sent to address `tox`, which has length `tolen`

Errors: On error, -1 is returned.

See also: `fpSocket` (1140), `fpSend` (1138), `fpRecvFrom` (1138)

72.4.16 `fpsetsockopt`

Synopsis: Set socket options.

Declaration: `function fpSetsockopt(s: cint; level: cint; optname: cint; optval: pointer; optlen: TSocketLen) : cint`

Visibility: default

Description: `fpSetSocketOpt` sets the connection options for socket `S`. The socket may be manipulated at different levels, indicated by `Level`, which can be one of the following:

SOL_SOCKETTo manipulate the socket itself.

XXXset `Level` to `XXX`, the protocol number of the protocol which should interpret the option.

The actual option is stored in a buffer pointed to by `optval`, with length `optlen`.

For more information on this call, refer to the unix manual page `setsockopt`

Errors: Errors are reported in `SocketError`, and include the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOTSOCK (1106)The descriptor is not a socket.

ESockEFAULT (1106)`OptVal` points outside your address space.

See also: `fpGetSocketOpt` (1137)

72.4.17 `fpshutdown`

Synopsis: Close one end of full duplex connection.

Declaration: `function fpshutdown(s: cint; how: cint) : cint`

Visibility: default

Description: `fpShutDown` closes one end of a full duplex socket connection, described by `S`. The parameter `How` determines how the connection will be shut down, and can be one of the following:

0Further receives are disallowed.

1Further sends are disallowed.

2Sending nor receiving are allowed.

On succes, the function returns 0, on error -1 is returned.

Errors: `SocketError` is used to report errors, and includes the following:

ESockEBADF (1106)The socket descriptor is invalid.

ESockENOTCONN (1106)The socket isn't connected.

ESockENOTSOCK (1106)The descriptor is not a socket.

See also: `fpSocket` (1140), `fpConnect` (1134)

72.4.18 `fpsocket`

Synopsis: Create new socket

Declaration: `function fpsocket(domain: cint; xtype: cint; protocol: cint) : cint`

Visibility: default

Description: `fpSocket` creates a new socket in domain `Domain`, from type `xType` using protocol `Protocol`. The `Domain`, `Socket` type and `Protocol` can be specified using predefined constants (see the section on constants for available constants) If succesfull, the function returns a socket descriptor, which can be passed to a subsequent `fpBind` (1133) call. If unsuccesfull, the function returns -1.

for an example, see `Accept` (1128).

Errors: Errors are returned in `SocketError`, and include the follwing:

ESockEPROTONOSUPPORT (1106)The protocol type or the specified protocol is not supported within this domain.

ESockEMFILE (1106)The per-process descriptor table is full.

SYS_ENFILEThe system file table is full.

ESockEACCESS (1106)Permission to create a socket of the specified type and/or protocol is denied.

ESockENOBUFS (1106)Insufficient buffer space is available. The socket cannot be created until sufficient resources are freed.

See also: `FPSocketPair` (1141)

72.4.19 fpsocketpair

Synopsis: Create socket pair.

Declaration: `function fpsocketpair(d: cint; xtype: cint; protocol: cint; sv: pcint) : cint`

Visibility: default

Description: `fpSocketPair` creates 2 sockets in domain `D`, from type `xType` and using protocol `Protocol`. The pair is returned in `sv`, and they are indistinguishable. The function returns -1 upon error and 0 upon success.

Errors: Errors are reported in `SocketError`, and are the same as in `FPSocket` (1140)

See also: `Str2UnixSockAddr` (1145)

72.4.20 HostAddrToStr

Synopsis: Convert a host address to a string.

Declaration: `function HostAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr` converts the host address in `Entry` to a string representation in human-readable form (a dotted quad).

Basically, it is the same as `NetAddrToStr` (1142), but with the bytes in correct order.

See also: `NetAddrToStr` (1142), `StrToHostAddr` (1145), `StrToNetAddr` (1145)

72.4.21 HostAddrToStr6

Synopsis: Convert a IPV6 host address to a string representation.

Declaration: `function HostAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `HostAddrToStr6` converts the IPV6 host address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` (1142), but with the bytes in correct order.

See also: `NetAddrToStr` (1142), `StrToHostAddr` (1145), `StrToNetAddr` (1145), `StrToHostAddr6` (1145)

72.4.22 HostToNet

Synopsis: Convert a host address to a network address

Declaration: `function HostToNet(Host: in_addr) : in_addr`
`function HostToNet(Host: LongInt) : LongInt`

Visibility: default

Description: `HostToNet` converts a host address to a network address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `NetToHost` (1143), `NToHS` (1143), `HToNS` (1142), `ShortHostToNet` (1143), `ShortNetToHost` (1144)

72.4.23 htonl

Synopsis: Convert long integer from host ordered to network ordered

Declaration: `function htonl(host: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `htonl` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htons` ([1142](#)), `ntohl` ([1143](#)), `ntohs` ([1143](#))

72.4.24 htons

Synopsis: Convert short integer from host ordered to network ordered

Declaration: `function htons(host: Word) : Word`

Visibility: default

Description: `htons` makes sure that the bytes in `host` are ordered in the correct way for sending over the network and returns the correctly ordered result.

See also: `htonl` ([1142](#)), `ntohl` ([1143](#)), `ntohs` ([1143](#))

72.4.25 NetAddrToStr

Synopsis: Convert a network address to a string.

Declaration: `function NetAddrToStr(Entry: in_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr` converts the network address in `Entry` to a string representation in human-readable form (a dotted quad).

See also: `HostAddrToStr` ([1141](#)), `StrToNetAddr` ([1145](#)), `StrToHostAddr` ([1145](#))

72.4.26 NetAddrToStr6

Synopsis: Convert a IPV6 network address to a string.

Declaration: `function NetAddrToStr6(Entry: Tin6_addr) : AnsiString`

Visibility: default

Description: `NetAddrToStr6` converts the IPV6 network address in `Entry` to a string representation in human-readable form.

Basically, it is the same as `NetAddrToStr6` ([1142](#)), but with the bytes in correct order.

See also: `NetAddrToStr` ([1142](#)), `StrToHostAddr` ([1145](#)), `StrToNetAddr` ([1145](#)), `StrToHostAddr6` ([1145](#))

72.4.27 NetToHost

Synopsis: Convert a network address to a host address.

Declaration: `function NetToHost (Net: in_addr) : in_addr`
`function NetToHost (Net: LongInt) : LongInt`

Visibility: default

Description: `NetToHost` converts a network address to a host address. It takes care of endianness of the host machine. The address can be specified as a dotted quad or as a longint.

Errors: None.

See also: `HostToNet` (1141), `NToHS` (1143), `HToNS` (1142), `ShortHostToNet` (1143), `ShortNetToHost` (1144)

72.4.28 NToHI

Synopsis: Convert long integer from network ordered to host ordered

Declaration: `function NToHI (Net: Cardinal) : Cardinal; Overload`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1142), `htons` (1142), `ntohs` (1143)

72.4.29 NToHs

Synopsis: Convert short integer from network ordered to host ordered

Declaration: `function NToHs (Net: Word) : Word`

Visibility: default

Description: `ntohs` makes sure that the bytes in `Net`, received from the network, are ordered in the correct way for handling by the host machine, and returns the correctly ordered result.

See also: `htonl` (1142), `htons` (1142), `ntohl` (1143)

72.4.30 ShortHostToNet

Synopsis: Convert a host port number to a network port number

Declaration: `function ShortHostToNet (Host: Word) : Word`

Visibility: default

Description: `ShortHostToNet` converts a host port number to a network port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` (1144), `HostToNet` (1141), `NToHS` (1143), `HToNS` (1142)

72.4.31 ShortNetToHost

Synopsis: Convert a network port number to a host port number

Declaration: `function ShortNetToHost (Net: Word) : Word`

Visibility: default

Description: `ShortNetToHost` converts a network port number to a host port number. It takes care of endianness of the host machine.

Errors: None.

See also: `ShortNetToHost` ([1144](#)), `HostToNet` ([1141](#)), `NToHS` ([1143](#)), `HToNS` ([1142](#))

72.4.32 Sock2File

Synopsis: Convert socket to untyped file descriptors

Declaration: `procedure Sock2File (Sock: LongInt; var SockIn: File; var SockOut: File)`

Visibility: default

Description: `Sock2File` transforms a socket `Sock` into 2 Pascal file descriptors of type `File`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1140](#)), `Sock2Text` ([1144](#))

72.4.33 Sock2Text

Synopsis: Convert socket to text file descriptors

Declaration: `procedure Sock2Text (Sock: LongInt; var SockIn: Text; var SockOut: Text)`

Visibility: default

Description: `Sock2Text` transforms a socket `Sock` into 2 Pascal file descriptors of type `Text`, one for reading from the socket (`SockIn`), one for writing to the socket (`SockOut`).

Errors: None.

See also: `FPSocket` ([1140](#)), `Sock2File` ([1144](#))

72.4.34 socketerror

Synopsis: Contains the error code for the last socket operation.

Declaration: `function socketerror : cint`

Visibility: default

Description: `SocketError` contains the error code for the last socket operation. It can be examined to return the last socket error.

72.4.35 Str2UnixSockAddr

Synopsis: Convert path to TUnixSockAddr ([1128](#))

Declaration: `procedure Str2UnixSockAddr(const addr: string; var t: TUnixSockAddr;
var len: LongInt)`

Visibility: default

Description: `Str2UnixSockAddr` transforms a Unix socket address in a string to a `TUnixSockAddr` structure which can be passed to the `Bind` ([1130](#)) call.

Errors: None.

See also: `FPSocket` ([1140](#)), `FPBind` ([1133](#))

72.4.36 StrToHostAddr

Synopsis: Convert a string to a host address.

Declaration: `function StrToHostAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToHostAddr` converts the string representation in `IP` to a host address and returns the host address.

Errors: On error, the host address is filled with zeroes.

See also: `NetAddrToStr` ([1142](#)), `HostAddrToStr` ([1141](#)), `StrToNetAddr` ([1145](#))

72.4.37 StrToHostAddr6

Synopsis: Convert a string to a IPV6 host address.

Declaration: `function StrToHostAddr6(IP: string) : Tin6_addr`

Visibility: default

Description: `StrToHostAddr6` converts the string representation in `IP` to a IPV6 host address and returns the host address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1142](#)), `HostAddrToStr6` ([1141](#)), `StrToHostAddr` ([1145](#))

72.4.38 StrToNetAddr

Synopsis: Convert a string to a network address.

Declaration: `function StrToNetAddr(IP: AnsiString) : in_addr`

Visibility: default

Description: `StrToNetAddr` converts the string representation in `IP` to a network address and returns the network address.

Errors: On error, the network address is filled with zeroes.

See also: `NetAddrToStr` ([1142](#)), `HostAddrToStr` ([1141](#)), `StrToHostAddr` ([1145](#))

72.4.39 StrToNetAddr6

Synopsis: Convert a string to a IPV6 network address

Declaration: `function StrToNetAddr6(IP: AnsiString) : Tin6_addr`

Visibility: default

Description: `StrToNetAddr6` converts the string representation in `IP` to a IPV6 network address and returns the network address.

Errors: On error, the address is filled with zeroes.

See also: `NetAddrToStr6` ([1142](#)), `HostAddrToStr6` ([1141](#)), `StrToHostAddr6` ([1145](#))

Chapter 73

Reference for unit 'strings'

73.1 Used units

Table 73.1: Used units by unit 'strings'

Name	Page
System	1194

73.2 Overview

This chapter describes the `STRINGS` unit for Free Pascal. This unit is system independent, and therefore works on all supported platforms.

73.3 Procedures and functions

73.3.1 `stralloc`

Synopsis: Allocate memory for a new null-terminated string on the heap

Declaration: `function stralloc(L: SizeInt) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Errors: If there is not enough memory, a run-time error occurs.

See also: `StrNew` ([1156](#)), `StrPCopy` ([1157](#))

73.3.2 `strcat`

Synopsis: Concatenate 2 null-terminated strings.

Declaration: `function strcat(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1152](#))

Listing: ./stringex/ex11.pp

Program Example11;

Uses strings;

{ Program to demonstrate the StrCat function. }

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin

P2:=StrAlloc (StrLen(P1)*2+1);

StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }

StrCat (P2,P1); { Append P2 once more }

WriteLn ('P2 : ',P2);

StrDispose(P2);

end.

73.3.3 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: function strcmp(str1: PChar; str2: PChar) : SizeInt

Visibility: default

Description: Compares the null-terminated strings S1 and S2. The result is

- A negative SizeInt when S1<S2.
- 0 when S1=S2.
- A positive SizeInt when S1>S2.

For an example, see StrLComp ([1153](#)).

Errors: None.

See also: StrLComp ([1153](#)), StrIComp ([1151](#)), StrLComp ([1154](#))

73.3.4 strcpy

Synopsis: Copy a null-terminated string

Declaration: function strcpy(dest: PChar; source: PChar) : PChar; Overload

Visibility: default

Description: Copy the null terminated string in Source to Dest, and returns a pointer to Dest. Dest needs enough room to contain Source, i.e. StrLen(Source)+1 bytes.

Errors: No length checking is performed.

See also: StrPCopy ([1157](#)), StrLCopy ([1153](#)), StrECopy ([1150](#))

Listing: ./stringex/ex4.pp

Program Example4;

Uses strings;

{ Program to demonstrate the StrCopy function. }

Const P : PChar = 'This is a PCHAR string.';

var PP : PChar;

begin

PP:=StrAlloc (Strlen(P)+1);

StrCopy (PP,P);

If StrComp (PP,P)<>0 then

 Writeln ('Oh-oh problems... ')

else

 Writeln ('All is well : PP=',PP);

StrDispose(PP);

end.

73.3.5 strdispose

Synopsis: disposes of a null-terminated string on the heap

Declaration: procedure strdispose(p: PChar)

Visibility: default

Description: Removes the string in P from the heap and releases the memory.

Errors: None.

See also: StrNew ([1156](#))

Listing: ./stringex/ex17.pp

Program Example17;

Uses strings;

{ Program to demonstrate the StrDispose function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

P2:=StrNew (P1);

Writeln ('P2 : ',P2);

StrDispose(P2);

end.

73.3.6 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy(dest: PChar; source: PChar) : PChar`

Visibility: default

Description: Copies the Null-terminated string in `Source` to `Dest`, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: `StrLCopy` ([1153](#)), `StrCopy` ([1148](#))

Listing: `./stringex/ex6.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrECopy function. }

Const `P : PChar = 'This is a PCHAR string.';`

Var `PP : PChar;`

begin

`PP:=StrAlloc (StrLen(P)+1);`

`If Longint(StrECopy(PP,P))-Longint(PP)<>StrLen(P) then`

`Writeln('Something is wrong here !')`

`else`

`Writeln ('PP= ',PP);`

`StrDispose(PP);`

end.

73.3.7 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the end of `P`. (i.e. to the terminating null-character.

Errors: None.

See also: `StrLen` ([1154](#))

Listing: `./stringex/ex7.pp`

Program `Example6;`

Uses `strings;`

{ Program to demonstrate the StrEnd function. }

Const `P : PChar = 'This is a PCHAR string.';`

```

begin
  If Longint(StrEnd(P)) - Longint(P) <> StrLen(P) then
    Writeln('Something is wrong here !')
  else
    Writeln('All is well..');
end.

```

73.3.8 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: PChar; str2: PChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

Errors: None.

See also: `StrLComp` ([1153](#)), `StrComp` ([1148](#)), `StrLComp` ([1154](#))

Listing: `./stringex/ex8.pp`

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

```

Const P1 : PChar = 'This is the first string.';
      P2 : PChar = 'This is the second string.';

```

Var L : Longint;

```

begin
  Write('P1 and P2 are ');
  If StrComp(P1,P2) <> 0 then write('NOT ');
  write('equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc(L);
  dec(L);
  Writeln(L,' characters are the same.');
```

73.3.9 stripos

Synopsis: Return the position of a substring in a string, case insensitive.

Declaration: `function stripos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: `strpos` returns the position of `str2` in `str1`. It searches in a case-insensitive manner, and if it finds a match, it returns a pointer to the location of the match. If no match is found, `Nil` is returned.

Errors: No checks are done on the validity of the pointers, and the pointers are assumed to point to a properly null-terminated string. If either of these conditions are not met, a run-time error may follow.

See also: `strscan` (1152), `strpos` (1158)

73.3.10 `strscan`

Synopsis: Scan a string for a character, case-insensitive

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `strscan` does the same as `strscan` (1159) but compares the characters case-insensitively. It returns a pointer to the first occurrence of the character `c` in the null-terminated string `p`, or `Nil` if `c` is not present in the string.

See also: `strscan` (1159), `strrscan` (1158)

73.3.11 `strlcat`

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Adds `L` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` (1147)

Listing: `./stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:=StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`WriteLn ('P2 = ',P2);`

`StrDispose(P2)`

end.

73.3.12 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

Errors: None.

See also: `StrComp` ([1148](#)), `StrIComp` ([1151](#)), `StrLComp` ([1154](#))

Listing: `./stringex/ex8.pp`

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

Write ('P1 and P2 are ');
If **StrComp** (P1,P2)<>0 **then write** ('NOT ');
write ('equal. The first ');
L:=1;
While **StrLComp**(P1,P2,L)=0 **do inc** (L);
dec(L);
WriteLn (L,' characters are the same.');

end.

73.3.13 strlcopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: PChar; source: PChar; maxlen: SizeInt) : PChar`
; Overload

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: `StrCopy` ([1148](#)), `StrECopy` ([1150](#))

Listing: `./stringex/ex5.pp`

```

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin
  PP:= StrAlloc(11);
  WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));
  StrDispose(PP);
end.

```

73.3.14 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string P. If P equals Nil, then zero (0) is returned.

Errors: None.

See also: StrNew ([1156](#))

Listing: ./stringex/ex1.pp

```

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin
  WriteLn ('P          : ',p);
  WriteLn ('length(P) : ',StrLen(P));
end.

```

73.3.15 strlicomp

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2, ignoring case. The result is

- A negative `SizeInt` when $S1 < S2$.
- 0 when $S1 = S2$.
- A positive `SizeInt` when $S1 > S2$.

For an example, see `StrIComp` (1151)

Errors: None.

See also: `StrLComp` (1153), `StrComp` (1148), `StrIComp` (1151)

73.3.16 `strlower`

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`

Visibility: default

Description: Converts `P` to an all-lowercase string. Returns `P`.

Errors: None.

See also: `StrUpper` (1159)

Listing: `./stringex/ex14.pp`

Program `Example14`;

Uses `strings`;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

`P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';`
`P2 : PChar = 'this is a lowercase string';`

begin

`WriteLn ('Uppercase : ', StrUpper(P2));`
`StrLower (P1);`
`WriteLn ('Lowercase : ', P1);`

end.

73.3.17 `strmove`

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar`

Visibility: default

Description: Copies `MaxLen` characters from `Source` to `Dest`. No terminating null-character is copied. Returns `Dest`

Errors: None.

See also: `StrLCopy` (1153), `StrCopy` (1148)

Listing: ./stringex/ex10.pp

Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function. }

Const P1 : PCHAR = 'This is a pchar string.';

Var P2 : Pchar;

begin

 P2:=StrAlloc (StrLen(P1)+1);

StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }

Writeln ('P2 = ',P2);

StrDispose(P2);

end.

73.3.18 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: PChar) : PChar`

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1148](#)), StrDispose ([1149](#))

Listing: ./stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

Const P1 : PChar = 'This is a PChar string';

var P2 : PChar;

begin

 P2:=StrNew (P1);

If P1=P2 **then**

writeln ('This can''t be happening... ')

else

writeln ('P2 : ',P2);

StrDispose(P2);

end.

73.3.19 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in P to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

See also: StrPCopy ([1157](#))

Listing: ./stringex/ex3.pp

Program Example3;

Uses strings;

{ Program to demonstrate the StrPas function. }

Const P : PChar = 'This is a PCHAR string';

var S : **string**;

begin

 S:=StrPas (P);

 WriteLn ('S : ',S);

end.

73.3.20 strcpy

Synopsis: Copy a pascal string to a null-terminated string

Declaration: `function strcpy(d: PChar; const s: string) : PChar`

Visibility: default

Description: Converts the Pascal string in S to a Null-terminated string, and copies it to D. D needs enough room to contain the string Source, i.e. Length(S)+1 bytes.

Errors: No length checking is performed.

See also: StrPas ([1157](#))

Listing: ./stringex/ex2.pp

Program Example2;

Uses strings;

{ Program to demonstrate the StrPCopy function. }

Const S = 'This is a normal string.';

Var P : Pchar;

```

begin
  p:= StrAlloc (length(S)+1);
  if StrPCopy (P,S)<>P then
    Writeln ('This is impossible !!')
  else
    writeln (P);
    StrDispose(P);
end.

```

73.3.21 strpos

Synopsis: Search for a null-terminated substring in a null-terminated string

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1159](#)), StrRScan ([1159](#))

Listing: ./stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
 S : PChar = 'is';

begin
 Writeln ('Position of ''is'' in P : ',sizeint(StrPos(P,S))-sizeint(P));
end.

73.3.22 strscan

Synopsis: Scan a string reversely for a character, case-insensitive

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: `strscan` does the same as `strrscan` ([1159](#)) but compares the characters case-insensitively. It returns a pointer to the last occurrence of the character `c` in the null-terminated string `p`, or Nil if `c` is not present in the string.

See also: `strrscan` ([1159](#)), `strscan` ([1152](#))

73.3.23 strscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan (1159).

Errors: None.

See also: StrScan (1159), StrPos (1158)

73.3.24 strscan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: StrRScan (1159), StrPos (1158)

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first 's' : ',StrScan(P,s));

WriteLn ('P, starting from last 's' : ',StrRScan(P,s));

end.

73.3.25 strupper

Synopsis: Convert null-terminated string to all-uppercase

Declaration: `function strupper(p: PChar) : PChar`

Visibility: default

Description: Converts P to an all-uppercase string. Returns P.

For an example, see StrLower (1155)

Errors: None.

See also: StrLower (1155)

Chapter 74

Reference for unit 'strutils'

74.1 Used units

Table 74.1: Used units by unit 'strutils'

Name	Page
System	1194
sysutils	1442

74.2 Constants, types and variables

74.2.1 Resource strings

```
SErrAmountStrings =  
    'Amount of search and replace strings don''t match'
```

Error message used in stringsreplace function

```
SInvalidRomanNumeral = '%s is not a valid Roman numeral'
```

Error string shown in exception raised when invalid roman numeral is encountered

74.2.2 Constants

```
AnsiResemblesProc : TCompareTextProc = @SoundexProc
```

This procedural variable is standard set to SoundexProc ([1188](#)) but can be overridden with a user-defined algorithm. This algorithm should return `True` if `AText` resembles `AOtherText`, or `False` otherwise. The standard routine compares the soundexes of the two strings and returns `True` if they are equal.

```
Brackets = ['(', ')', '[', ']', '{', '}']
```

Set of characters that contain all possible bracket characters

```
DigitChars = ['0'..'9']
```

Set of digit characters

```
StdSwitchChars = ['-','/']
```

Standard characters for the `SwitchChars` argument of `GetCmdLineArg` (1175).

```
StdWordDelims = [#0..' ', ',', '.', ';', '/', '\', ':', "'", '"',
  , ''] + Brackets
```

Standard word delimiter values.

```
WordDelimiters : Set of Char = [#0..#255] - ['a'..'z', 'A'..'Z', '1'
  ..'9', '0']
```

Standard word delimiters, used in the `SearchBuf` (1186) call.

74.2.3 Types

```
SizeIntArray = Array of SizeInt
```

`SizeIntArray` is an auxiliary type used in `StringReplace` (1189)

```
TCompareTextProc = function(const AText: string; const AOther: string
  )
    : Boolean
```

Function prototype for comparing two string in `AnsiResemblesText` (1167)

```
TRomanConversionStrictness = (rcsStrict, rcsRelaxed, rcsDontCare)
```

Table 74.2: Enumeration values for type `TRomanConversionStrictness`

Value	Explanation
<code>rcsDontCare</code>	Do not check correctness
<code>rcsRelaxed</code>	Like <code>rcsStrict</code> but allow more than 3 consecutive identical letters.
<code>rcsStrict</code>	Only accept correct roman numerals.

`TRomanConversionStrictness` is an enumerated type that can be used to decide how to react to invalid roman numerals.

rcsStrict Strict adherence to roman numerals. Up to 3 consecutive identical letters. No negative numbers. Ordering must be correct.

rcsRelaxed Same as `rcsStrict` but allow more than 3 consecutive identical letters.

rcsDontCare Do not check validity at all

```
TSoundexIntLength = 1..8
```

Range of allowed integer soundex lengths.

```
TSoundexLength = 1..MaxInt
```

Range of allowed soundex lengths.

```
TStringReplaceAlgorithm = (sraDefault, sraManySmall, sraBoyerMoore)
```

Table 74.3: Enumeration values for type TStringReplaceAlgorithm

Value	Explanation
sraBoyerMoore	Use a Boyer-Moore search algorithm
sraDefault	Use the sysutils algorithm, which does a straightforward linear search and replace
sraManySmall	Use an approach which is suitable for a string with many occurrences of the same small text

TStringReplaceAlgorithm enumerates the available algorithms to StringReplace ([1189](#))

sraDefault Use the sysutils algorithm, which does a straightforward linear search and replace

sraManySmall Use an approach which is suitable for a string with many occurrences of the same small text

sraBoyerMoore Use a Boyer-Moore search algorithm

Depending on the kind of data that is being treated, one or the other of these algorithms may produce faster results.

```
TStringSeachOption = TStringSearchOption
```

There is a typo error in the original Borland StrUtils unit. This type just refers to the correct TStringSearchOption ([1162](#)) and is provided for compatibility only.

```
TStringSearchOption = (soDown, soMatchCase, soWholeWord)
```

Table 74.4: Enumeration values for type TStringSearchOption

Value	Explanation
soDown	Search in down direction.
soMatchCase	Match case
soWholeWord	Search whole words only.

Possible options for SearchBuf ([1186](#)) call.

```
TStringSearchOptions = Set of TStringSearchOption
```

Set of options for SearchBuf ([1186](#)) call.

74.3 Procedures and functions

74.3.1 AddChar

Synopsis: Add characters to the left of a string till a certain length

Declaration: `function AddChar(C: Char; const S: string; N: Integer) : string`

Visibility: default

Description: `AddChar` adds characters (C) to the left of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a right-aligned version of S, with length N.

Errors: None

See also: `AddCharR` (1163), `PadLeft` (1181), `PadRight` (1181), `PadCenter` (1181)

74.3.2 AddCharR

Synopsis: Add chars at the end of a string till it reaches a certain length

Declaration: `function AddCharR(C: Char; const S: string; N: Integer) : string`

Visibility: default

Description: `AddCharR` adds characters (C) to the right of S till the length N is reached, and returns the resulting string. If the length of S is already equal to or larger than N, then no characters are added. The resulting string can be thought of as a left-aligned version of S, with length N.

Errors: None

See also: `AddChar` (1163)

74.3.3 AnsiContainsStr

Synopsis: Checks whether a string contains a given substring

Declaration: `function AnsiContainsStr(const AText: string; const ASubText: string)
: Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether AText contains ASubText, and returns True if this is the case, or returns False otherwise. The search is performed case-sensitive.

Errors: None

See also: `AnsiContainsText` (1163), `AnsiEndsStr` (1164), `AnsiIndexStr` (1164), `AnsiStartsStr` (1168)

74.3.4 AnsiContainsText

Synopsis: Check whether a string contains a certain substring, ignoring case.

Declaration: `function AnsiContainsText(const AText: string; const ASubText: string)
: Boolean`

Visibility: default

Description: `AnsiContainsString` checks whether `AText` contains `ASubText`, and returns `True` if this is the case, or returns `False` otherwise. The search is performed case-insensitive.

See also: `AnsiContainsStr` ([1163](#)), `AnsiEndsText` ([1164](#)), `AnsiIndexText` ([1165](#)), `AnsiStartsText` ([1168](#))

74.3.5 `AnsiEndsStr`

Synopsis: Check whether a string ends with a certain substring

Declaration: `function AnsiEndsStr(const ASubText: string; const AText: string) : Boolean`

Visibility: default

Description: `AnsiEndsStr` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None.

See also: `AnsiEndsText` ([1164](#)), `AnsiStartsStr` ([1168](#)), `AnsiIndexStr` ([1164](#)), `AnsiContainsStr` ([1163](#))

74.3.6 `AnsiEndsText`

Synopsis: Check whether a string ends with a certain substring, ignoring case.

Declaration: `function AnsiEndsText(const ASubText: string; const AText: string) : Boolean`

Visibility: default

Description: `AnsiEndsText` checks `AText` to see whether it ends with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals the length of `AText` minus the length of `ASubText` plus one.

Errors: None

See also: `AnsiStartsText` ([1168](#)), `AnsiEndsStr` ([1164](#)), `AnsiIndexText` ([1165](#)), `AnsiContainsText` ([1163](#))

74.3.7 `AnsiIndexStr`

Synopsis: Searches, observing case, for a string in an array of strings.

Declaration: `function AnsiIndexStr(const AText: string; const AValues: Array of string) : Integer`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched observing case.

Errors: None.

See also: `AnsiIndexText` ([1165](#)), `AnsiMatchStr` ([1165](#)), `AnsiMatchText` ([1165](#))

74.3.8 AnsiIndexText

Synopsis: Searches, case insensitive, for a string in an array of strings.

Declaration: `function AnsiIndexText(const AText: string;
const AValues: Array of string) : Integer`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, the corresponding index (zero-based) in the `AValues` array is returned. If no match is found, -1 is returned. The strings are matched ignoring case.

Errors: None

See also: `AnsiIndexStr` (1164), `AnsiMatchStr` (1165), `IndexStr` (1176), `MatchStr` (1178), `AnsiMatchText` (1165)

74.3.9 AnsiLeftStr

Synopsis: Copies a number of characters starting at the left of a string

Declaration: `function AnsiLeftStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` leftmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes. This function corresponds to the Visual Basic `LeftStr` function.

Errors: None.

See also: `AnsiMidStr` (1166), `AnsiRightStr` (1167), `LeftStr` (1178), `RightStr` (1185), `MidStr` (1179), `LeftBStr` (1178), `RightBStr` (1184), `MidBStr` (1179)

74.3.10 AnsiMatchStr

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration: `function AnsiMatchStr(const AText: string;
const AValues: Array of string) : Boolean`

Visibility: default

Description: `AnsiMatchStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case. This function simply calls `AnsiIndexStr` (1164) and checks whether it returns -1 or not.

74.3.11 AnsiMatchText

Synopsis: Check whether a string occurs in an array of strings, disregarding case.

Declaration: `function AnsiMatchText(const AText: string;
const AValues: Array of string) : Boolean`

Visibility: default

Description: `AnsiIndexStr` matches `AText` against each string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched ignoring case.

This function simply calls `AnsiIndexText` (1165) and checks whether it returns -1 or not.

74.3.12 `AnsiMidStr`

Synopsis: Returns a number of characters copied from a given location in a string

Declaration: `function AnsiMidStr(const AText: AnsiString; const AStart: SizeInt; const ACount: SizeInt) : AnsiString`

Visibility: default

Description: `AnsiMidStr` returns `ACount` characters from `AText`, starting at position `AStart`. If `AStart+ACount` is larger than the length of `AText`, only as much characters as available in `AText` (starting from `AStart`) will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.

This function corresponds to the Visual Basic `MidStr` function.

Errors: None

See also: `AnsiLeftStr` (1165), `AnsiRightStr` (1167), `LeftStr` (1178), `RightStr` (1185), `MidStr` (1179), `LeftBStr` (1178), `RightBStr` (1184), `MidBStr` (1179)

74.3.13 `AnsiProperCase`

Synopsis: Pretty-Print a string: make lowercase and capitalize first letters of words

Declaration: `function AnsiProperCase(const S: string; const WordDelims: TSysCharSet) : string`

Visibility: default

Description: `AnsiProperCase` converts `S` to an all lowercase string, but capitalizes the first letter of every word in the string, and returns the resulting string. When searching for words, the characters in `WordDelimiters` are used to determine the boundaries of words. The constant `StdWordDelims` (1161) can be used for this.

74.3.14 `AnsiReplaceStr`

Synopsis: Search and replace all occurrences of a string, case sensitive.

Declaration: `function AnsiReplaceStr(const AText: string; const AFromText: string; const AToText: string) : string`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed observing case.

Errors: None.

See also: `AnsiReplaceText` (1167), `SearchBuf` (1186)

74.3.15 AnsiReplaceText

Synopsis: Search and replace all occurrences of a string, case insensitive.

Declaration: `function AnsiReplaceText(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `AnsiReplaceString` searches `AText` for all occurrences of the string `AFromText` and replaces them with `AToText`, and returns the resulting string. The search is performed ignoring case.

Errors: None.

See also: `AnsiReplaceStr` ([1166](#)), `SearchBuf` ([1186](#))

74.3.16 AnsiResemblesText

Synopsis: Check whether 2 strings resemble each other.

Declaration: `function AnsiResemblesText(const AText: string; const AOther: string)
: Boolean`

Visibility: default

Description: `AnsiResemblesText` will check whether `AnsiResemblesProc` ([1160](#)) is set. If it is not set, `False` is returned. If it is set, `AText` and `AOtherText` are passed to it and its result is returned.

Errors: None.

See also: `AnsiResemblesProc` ([1160](#)), `SoundexProc` ([1188](#))

74.3.17 AnsiReverseString

Synopsis: Reverse the letters in a string.

Declaration: `function AnsiReverseString(const AText: AnsiString) : AnsiString`

Visibility: default

Description: `AnsiReverseString` returns a string with all characters of `AText` in reverse order.
if the result of this function equals `AText`, `AText` is called an anagram.

Errors: None.

74.3.18 AnsiRightStr

Synopsis: Copies a number of characters starting at the right of a string

Declaration: `function AnsiRightStr(const AText: AnsiString; const ACount: SizeInt)
: AnsiString`

Visibility: default

Description: `AnsiLeftStr` returns the `ACount` rightmost characters from `AText`. If `ACount` is larger than the length of `AText`, only as much characters as available in `AText` will be copied. If `ACount` is zero or negative, no characters will be copied. The characters are counted as characters, not as Bytes.
This function corresponds to the Visual Basic `RightStr` function.

Errors: None.

See also: [AnsiLeftStr \(1165\)](#), [AnsiMidStr \(1166\)](#), [LeftStr \(1178\)](#), [RightStr \(1185\)](#), [MidStr \(1179\)](#), [LeftBStr \(1178\)](#), [RightBStr \(1184\)](#), [MidBStr \(1179\)](#)

74.3.19 AnsiStartsStr

Synopsis: Check whether a string starts with a given substring, observing case

Declaration: `function AnsiStartsStr(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiStartsStr` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-sensitive. Basically, it checks whether the position of `ASubText` equals 1.

See also: [AnsiEndsStr \(1164\)](#), [AnsiStartsStr \(1168\)](#), [AnsiIndexStr \(1164\)](#), [AnsiContainsStr \(1163\)](#)

74.3.20 AnsiStartsText

Synopsis: Check whether a string starts with a given substring, ignoring case

Declaration: `function AnsiStartsText(const ASubText: string; const AText: string)
: Boolean`

Visibility: default

Description: `AnsiStartsText` checks `AText` to see whether it starts with `ASubText`, and returns `True` if it does, `False` if not. The check is performed case-insensitive. Basically, it checks whether the position of `ASubText` equals 1.

Errors: None.

See also: [AnsiEndsText \(1164\)](#), [AnsiStartsStr \(1168\)](#), [AnsiIndexText \(1165\)](#), [AnsiContainsText \(1163\)](#)

74.3.21 BinToHex

Synopsis: Convert a binary buffer to a hexadecimal string

Declaration: `procedure BinToHex(BinValue: PChar; HexValue: PChar;
BinBufSize: Integer)`

Visibility: default

Description: `BinToHex` converts the byte values in `BinValue` to a string consisting of 2-character hexadecimal strings in `HexValue`. `BufSize` specifies the length of `BinValue`, which means that `HexValue` must have size $2 * \text{BufSize}$.

For example a buffer containing the byte values 255 and 0 will be converted to FF00.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: [HexToBin \(1175\)](#)

74.3.22 Copy2Space

Synopsis: Returns all characters in a string till the first space character (not included).

Declaration: `function Copy2Space(const S: string) : string`

Visibility: default

Description: `Copy2Space` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. The string `S` is left untouched. If there is no space in `S`, then the whole string `S` is returned.

This function simply calls `Copy2Symb` (1169) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2Symb` (1169), `Copy2SpaceDel` (1169)

74.3.23 Copy2SpaceDel

Synopsis: Deletes and returns all characters in a string till the first space character (not included).

Declaration: `function Copy2SpaceDel(var S: string) : string`

Visibility: default

Description: `Copy2SpaceDel` determines the position of the first space in the string `S` and returns all characters up to this position. The space character itself is not included in the result string. All returned characters, including the space, are deleted from the string `S`, after which it is right-trimmed. If there is no space in `S`, then the whole string `S` is returned, and `S` itself is emptied.

This function simply calls `Copy2SymbDel` (1170) with the space (ASCII code 32) as the symbol argument.

Errors: None.

See also: `Copy2SymbDel` (1170), `Copy2Space` (1169)

74.3.24 Copy2Symb

Synopsis: Returns all characters in a string till a given character (not included).

Declaration: `function Copy2Symb(const S: string; Symb: Char) : string`

Visibility: default

Description: `Copy2Symb` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. The string `S` is left untouched. If `Symb` does not appear in `S`, then the whole of `S` is returned.

Errors: None.

See also: `Copy2Space` (1169), `Copy2SymbDel` (1170)

74.3.25 Copy2SymbDel

Synopsis: Deletes and returns all characters in a string till a given character (not included).

Declaration: `function Copy2SymbDel(var S: string; Symb: Char) : string`

Visibility: default

Description: `Copy2SymbDel` determines the position of the first occurrence of `Symb` in the string `S` and returns all characters up to this position. The `Symb` character itself is not included in the result string. All returned characters and the `Symb` character, are deleted from the string `S`, after which it is right-trimmed. If `Symb` does not appear in `S`, then the whole of `S` is returned, and `S` itself is emptied.

Errors: None.

See also: `Copy2SpaceDel` (1169), `Copy2Symb` (1169)

74.3.26 Dec2Numb

Synopsis: Convert a decimal number to a string representation, using given a base.

Declaration: `function Dec2Numb(N: LongInt; Len: Byte; Base: Byte) : string`

Visibility: default

Description: `Dec2Numb` converts `N` to its representation using base `Base`. `N` must be a positive integer. The resulting string is left-padded with zeroes till it has length `Len`. `Base` must be in the range 2-36 to be meaningful, but no checking on this is performed.

Errors: If `Base` is out of range, the resulting string will contain unreadable (non-alphanumeric) characters.

See also: `Hex2Dec` (1175), `IntToBin` (1176), `intToRoman` (1176), `RomanToInt` (1185)

74.3.27 DecodeSoundexInt

Synopsis: Decodes the integer representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexInt(AValue: Integer) : string`

Visibility: default

Description: `DecodeSoundexInt` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexInt` (1187) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: `SoundexInt` (1187), `DecodeSoundexWord` (1170), `Soundex` (1187)

74.3.28 DecodeSoundexWord

Synopsis: Decodes the word-sized representation of a soundex code and returns the original soundex code.

Declaration: `function DecodeSoundexWord(AValue: Word) : string`

Visibility: default

Description: `DecodeSoundexWord` converts the integer value `AValue` to a soundex string. It performs the reverse operation of the `SoundexWord` (1188) function. The result is the soundex string corresponding to `AValue`.

Errors: None.

See also: [SoundexInt \(1187\)](#), [DecodeSoundexInt \(1170\)](#), [Soundex \(1187\)](#)

74.3.29 DelChars

Synopsis: Delete all occurrences of a given character from a string.

Declaration: `function DelChars(const S: string; Chr: Char) : string`

Visibility: default

Description: `DelChars` returns a copy of `S` with all `Chr` characters removed from it.

Errors: None.

See also: [DelSpace \(1171\)](#), [DelSpace1 \(1171\)](#)

74.3.30 DelSpace

Synopsis: Delete all occurrences of a space from a string.

Declaration: `function DelSpace(const S: string) : string`

Visibility: default

Description: `DelSpace` returns a copy of `S` with all spaces (ASCII code 32) removed from it.

Errors: None.

See also: [DelChars \(1171\)](#), [DelSpace1 \(1171\)](#)

74.3.31 DelSpace1

Synopsis: Reduces sequences of space characters to 1 space character.

Declaration: `function DelSpace1(const S: string) : string`

Visibility: default

Description: `DelSpace1` returns a copy of `S` with all sequences of spaces reduced to 1 space.

Errors: None.

See also: [DelChars \(1171\)](#), [DelSpace \(1171\)](#)

74.3.32 DupeString

Synopsis: Creates and concatenates N copies of a string

Declaration: `function DupeString(const AText: string; ACount: Integer) : string`

Visibility: default

Description: `DupeString` returns a string consisting of `ACount` concatenations of `AText`. Thus

```
DupeString('1234567890', 3);
```

will produce a string

```
'123456789012345678901234567890'
```

Errors: None.

74.3.33 ExtractDelimited

Synopsis: Extract the N-th delimited part from a string.

Declaration:

```
function ExtractDelimited(N: Integer; const S: string;
                           const Delims: TSysCharSet) : string
```

Visibility: default

Description: `ExtractDelimited` extracts the N-th part from the string `S`. The set of characters in `Delims` are used to mark part boundaries. When a delimiter is encountered, a new part is started and the old part is ended. Another way of stating this is that any (possibly empty) series of characters not in `Delims`, situated between 2 characters in `Delims`, it is considered as piece of a part. This means that if 2 delimiter characters appear next to each other, there is an empty part between it. If an N-th part cannot be found, an empty string is returned. However, unlike `ExtractWord` (1172), an empty string is a valid return value, i.e. a part can be empty.

The pre-defined constant `StdWordDelims` (1161) can be used for the `Delims` argument. The pre-defined constant `Brackets` (1160) would be better suited the `Delims` argument e.g. in case factors in a mathematical expression are searched.

Errors: None.

See also: `ExtractSubStr` (1172), `ExtractWord` (1172), `ExtractWordPos` (1173)

74.3.34 ExtractSubstr

Synopsis: Extract a word from a string, starting at a given position in the string.

Declaration:

```
function ExtractSubstr(const S: string; var Pos: Integer;
                       const Delims: TSysCharSet) : string
```

Visibility: default

Description: `ExtractSubStr` returns all characters from `S` starting at position `Pos` till the first character in `Delims`, or till the end of `S` is reached. The delimiter character is not included in the result. `Pos` is then updated to point to the next first non-delimiter character in `S`. If `Pos` is larger than the Length of `S`, an empty string is returned.

The pre-defined constant `StdWordDelims` (1161) can be used for the `Delims` argument.

Errors: None.

See also: `ExtractDelimited` (1172), `ExtractWord` (1172), `ExtractWordPos` (1173)

74.3.35 ExtractWord

Synopsis: Extract the N-th word out of a string.

Declaration:

```
function ExtractWord(N: Integer; const S: string;
                     const WordDelims: TSysCharSet) : string
```

Visibility: default

Description: `ExtractWord` extracts the N-th word from the string `S`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned.

Unlike `ExtractDelimited` (1172), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1161) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWordPos` (1173), `ExtractSubStr` (1172), `ExtractDelimited` (1172), `IsWordPresent` (1177), `WordCount` (1191), `WordPosition` (1192)

74.3.36 ExtractWordPos

Synopsis: Extract a word from a string, and return the position where it was located in the string.

Declaration:

```
function ExtractWordPos(N: Integer; const S: string;
    const WordDelims: TSysCharSet; out Pos: Integer)
    : string
```

Visibility: default

Description: `ExtractWordPos` extracts the N-th word from the string `S` and returns the position of this word in `Pos`. The set of characters in `WordDelims` are used to mark word boundaries. A word is defined as any non-empty sequence of characters which are not present in `WordDelims`: if a character is not in `WordDelims`, it is considered as part of a word. If an N-th word cannot be found, an empty string is returned and `Pos` is zero.

Unlike `ExtractDelimited` (1172), an empty string is not a valid return value, i.e. is not a word. If an empty string is returned, the index `N` was out of range.

The pre-defined constant `StdWordDelims` (1161) can be used for the `WordDelims` argument.

Errors: None.

See also: `ExtractWord` (1172), `ExtractSubStr` (1172), `IsWordPresent` (1177), `WordCount` (1191), `WordPosition` (1192)

74.3.37 FindMatchesBoyerMooreCaseInsensitive

Synopsis: Find case-sensitive matches of a string using a Boyer-Moore algorithm

Declaration:

```
procedure FindMatchesBoyerMooreCaseInsensitive(const S: PChar;
    const OldPattern: PChar;
    const SSize: SizeInt;
    const OldPatternSize: SizeInt;
    out aMatches: SizeIntArray;
    const aMatchAll: Boolean)
    procedure FindMatchesBoyerMooreCaseInsensitive(const S: string;
    const OldPattern: string;
    out aMatches: SizeIntArray;
    const aMatchAll: Boolean)
```

Visibility: default

Description: `FindMatchesBoyerMooreCaseInsensitive` finds occurrences of `OldPattern` (with length `OldPatternSize`) in `S` (with length `SSize`). The search is performed case-insensitively, and all (zero based) positions are reported in `aMatches`. If `aMatchAll` is `True`, all positions will be reported. If `aMatchAll` is `False`, only the first position is reported.

Errors: None.

See also: `FindMatchesBoyerMooreCaseSensitive` (1174), `StringReplace` (1160)

74.3.38 FindMatchesBoyerMooreCaseSensitive

Synopsis: Find case-sensitive matches of a string using a Boyer-Moore algorithm

Declaration:

```

procedure FindMatchesBoyerMooreCaseSensitive(const S: PChar;
                                             const OldPattern: PChar;
                                             const SSize: SizeInt;
                                             const OldPatternSize: SizeInt;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
procedure FindMatchesBoyerMooreCaseSensitive(const S: string;
                                             const OldPattern: string;
                                             out aMatches: SizeIntArray;
                                             const aMatchAll: Boolean)
```

Visibility: default

Description: `FindMatchesBoyerMooreCaseSensitive` finds occurrences of `OldPattern` (with length `OldPatternSize`) in `S` (with length `SSize`). The search is performed case-sensitively, and all (zero based) positions are reported in `aMatches`. If `aMatchAll` is `True`, all positions will be reported. If `aMatchAll` is `False`, only the first position is reported.

Errors: None.

See also: `FindMatchesBoyerMooreCaseInsensitive` (1173), `StringReplace` (1160)

74.3.39 FindPart

Synopsis: Search for a substring in a string, using wildcards.

Declaration:

```

function FindPart(const HelpWilds: string; const InputStr: string)
                 : SizeInt
```

Visibility: default

Description: `FindPart` searches the string `InputStr` and returns the first string that matches the wildcards specification in `HelpWilds`. If no match is found, an empty string is returned. Currently, the only valid wildcards is the "?" character.

Errors: None.

See also: `SearchBuf` (1186)

74.3.40 GetCmdLineArg

Synopsis: Returns the command-line argument following the given switch.

Declaration: `function GetCmdLineArg(const Switch: string; SwitchChars: TSysCharSet) : string`

Visibility: default

Description: `GetCmdLineArg` returns the value for the `Switch` option on the command-line, if any is given. Command-line arguments are considered switches if they start with one of the characters in the `SwitchChars` set. The value is the command-line argument following the switch command-line argument.

Gnu-style (long) Options of the form `switch=value` are not supported.

The `StdSwitchChars` (1161) constant can be used as value for the `SwitchChars` parameter.

Errors: The `GetCmdLineArg` does not check whether the value of the option does not start with a switch character. i.e.

```
myprogram -option1 -option2
```

will result in "-option2" as the result of the `GetCmdLineArg` call for `option1`.

See also: `StdSwitchChars` (1161)

74.3.41 Hex2Dec

Synopsis: Converts a hexadecimal string to a decimal value

Declaration: `function Hex2Dec(const S: string) : LongInt`

Visibility: default

Description: `Hex2Dec` converts the hexadecimal value in the string `S` to its decimal value. Unlike the standard `Val` or `StrToInt` functions, there need not be a \$ sign in front of the hexadecimal value to indicate that it is indeed a hexadecimal value.

Errors: If `S` does not contain a valid hexadecimal value, an `EConvertError` exception will be raised.

See also: `Dec2Numb` (1170), `IntToBin` (1176), `intToRoman` (1176), `RomanToInt` (1185)

74.3.42 HexToBin

Synopsis: Convert a hexadecimal string to a binary buffer

Declaration: `function HexToBin(HexValue: PChar; BinValue: PChar; BinBufSize: Integer) : Integer`

Visibility: default

Description: `HexToBin` scans the hexadecimal string representation in `HexValue` and transforms every 2 character hexadecimal number to a byte and stores it in `BinValue`. The buffer size is the size of the binary buffer. Scanning will stop if the size of the binary buffer is reached or when an invalid character is encountered. The return value is the number of stored bytes.

Errors: No length checking is done, so if an invalid size is specified, an exception may follow.

See also: `BinToHex` (1168)

74.3.43 IfThen

Synopsis: Returns one of two strings, depending on a boolean expression

Declaration: `function IfThen(AValue: Boolean; const ATrue: string;
const AFalse: string) : string; Overload`

Visibility: default

Description: IfThen returns ATrue if AValue is True, and returns AFalse if AValue is false.

Errors: None.

See also: [AnsiMatchStr \(1165\)](#), [AnsiMatchText \(1165\)](#)

74.3.44 IndexStr

Synopsis: Searches, observing case, for a string in an array of strings.

Declaration: `function IndexStr(const AText: UnicodeString;
const AValues: Array of UnicodeString) : Integer`

Visibility: default

Description: IndexStr matches AText against each unicode string in AValues. If a match is found, the corresponding index (zero-based) in the AValues array is returned. If no match is found, -1 is returned. The strings are matched observing case.

Errors: None.

See also: [AnsiIndexText \(1165\)](#), [MatchStr \(1178\)](#), [AnsiIndexStr \(1164\)](#)

74.3.45 IntToBin

Synopsis: Converts an integer to a binary string representation, inserting spaces at fixed locations.

Declaration: `function IntToBin(Value: LongInt; Digits: Integer; Spaces: Integer)
: string
function IntToBin(Value: LongInt; Digits: Integer) : string
function intToBin(Value: Int64; Digits: Integer) : string`

Visibility: default

Description: IntToBin converts Value to a string with it's binary (base 2) representation. The resulting string contains at least Digits digits, with spaces inserted every Spaces digits. Spaces should be a nonzero value. If Digits is larger than 32, it is truncated to 32.

Errors: If spaces is zero, a division by zero error will occur.

See also: [Hex2Dec \(1175\)](#), [IntToRoman \(1176\)](#)

74.3.46 IntToRoman

Synopsis: Represent an integer with roman numerals

Declaration: `function IntToRoman(Value: LongInt) : string`

Visibility: default

Description: `IntToRoman` converts `Value` to a string with the Roman representation of `Value`. Number up to 1 million can be represented this way.

Errors: None.

See also: `RomanToInt` ([1185](#)), `Hex2Dec` ([1175](#)), `IntToBin` ([1176](#))

74.3.47 `IsEmptyStr`

Synopsis: Check whether a string is empty, disregarding whitespace characters

Declaration: `function IsEmptyStr(const S: string; const EmptyChars: TSysCharSet) : Boolean`

Visibility: default

Description: `IsEmptyStr` returns `True` if the string `S` only contains characters whitespace characters, all characters in `EmptyChars` are considered whitespace characters. If a character not present in `EmptyChars` is found in `S`, `False` is returned.

Errors: None.

See also: `IsWild` ([1177](#)), `FindPart` ([1174](#)), `IsWordPresent` ([1177](#))

74.3.48 `IsWild`

Synopsis: Check whether a string matches a wildcard search expression.

Declaration: `function IsWild(InputStr: string; Wilds: string; IgnoreCase: Boolean) : Boolean`

Visibility: default

Description: `IsWild` checks `InputStr` for the presence of the `Wilds` string. `Wilds` may contain "?" and "*" wildcard characters, which have their usual meaning: "*" matches any series of characters, possibly empty. "?" matches any single character. The function returns `True` if a string is found that matches `Wilds`, `False` otherwise.

If `IgnoreCase` is `True`, the non-wildcard characters are matched case insensitively. If it is `False`, case is observed when searching.

Errors: None.

See also: `SearchBuf` ([1186](#)), `FindPart` ([1174](#))

74.3.49 `IsWordPresent`

Synopsis: Check for the presence of a word in a string.

Declaration: `function IsWordPresent(const W: string; const S: string; const WordDelims: TSysCharSet) : Boolean`

Visibility: default

Description: `IsWordPresent` checks for the presence of the word `W` in the string `S`. Words are delimited by the characters found in `WordDelims`. The function returns `True` if a match is found, `False` otherwise. The search is performed case sensitive.

This function is equivalent to the `SearchBuf` ([1186](#)) function with the `soWholeWords` option specified.

Errors: None.

See also: [SearchBuf \(1186\)](#)

74.3.50 LeftBStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration:

```
function LeftBStr(const AText: AnsiString; const AByteCount: SizeInt)
                  : AnsiString
```

Visibility: default

Description: `LeftBStr` returns a string containing the leftmost `AByteCount` bytes from the string `AText` .
If `AByteCount` is larger than the length (in bytes) of `AText` , only as many bytes as available are returned.

Errors: None.

See also: [LeftStr \(1178\)](#), [AnsiLeftStr \(1165\)](#), [RightBStr \(1184\)](#), [MidBStr \(1179\)](#)

74.3.51 LeftStr

Synopsis: Copies Count characters starting at the left of a string.

Declaration:

```
function LeftStr(const AText: AnsiString; const ACount: SizeInt)
                : AnsiString
function LeftStr(const AText: WideString; const ACount: SizeInt)
                : WideString
```

Visibility: default

Description: `LeftStr` returns a string containing the leftmost `ACount` characters from the string `AText` . If `ACount` is larger than the length (in characters) of `AText` , only as many characters as available are returned.

Errors: None.

See also: [LeftBStr \(1178\)](#), [AnsiLeftStr \(1165\)](#), [RightStr \(1185\)](#), [MidStr \(1179\)](#)

74.3.52 MatchStr

Synopsis: Check whether a string occurs in an array of strings, observing case.

Declaration:

```
function MatchStr(const AText: UnicodeString;
                  const AValues: Array of UnicodeString) : Boolean
```

Visibility: default

Description: `MatchStr` matches `AText` against each unicode string in `AValues`. If a match is found, it returns `True`, otherwise `False` is returned. The strings are matched observing case.

This function simply calls [IndexStr \(1176\)](#) and checks whether it returns -1 or not.

74.3.53 MidBStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidBStr(const AText: AnsiString; const AByteStart: SizeInt;
const AByteCount: SizeInt) : AnsiString`

Visibility: default

Description: `MidBStr` returns a string containing the first `AByteCount` bytes from the string `AText` starting at position `AByteStart`. If `AByteStart+AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned. If `AByteStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

Errors: None.

See also: `LeftBStr` (1178), `AnsiMidStr` (1166), `RightBStr` (1184), `MidStr` (1179)

74.3.54 MidStr

Synopsis: Copies a number of characters starting at a given position in a string.

Declaration: `function MidStr(const AText: AnsiString; const AStart: SizeInt;
const ACount: SizeInt) : AnsiString`
`function MidStr(const AText: WideString; const AStart: SizeInt;
const ACount: SizeInt) : WideString`

Visibility: default

Description: `MidStr` returns a string containing the first `ACount` bytes from the string `AText` starting at position `AStart`. If `AStart+ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned. If `AStart` is less than 1 or larger than the length of `AText`, then no characters are returned.

This function is equivalent to the standard `Copy` function, and is provided for completeness only.

Errors: None.

See also: `LeftStr` (1178), `AnsiMidStr` (1166), `RightStr` (1185), `MidBStr` (1179)

74.3.55 NaturalCompareText

Synopsis: Compare using natural sort

Declaration: `function NaturalCompareText(const S1: string; const S2: string)
: Integer`
`function NaturalCompareText(const Str1: string; const Str2: string;
const ADecSeparator: Char;
const AThousandSeparator: Char) : Integer`

Visibility: default

Description: `NaturalCompareText` will compare 2 strings and return one of the following values:

-1If S1 comes before S2

0If S1 equals S2

1If S1 comes after S2

When `S1` and `S2` are integer or floating point values, the actual values are compared. Thus '12' will come after '2'. If either of the values is not a valid integer or floating point values, the strings are compared case insensitively as texts using `CompareText` ([1495](#))

A decimal separator and thousands separator can optionally be specified in `ADecSeparator`, `AThousandSeparator`. If none are specified, the defaults from the system unit will be used.

See also: `CompareText` ([1160](#))

74.3.56 NPos

Synopsis: Returns the position of the `N`-th occurrence of a substring in a string.

Declaration: `function NPos(const C: string; S: string; N: Integer) : SizeInt`

Visibility: default

Description: `NPos` checks `S` for the position of the `N`-th occurrence of `C`. If `C` occurs less than `N` times in `S`, or does not occur in `S` at all, 0 is returned. If `N` is less than 1, zero is returned.

Errors: None.

See also: `WordPosition` ([1192](#)), `FindPart` ([1174](#))

74.3.57 Numb2Dec

Synopsis: Converts a string representation of a number to its numerical value, given a certain base.

Declaration: `function Numb2Dec(S: string; Base: Byte) : LongInt`

Visibility: default

Description: `Numb2Dec` converts the number in string `S` to a decimal value. It assumes the number is represented using `Base` as the base. No checking is performed to see whether `S` contains a valid number using base `Base`.

Errors: None.

See also: `Hex2Dec` ([1175](#)), `Numb2USA` ([1180](#))

74.3.58 Numb2USA

Synopsis: Insert thousand separators.

Declaration: `function Numb2USA(const S: string) : string`

Visibility: default

Description: `Numb2USA` inserts thousand separators in the string `S` at the places where they are supposed to be, i.e. every 3 digits. The string `S` should contain a valid integer number, i.e. no digital number. No checking on this is done.

Errors: None.

74.3.59 PadCenter

Synopsis: Pad the string to a certain length, so the string is centered.

Declaration: `function PadCenter(const S: string; Len: SizeInt) : string`

Visibility: default

Description: `PadCenter` add spaces to the left and right of the string `S` till the result reaches length `Len`. If the number of spaces to add is odd, then the extra space will be added at the end. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is.

Errors: None.

See also: `PadLeft` (1181), `PadRight` (1181), `AddChar` (1163), `AddCharR` (1163)

74.3.60 PadLeft

Synopsis: Add spaces to the left of a string till a certain length is reached.

Declaration: `function PadLeft(const S: string; N: Integer) : string`

Visibility: default

Description: `PadLeft` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, right-justified on length `Len`.

Errors: None.

See also: `PadLeft` (1181), `PadCenter` (1181), `AddChar` (1163), `AddCharR` (1163)

74.3.61 PadRight

Synopsis: Add spaces to the right of a string till a certain length is reached.

Declaration: `function PadRight(const S: string; N: Integer) : string`

Visibility: default

Description: `PadRight` add spaces to the left of the string `S` till the result reaches length `Len`. If the string `S` has length equal to or largert than `Len`, no spaces are added, and the string `S` is returned as-is. The resulting string is `S`, left-justified on length `Len`.

Errors: None.

See also: `PadLeft` (1181), `PadCenter` (1181), `AddChar` (1163), `AddCharR` (1163)

74.3.62 PosEx

Synopsis: Search for the occurrence of a character in a string, starting at a certain position.

Declaration: `function PosEx(const SubStr: string; const S: string; Offset: SizeUInt)
: SizeInt
function PosEx(const SubStr: string; const S: string) : SizeInt
function PosEx(c: Char; const S: string; Offset: SizeUInt) : SizeInt
function PosEx(const SubStr: UnicodeString; const S: UnicodeString;
Offset: SizeUInt) : SizeInt`

```
function PosEx(c: WideChar; const S: UnicodeString; Offset: SizeUInt)
    : SizeInt
function PosEx(const SubStr: UnicodeString; const S: UnicodeString)
    : SizeInt
```

Visibility: default

Description: `PosEx` returns the position of the first occurrence of the character `C` or the substring `SubStr` in the string `S`, starting the search at position `Offset` (default 1). If `C` or `SubStr` does not occur in `S` after the given `Offset`, zero is returned. The position `Offset` is also searched.

Errors: None.

See also: `NPos` ([1180](#)), `AnsiContainsText` ([1163](#)), `AnsiContainsStr` ([1163](#))

74.3.63 PosSet

Synopsis: Return the position in a string of any character out of a set of characters

```
Declaration: function PosSet(const c: TSysCharSet; const s: ansistring) : SizeInt
function PosSet(const c: string; const s: ansistring) : SizeInt
```

Visibility: default

Description: `PosSet` returns the position in `s` of the first found character which is in the set `c`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1181](#)), `PosSetEx` ([1182](#)), `#rtl.system.pos` ([1365](#)), `RPosEx` ([1186](#))

74.3.64 PosSetEx

Synopsis: Return the position in a string of any character out of a set of characters, starting at a certain position

```
Declaration: function PosSetEx(const c: TSysCharSet; const s: ansistring;
                           count: Integer) : SizeInt
function PosSetEx(const c: string; const s: ansistring; count: Integer)
    : SizeInt
```

Visibility: default

Description: `PosSetEx` returns the position in `s` of the first found character which is in the set `c`, and starts searching at character position `Count`. If none of the characters in `c` is found in `s`, then 0 is returned.

Errors: None.

See also: `PosEx` ([1181](#)), `PosSet` ([1182](#)), `#rtl.system.pos` ([1365](#)), `RPosEx` ([1186](#))

74.3.65 RandomFrom

Synopsis: Choose a random string from an array of strings.

```
Declaration: function RandomFrom(const AValues: Array of string) : string; Overload
```

Visibility: default

Description: `RandomFrom` picks at random a valid index in the array `AValues` and returns the string at that position in the array.

Errors: None.

See also: `AnsiMatchStr` ([1165](#)), `AnsiMatchText` ([1165](#))

74.3.66 Removeleadingchars

Synopsis: Remove any leading characters in a set from a string

Declaration: `procedure Removeleadingchars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `Removeleadingchars` removes any starting characters from `S` that appear in the set `CSet`. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimLeft` ([1600](#)) which used whitespace as the set.

Errors: None.

See also: `TrimLeft` ([1600](#)), `RemoveTrailingChars` ([1183](#)), `RemovePadChars` ([1183](#)), `TrimLeftSet` ([1190](#))

74.3.67 RemovePadChars

Synopsis: Remove any trailing or leading characters in a set from a string

Declaration: `procedure RemovePadChars(var S: AnsiString; const CSet: TSysCharSet)`

Visibility: default

Description: `RemovePadChars` removes any leading trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string, and it stops removing characters as soon as a character not in `CSet` is encountered. Then the same procedure is repeated starting from the beginning of the string. This is similar in behaviour to `Trim` ([1599](#)) which used whitespace as the set.

Errors: None.

See also: `Trim` ([1599](#)), `RemoveLeadingChars` ([1183](#)), `RemoveTrailingChars` ([1183](#)), `TrimSet` ([1191](#)), `TrimLeftSet` ([1190](#)), `TrimRightSet` ([1190](#))

74.3.68 RemoveTrailingChars

Synopsis: Remove any trailing characters in a set from a string

Declaration: `procedure RemoveTrailingChars(var S: AnsiString;
const CSet: TSysCharSet)`

Visibility: default

Description: `RemoveTrailingChars` removes any trailing characters from `S` that appear in the set `CSet`, i.e. it starts with the last character and works its way to the start of the string. It stops removing characters as soon as a character not in `CSet` is encountered. This is similar in behaviour to `TrimRight` ([1600](#)) which used whitespace as the set.

See also: `TrimRight` ([1600](#)), `RemoveLeadingChars` ([1183](#)), `TrimRightSet` ([1190](#))

74.3.69 ReplaceStr

Synopsis: Replace strings case-sensitively

Declaration: `function ReplaceStr(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `ReplaceStr` is a utility function that scans `AText` and replaces all occurrences of `AFromText` with `AToText` and returns the resulting string. It simply calls `StringReplace` (1576) with the appropriate options.

See also: `StringReplace` (1576), `ReplaceText` (1184)

74.3.70 ReplaceText

Synopsis: Replace strings case-insensitively

Declaration: `function ReplaceText(const AText: string; const AFromText: string;
const AToText: string) : string`

Visibility: default

Description: `ReplaceText` is a utility function that scans `AText` and replaces all occurrences of `AFromText` (case insensitive) with `AToText` and returns the resulting string. It simply calls `StringReplace` (1576) with the appropriate options.

See also: `StringReplace` (1576), `ReplaceText` (1184)

74.3.71 ReverseString

Synopsis: Reverse characters in a string

Declaration: `function ReverseString(const AText: string) : string`

Visibility: default

Description: `ReverseString` returns a string, made up of the characters in string `AText`, in reverse order.

Errors: None.

See also: `RandomFrom` (1182)

74.3.72 RightBStr

Synopsis: Copy a given number of characters (bytes), counting from the right of a string.

Declaration: `function RightBStr(const AText: AnsiString; const AByteCount: SizeInt)
: AnsiString`

Visibility: default

Description: `RightBStr` returns a string containing the rightmost `AByteCount` bytes from the string `AText`. If `AByteCount` is larger than the length (in bytes) of `AText`, only as many bytes as available are returned.

Errors: None.

See also: `LeftBStr` (1178), `AnsiRightStr` (1167), `RightStr` (1185), `MidBStr` (1179)

74.3.73 RightStr

Synopsis: Copy a given number of characters, counting from the right of a string.

Declaration:

```
function RightStr(const AText: AnsiString; const ACount: SizeInt)
                : AnsiString
function RightStr(const AText: WideString; const ACount: SizeInt)
                : WideString
```

Visibility: default

Description: `RightStr` returns a string containing the rightmost `ACount` characters from the string `AText`. If `ACount` is larger than the length (in characters) of `AText`, only as many characters as available are returned.

Errors: None.

See also: [LeftStr \(1178\)](#), [AnsiRightStr \(1167\)](#), [RightBStr \(1184\)](#), [MidStr \(1179\)](#)

74.3.74 RomanToInt

Synopsis: Convert a string with a Roman number to its decimal value.

Declaration:

```
function RomanToInt(const S: string;
                    Strictness: TRomanConversionStrictness) : LongInt
```

Visibility: default

Description: `RomanToInt` returns the decimal equivalent of the Roman numerals in the string `S`. Invalid characters are dropped from `S`. A negative numeral is supported as well. The level of error checking is determined by the `strictness` parameter, the values are described in the type `TRomanConversionStrictness` ([1161](#)).

Errors: On error, a `EConvertError` ([1160](#)) exception is raised.

See also: [TRomanConversionStrictness \(1161\)](#), [IntToRoman \(1176\)](#), [Hex2Dec \(1175\)](#), [Numb2Dec \(1180\)](#)

74.3.75 RomanToIntDef

Synopsis: Convert a roman numeral to an integer value

Declaration:

```
function RomanToIntDef(const S: string; const ADefault: LongInt;
                       Strictness: TRomanConversionStrictness) : LongInt
```

Visibility: default

Description: `RomanToInt` converts the roman numeral in `S` to an integer and returns the integer value. The strictness of the conversion algorithm is determined by `Strictness`. If the conversion fails, `ADefault` is returned.

See also: [TRomanConversionStrictness \(1161\)](#), [TryRomanToInt \(1191\)](#), [RomanToInt \(1185\)](#), [IntToRoman \(1176\)](#)

74.3.76 RPos

Synopsis: Find last occurrence of substring or character in a string

Declaration: `function RPos(c: Char; const S: AnsiString) : SizeInt; Overload`
`function RPos(const Substr: AnsiString; const Source: AnsiString)`
`: SizeInt; Overload`

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at the end of the string, and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPosEx` ([1186](#))

74.3.77 RPosEx

Synopsis: Find last occurrence substring or character in a string, starting at a certain position

Declaration: `function RPosEX(C: Char; const S: AnsiString; offs: Cardinal) : SizeInt`
`; Overload`
`function RPosEx(const Substr: AnsiString; const Source: AnsiString;`
`offs: Cardinal) : SizeInt; Overload`

Visibility: default

Description: `RPos` looks in `S` for the character `C` or the string `SubStr`. It starts looking at position `Offs` (counted from the start of the string), and searches towards the beginning of the string. If a match is found, it returns the position of the match.

See also: `RPos` ([1186](#))

74.3.78 SearchBuf

Synopsis: Search a buffer for a certain string.

Declaration: `function SearchBuf(Buf: PChar; BufLen: SizeInt; SelStart: SizeInt;`
`SelLength: SizeInt; SearchString: string;`
`Options: TStringSearchOptions) : PChar`
`function SearchBuf(Buf: PChar; BufLen: SizeInt; SelStart: SizeInt;`
`SelLength: SizeInt; SearchString: string) : PChar`

Visibility: default

Description: `SearchBuf` searches the buffer `Buf` for the occurrence of `SearchString`. At most `Buflen` characters are searched, and the search is started at `SelStart+SelLength`. If a match is found, a pointer to the position of the match is returned. The parameter `Options` ([1162](#)) specifies how the search is conducted. It is a set of the following options:

Table 74.5:

Option	Effect
<code>soDown</code>	Searches forward, starting at the end of the selection. Default is searching up
<code>soMatchCase</code>	Observe case when searching. Default is to ignore case.
<code>soWholeWord</code>	Match only whole words. Default also returns parts of words

The standard constant `WordDelimiters` (1161) is used to mark the boundaries of words.

The `SelStart` parameter is zero based.

Errors: Buflen must be the real length of the string, no checking on this is performed.

See also: `FindPart` (1174), `ExtractWord` (1172), `ExtractWordPos` (1173), `ExtractSubStr` (1172), `IsWordPresent` (1177)

74.3.79 Soundex

Synopsis: Compute the soundex of a string

Declaration: `function Soundex(const AText: string; ALength: TSoundexLength) : string`
`function Soundex(const AText: string) : string`

Visibility: default

Description: `Soundex` computes a soundex code for `AText`. The resulting code will at most have `ALength` characters. The soundex code is computed according to the US system of soundex computing, which may result in inaccurate results in other languages.

Note that `AText` may not contain null characters.

Errors: None.

See also: `SoundexCompare` (1187), `SoundexInt` (1187), `SoundexProc` (1188), `SoundexWord` (1188), `SoundexSimilar` (1188)

74.3.80 SoundexCompare

Synopsis: Compare soundex values of 2 strings.

Declaration: `function SoundexCompare(const AText: string; const AOther: string; ALength: TSoundexLength) : Integer`
`function SoundexCompare(const AText: string; const AOther: string) : Integer`

Visibility: default

Description: `SoundexCompare` computes the soundex codes of `AText` and `AOther` and feeds these to `CompareText`. It will return -1 if the soundex code of `AText` is less than the soundex code of `AOther`, 0 if they are equal, and 1 if the code of `AOther` is larger than the code of `AText`.

Errors: None.

See also: `Soundex` (1187), `SoundexInt` (1187), `SoundexProc` (1188), `SoundexWord` (1188), `SoundexSimilar` (1188)

74.3.81 SoundexInt

Synopsis: Soundex value as an integer.

Declaration: `function SoundexInt(const AText: string; ALength: TSoundexIntLength) : Integer`
`function SoundexInt(const AText: string) : Integer`

Visibility: default

Description: `SoundexInt` computes the Soundex (1187) code (with length `ALength`, default 4) of `AText`, and converts the code to an integer value.

Errors: None.

See also: `Soundex` (1187), `SoundexCompare` (1187), `SoundexProc` (1188), `SoundexWord` (1188), `SoundexSimilar` (1188)

74.3.82 SoundexProc

Synopsis: Default `AnsiResemblesText` implementation.

Declaration: `function SoundexProc(const AText: string; const AOther: string) : Boolean`

Visibility: default

Description: `SoundexProc` is the standard implementation for the `AnsiResemblesText` (1167) procedure: By default, `AnsiResemblesProc` is set to this function. It compares the soundex codes of `AOther` and `AText` and returns `True` if they are equal, or `False` if they are not.

Errors: None.

See also: `Soundex` (1187), `SoundexCompare` (1187), `SoundexInt` (1187), `SoundexWord` (1188), `SoundexSimilar` (1188)

74.3.83 SoundexSimilar

Synopsis: Check whether 2 strings have equal soundex values

Declaration: `function SoundexSimilar(const AText: string; const AOther: string; ALength: TSoundexLength) : Boolean`
`function SoundexSimilar(const AText: string; const AOther: string) : Boolean`

Visibility: default

Description: `SoundexSimilar` returns `True` if the soundex codes (with length `ALength`) of `AText` and `AOther` are equal, and `False` if they are not.

Errors: None.

See also: `Soundex` (1187), `SoundexCompare` (1187), `SoundexInt` (1187), `SoundexProc` (1188), `SoundexWord` (1188), `Soundex` (1187)

74.3.84 SoundexWord

Synopsis: Calculate a word-sized soundex value

Declaration: `function SoundexWord(const AText: string) : Word`

Visibility: default

Description: `SoundexInt` computes the Soundex (1187) code (with length 4) of `AText`, and converts the code to a word-sized value.

`AText` may not contain null characters.

Errors: None.

See also: [Soundex \(1187\)](#), [SoundexCompare \(1187\)](#), [SoundexInt \(1187\)](#), [SoundexProc \(1188\)](#), [SoundexSimilar \(1188\)](#)

74.3.85 StringReplace

Synopsis: Optimized search-and-replace algorithm

Declaration:

```
function StringReplace(const S: string; const OldPattern: string;
                      const NewPattern: string; Flags: TReplaceFlags;
                      Algorithm: TStringReplaceAlgorithm) : string
; Overload

function StringReplace(const S: UnicodeString;
                      const OldPattern: UnicodeString;
                      const NewPattern: UnicodeString;
                      Flags: TReplaceFlags) : UnicodeString; Overload

function StringReplace(const S: WideString;
                      const OldPattern: WideString;
                      const NewPattern: WideString;
                      Flags: TReplaceFlags) : WideString; Overload
```

Visibility: default

Description: `StringReplace` replaces one or all occurrences of `OldPattern` with `NewPattern` in the string `S`. The behaviour is controlled by `Flags` and the search mechanism may be optimized using `Algorithm`. A list of possible algorithms is specified in [TStringReplaceAlgorithm \(1162\)](#).

For ansistrings, this is an optimized version of the `SysUtils.StringReplace (1576)` algorithm. For widestrings or unicodestrings, the algorithm parameter is ignored and the default mechanism in `sysutils` is always used.

Errors: None.

See also: [SysUtils.StringReplace \(1576\)](#), [TStringReplaceAlgorithm \(1162\)](#)

74.3.86 StringsReplace

Synopsis: Replace occurrences of a set of strings to another set of strings

Declaration:

```
function StringsReplace(const S: string; OldPattern: Array of string;
                      NewPattern: Array of string;
                      Flags: TReplaceFlags) : string
```

Visibility: default

Description: `StringsReplace` scans `S` for the occurrence of one of the strings in `OldPattern` and replaces it with the corresponding string in `NewPattern`. It takes into account `Flags`, which has the same meaning as in [StringReplace \(1576\)](#).

Corresponding strings are matched by location: the `N`-th string in `OldPattern` is replaced by the `N`-th string in `NewPattern`. Note that this means that the number of strings in both arrays must be the same.

Errors: If the number of strings in both arrays is different, then an exception is raised.

See also: [StringReplace \(1576\)](#), [TReplaceFlags \(1465\)](#)

74.3.87 StuffString

Synopsis: Replace part of a string with another string.

Declaration: `function StuffString(const AText: string; AStart: Cardinal;
 ALength: Cardinal; const ASubText: string) : string`

Visibility: default

Description: `StuffString` returns a copy of `AText` with the segment starting at `AStart` with length `ALength`, replaced with the string `ASubText`. Basically it deletes the segment of `Atext` and inserts the new text in it's place.

Errors: No checking on the validity of the `AStart` and `ALength` parameters is done. Providing invalid values may result in access violation errors.

See also: [FindPart \(1174\)](#), [DelChars \(1171\)](#), [DelSpace \(1171\)](#), [ExtractSubStr \(1172\)](#), [DupeString \(1171\)](#)

74.3.88 Tab2Space

Synopsis: Convert tab characters to a number of spaces

Declaration: `function Tab2Space(const S: string; Numb: Byte) : string`

Visibility: default

Description: `Tab2Space` returns a copy of `S` with all tab characters (ASCII character 9) converted to `Numb` spaces.

Errors: None.

See also: [StuffString \(1190\)](#), [FindPart \(1174\)](#), [ExtractWord \(1172\)](#), [DelChars \(1171\)](#), [DelSpace \(1171\)](#), [DelSpace1 \(1171\)](#), [DupeString \(1171\)](#)

74.3.89 TrimLeftSet

Synopsis: Remove any leading characters in a set from a string and returns the result

Declaration: `function TrimLeftSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimLeftSet` performs the same action as [RemoveLeadingChars \(1183\)](#), but returns the resulting string.

Errors: None.

See also: [TrimLeft \(1600\)](#), [RemoveLeadingChars \(1183\)](#), [RemoveTrailingChars \(1183\)](#), [RemovePadChars \(1183\)](#), [TrimSet \(1191\)](#), [TrimRightSet \(1190\)](#)

74.3.90 TrimRightSet

Synopsis: Remove any trailing characters in a set from a string and returns the result

Declaration: `function TrimRightSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimLeftSet` performs the same action as `RemoveTrailingChars` (1183), but returns the resulting string.

Errors: None.

See also: `TrimRight` (1600), `RemoveLeadingChars` (1183), `RemoveTrailingChars` (1183), `RemovePadChars` (1183), `TrimSet` (1191), `TrimLeftSet` (1190)

74.3.91 TrimSet

Synopsis: Remove any leading or trailing characters in a set from a string and returns the result

Declaration: `function TrimSet(const S: string; const CSet: TSysCharSet) : string`

Visibility: default

Description: `TrimSet` performs the same action as `RemovePadChars` (1183), but returns the resulting string.

Errors: None.

See also: `Trim` (1599), `RemoveLeadingChars` (1183), `RemoveTrailingChars` (1183), `RemovePadChars` (1183), `TrimRightSet` (1190), `TrimLeftSet` (1190)

74.3.92 TryRomanToInt

Synopsis: Try to convert a roman numeral to an integer value.

Declaration: `function TryRomanToInt(S: string; out N: LongInt;
Strictness: TRomanConversionStrictness) : Boolean`

Visibility: default

Description: `TryRomanToInt` will try to convert the roman numeral in `S` to an integer and returns the integer value in `N`. The strictness of the conversion algorithm is determined by `Strictness`. If the conversion succeeds, then `True` is returned, or else `False`.

See also: `TRomanConversionStrictness` (1161), `RomanToIntDef` (1185), `RomanToInt` (1185), `IntToRoman` (1176)

74.3.93 WordCount

Synopsis: Count the number of words in a string.

Declaration: `function WordCount(const S: string; const WordDelims: TSysCharSet)
: SizeInt`

Visibility: default

Description: `WordCount` returns the number of words in the string `S`. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`.

The pre-defined `StdWordDelims` (1161) constant can be used for the `WordDelims` argument.

Errors: None.

See also: `WordPosition` (1192), `StdWordDelims` (1161), `ExtractWord` (1172), `ExtractWordPos` (1173)

74.3.94 WordPosition

Synopsis: Search position of Nth word in a string.

Declaration: `function WordPosition(const N: Integer; const S: string;
const WordDelims: TSysCharSet) : SizeInt`

Visibility: default

Description: `WordPosition` returns the position (in characters) of the N-th word in the string S. A word is a non-empty string of characters bounded by one of the characters in `WordDelims`. If N is out of range, zero is returned.

The pre-defined `StdWordDelims` (1161) constant can be used for the `WordDelims` argument.

Errors: None

See also: `WordCount` (1191), `StdWordDelims` (1161), `ExtractWord` (1172), `ExtractWordPos` (1173)

74.3.95 XorDecode

Synopsis: Decode a string encoded with `XorEncode` (1192)

Declaration: `function XorDecode(const Key: string; const Source: string) : string`

Visibility: default

Description: `XorDecode` decodes `Source` and returns the original string that was encrypted using `XorEncode` (1192) with key `Key`. If a different key is used than the key used to encode the string, the result will be unreadable.

Errors: If the string `Source` is not a valid `XorEncode` result (e.g. contains non-numerical characters), then a `EConversionError` exception will be raised.

See also: `XorEncode` (1192), `XorString` (1193)

74.3.96 XorEncode

Synopsis: Encode a string by XOR-ing its characters using characters of a given key, representing the result as hex values.

Declaration: `function XorEncode(const Key: string; const Source: string) : string`

Visibility: default

Description: `XorEncode` encodes the string `Source` by XOR-ing each character in `Source` with the corresponding character in `Key` (repeating `Key` as often as necessary) and representing the resulting ASCII code as a hexadecimal number (of length 2). The result is therefore twice as long as the original string, and every 2 bytes represent an ASCII code.

Feeding the resulting string with the same key `Key` to the `XorDecode` (1192) function will result in the original `Source` string.

This function can be used e.g. to trivially encode a password in a configuration file.

Errors: None.

See also: `XorDecode` (1192), `XorString` (1193), `Hex2Dec` (1175)

74.3.97 XorString

Synopsis: Encode a string by XOR-ing its characters using characters of a given key.

Declaration: `function XorString(const Key: ShortString; const Src: ShortString)
: ShortString`

Visibility: default

Description: `XorString` encodes the string `Src` by XOR-ing each character in `Source` with the corresponding character in `Key`, repeating `Key` as often as necessary. The resulting string may contain unreadable characters and may even contain null characters. For this reason it may be a better idea to use the `XorEncode` ([1192](#)) function instead, which will representing each resulting ASCII code as a hexadecimal number (of length 2).

Feeding the result again to `XorString` with the same `Key`, will result in the original string `Src`.

Errors: None.

See also: `XorEncode` ([1192](#)), `XorDecode` ([1192](#))

Chapter 75

Reference for unit 'System'

75.1 Overview

The system unit contains the standard supported functions of Free Pascal. It is the same for all platforms. Basically it is the same as the system unit provided with Borland or Turbo Pascal.

Functions are listed in alphabetical order. Arguments of functions or procedures that are optional are put between square brackets.

The pre-defined constants and variables are listed in the first section. The second section contains an overview of all functions, grouped by functionality, and the last section contains the supported functions and procedures.

75.2 Unicode and codepage support

The system unit works with Short-, Ansi-, and UnicodeString routines for all string related operations.

Ansistrings are code-page aware, which means that code page information is associated with them. For most routines, the support for converting these code pages is natural. For some routines, care must be taken when converting from codepage-aware strings to widestring.

The codepage conversion support is influenced by the following variables:

Table 75.1:

Name	Description
DefaultSystemCodePage (1262)	Actual code page to use when CP_ACP (1200) is encountered
DefaultUnicodeCodePage (1263)	Code page for new unicode strings
DefaultFileSystemCodePage (1261)	Codepage to use when sending strings to single-byte OS filesystem routines.
DefaultRTLFileSystemCodePage (1262)	Codepage to use when receiving strings from single-byte OS filesystem routines.

The windows code page identifiers are used. There are 3 special codepage identifiers:

Table 75.2:

Name	Description
CP_ACP (1200)	Currently set default syststem cpdepage
CP_OEMCP (1200)	OEM (console) code page (only on windows)
CP_NONE (1200)	Indicates absence of code page information for a string
DefaultRTLFileSystemCodePage (1262)	

The following routines may perform code page conversions:

Table 75.3:

Name	Description
LowerCase (1356)	Return lowercase version of a string.
UpCase (1410)	Convert a string to all uppercase.
GetDir (1330)	Return the current directory
MkDir (1357)	Create a new directory.
ChDir (1297)	Change current working directory.
RmDir (1375)	Remove directory when empty.
Assign (1270)	Assign a name to a file
Erase (1317)	Delete a file from disk
Rename (1372)	Rename file on disk
Read (1369)	Read from a text file into variable
ReadLn (1370)	Read from a text file into variable and goto next line
Write (1194)	Write variable to a text file
WriteLn (1194)	Write variable to a text file and append newline
ReadStr (1194)	Read variables from a string
WriteStr (1194)	Write variables to a string
Insert (1345)	Insert one string in another.
Copy (1194)	Copy part of a string.
Delete (1308)	Delete part of a string.
SetString (1388)	Set length of a string and copy buffer.

All these routines exist also in Unicode versions.

Note that for conversion of codepages and unicode strings, a unicode manager must be present. On windows, the system is used for this. On Unix, one of the fpwdestring or cwstring units must be used.

75.3 Miscellaneous functions

Functions that do not belong in one of the other categories.

Table 75.4:

Name	Description
Assert (1270)	Conditionally abort program with error
Break (1293)	Abort current loop
Continue (1304)	Next cycle in current loop
Exclude (1317)	Exclude an element from a set
Exit (1319)	Exit current function or procedure
Include (1340)	Include an element into a set
LongJump (1355)	Jump to execution point
Ord (1362)	Return ordinal value of enumerated type
Pred (1366)	Return previous value of ordinal type
SetJump (1385)	Mark execution point for jump
SizeOf (1392)	Return size of variable or type
Succ (1400)	Return next value of ordinal type

75.4 Operating System functions

Functions that are connected to the operating system.

Table 75.5:

Name	Description
Chdir (1297)	Change working directory
Getdir (1330)	Return current working directory
Halt (1336)	Halt program execution
Paramcount (1363)	Number of parameters with which program was called
Paramstr (1364)	Retrieve parameters with which program was called
Mkdir (1357)	Make a directory
Rmdir (1375)	Remove a directory
Runerror (1379)	Abort program execution with error condition

75.5 String handling

All things connected to string handling.

Table 75.6:

Name	Description
BinStr (1291)	Construct binary representation of integer
Chr (1297)	Convert ASCII code to character
Concat (1303)	Concatenate two strings
Copy (1194)	Copy part of a string
Delete (1308)	Delete part of a string
HexStr (1336)	Construct hexadecimal representation of integer
Insert (1345)	Insert one string in another
Length (1194)	Return length of string
Lowercase (1356)	Convert string to all-lowercase
OctStr (1361)	Construct octal representation of integer
Pos (1365)	Calculate position of one string in another
SetLength (1194)	Set length of a string
SetString (1388)	Set contents and length of a string
Str (1395)	Convert number to string representation
StringOfChar (1397)	Create string consisting of a number of characters
Uppcase (1410)	Convert string to all-uppercase
Val (1413)	Convert string to number

75.6 Mathematical routines

Functions connected to calculating and converting numbers.

Table 75.7:

Name	Description
Abs (1265)	Calculate absolute value
Arctan (1269)	Calculate inverse tangent
Cos (1305)	Calculate cosine of angle
Dec (1306)	Decrease value of variable
Exp (1320)	Exponentiate
Frac (1328)	Return fractional part of floating point value
Hi (1337)	Return high byte/word of value
Inc (1339)	Increase value of variable
Int (1345)	Calculate integer part of floating point value
Ln (1352)	Calculate logarithm
Lo (1353)	Return low byte/word of value
Odd (1361)	Is a value odd or even ?
Pi (1364)	Return the value of pi
Random (1368)	Generate random number
Randomize (1368)	Initialize random number generator
Round (1378)	Round floating point value to nearest integer number
Sin (1391)	Calculate sine of angle
Sqr (1393)	Calculate the square of a value
Sqrt (1394)	Calculate the square root of a value
Swap (1400)	Swap high and low bytes/words of a variable
Trunc (1406)	Truncate a floating point value

75.7 Memory management functions

Functions concerning memory issues.

Table 75.8:

Name	Description
Addr (1267)	Return address of variable
Assigned (1289)	Check if a pointer is valid
CompareByte (1298)	Compare 2 memory buffers byte per byte
CompareChar (1299)	Compare 2 memory buffers byte per byte
CompareDWord (1301)	Compare 2 memory buffers byte per byte
CompareWord (1302)	Compare 2 memory buffers byte per byte
CSeg (1306)	Return code segment
Dispose (1308)	Free dynamically allocated memory
DSeg (1310)	Return data segment
FillByte (1322)	Fill memory region with 8-bit pattern
FillChar (1322)	Fill memory region with certain character
FillDWord (1323)	Fill memory region with 32-bit pattern
FillQWord (1324)	Fill memory region with 64-bit pattern
FillWord (1324)	Fill memory region with 16-bit pattern
Freemem (1328)	Release allocated memory
Getmem (1331)	Allocate new memory
GetMemoryManager (1331)	Return current memory manager
High (1337)	Return highest index of open array or enumerated
IndexByte (1340)	Find byte-sized value in a memory range
IndexChar (1341)	Find char-sized value in a memory range
IndexDWord (1342)	Find DWord-sized (32-bit) value in a memory range
IndexQWord (1343)	Find QWord-sized value in a memory range
IndexWord (1343)	Find word-sized value in a memory range
IsMemoryManagerSet (1350)	Is the memory manager set
Low (1356)	Return lowest index of open array or enumerated
Move (1358)	Move data from one location in memory to another
MoveChar0 (1358)	Move data till first zero character
New (1360)	Dynamically allocate memory for variable
Ofs (1362)	Return offset of variable
Ptr (1367)	Combine segment and offset to pointer
ReAllocMem (1371)	Resize a memory block on the heap
Seg (1383)	Return segment
SetMemoryManager (1386)	Set a memory manager
Sptr (1393)	Return current stack pointer
SSeg (1394)	Return stack segment register value

75.8 File handling functions

Functions concerning input and output from and to file.

Table 75.9:

Name	Description
Append (1268)	Open a file in append mode
Assign (1270)	Assign a name to a file
Blockread (1292)	Read data from a file into memory
Blockwrite (1293)	Write data from memory to a file
Close (1298)	Close a file
Eof (1315)	Check for end of file
Eoln (1316)	Check for end of line
Erase (1317)	Delete file from disk
Filepos (1320)	Position in file
Filesize (1321)	Size of file
Flush (1326)	Write file buffers to disk
IOresult (1349)	Return result of last file IO operation
Read (1369)	Read from file into variable
Readln (1370)	Read from file into variable and goto next line
Rename (1372)	Rename file on disk
Reset (1373)	Open file for reading
Rewrite (1374)	Open file for writing
Seek (1381)	Set file position
SeekEof (1382)	Set file position to end of file
SeekEoln (1382)	Set file position to end of line
SetTextBuf (1388)	Set size of file buffer
Truncate (1407)	Truncate the file at position
Write (1194)	Write variable to file
WriteLn (1194)	Write variable to file and append newline

75.9 Run-Time Error behaviour

The sytem unit handles errors by default by generating a run-time error, and halting the program with an exit code equal to the run-time error number.

This behaviour changes when the SysUtils (1442) unit is used. In that case, all run-time errors are converted to exceptions: most run-time errors have their own exception class.

If these exceptions are caught, the program code decides what to do with it. If the exception is not caught, the program will exit through the default exception handler.

When the system unit documentation refers to run-time errors, the above should be kept in mind.

75.10 Constants, types and variables

75.10.1 Constants

```
AbstractErrorProc : TAbstractErrorProc = Nil
```

If set, the `AbstractErrorProc` constant is used when an abstract error occurs. If it is not set, then the standard error handling is done: A stack dump is performed, and the program exits with error code 211.

The `SysUtils` unit sets this procedure and raises an exception in its handler.

`AssertErrorProc : TAssertErrorProc = @SysAssert`

If set, the `AbstractErrorProc` constant is used when an assert error occurs. If it is not set, then the standard error handling is done: The assertion error message is printed, together with the location of the assertion, and A stack dump is performed, and the program exits with error code 227.

The **SysUtils** unit sets this procedure and raises an exception in its handler.

`BackTraceStrFunc : TBackTraceStrFunc = @SysBackTraceStr`

This handler is called to get a standard format for the backtrace routine.

`CP_ACP = 0`

`CP_ACP` is the default Windows codepage identifier.

`CP_ASCII = 20127`

`CP_ASCII` is the Windows ASCII encoding codepage identifier.

`CP_NONE = $FFFF`

`CP_NONE` is used when no code page information is available.

`CP_OEMCP = 1`

`CP_ACP` is the default Windows OEM (MS-DOS) codepage identifier.

`CP_UTF16 = 1200`

`CP_UTF16` is the default Windows unicode codepage identifier (little endian).

`CP_UTF16BE = 1201`

`CP_UTF16BE` is the Windows unicode codepage identifier (big endian).

`CP_UTF7 = 65000`

`CP_UTF7` is the Windows unicode 7-Bit encoding codepage identifier.

`CP_UTF8 = 65001`

`CP_UTF8` is the Windows unicode 8-Bit encoding codepage identifier.

`Default8087CW : Word = $1332`

`DefaultMXCSR : DWord = $1900`

`DefaultStackSize = 4 * 1024 * 1024`

Default size for a new thread's stack (4MiB by default).

Erroraddr : CodePointer = Nil

Address where the last error occurred.

Errorcode : Word = 0

Last error code.

ErrorProc : TErrorProc = Nil

If set, the ErrorProc constant is used when a run-time error occurs. If it is not set, then the standard error handling is done: a stack dump is performed, and the program exits with the indicated error code.

The SysUtils unit sets this procedure and raises an exception in its handler.

ExceptClsProc : Pointer = Nil

ExceptClsProc is used in SEH (Structured Exception Support) to convert OS exception information to FPC exception classes when filtering exceptions. It is set e.g. by the sysutils unit. If it is not set, the exception is not handled.

ExceptObjProc : Pointer = Nil

ExceptObjProc is used in SEH (Structured Exception Support) to convert OS exception information to FPC exceptions. It is set e.g. by the sysutils unit. If it is not set, a run-time error results when OS exceptions are intercepted.

ExceptProc : TExceptProc = Nil

This constant points to the current exception handling procedure. This routine is called when an unhandled exception occurs, i.e. an exception that is not stopped by a except block.

If the handler is not set, the RTL will emit a run-time error 217 when an unhandler exception occurs.

It is set by the sysutils ([1442](#)) unit.

ExitProc : CodePointer = Nil

Exit procedure pointer.

E_NOINTERFACE = (\$80004002)

Interface call result: Error: not an interface

E_NOTIMPL = (\$80004001)

Interface call result: Interface not implemented

E_UNEXPECTED = (\$8000FFFF)

Interface call result: Unexpected error

Filemode : Byte = 2

Default file mode for untyped files.

filerecnamelength = 255

filerecnamelength is the maximum filename size for untyped files.

float_flag_denormal = exDenormalized

IEC/IEEE floating-point exception flag: ?

float_flag_divbyzero = exZeroDivide

IEC/IEEE floating-point exception flag: Division by zero error

float_flag_inexact = exPrecision

IEC/IEEE floating-point exception flag: ?

float_flag_invalid = exInvalidOp

IEC/IEEE floating-point exception flag: Invalid operation error

float_flag_overflow = exOverflow

IEC/IEEE floating-point exception flag: Overflow error

float_flag_underflow = exUnderflow

IEC/IEEE floating-point exception flag: Underflow error

float_round_down = rmDown

Round down

float_round_nearest_even = rmNearest

Round to nearest even number

float_round_to_zero = rmTruncate

Round in the direction of zero (down for positive, up for negative)

float_round_up = rmUp

Round up

fmAppend = \$D7B4

File mode: File is open for writing, appending to the end.

`fmClosed = $D7B0`

File mode: File is closed.

`fmInOut = $D7B3`

File mode: File is open for reading and writing.

`fmInput = $D7B1`

File mode: File is open for reading.

`fmOutput = $D7B2`

File mode: File is open for writing.

`fpc_in_abs_long = 64`

Internal ABS function

`fpc_in_abs_real = 127`

FPC compiler internal procedure index: abs (real)

`fpc_in_addr_x = 42`

FPC compiler internal procedure index: addr

`fpc_in_aligned_x = 80`

FPC compiler internal procedure index: aligned

`fpc_in_arctan_real = 130`

FPC compiler internal procedure index: arctan (real)

`fpc_in_assert_x_y = 41`

FPC compiler internal procedure index: assert

`fpc_in_assigned_x = 19`

FPC compiler internal procedure index: assigned

`fpc_in_bitsizeof_x = 61`

FPC compiler internal procedure index: bitsizeof

`fpc_in_box_x = 77`

FPC compiler internal procedure index: box

fpc_in_break = 39

FPC compiler internal procedure index: break

fpc_in_bsf_x = 74

FPC compiler internal procedure index: bsf_x

fpc_in_bsr_x = 75

FPC compiler internal procedure index: bsr_x

fpc_in_chr_byte = 7

FPC compiler internal procedure index: chr

fpc_in_concat_x = 18

FPC compiler internal procedure index: concat

fpc_in_const_abs = 101

FPC compiler internal procedure index: abs

fpc_in_const_odd = 102

FPC compiler internal procedure index: sqr

fpc_in_const_ptr = 103

FPC compiler internal procedure index: sqr

fpc_in_const_sqr = 100

FPC compiler internal procedure index: sqr

fpc_in_const_swap_long = 105

FPC compiler internal procedure index: swap (long)

fpc_in_const_swap_qword = 108

FPC compiler internal procedure index: swap (qword)

fpc_in_const_swap_word = 104

FPC compiler internal procedure index: swap (word)

fpc_in_continue = 40

FPC compiler internal procedure index: continue

`fpc_in_copy_x` = 49

FPC compiler internal procedure index: copy

`fpc_in_cos_real` = 125

FPC compiler internal procedure index: cos (real)

`fpc_in_cycle` = 52

FPC compiler internal procedure index: cycle

`fpc_in_dec_x` = 36

FPC compiler internal procedure index: dec

`fpc_in_default_x` = 76

FPC compiler internal procedure index: default

`fpc_in_dispose_x` = 47

FPC compiler internal procedure index: dispose

`fpc_in_exclude_x_y` = 38

FPC compiler internal procedure index: exclude

`fpc_in_exit` = 48

FPC compiler internal procedure index: exit

`fpc_in_exp_real` = 124

FPC internal compiler routine: `in_exp_real`

`fpc_in_fillchar_x` = 55

FPC internal compiler routine: `in_fillchar_x`

`fpc_in_finalize_x` = 45

FPC compiler internal procedure index: finalize

`fpc_in_fma_double` = 134

FPC compiler internal procedure index: fma (double)

`fpc_in_fma_extended` = 135

FPC compiler internal procedure index: fma (extended)

`fpc_in_fma_float128 = 136`

FPC compiler internal procedure index: fma (float 128)

`fpc_in_fma_single = 133`

FPC compiler internal procedure index: fma (single)

`fpc_in_frac_real = 122`

FPC internal compiler routine: `in_frac_real`

`fpc_in_get_caller_addr = 57`

FPC internal compiler routine: `in_get_caller_addr`

`fpc_in_get_caller_frame = 58`

FPC internal compiler routine: `in_get_caller_frame`

`fpc_in_get_frame = 56`

FPC internal compiler routine: `in_get_frame`

`fpc_in_high_x = 28`

FPC compiler internal procedure index: high

`fpc_in_hi_long = 4`

FPC compiler internal procedure index: hi (long)

`fpc_in_hi_qword = 107`

FPC compiler internal procedure index: hi (qword)

`fpc_in_hi_word = 2`

FPC compiler internal procedure index: hi (word)

`fpc_in_include_x_y = 37`

FPC compiler internal procedure index: include

`fpc_in_inc_x = 35`

FPC compiler internal procedure index: inc

`fpc_in_initialize_x = 50`

FPC compiler internal procedure index: initialize

`fpc_in_int_real = 123`

FPC internal compiler routine: `in_int_real`

`fpc_in_leave = 51`

FPC compiler internal procedure index: leave

`fpc_in_length_string = 6`

FPC compiler internal procedure index: length

`fpc_in_ln_real = 131`

FPC compiler internal procedure index: `ln (real)`

`fpc_in_low_x = 27`

FPC compiler internal procedure index: low

`fpc_in_lo_long = 3`

FPC compiler internal procedure index: `lo (long)`

`fpc_in_lo_qword = 106`

FPC compiler internal procedure index: `lo (qword)`

`fpc_in_lo_word = 1`

FPC compiler internal procedure index: `lo (word)`

`fpc_in_mmx_pcmpeqb = 200`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqd = 202`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpeqw = 201`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtb = 203`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtd = 205`

FPC compiler internal procedure index: MMX

`fpc_in_mmx_pcmpgtw` = 204

FPC compiler internal procedure index: MMX

`fpc_in_move_x` = 54

FPC internal compiler routine: `in_move_x`

`fpc_in_new_x` = 46

FPC compiler internal procedure index: new

`fpc_in_ofs_x` = 21

FPC compiler internal procedure index: ofs

`fpc_in_ord_x` = 5

FPC compiler internal procedure index: ord

`fpc_in_pack_x_y_z` = 59

FPC compiler internal procedure index: pack

`fpc_in_pi_real` = 126

FPC internal compiler routine: `in_pi_real`

`fpc_in_popcnt_x` = 79

FPC compiler internal procedure index: popcnt

`fpc_in_pred_x` = 30

FPC compiler internal procedure index: pred

`fpc_in_prefetch_var` = 109

FPC compiler internal procedure index: prefetch

`fpc_in_readln_x` = 17

FPC compiler internal procedure index: readln

`fpc_in_readstr_x` = 63

Internal read string procedure

`fpc_in_read_x` = 16

FPC compiler internal procedure index: read

fpc_in_reset_typedfile = 32

FPC compiler internal procedure index: reset

fpc_in_reset_x = 25

FPC compiler internal procedure index: reset

fpc_in_rewrite_typedfile = 33

FPC compiler internal procedure index: rewrite

fpc_in_rewrite_x = 26

FPC compiler internal procedure index: rewrite

fpc_in_rol_x = 67

fpc_in_rol_x_x = 68

fpc_in_ror_x = 65

fpc_in_ror_x_x = 66

fpc_in_round_real = 121

FPC internal compiler routine: in_round_real

fpc_in_sar_x = 73

FPC compiler internal procedure index: sar_x

fpc_in_sar_x_y = 72

FPC compiler internal procedure index: sar_x_y

fpc_in_seg_x = 29

FPC compiler internal procedure index: seg

fpc_in_setlength_x = 44

FPC compiler internal procedure index: setlength

fpc_in_setstring_x_y_z = 81

FPC compiler internal procedure index: setstring

fpc_in_settextbuf_file_x = 34

FPC compiler internal procedure index: setttextbuf

fpc_in_sin_real = 132

FPC compiler internal procedure index: sin (real)

fpc_in_sizeof_x = 22

FPC compiler internal procedure index: sizeof

fpc_in_slice = 53

FPC internal compiler routine: in_slice

fpc_in_sqrt_real = 129

FPC compiler internal procedure index: sqrt (real)

fpc_in_sqr_real = 128

FPC compiler internal procedure index: sqr (real)

fpc_in_str_x_string = 20

FPC compiler internal procedure index: str

fpc_in_succ_x = 31

FPC compiler internal procedure index: succ

fpc_in_trunc_real = 120

FPC internal compiler routine: in_trunc_real

fpc_in_typeinfo_x = 43

FPC compiler internal procedure index: typeinfo

fpc_in_typeof_x = 23

FPC compiler internal procedure index: typeof

fpc_in_unbox_x_y = 78

FPC compiler internal procedure index: unbox

fpc_in_unpack_x_y_z = 60

FPC compiler internal procedure index: unpack

`fpc_in_val_x = 24`

FPC compiler internal procedure index: val

`fpc_in_writeln_x = 15`

FPC compiler internal procedure index: writeln

`fpc_in_writestr_x = 62`

Internal write string procedure

`fpc_in_write_x = 14`

FPC compiler internal procedure index: write

`fpc_objc_encode_x = 71`

FPC compiler internal procedure index: encode

`fpc_objc_protocol_x = 70`

FPC compiler internal procedure index: protocol

`fpc_objc_selector_x = 69`

`growheapsize1 : PtrUInt = 256 * 1024`

Grow rate for block less than 256 Kb.

`growheapsize2 : PtrUInt = 1024 * 1024`

Grow rate for block larger than 256 Kb.

`growheapsize_small : PtrUInt = 32 * 1024`

Fixed size small blocks grow rate

`InitProc : CodePointer = Nil`

`InitProc` is a routine that can be called after all units were initialized. It can be set by units to execute code that can be initialized after all units were initialized.

Remark: When setting the value of `InitProc`, the previous value should always be saved, and called when the installed initialization routine has finished executing.

`IObjectInstance : TGuid =
 ' {D91C9AF4-3C93-420F-A303-BF5BA82BFD23} '`

`IObjectInstance` is an internal GUID, which should not be used in end-user code. It is used in the `as` operator.

`IsMultiThread : longbool = False`

Indicates whether more than one thread is running in the application.

`maxint = maxsmallint`

Maximum integer value.

`MaxKeptOSChunks : DWord = 4`

`MaxKeptOSChunks` tells the heap manager how many free chunks of OS-allocated memory it should keep in memory. When freeing memory, it can happen that a memory block obtained from the OS is completely free. If more than `MaxKeptOSChunks` such blocks are free, then the heap manager will return them to the OS, to reduce memory requirements.

`maxLongint = $7fffffff`

Maximum longint value.

`MaxSIntValue = (ValSInt)`

Maximum String-size value.

`maxSmallint = 32767`

Maximum smallint value.

`MaxUIntValue = (ValUInt)`

Maximum unsigned integer value.

`Max_Frame_Dump : Word = 8`

Maximum number of frames to show in error frame dump.

`ModuleIsCpp : Boolean = False`

`ModuleIsCpp` is always false for FPC programs, it is provided for Delphi compatibility only.

`ModuleIsLib : Boolean = False`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a library (or package) (`True`) or program (`False`).

`ModuleIsPackage : Boolean = False`

`ModuleIsLib` is set by the compiler when linking a library, program or package, and determines whether the current module is a package (`True`) or a library or program (`False`).

RaiseMaxFrameCount : LongInt = 16

Maximum number of frames to include in TExceptObject ([1238](#))

RaiseProc : TExceptProc = Nil

Procedure to raise an exception.

RT_ACCELERATOR = (9)

Constant identifying an accelerator resource

RT_ANICURSOR = (21)

This constant can be used to specify a resource of type "animated cursor".

RT_ANIICON = (22)

This constant can be used to specify a resource of type "animated icon".

RT_BITMAP = (2)

Constant identifying a bitmap resource

RT_CURSOR = (1)

Constant identifying a cursor resource

RT_DIALOG = (5)

Constant identifying a dialog resource

RT_FONT = (8)

Constant identifying a font resource

RT_FONTDIR = (7)

Constant identifying a font directory resource

RT_GROUP_CURSOR = (12)

Constant identifying a group cursor resource

RT_GROUP_ICON = (14)

Constant identifying a group icon resource

RT_HTML = (23)

This constant can be used to specify a resource of type "HTML data".

RT_ICON = (3)

Constant identifying an icon resource

RT_MANIFEST = (24)

This constant can be used to specify a resource of type "Manifest".

RT_MENU = (4)

Constant identifying a menu resource

RT_MESSAGE_TABLE = (11)

Constant identifying a message data resource

RT_RCDATA = (10)

Constant identifying a binary data resource

RT_STRING = (6)

Constant identifying a string table resource

RT_VERSION = (16)

Constant identifying a version info resource

```
RuntimeErrorExitCodes : Array[TRuntimeError] of Byte = (0, 203, 204
    , 200, 201, 215, 207, 200, 205, 206, 219, 216, 218, 217, 202, 220
    , 221, 222, 223, 224, 225, 227, 212, 228, 229, 233, 234)
```

This array is used by the Error ([1317](#)) routine to convert a TRuntimeError ([1246](#)) enumeration type to a process exit code.

```
SafeCallErrorProc : TSafeCallErrorProc = Nil
```

SafeCallErrorProc is a Handler called in case of a safecall calling convention error. Error is the error number (passed by the Windows operating system) and Addr is the address where the error occurred.

```
StackError : Boolean = False
```

Indicate whether there was a stack error.

S_FALSE = 1

Interface call result: Not OK

S_OK = 0

Interface call result: OK

`TextRecBufSize = 256`

`TextRecBufSize` is the default buffer size for text files. The actual buffer can be set to another size using `SetTextBuf` ([1388](#)).

`TextRecNameLength = 256`

`TextRecNameLength` is the maximum filename size for text files.

`ThreadingAlreadyUsed : Boolean = False`

Internal constant for the threading system. Don't use.

`VarAddRefProc : procedure(var v: tvardata) = Nil`

Callback to increase reference count of a variant.

`varany = $101`

Variant type: Any

`vararray = $2000`

Variant type: variant Array

`varboolean = 11`

Variant type: Boolean type

`varbyref = $4000`

Variant type: By reference

`varbyte = 17`

Variant type: Byte (8 bit)

`VarClearProc : procedure(var v: tvardata) = Nil`

Callback to clear a variant.

`VarCopyProc : procedure(var d: tvardata; const s: tvardata) = Nil`

Callback to copy a variant

`varcurrency = 6`

Variant type: Currency

`vardate = 7`

Variant type: Date

`vardecimal = 14`

Variant type: Decimal (BCD)

`vardispatch = 9`

Variant type: dispatch interface

`vardouble = 5`

Variant type: Double float

`vareempty = 0`

Variant type: Empty variant

`varerror = 10`

Variant type: Error type

`varint64 = 20`

Variant type: Integer (64-Bit)

`varinteger = 3`

Variant type: Integer (32-bit)

`varlongword = 19`

Variant type: Word (32 bit)

`varnull = 1`

Variant type: Null ([1361](#)) variant

`varolestr = 8`

Variant type: OLE string (widerstring)

`varqword = 21`

Variant type: Word (64-bit)

`varrecord = 36`

Record variant type

`varshortint = 16`

Variant type: Shortint (16 bit)

`varsingle = 4`

Variant type: Single float

`varsmallint = 2`

Variant type: smallint (8 bit)

`varstrarg = $48`

Variant type: String

`varstring = $100`

Variant type: String

`VarToLStrProc : procedure(var d: AnsiString; const s: tvardata) =
Nil`

Callback to convert a variant to a ansistring.

`VarToWStrProc : procedure(var d: WideString; const s: tvardata) =
Nil`

Callback to convert a variant to a widestring.

`vartypemask = $fff`

Variant type: Mask to extract type

`varuint64 = varqword`

`varuint64` denotes an unsigned 64-bit value in a variant. It is one of the values found in the `VType` field of the variant record `tvdata` ([1254](#)).

`varunknown = 13`

Variant type: Unknown

`varustrarg = $49`

`varustrarg` denotes a unicode string argument in `DispInvoke` call. It will be converted to `varuststring` in a variant.

`varuststring = $102`

`varuststring` denotes a unicode string value in a variant. It is one of the values found in the `VType` field of the variant record `tvdata` ([1254](#)).

`varvariant = 12`

Variant type: Variant (arrays only)

`varword = 18`

Variant type: Word (16 bit)

`varword64 = varqword`

Variant type: Word (64-bit)

`vmtAfterConstruction = vmtMethodStart + ((codepointer) * 5)`

VMt Layout: ?

`vmtAutoTable = vmtParent + ((pointer) * 7)`

VMt layout: ?

`vmtBeforeDestruction = vmtMethodStart + ((codepointer) * 6)`

VMt Layout: ?

`vmtClassName = vmtParent + (pointer)`

VMt Layout: location of class name.

`vmtDefaultHandler = vmtMethodStart + ((codepointer) * 4)`

VMt Layout: ?

`vmtDefaultHandlerStr = vmtMethodStart + ((codepointer) * 7)`

VMt Layout: ?

`vmtDestroy = vmtMethodStart`

VMt Layout: Location of destructor pointer.

`vmtDispatch = vmtMethodStart + ((codepointer) * 8)`

`vmtDispatch` is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.Dispatch` ([1438](#))

`vmtDispatchStr = vmtMethodStart + ((codepointer) * 9)`

`vmtDispatchStr` is the offset from the VMT start, in bytes to the dispatch table for a class. The dispatch table is used when dispatching messages in `TObject.DispatchStr` ([1439](#))

`vmtDynamicTable = vmtParent + ((pointer) * 2)`

VMT Layout: location of dynamic methods table.

```
vmtEquals = vmtMethodStart + ((codepointer) * 10)
```

vmtEquals contains the offset from the VMT start, of the location of the TObjct.Equals (1441) method pointer.

```
vmtFieldTable = vmtParent + ((pointer) * 4)
```

VMT Layout: Location of fields table.

```
vmtFreeInstance = vmtMethodStart + ((codepointer) * 2)
```

VMT Layout: location of FreeInstance method.

```
vmtGetHashCode = vmtMethodStart + ((codepointer) * 11)
```

vmtGetHashCode contains the offset from the VMT start, of the location of the TObjct.GetHashCode (1441) method pointer.

```
vmtInitTable = vmtParent + ((pointer) * 6)
```

VMT Layout: ?

```
vmtInstanceSize = 0
```

VMT Layout: Location of class instance size in VMT

```
vmtIntfTable = vmtParent + ((pointer) * 8)
```

VMT layout: Interface table

```
vmtMethodStart = vmtParent + ((pointer) * 10)
```

VMT layout: start of method table.

```
vmtMethodTable = vmtParent + ((pointer) * 3)
```

VMT Layout: Method table start.

```
vmtMsgStrPtr = vmtParent + ((pointer) * 9)
```

VMT layout: message strings table.

```
vmtNewInstance = vmtMethodStart + (codepointer)
```

VMT Layout: location of NewInstance method.

```
vmtParent = (SizeInt) * 2
```

VMT Layout: location of pointer to parent VMT.

`vmtSafeCallException = vmtMethodStart + ((codepointer) * 3)`

VMT Layout: ?

`vmtToString = vmtMethodStart + ((codepointer) * 12)`

`vmtToString` contains the offset from the VMT start, of the location of the `TObject.ToString` (1441) method pointer.

`vmtTypeInfo = vmtParent + ((pointer) * 5)`

VMT Layout: Location of class type information.

`vtAnsiString = 11`

TVarRec type: Ansistring

`vtBoolean = 1`

TVarRec type: Boolean

`vtChar = 2`

TVarRec type: Char

`vtClass = 8`

TVarRec type: Class type

`vtCurrency = 12`

TVarRec type: Currency

`vtExtended = 3`

TVarRec type: Extended

`vtInt64 = 16`

TVarRec type: Int64 (signed 64-bit integer)

`vtInteger = 0`

TVarRec type: Integer

`vtInterface = 14`

TVarRec type: Interface

`vtObject = 7`

TVarRec type: Object instance

vtPChar = 6

TVarRec type: PChar

vtPointer = 5

TVarRec type: pointer

vtPWideChar = 10

TVarRec type: PWideChar

vtQWord = 17

TVarRec type: QWord (unsigned 64-bit integer)

vtString = 4

TVarRec type: String

vtUnicodeString = 18

vtUnicodeString denotes a unicode string argument in the array of const. The TVarRec.VUnicodeString field will contain the actual value.

vtVariant = 13

TVarRec type: Variant

vtWideChar = 9

TVarRec type: Widechar

vtWideString = 15

TVarRec type: WideString

75.10.2 Types

AnsiChar = Char

Alias for 1-byte sized char.

Byte = 0..255

An unsigned 8-bits integer

Cardinal = LongWord

An unsigned 32-bits integer.

```
Char = #0..#255
```

Char is the basic ANSI character type, with a range of [#0..#255].

```
CodePointer = Pointer
```

CodePointer is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals Pointer.

```
CodePointer = Pointer
```

CodePointer is used in 8/16-bit targets to indicate pointers to code segments. On all other platforms this equals Pointer.

```
CodePtrInt = PtrInt
```

CodePtrInt is a signed integer with the same size as CodePointer ([1222](#))

```
CodePtrInt = PtrInt
```

CodePtrInt is a signed integer with the same size as CodePointer ([1222](#))

```
CodePtrUInt = PtrUInt
```

CodePtrUInt is an unsigned integer with the same size as CodePointer ([1222](#))

```
CodePtrUInt = PtrUInt
```

CodePtrUInt is an unsigned integer with the same size as CodePointer ([1222](#))

```
DWord = LongWord
```

An unsigned 32-bits integer

```
EnumResLangProc = function(ModuleHandle: TFPResourceHMODULE;
  ResourceType: PChar; ResourceName: PChar;
  IDLanguage: Word; lParam: PtrInt) :
  LongBool
```

EnumResNameProcs used in the EnumResourceLanguages ([1314](#)) call. It is called for all languages for a resource of the specified type and name, and is passed the ModuleHandle, ResourceName, ResourceName and IDLanguage values for each language encountered for the specified resource. Additionally, the lParam parameter from the EnumResourceLanguages is passed unaltered.

```
EnumResNameProc = function(ModuleHandle: TFPResourceHMODULE;
  ResourceType: PChar; ResourceName: PChar;
  lParam: PtrInt) : LongBool
```

EnumResNameProcs used in the EnumResourceNames (1314) call. It is called for all resources of the specified type, and is passed the ModuleHandle, ResourceType, ResourceName values for each resource encountered. Additionally, the lParam parameter from the EnumResourceNames is passed unaltered.

```
EnumResTypeProc = function(ModuleHandle: TFPResourceHMODULE;
    ResourceType: PChar; lParam: PtrInt)
    : LongBool
```

EnumResTypeProc is used in the EnumResourceTypes (1315) call. It is called for all resources, and is passed the ModuleHandle, ResourceType values for each resource encountered. Additionally, the lParam parameter from the EnumResourceTypes is passed unaltered.

```
FarPointer = Pointer
```

FarPointer is used in 8/16-bit targets to indicate far pointers (over segments). On all other platforms this equals Pointer.

```
FileRec = record
    Handle : THandle;
    Mode : LongInt;
    RecSize
    : SizeInt;
    _private : Array[1..3*SizeOf(SizeInt)+5*SizeOf(pointer
    )] of Byte;
    UserData : Array[1..32] of Byte;
    name : Array[0..filerecnamelength
    ] of TFileTextRecChar;
end
```

FileRec is the underlying type used in untyped files. It should be treated as opaque and never manipulated directly.

```
HGLOBAL = PtrUInt
```

This is an opaque type.

```
HMODULE = PtrUInt
```

This is an opaque type.

```
HRESULT = LongInt
```

32-Bit signed integer.

```
IInterface = IUnknown
```

IInterface is the basic interface from which all COM style interfaces descend.

```
Int16 = SmallInt
```

A signed 16-bits integer

`Int32 = LongInt`

A signed 32-bits integer

`Int64 = -9223372036854775808..9223372036854775807`

`Int64` is a 64-bit, signed integer type, with range [-9223372036854775808..9223372036854775807].

`Int8 = ShortInt`

A signed 8-bits integer

`Integer = SmallInt`

The system unit defines `Integer` as a signed 16-bit integer. But when DELPHI or OBJFPC mode are active, then the `objpas` unit redefines `Integer` as a 32-bit integer.

`IntegerArray = Array[0..$effffff] of Integer`

Generic array of integer.

`IntPtr = PtrInt`

A signed integer with the same size in bytes as pointer

```
jmp_buf = packed record
  ebx : LongInt;
  esi : LongInt;
  edi :
    LongInt;
  bp  : Pointer;
  sp  : Pointer;
  pc  : Pointer;
end
```

Record type to store processor information.

`Longint = -2147483648..2147483647`

A signed 32-bits integer

`Longword = 0..4294967295`

The base 32-bit unsigned type. See the reference manual for more details

`MAKEINTRESOURCE = PChar`

Alias for the `PChar` ([1225](#)) type.

`NativeInt = PtrInt`

`NativeInt` is defined for Delphi compatibility. It is a signed integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms.

`NativeUInt` = `PtrUInt`

`NativeUInt` is defined for Delphi compatibility. It is an unsigned integer with the size of a pointer, so 32-bit on 32-bit platforms, 64-bit on 64-bit platforms.

`PAnsiChar` = `PChar`

Alias for `PChar` (1225) type.

`PAnsiString` = `^AnsiString`

Pointer to an `ansistring` type.

`PBoolean` = `^Boolean`

Pointer to a `Boolean` type.

`PByte` = `^Byte`

Pointer to `byte` (1221) type

`pcalldesc` = `^tcalldesc`

Pointer to `TCallDesc` (1235) record.

`PCardinal` = `^Cardinal`

Pointer to `Cardinal` (1222) type

`PChar` = `^Char`

Or the same as a pointer to an array of `char`. See the reference manual for more information about this type.

`PClass` = `^TClass`

Pointer to `TClass` (1236)

`PCodePointer` = `^CodePointer`

`PCodePointer` is a typed pointer to `CodePointer` (1222).

`PComp` = `^Comp`

`PComp` is a pointer to a complex type.

`PCurrency` = `^Currency`

Pointer to currency type.

```
PDate = ^TDateTime
```

Pointer to a TDateTime (1237) type.

```
PDateTime = ^TDateTime
```

Pointer to TDatetime

```
PDispatch = ^IDispatch
```

Pointer to IDispatch (1424) interface type

```
pdispdesc = ^tdispdesc
```

Pointer to tdispdesc (1237) record

```
PDouble = ^Double
```

Pointer to double-sized float value.

```
PDWord = ^DWord
```

Pointer to DWord (1222) type

```
pdynarrayindex = ^tdynarrayindex
```

Pointer to tdynarrayindex (1237) type.

```
pdynarraytypeinfo = ^tdynarraytypeinfo
```

Pointer to TDynArrayTypeInfo (1237) type.

```
PError = ^TError
```

Pointer to an Error (1317) type.

```
PEventState = pointer
```

Pointer to EventState, which is an opaque type.

```
PExceptObject = ^TExceptObject
```

Pointer to Exception handler procedural type TExceptProc (1238)

```
PExtended = ^Extended
```

Pointer to extended-sized float value.

```
PFileTextRecChar = ^TFileTextRecChar
```

PFileTextRecChar is a typed pointer to TFileTextRecChar (1239).

PGuid = ^TGuid

Pointer to TGUID (1242) type.

pInt16 = PSmallInt

Pointer to Int16 (1223) type

pInt32 = PLongint

Pointer to Int32 (1224) type

PInt64 = ^Int64

Pointer to Int64 type

pInt8 = PShortInt

Pointer to Int8 (1224) type

PInteger = ^Integer

Pointer to integer (1224) type

PIntegerArray = ^IntegerArray

Pointer to IntegerArray (1224) type

PInterface = PUnknown

Pointer to IInterface (1223) interface

pinterfaceentry = ^tinterfaceentry

Pointer to tinterfaceentry (1243) record.

pinterfacetable = ^tinterfacetable

Pointer to tinterfacetable (1243) record.

PIntPtr = PPtrInt

Pointer to IntPtr (1224) type

PJump_buf = ^jmp_buf

Pointer to jmp_buf (1224) record

PLongBool = ^LongBool

Pointer to a LongBool type.

PLongint = ^LongInt

Pointer to Longint (1224) type

PLongWord = ^LongWord

Pointer to LongWord type

PMemoryManager = ^TMemoryManager

Pointer to TMemoryManager (1244) record

PMethod = ^TMethod

PMsgStrTable = ^TMsgStrTable

Pointer to array of TMsgStrTable (1244) records.

PNativeInt = ^NativeInt

Pointer to NativeInt (1225) type

PNativeUInt = ^NativeUInt

Pointer to NativeInt (1225) type

PointerArray = Array[0..512*1024*1024-2] of Pointer

Generic pointer array.

POleVariant = ^OleVariant

Pointer to OleVariant type.

PPAnsiChar = PPChar

Alias for PPChar (1228) type.

PPByte = ^PByte

PPByte is a pointer to a PByte (1225) type.

PPChar = ^PChar

Pointer to an array of pointers to null-terminated strings.

PPCharArray = ^TPCharArray

Pointer to TPCharArray (1244) type.

PPCodePointer = ^PCodePointer

PPCodePointer is a typed pointer to PCodePointer (1225).

PPDispatch = ^PDispatch

Pointer to PDispatch (1226) pointer type

PPDouble = ^PDouble

PPDouble is a pointer to a PDouble (1226) type.

PPLongint = ^PLongint

PPLongint is a pointer to a PLongint (1228) type.

PPointer = ^Pointer

Pointer to a pointer type.

PPointerArray = ^PointerArray

Pointer to PointerArray (1228) type

PPPAnsiChar = PPPChar

PPPAnsiChar is a typed pointer to PPAnsichar (1228).

PPPChar = ^PPChar

PPPChar is a pointer to a PPChar (1228)

PPPPointer = ^PPPointer

Pointer to a PPointer (1229) type.

PPPWideChar = ^PPWideChar

PPPWideChar is a pointer to a PPWideChar (1230) type.

PPPtrInt = ^PtrInt

Pointer to PtrInt (1231) type.

PPPtrUInt = ^PtrUInt

Pointer to unsigned integer of pointer size

PPUnknown = ^PUnknown

Pointer to untyped pointer

`PPWideChar = ^PWideChar`

Pointer to link id="PWideChar"> type.

`PQWord = ^QWord`

Pointer to QWord type

`PRTLCriticalSection = ^RTLCriticalSection`

Pointer to #rtl.system.RTLCriticalSection (1246) type.

`PRTLEvent = pointer`

Pointer to RTLEvent, which is an opaque type.

`PShortInt = ^ShortInt`

Pointer to shortint (1234) type

`PShortString = ^ShortString`

Pointer to a shortstring type.

`PSingle = ^Single`

Pointer to single-sized float value.

`PSizeInt = ^SizeInt`

Pointer to a SizeInt (1234) type

`PSizeUInt = ^SizeUInt`

`PSizeUInt64` is a pointer to a `SizeUInt` (1234), an unsigned integer of architecture-dependent size.

`PSmallInt = ^SmallInt`

Pointer to smallint (1234) type

`pstringmessagetable = ^TStringMessageTable`

Pointer to TStringMessageTable (1248) record.

`PText = ^Text`

Pointer to text file.

`PtrInt = LongInt`

`Ptrint` is a signed integer type which has always the same size as a pointer. `Ptprint` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7ffffff0.}
q:=pointer(ptprint(p)+1024); {Overflow error.}
writeln(q>p);             {Incorrect answer.}
```

`Ptprint` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `ptprint` causes trouble in case the distance is larger than `high(ptprint)` and must be used with great care.

The introduction of the `ptprint` type was a mistake. Please use `ptruint` ([1231](#)) instead.

`PtrInt = Int64`

`Ptprint` is a signed integer type which has always the same size as a pointer. `Ptprint` is considered harmful and should almost never be used in actual code, because pointers are normally unsigned. For example, consider the following code:

```
getmem(p, 2048);           {Assume the address of p becomes $7ffffff0.}
q:=pointer(ptprint(p)+1024); {Overflow error.}
writeln(q>p);             {Incorrect answer.}
```

`Ptprint` might have a valid use when two pointers are subtracted from each other if it is unknown which pointer has the largest address. However, even in this case `ptprint` causes trouble in case the distance is larger than `high(ptprint)` and must be used with great care.

The introduction of the `ptprint` type was a mistake. Please use `ptruint` ([1231](#)) instead.

`PtrUInt = DWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PtrUInt = QWord`

`PtrUInt` is an unsigned integer type which has always the same size as a pointer. When using integers which will be cast to pointers and vice versa, use this type, never the regular `Cardinal` type.

`PUCS2Char = PWideChar`

Pointer to `UCS2Char` ([1260](#)) character.

`PUCS4Char = ^UCS4Char`

Pointer to `UCS4Char` ([1260](#))

`PUCS4CharArray = ^TUCS4CharArray`

Pointer to array of `UCS4Char` ([1260](#)) characters.

`pUInt16 = PWord`

Pointer to UInt16 (1260) type

```
pUInt32 = PWord
```

Pointer to UInt32 (1260) type

```
PUInt64 = ^UInt64
```

PUInt64 is a pointer to a UInt64 (1260), an unsigned 64-bit integer.

```
pUInt8 = PByte
```

Pointer to UInt8 (1260) type

```
PUIntPtr = PPtrUInt
```

Pointer to UIntPtr (1260) type

```
PUnicodeChar = ^UnicodeChar
```

PUnicodeChar is a pointer to a unicode character, just like PChar is a pointer to a Char an-
sistring character.

```
PUnicodeString = ^UnicodeString
```

PUnicodeString is a pointer to a UnicodeString string.

```
PUnknown = ^IUnknown
```

Untyped pointer

```
PUTF8String = ^UTF8String
```

Pointer to UTF8String (1260)

```
pvararray = ^tvararray
```

Pointer to TVarArray (1252) type.

```
pvararraybound = ^tvararraybound
```

Pointer to tvararraybound (1252) type.

```
pvararrayboundarray = ^tvararrayboundarray
```

Pointer to tvararrayboundarray (1252) type.

```
pvararraycoorarray = ^tvararraycoorarray
```

Pointer to tvararraycoorarray (1252) type.

`pvardata = ^tvardata`

Pointer to TVarData (1254) record.

`PVariant = ^Variant`

Pointer to Variant type.

`pvariantmanager = ^tvariantmanager`

Pointer to TVariantManager (1256) record.

`PVarRec = ^TVarRec`

Pointer to TVarRec (1258) type.

`PVmt = ^TVmt`

Pointer to TVMT (1259) record

`PWideChar = ^WideChar`

Pointer to WChar (1261).

`PWideString = ^WideString`

Pointer to widestring type

`PWord = ^Word`

Pointer to word (1261) type

`PWordBool = ^WordBool`

Pointer to a WordBool type.

`QWord = 0..18446744073709551615`

QWord is a 64-bit, unsigned integer type, with range [0..18446744073709551615].

`RawByteString = ansistring`

RawByteString is a single-byte character string which does not have any codepage associated with it.

This means that assigning a single-byte character string to this kind of string will not change the codepage of the string.

Inversely, when assigning a RawByteString to a single-byte string, the codepage of the destination is simply set to the codepage of the rawbytestring: no codepage conversion happens, the reference count is simply increased.

`Real = Double`

Alias for real type

`real48 = Array[0..5] of Byte`

TP compatible real type (6 bytes) definition

`Shortint = -128..127`

A signed 8-bits integer

`SizeInt = LongInt`

`SizeInt` is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeInt = Int64`

`SizeInt` is used to describe sizes of structures in FPC using a signed integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeUInt = DWord`

`SizeUInt` is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`SizeUInt = QWord`

`SizeUInt` is used to describe sizes of structures in FPC using an unsigned integer. The actual type of this type depends on the architecture: its size reflects the maximum addressable memory on the current architecture, thus it is 64-bit on 64-bit platforms, 32-bit on 32-bit platforms, and 16 bit on 16 bit platforms.

`Smallint = -32768..32767`

A signed 16-bits integer

`TAbstractErrorProc = procedure`

Abstract error handler procedural type.

`TAllocateThreadVarsHandler = procedure`

Threadvar allocation callback type for `TThreadManager` ([1250](#)).

TAnsiChar = Char

Alias for 1-byte sized char.

```
TAssertErrorProc = procedure(const msg: ShortString;
    const fname: ShortString; lineno: LongInt;
    erroraddr: pointer)
```

Assert error handler procedural type.

```
TBackTraceStrFunc = function(Addr: CodePointer) : ShortString
```

Type for formatting of backtrace dump.

```
TBasicEventCreateHandler = function(EventAttributes: Pointer;
    AManualReset: Boolean;
    InitialState: Boolean;
    const Name: ansistring)
    : PEventState
```

callback type for creating eventstate in TThreadManager (1250).

```
TBasicEventHandler = procedure(state: PEventState)
```

Generic callback type for handling eventstate in TThreadManager (1250).

```
TBasicEventWaitForHandler = function(timeout: Cardinal;
    state: PEventState) : LongInt
```

Wait for basic event callback type for TThreadManager (1250).

```
TBeginThreadHandler = function(sa: Pointer; stacksize: PtrUInt;
    ThreadFunction: TThreadFunc; p: pointer
    ;
                                creationFlags: DWord;
    var ThreadId: TThreadID) : TThreadID
```

Callback for thread start in TThreadManager (1250).

```
TBoundArray = Array of SizeInt
```

Dynamic array of integer.

```
tcalldesc = packed record
    calltype : Byte;
    argcount : Byte;
    namedargcount : Byte;
    argtypes : Array[0..255] of Byte;
end
```

tcalldesc is used to encode the arguments to a dispatch call to an OLE dual interface. It is used on windows only. It describes the arguments to a call.

TClass = Class of TObject

Class of TObject ([1432](#)).

```
TCompareOption = (coLingIgnoreCase, coLingIgnoreDiacritic, coIgnoreCase
,
coIgnoreKanaType, coIgnoreNonSpace, coIgnoreSymbols
,
coIgnoreWidth, coLingCasing, coDigitAsNumbers,
coStringSort)
```

Table 75.10: Enumeration values for type TCompareOption

Value	Explanation
coDigitAsNumbers	Treat digits as numbers (20 before 120)
coIgnoreCase	Ignore case (usually identical to coLingIgnoreCase)
coIgnoreKanaType	Corresponding hiragana and katakana characters compare as equal.
coIgnoreNonSpace	Ignore nonspace characters (usually identical to coLingIgnoreDiacritic)
coIgnoreSymbols	Ignore symbols and punctuation characters
coIgnoreWidth	Ignore half-width and full width characters (used in Chinese and Japanese)
coLingCasing	Use linguistic rules for casing, instead of file system rules
coLingIgnoreCase	Ignore case linguistically (usually identical to coIgnoreCase)
coLingIgnoreDiacritic	Ignore diacritic caharacters
coStringSort	Handle punctuation as symbols

TCompareOption indicates how 2 strings should be compared. This option is used in the WideString-Manager ([1259](#)) implementation when comparing 2 strings. The following options exist:

Ignore case linguistically (usually identical to coIgnoreCase)

Ignore diacritic caharacters

Ignore case (usually identical to coLingIgnoreCase)

Corresponding hiragana and katakana characters compare as equal.

Corresponding hiragana and katakana characters compare as equal.

Ignore nonspace characters (usually identical to coLingIgnoreDiacritic)

Ignore symbols and punctuation characters

Ignore half-width and full width characters (used in Chinese and Japanese)

Use linguistic rules for casing, instead of file system rules

Treat digits as numbers (20 before 120)

Handle punctuation as symbols

Not all platforms will support all possibilities.

TCompareOptions = Set of TCompareOption

TCompareOptions is simply a set of TCompareOption (1236) enumeration values.

TCriticalSectionHandler = procedure(var cs)

Generic callback type for critical section handling in TThreadManager (1250).

TCriticalSectionHandlerTryEnter = function(var cs) : LongInt

TCriticalSectionHandlerTryEnter is the function prototype for the TryEnterCriticalSection (1407) function, in the TThreadManager (1250) record's TryEnterCriticalSection field.

TCtrlBreakHandler = function(CtrlBreak: Boolean) : Boolean

TCtrlBreakHandler is the prototype for the CTRL-C handler. If CtrlBreak is True then Ctrl-Break was hit, otherwise CTRL-C was hit. The handlers should return True to signal that the key-combination was handled. If False is returned, then default handling will be used, which by default means an exception will be raised if the sysutils unit is used.

TDate = TDateTime

TDate is defined for Delphi compatibility. This type is deprecated, use TDateTime (1237) instead.

TDateTime = Double

Encoded Date-Time type.

```
tdispdesc = packed record
  dispid : LongInt;
  restype : Byte;
  calldesc : tcalldesc;
end
```

tcalldesc is used to encode a dispatch call to an OLE dispatch interface. It is used on windows only. It describes the dispatch call call.

tdynarrayindex = SizeInt

A variable of type tdynarrayindex will always have the correct size, suitable for serving as an index in a dynamic array.

```
tdynarraytypeinfo = packed record
  kind : Byte;
  namelen : Byte
  ;
  elesize : SizeInt;
  eletype : pdynarraytypeinfo;
  vartype :
    LongInt;
end
```

tdynarraytypeinfo describes the structure of a multi-dimensional dynamical array. It is used in the DynArraySetLength (1312) call.

TEndThreadHandler = procedure(ExitCode: DWord)

Callback for thread end in TThreadManager ([1250](#)).

```
TEntryInformation = record
  InitFinalTable : Pointer;
  ThreadvarTablesTable
    : Pointer;
  asm_exit : procedure;
  PascalMain : procedure;
  valgrind_used
    : Boolean;
end
```

TEntryInformation is used to initialize a Free Pascal program or library. Under normal circumstances, there should be no need to use this structure directly: it is used by the system unit and special linking units.

TError = LongInt

Error type, used in variants.

```
TErrorProc = procedure(ErrNo: LongInt; Address: CodePointer;
  Frame: Pointer)
```

Standard error handler procedural type.

```
TExceptObject = record
  FObject : TObject;
  Addr : CodePointer;
  Next : PExceptObject;
  refcount : LongInt;
  Framecount : LongInt
;
  Frames : PCodePointer;
end
```

TExceptObject is the exception description record which is found on the exception stack.

```
TExceptProc = procedure(Obj: TObject; Addr: CodePointer;
  FrameCount: LongInt; Frame: PCodePointer)
```

Exception handler procedural type

```
TextBuf = Array[0..TextRecBufSize-1] of AnsiChar
```

TextBuf is a type for the default buffer used in TextRec ([1239](#)).

```
TextFile = Text
```

Alias for Text file type.

```

TextRec = record
  Handle : THandle;
  Mode : LongInt;
  bufsize
    : SizeInt;
  _private : SizeInt;
  bufpos : SizeInt;
  bufend : SizeInt
;
  bufptr : ^TextBuf;
  openfunc : CodePointer;
  inoutfunc : CodePointer
;
  flushfunc : CodePointer;
  closefunc : CodePointer;
  UserData
    : Array[1..32] of Byte;
  name : Array[0..textrecnamelength-1] of
    TFileTextRecChar;
  LineEnd : TLineEndStr;
  buffer : TextBuf;
end

```

TextRec is the underlying type used in text files. It should be treated as opaque and never manipulated directly.

```
TFileTextRecChar = UnicodeChar
```

TFileTextRecChar is the type of character used in TextRec (1239) or FileRec (1223) file types. It is an alias type, depending on platform and RTL compilation flags. No assumptions should be made on the actual character type.

```

TFloatSpecial = (fsZero, fsNZero, fsDenormal, fsNDenormal, fsPositive
,
                fsNegative, fsInf, fsNInf, fsNaN, fsInvalidOp)

```

Table 75.11: Enumeration values for type TFloatSpecial

Value	Explanation
fsDenormal	Denormal value
fsInf	Infinity
fsInvalidOp	Invalid operation
fsNaN	Not a number
fsNDenormal	Negative enormal value
fsNegative	Negative value
fsNInf	Negative infinity
fsNZero	Negative zero
fsPositive	Positive value
fsZero	Zero

TFloatSpecial enumerates a series of floating point value properties.


```

TFPCHepStatus = record
  MaxHeapSize : PtrUInt;
  MaxHeapUsed : PtrUInt
;
  CurrHeapSize : PtrUInt;
  CurrHeapUsed : PtrUInt;
  CurrHeapFree
  : PtrUInt;
end

```

TFPCHepStatus describes the state of the FPC heap manager. This is not equivalent to the THeapStatus (1242) record defined by Delphi, which contains information not meaningful for the FPC heap manager. The heap status can be retrieved by the GetFPCHeapStatus (1330) call.

```
TFPResourceHandle = PtrUInt
```

TFPResourceHandle represents a handle to a binary resource and is used in the various resource calls. Its actual type and size may differ accross platforms.

```
TFPResourceHGLOBAL = PtrUInt
```

TFPResourceHGLOBAL represents a handle to the global module containing a resource. It is used in the various resource calls. It is an opaque type: its actual type and size may differ accross platforms.

```
TFPResourceHMODULE = PtrUInt
```

TFPResourceHMODULE represents a module (library, executable, other) in which a resource is located. It is used in the various resource calls. It is an opaque type: its actual type and size may differ accross platforms.

```

TFPUException = (exInvalidOp, exDenormalized, exZeroDivide, exOverflow
,
                  exUnderflow, exPrecision)

```

Table 75.12: Enumeration values for type TFPUException

Value	Explanation
exDenormalized	
exInvalidOp	Invalid operation error
exOverflow	Float overflow error
exPrecision	Precision error
exUnderflow	Float underflow error
exZeroDivide	Division by zero error.

TFPUException describes what floating point errors raise exceptions. It has been moved here from the Math unit.

```
TFPUExceptionMask = Set of TFPUException
```

TFPUExceptionMask is a set of TFPUEXception constants

TFPUPrecisionMode = (pmSingle, pmReserved, pmDouble, pmExtended)

Table 75.13: Enumeration values for type TFPUPrecisionMode

Value	Explanation
pmDouble	Double-type precision
pmExtended	Extended-type precision
pmReserved	?
pmSingle	Single-type precision

TFPUPrecisionMode describes the possible default precisions for the software Floating Point math routines. It has been moved here from the math unit.

TFPURoundingMode = (rmNearest, rmDown, rmUp, rmTruncate)

Table 75.14: Enumeration values for type TFPURoundingMode

Value	Explanation
rmDown	Round to biggest integer smaller than value.
rmNearest	Round to nearest integer
rmTruncate	Cut off fractional part
rmUp	Round to smallest integer larger than value

TFPURoundingMode enumerates the possible values for software floating point math rounding. It has been moved here from the math unit.

TGetCurrentThreadIdHandler = function : TThreadID

Callback type for retrieving thread ID in TThreadManager ([1250](#)).

```

TGuid = packed record
case Integer of
1: (
    Data1 : DWord;
    Data2
    : Word;
    Data3 : Word;
    Data4 : Array[0..7] of Byte;
);
2: (
    D1 : DWord;
    D2 : Word;
    D3 : Word;
    D4 : Array[0..7] of Byte
    ;
);

```

```

3: (
  time_low : DWord;
  time_mid : Word;
  time_hi_and_version
    : Word;
  clock_seq_hi_and_reserved : Byte;
  clock_seq_low : Byte
  ;
  node : Array[0..5] of Byte;
);
end

```

Standard GUID representation type.

THandle = LongInt

This type should be considered opaque. It is used to describe file and other handles.

```

THeapStatus = record
  TotalAddrSpace : Cardinal;
  TotalUncommitted
    : Cardinal;
  TotalCommitted : Cardinal;
  TotalAllocated : Cardinal
  ;
  TotalFree : Cardinal;
  FreeSmall : Cardinal;
  FreeBig : Cardinal
  ;
  Unused : Cardinal;
  Overhead : Cardinal;
  HeapErrorCode : Cardinal
  ;
end

```

THeapStatus is the record describing the current heap status. It is returned by the GetHeapStatus (1330) call.

TInitThreadVarHandler = procedure(var offset: DWord; size: DWord)

Threadvar initialization callback type for TThreadManager (1250).

TInterfacedClass = Class of TInterfacedObject

TInterfacedClass is a descendent of

```

tinterfaceentry = record
  IID : PGuid;
  VTable : Pointer;
  IOffset
    : SizeUInt;
  IIDStr : PShortString;

```

```

case Boolean of
True: (
  IType
  : tinterfaceentrytype;
);
False: (
  __pad_dummy : SizeInt;
);
end

```

`tinterfaceentry` is used to store the list of Interfaces of a class. This list is stored as an array of `tinterfaceentry` records.

```

tinterfaceentrytype = (etStandard, etVirtualMethodResult,
  etStaticMethodResult, etFieldValue,
  etVirtualMethodClass, etStaticMethodClass,
  etFieldValueClass)

```

Table 75.15: Enumeration values for type `tinterfaceentrytype`

Value	Explanation
<code>etFieldValue</code>	Field value
<code>etFieldValueClass</code>	Interface provided by a class field
<code>etStandard</code>	Standard entry
<code>etStaticMethodClass</code>	Interface provided by a static class method
<code>etStaticMethodResult</code>	Static method
<code>etVirtualMethodClass</code>	Interface provided by a virtual class method
<code>etVirtualMethodResult</code>	Virtual method

This is an internal type for the compiler to encode calls to dispatch interfaces.

```

tinterfacetable = record
  EntryCount : SizeUInt;
  Entries : Array
    [0..0] of tinterfaceentry;
end

```

Record to store list of interfaces of a class.

```
TLineEndStr = string
```

`TLineEndStr` is an alias for the actual line ending string type, used in `TextRec` (1239). It should be treated as opaque.

```

TMemoryManager = record
  NeedLock : Boolean;
  Getmem : function
    (Size: PtrUInt) : Pointer;
  Freemem : function(p: pointer) : PtrUInt

```

```

;
FreememSize : function(p: pointer; Size: PtrUInt) : PtrUInt;
AllocMem : function(Size: PtrUInt) : Pointer;
ReAllocMem : function
  (var p: pointer; Size: PtrUInt) : Pointer;
MemSize : function(p
  : pointer) : PtrUInt;
InitThread : procedure;
DoneThread : procedure
;
RelocateHeap : procedure;
GetHeapStatus : function : THeapStatus
;
GetFPCHeapStatus : function : TFPCHeapStatus;
end

```

TMemoryManager describes the memory manager. For more information about the memory manager, see the programmer's reference.

```

TMethod = record
  Code : CodePointer;
  Data : Pointer;
end

```

TMethod describes a general method pointer, and is used in Run-Time Type Information handling.

```

TMsgStrTable = record
  name : PShortString;
  method : CodePointer
;
end

```

Record used in string message handler table.

```

TPCharArray = packed Array[0..(MaxLongintdivSizeOf(PChar))-1] of
  PChar

```

Array of PChar

```

TProcedure = procedure

```

Simple procedural type.

```

TReleaseThreadVarsHandler = procedure

```

Threadvar release callback type for TThreadManager ([1250](#)).

```

TRelocateThreadVarHandler = function(offset: DWord) : pointer

```

Threadvar relocation callback type for TThreadManager ([1250](#)).

```
TResourceHandle = PtrUInt
```

This is an opaque type.

```
TResourceManager = record
  HINSTANCEFunc : function : TFPResourceHMODULE
  ;
  EnumResourceTypesFunc : function(ModuleHandle: TFPResourceHMODULE
  ; EnumFunc: EnumResTypeProc;
    lParam: PtrInt) : LongBool
  ;
  EnumResourceNamesFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceType: PChar;
    EnumFunc: EnumResNameProc; lParam
    : PtrInt) : LongBool;
  EnumResourceLanguagesFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResourceType: PChar;
    ResourceName
    : PChar; EnumFunc: EnumResLangProc; lParam: PtrInt)
    :
  LongBool;
  FindResourceFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceName: PChar;
    ResourceType: PChar) : TFPResourceHandle
  ;
  FindResourceExFunc : function(ModuleHandle: TFPResourceHMODULE
  ; ResourceType: PChar;
    ResourceName: PChar; Language:
    Word) : TFPResourceHandle;
  LoadResourceFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResHandle: TFPResourceHandle)
    :
  TFPResourceHGLOBAL;
  SizeofResourceFunc : function(ModuleHandle
  : TFPResourceHMODULE; ResHandle: TFPResourceHandle)
    :
  LongWord;
  LockResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : Pointer;
  UnlockResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : LongBool;
  FreeResourceFunc : function(ResData: TFPResourceHGLOBAL
  ) : LongBool;
end
```

`TResourceManager` is the record describing the resource manager. Depending on the kind of resources (internal, external), another resource managing handler is installed by the system. The resource manager record is used by all resource handling functions to do the actual work: for each function in the API, a handler function is available. People wishing to implement their own resource manager, must implement all handler functions in their implementation.

As soon as resources are used, the compiler will install a resource manager, depending on the platform, this may be an internal or an external resource manager.

```
TRTLCreateEventHandler = function : PRTLEvent
```

Callback type for creating a `TRTLEvent` type in `TThreadManager` (1250).

```
TRTLCriticalSection = Opaque type
```

`TRTLCriticalSection` represents a critical section (a mutex). This is an opaque type, it can differ from operating system to operating system. No assumptions should be made about its structure or contents.

```
TRTLEventHandler = procedure(AEvent: PRTLEvent)
```

Generic `TRTLEvent` handling type for `TThreadManager` (1250).

```
TRTLEventHandlerTimeout = procedure(AEvent: PRTLEvent; timeout: LongInt
)
```

`TRTLEvent` timeout handling type for `TThreadManager` (1250).

```
trtlmethod = procedure of object
```

Callback type for synchronization event.

```
TRuntimeError = (reNone, reOutOfMemory, reInvalidPtr, reDivByZero,
  reRangeError, reIntOverflow, reInvalidOp, reZeroDivide
,
  reOverflow, reUnderflow, reInvalidCast, reAccessViolation
,
  rePrivInstruction, reControlBreak, reStackOverflow
,
  reVarTypeCast, reVarInvalidOp, reVarDispatch,
reVarArrayCreate, reVarNotArray, reVarArrayBounds,
reAssertionFailed, reExternalException, reIntfCastError
,
  reSafeCallError, reQuit, reCodesetConversion)
```

Table 75.16: Enumeration values for type TRuntimeError

Value	Explanation
reAccessViolation	Access Violation
reAssertionFailed	Assertion failed error
reCodesetConversion	Code set conversion error
reControlBreak	User pressed CTRL-C
reDivByZero	Division by zero error
reExternalException	An external exception occurred
reIntfCastError	Interface typecast error
reIntOverflow	Integer overflow error
reInvalidCast	Invalid (class) typecast error
reInvalidOp	Invalid operation error
reInvalidPtr	Invalid pointer error
reNone	No error
reOutOfMemory	Out of memory error
reOverflow	Overflow error
rePrivInstruction	Privileged instruction error
reQuit	Quit signal error
reRangeError	Range check error
reSafeCallError	Safecall (IDispInterface) error
reStackOverflow	Stack overflow error
reUnderflow	Underflow error
reVarArrayBounds	Variant array bounds error
reVarArrayCreate	Variant array creation error
reVarDispatch	Variant Dispatch error.
reVarInvalidOp	Invalid variant operation error
reVarNotArray	Variant is not an array error.
reVarTypeCast	Invalid typecase from variant
reZeroDivide	Division by zero error

TRuntimeError is used in the Error (1317) procedure to indicate what kind of error should be reported.

```
TSafeCallErrorProc = procedure(error: HRESULT; addr: pointer)
```

Prototype of a safecall error handler routine. Error is the error number (passed by the Windows operating system) and Addr is the address where the error occurred.

```
TSemaphoreDestroyHandler = procedure(const sem: Pointer)
```

TSemaphoreDestroyHandler is the function prototype to destroy an existing semaphore, as returned by (ThreadManager.SemaphoreInit). It is used by the thread manager (ThreadManager.SemaphoreDest

```
TSemaphorePostHandler = procedure(const sem: Pointer)
```

TSemaphorePostHandler is the function prototype to post an event to the semaphore. It should handle a pointer as returned by the ThreadManager.SemaphoreInit procedure. it's used by the thread manager ThreadManager.SemaphorePost.

```
TSemaphoreWaitHandler = procedure(const sem: Pointer)
```


`TSemaphoreWaitHandler` is the function prototype to wait on an event on the semaphore (which should be posted to the semaphore with `ThreadManager.SemaphorePost`). It should handle a pointer as returned by the `ThreadManager.SemaphoreInit` procedure. It's used by the thread manager `ThreadManager.SemaphoreWait`.

`TSemaphoreInitHandler` = function : Pointer

`TSemaphoreInitHandler` is the function prototype for initializing a semaphore. It is used by the thread manager (`ThreadManager.SemaphoreInit`) to create semaphores. The function should return a pointer, usable by the other semaphore functions of the thread manager.

`TStandardCodePageEnum` = (scpAnsi, scpConsoleInput, scpConsoleOutput
,
scpFileSystemSingleByte)

Table 75.17: Enumeration values for type `TStandardCodePageEnum`

Value	Explanation
scpAnsi	Ansi codepage (CP_ACP)
scpConsoleInput	Console input codepage
scpConsoleOutput	Console output codepage
scpFileSystemSingleByte	File system single byte codepage.

`TStandardCodePageEnum` describes several types of standard used codepages, which can be queried by the unicode string manager `TUnicodeStringManager` ([1252](#)).

`TStringMessageTable` = record
 count : LongInt;
 msgstrtable : Array
 [0..0] of TMsgStrTable;
end

Record used to describe the string messages handled by a class. It consists of a count, followed by an array of `TMsgStrTable` ([1244](#)) records.

`TSystemCodePage` = Word

`TSystemCodePage` is a type used to indicate code pages. It should be treated as an opaque type.

`TTextBuf` = TextBuf

`TTextBuf` is an alias for `TextBuf`

`TTextLineBreakStyle` = (tlbsLF, tlbsCRLF, tlbsCR)

Table 75.18: Enumeration values for type `TTextLineBreakStyle`

Value	Explanation
tlbsCR	Carriage-return (#13, Mac-OS style)
tlbsCRLF	Carriage-return, line-feed (#13#30, Windows style)
tlbsLF	Line-feed only (#10, Unix style)

Text line break style. (end of line character)

```
TThreadFunc = function(parameter: pointer) : PtrInt
```

Thread function prototype

```
TThreadGetPriorityHandler = function(threadHandle: TThreadID) :  
    LongInt
```

Callback type for thread priority getting in TThreadManager ([1250](#)).

```
TThreadHandler = function(threadHandle: TThreadID) : DWord
```

Generic thread handler callback for TThreadManager ([1250](#)).

```
TThreadID = PtrUInt
```

This is an opaque type, it can differ from operating system to operating system.

```
TThreadManager = record  
    InitManager : function : Boolean;  
    DoneManager  
    : function : Boolean;  
    BeginThread : TBeginThreadHandler;  
    EndThread  
    : TEndThreadHandler;  
    SuspendThread : TThreadHandler;  
    ResumeThread  
    : TThreadHandler;  
    KillThread : TThreadHandler;  
    CloseThread :  
    TThreadHandler;  
    ThreadSwitch : TThreadSwitchHandler;  
    WaitForThreadTerminate  
    : TWaitForThreadTerminateHandler;  
    ThreadSetPriority : TThreadSetPriorityHandler  
    ;  
    ThreadGetPriority : TThreadGetPriorityHandler;  
    GetCurrentThreadId  
    : TGetCurrentThreadIdHandler;  
    InitCriticalSection : TCriticalSectionHandler  
    ;  
    DoneCriticalSection : TCriticalSectionHandler;  
    EnterCriticalSection  
    : TCriticalSectionHandler;  
    TryEnterCriticalSection : TCriticalSectionHandlerTryEnter  
    ;  
    LeaveCriticalSection : TCriticalSectionHandler;  
    InitThreadVar  
    : TInitThreadVarHandler;  
    RelocateThreadVar : TRelocateThreadVarHandler  
    ;  
end record
```

```

AllocateThreadVars : TAllocateThreadVarsHandler;
ReleaseThreadVars
: TReleaseThreadVarsHandler;
BasicEventCreate : TBasicEventCreateHandler
;
BasicEventDestroy : TBasicEventHandler;
BasicEventResetEvent
: TBasicEventHandler;
BasicEventSetEvent : TBasicEventHandler;
BasicEventWaitFor : TBasicEventWaitForHandler;
RTLEventCreate
: TRTLCreateEventHandler;
RTLEventDestroy : TRTLEventHandler;
RTLEventSetEvent : TRTLEventHandler;
RTLEventResetEvent : TRTLEventHandler
;
RTLEventWaitFor : TRTLEventHandler;
RTLEventWaitForTimeout
: TRTLEventHandlerTimeout;
SemaphoreInit : TSemaphoreInitHandler
;
SemaphoreDestroy : TSemaphoreDestroyHandler;
SemaphorePost
: TSemaphorePostHandler;
SemaphoreWait : TSemaphoreWaitHandler;
end

```

`TThreadManager` is a record that contains all callbacks needed for the thread handling routines of the Free Pascal Run-Time Library. The thread manager can be set by the `SetThreadManager` (1390) procedure, and the current thread manager can be retrieved with the `GetThreadManager` (1333) procedure.

The Windows RTL will set the thread manager automatically to a system thread manager, based on the Windows threading routines. Unix operating systems provide a unit `cthreads` which implements threads based on the C library POSIX thread routines. It is not included by default, because it would make the system unit dependent on the C library.

For more information about thread programming, see the programmer's guide.

```

TThreadSetPriorityHandler = function(threadHandle: TThreadID;
  Prio: LongInt) : Boolean

```

Callback type for thread priority setting in `TThreadManager` (1250).

```

TThreadSwitchHandler = procedure

```

Callback type for thread switch in `TThreadManager` (1250).

```

TTime = TDateTime

```

`TTime` is defined for Delphi compatibility. This type is deprecated, use `TDateTime` (1237) instead.

```

TUCS4CharArray = Array[0..$efffffff] of UCS4Char

```

Array of `UCS4Char` (1260) characters.

```

TUnicodeStringManager = record
  Wide2AnsiMoveProc : procedure(source
    : PWideChar; var dest: RawByteString;
      cp: TSystemCodePage
    ; len: SizeInt);
  Ansi2WideMoveProc : procedure(source: PChar; cp
    : TSystemCodePage; var dest: widestring;
      len: SizeInt
    );
  UpperWideStringProc : function(const S: WideString) : WideString
  ;
  LowerWideStringProc : function(const S: WideString) : WideString
  ;
  CompareWideStringProc : function(const s1: WideString; const s2
    : WideString;
      Options: TCompareOptions) : PtrInt;
  CharLengthPCharProc
    : function(const Str: PChar) : PtrInt;
  CodePointLengthProc : function
    (const Str: PChar; MaxLookAead: PtrInt) : PtrInt;
  UpperAnsiStringProc
    : function(const s: ansistring) : ansistring;
  LowerAnsiStringProc
    : function(const s: ansistring) : ansistring;
  CompareStrAnsiStringProc
    : function(const S1: ansistring; const S2: ansistring) : PtrInt;
  CompareTextAnsiStringProc : function(const S1: ansistring; const
    S2: ansistring) : PtrInt;
  StrCompAnsiStringProc : function(S1:
    PChar; S2: PChar) : PtrInt;
  StrICompAnsiStringProc : function(S1
    : PChar; S2: PChar) : PtrInt;
  StrLCompAnsiStringProc : function
    (S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
  StrLICompAnsiStringProc
    : function(S1: PChar; S2: PChar; MaxLen: PtrUInt) : PtrInt;
  StrLowerAnsiStringProc
    : function(Str: PChar) : PChar;
  StrUpperAnsiStringProc : function
    (Str: PChar) : PChar;
  ThreadInitProc : procedure;
  ThreadFiniProc
    : procedure;
  Unicode2AnsiMoveProc : procedure(source: PUnicodeChar
    ; var dest: RawByteString;
      cp: TSystemCodePage; len:
    SizeInt);
  Ansi2UnicodeMoveProc : procedure(source: PChar; cp: TSystemCodePage
    ; var dest: unicodestring;
      len: SizeInt);
  UpperUnicodeStringProc
    : function(const S: UnicodeString) : UnicodeString;
  LowerUnicodeStringProc
    : function(const S: UnicodeString) : UnicodeString;

```

```

CompareUnicodeStringProc
: function(const s1: UnicodeString; const s2: UnicodeString;
Options: TCompareOptions) : PtrInt;
GetStandardCodePageProc
: function(const stdcp: TStandardCodePageEnum) : TSystemCodePage
;
end

```

TUnicodeStringManager is currently the same as the TUnicodeStringManager (1252) manager record. It performs the same functions: converting unicode strings to ansistrings and vice-versa, performing uppercase to lowercase transformations and comparing strings.

```

tvararray = record
  dimcount : Word;
  flags : Word;
  elementsize
: LongInt;
  lockcount : LongInt;
  data : pointer;
  bounds : tvararrayboundarray
;
end

```

tvararray is a record describing a variant array. It contains some general data, followed by a number of TVarArrayBound (1252) records equal to the number of dimensions in the array (dimcount).

```

tvararraybound = record
  elementcount : LongInt;
  lowbound : LongInt
;
end

```

tvararraybound is used to describe one dimension in a variant array.

tvararrayboundarray = Array[0..0] of tvararraybound

array of tvararraybound (1252) records.

tvararraycoorarray = Array[0..0] of LongInt

Array of variant array coordinates

```

tvardata = packed record
  vtype : tvartype;
case Integer of
0: (
  res1 : Word;
case Integer of
0: (
  res2 : Word;
  res3 : Word
;

```

```
case Word of
varsmallint: (
    vsmallint : SmallInt;
);
varinteger
    : (
        vinteger : LongInt;
    );
varsingle: (
    vsingle : single;
);
vardouble
    : (
        vdouble : Double;
    );
vardate: (
    vdate : TDateTime;
);
varcurrency
    : (
        vcurrency : currency;
    );
varolestr: (
    volestr : PWideChar
    ;
);
vardispatch: (
    vdispatch : pointer;
);
varerror: (
    verror
        : HRESULT;
);
varboolean: (
    vboolean : wordbool;
);
varunknown
    : (
        vunknown : pointer;
    );
varshortint: (
    vshortint : ShortInt
    ;
);
varbyte: (
    vbyte : Byte;
);
varword: (
    vword : Word;
);
varlongword
    : (
        vlongword : DWord;
    );
```

```

varint64: (
  vint64 : Int64;
);
varqword
  : (
    vqword : QWord;
  );
varword64: (
  vword64 : QWord;
);
varstring
  : (
    vstring : pointer;
  );
varany: (
  vany : pointer;
);
vararray
  : (
    varray : pvararray;
  );
varbyref: (
  vpointer : pointer;
);
);
1: (
  vlongs : Array[0..2] of LongInt;
);
);
1: (
  vwords :
    Array[0..6] of Word;
);
2: (
  vbytes : Array[0..13] of Byte;
);
end

```

TVarData is a record representation of a variant. It contains the internal structure of a variant and is handled by the various variant handling routines.

```

tvariantmanager = record
  vartoint : function(const v: variant)
    : LongInt;
  vartoint64 : function(const v: variant) : Int64;
  vartoword64
    : function(const v: variant) : QWord;
  vartobool : function(const
    v: variant) : Boolean;
  vartoreal : function(const v: variant)
    : extended;
  vartotdatetime : function(const v: variant) : TDateTime
    ;
  vartocurr : function(const v: variant) : currency;

```

```

vartopstr
: procedure(var s; const v: variant);
vartolstr : procedure(var
s: ansistring; const v: variant);
vartowstr : procedure(var s:
widestring; const v: variant);
vartointf : procedure(var intf:
IInterface; const v: variant);
vartodisp : procedure(var disp:
IDispatch; const v: variant);
vartodynarray : procedure(var dynarr
: pointer; const v: variant; typeinfo: pointer);
varfrombool : procedure
(var dest: variant; const source: Boolean);
varfromint : procedure
(var dest: variant; const source: LongInt;
const Range
: LongInt);
varfromint64 : procedure(var dest: variant; const source
: Int64);
varfromword64 : procedure(var dest: variant; const source
: QWord);
varfromreal : procedure(var dest: variant; const source
: extended);
varfromtdatetime : procedure(var dest: Variant; const
source: TDateTime);
varfromcurr : procedure(var dest: Variant;
const source: Currency);
varfrompstr : procedure(var dest: variant
; const source: ShortString);
varfromlstr : procedure(var dest:
variant; const source: ansistring);
varfromwstr : procedure(var
dest: variant; const source: WideString);
varfromintf : procedure
(var dest: variant; const source: IInterface);
varfromdisp : procedure
(var dest: variant; const source: IDispatch);
varfromdynarray :
procedure(var dest: variant; const source: pointer; typeinfo: pointer
);
olevarfrompstr : procedure(var dest: olevariant; const source
: shortstring);
olevarfromlstr : procedure(var dest: olevariant
; const source: ansistring);
olevarfromvar : procedure(var dest
: olevariant; const source: variant);
olevarfromint : procedure
(var dest: olevariant; const source: LongInt;
const range
: ShortInt);
varop : procedure(var left: variant; const right: variant
; opcode: tvarop);
cmpop : function(const left: variant; const right

```



```

: variant;
      const opcode: tvarop) : Boolean;
varneg
: procedure(var v: variant);
varnot : procedure(var v: variant)
;
varinit : procedure(var v: variant);
varclear : procedure(var
v: variant);
varaddref : procedure(var v: variant);
varcopy
: procedure(var dest: variant; const source: variant);
varcast
: procedure(var dest: variant; const source: variant; vartype: LongInt
);
varcastole : procedure(var dest: variant; const source: variant
; vartype: LongInt);
dispinvoke : procedure(dest: pvardata; var
source: tvardata; calldesc: pcalldesc;
      params: pointer
);
vararrayredim : procedure(var a: variant; highbound: SizeInt
);
vararrayget : function(const a: variant; indexcount: SizeInt
; indices: PLongint)
      : variant;
vararrayput : procedure
(var a: variant; const value: variant; indexcount: SizeInt;
indices: PLongint);
writevariant : function(var t: text
; const v: variant; width: LongInt) : Pointer;
write0Variant : function
(var t: text; const v: Variant) : Pointer;
end

```

TVariantManager describes the variant manager as expected by the SetVariantManager [\(1390\)](#) call.

```

tvarop = (opadd, opsubtract, opmultiply, opdivide, opintdivide, opmodulus
,
      opshiftleft, opshiftright, opand, opor, opxor, opcompare, opnegate
,
      opnot, opcmpeq, opcmpne, opcmplt, opcmple, opcmpgt, opcmpge
, oppower)

```

Table 75.19: Enumeration values for type tvarop

Value	Explanation
opadd	Variant operation: Addition.
opand	Variant operation: Binary AND operation
opcmpeq	Variant operation: Compare equal.
opcmpge	Variant operation: Compare larger than or equal
opcmpgt	Variant operation: Compare larger than
opcmple	Variant operation: Compare less than or equal to
opcmplt	Variant operation: Compare less than.
opcmpne	Variant operation: Compare not equal
opcompare	Variant operation: Compare
opdivide	Variant operation: division
opintdivide	Variant operation: integer divide
opmodulus	Variant operation: Modulus
opmultiply	Variant operation: multiplication
opnegate	Variant operation: negation.
opnot	Variant operation: Binary NOT operation.
opor	Variant operation: Binary OR operation
oppower	Variant operation: Power
opshiftright	Variant operation: Shift left
opshiftright	Variant operation: Shift right
opsubtract	Variant operation: Substraction
opxor	Variant operation: binary XOR operation.

tvarop describes a variant operation. It is mainly used for the variant manager to implement the various conversions and mathematical operations on a variant.

```

TVarRec = record
case VType : SizeInt of
vtInteger: (
    VInteger
    : LongInt;
);
vtBoolean: (
    VBoolean : Boolean;
);
vtChar: (
    VChar
    : Char;
);
vtWideChar: (
    VWideChar : WideChar;
);
vtExtended:
(
    VExtended : PExtended;
);
vtString: (
    VString : PShortString
;
);

```

```

vtPointer: (
    VPointer : Pointer;
);
vtPChar: (
    VPChar : PAnsiChar
    ;
);
vtObject: (
    VObject : TObject;
);
vtClass: (
    VClass : TClass
    ;
);
vtPWideChar: (
    VPWideChar : PWideChar;
);
vtAnsiString: (
    VAnsiString : Pointer;
);
vtCurrency: (
    VCurrency : PCurrency
    ;
);
vtVariant: (
    VVariant : PVariant;
);
vtInterface: (
    VInterface
    : Pointer;
);
vtWideString: (
    VWideString : Pointer;
);
vtInt64
    : (
        VInt64 : PInt64;
    );
vtUnicodeString: (
    VUnicodeString : Pointer
    ;
);
vtQWord: (
    VQWord : PQWord;
);
end

```

TVarRec is a record generated by the compiler for each element in a array of const call. The procedure that receives the constant array receives an array of TVarRec elements, with lower bound zero and high bound equal to the number of elements in the array minus one (as returned by High(Args))

```
tvartype = Word
```

Type with size of variant type.

```
TVmt = record
  vInstanceSize : SizeInt;
  vInstanceSize2 : SizeInt
;
  vParent : PVmt;
  vClassName : PShortString;
  vDynamicTable
  : Pointer;
  vMethodTable : Pointer;
  vFieldTable : Pointer;
  vTypeInfo
  : Pointer;
  vInitTable : Pointer;
  vAutoTable : Pointer;
  vIntfTable
  : pinterfacetable;
  vMsgStrPtr : pstringmessagetable;
  vDestroy
  : CodePointer;
  vNewInstance : CodePointer;
  vFreeInstance : CodePointer
;
  vSafeCallException : CodePointer;
  vDefaultHandler : CodePointer
;
  vAfterConstruction : CodePointer;
  vBeforeDestruction : CodePointer
;
  vDefaultHandlerStr : CodePointer;
  vDispatch : CodePointer;
  vDispatchStr : CodePointer;
  vEquals : CodePointer;
  vGetHashCode
  : CodePointer;
  vToString : CodePointer;
end
```

TVMT is a record describing the VMT of a class. It's various fields represent the available information in the VMT, as far as it is common to all classes.

```
TWaitForThreadTerminateHandler = function(threadHandle: TThreadID
;
                                     TimeoutMs: LongInt)
: DWord
```

Callback type for thread termination in TThreadManager ([1250](#)).

```
TWideStringManager = TUnicodeStringManager
```

TWideStringManager contains the definition of the widestring manager.

```
UCS2Char = WideChar
```

UCS2 unicode character.

UCS4Char =

UCS unicode character (unsigned 32 bit word)

UCS4String = Array of UCS4Char

String of UCS4Char ([1260](#)) characters.

UInt16 = Word

An unsigned 16-bits integer

UInt32 = Cardinal

An unsigned 32-bits integer

UInt64 = QWord

Unsigned 64-bit integer

UInt8 = Byte

An unsigned 8-bits integer

UIntPtr = PtrUInt

Alias for PtrUInt ([1231](#)) type for compatibility with later Delphi versions.

UnicodeChar = WideChar

UnicodeChar is a single character from a UnicodeString. It equals WideChar in all respects.

UnicodeString = UnicodeString

UnicodeString is a string of WideChars. The main difference with WideString is that unicode-string is reference counted, and WideString is not reference counted on Windows.

UTF8String = ansistring

UTF-8 unicode (ansi) string.

ValReal = Extended

ValReal is an alias for the largest available floating point type on the architecture the program runs on. On most processors, it should be one of Double or Extended.

ValSInt = Int64

Integer with the same size as the return code of the Val ([1413](#)) function.

`ValSInt = LongInt`

Integer with the same size as the return code of the `Val` (1413) function.

`ValUInt = Cardinal`

Integer with the same size as the return code of the `Val` (1413) function.

`ValUInt = QWord`

Integer with the same size as the return code of the `Val` (1413) function.

`WChar = WideChar`

Wide char (16-bit sized char)

`WideChar = #$0000..#$FFFF`

This type is the base unit for all two byte character types, like `UnicodeString` (1260) and `WideString` (1261)

`WideString = WideString`

`WideString` is an alias for `UnicodeString` on unix. On windows, it is a different type which has no reference counting.

`Word = 0..65535`

An unsigned 16-bits integer

75.10.3 Variables

`DefaultFileSystemCodePage : TSystemCodePage`

`DefaultFileSystemCodePage` determines the code page to which file/path names are translated before they are passed to OS API calls, if the RTL uses a single byte OS API for this purpose on the current platform.

This code page is also used for intermediate operations on file paths inside the RTL before making OS API calls.

This variable does not exist in Delphi, and has been introduced in FPC to make it possible to change the value of `DefaultSystemCodePage` without breaking RTL interfaces with the OS file system API calls.

The initial value of this variable depends on the platform:

- Windows: UTF-8, because the RTL uses UTF-16 OS API calls (so no data is lost in intermediate operations).
- OS X and iOS: UTF-8 (as defined by Apple)
- Unix (excluding OS X and iOS): equals `DefaultSystemCodePage` (1262). This is because the encoding of file names is undefined on Unix platforms: it is an untyped array of bytes that can be interpreted in any way; Specifically, it is not guaranteed to be valid UTF-8.

- Other platforms: same as `DefaultSystemCodePage` (1262).

The value of this variable may be changed using the `SetMultiByteFileSystemCodePage` (1386) procedure.

Remark: The Unix/OS X/iOS settings only apply in case the `cstring` widestring manager is installed, otherwise `DefaultFileSystemCodePage` will have the same value as `DefaultSystemCodePage` after program startup.

`DefaultRTLFileSystemCodePage` : `TSystemCodePage`

`DefaultRTLFileSystemCodePage` determines the code page to which file/path names are translated before they are returned from `RawByteString` (1233) file/path RTL routines.

Examples include the file/path names returned by the `RawByteString` versions of `SysUtils.FindFirst` (1194) and `GetDir` (1330).

The main reason for its existence is to enable the RTL to provide backward compatibility with earlier versions of FPC, as these always returned strings encoded in whatever the OS' single byte API used (normally `DefaultSystemCodePage` (1262)).

The initial value of this variable depends on the platform:

- Windows: `DefaultSystemCodePage`, for backward compatibility.
- OS X and iOS: UTF-8, for backward compatibility. It was already always UTF-8 in the past, since that's what the OS file APIs returned, and the data was never converted.
- Other Unixes: `DefaultSystemCodePage`, for the same reason as `DefaultFileSystemCodePage` (1261). Setting this to a different value than `DefaultFileSystemCodePage` is a bad idea on these platforms, since any code page conversion can corrupt these strings as their initial encoding is unknown.
- Other platforms: same as `DefaultSystemCodePage`.

The value of this variable can be set using the `SetMultiByteRTLFileSystemCodePage` (1387) call.

`DefaultSystemCodePage` : `TSystemCodePage`

`DefaultSystemCodePage` is used to determine how `CP_ACP` is interpreted; it is what the program considers to be the current system codepage.

It is initialized to the default system codepage.

- On windows, this is the result of the `GetACP` operating call, which returns the Windows ANSI code page.
- On iOS, this is UTF-8
- on other Unixes this will be based on the currently set `LANG` or `LC_CTYPE` environment variables. Normally this is UTF-8, but that is not guaranteed to be the case.
- For all other platforms it is set to `CP_ACP`, as these platforms currently do not support multiple code pages, and are hardcoded to use their OS-specific code page in all cases.

The `DefaultSystemCodePage` value may be set using `SetMultiByteConversionCodePage` (1386). That means that it is not a good idea to use its value to determine the real OS "default system code page".

`DefaultUnicodeCodePage : TSystemCodePage`

`DefaultUnicodeCodePage` is the unicode code page for a new unicode string. On most platforms, this is `CP_UTF16` (1200).

`DispCallByIDProc : CodePointer`

`VarDispProc` is called by the compiler if it needs to perform an interface call from a variant which contains a dispatch interface. For instance, the following call:

```
Var
  V : OleVariant;
begin
  (V as IWord).OpenDocument('c:\temp\mydoc.doc');
end;
```

where `IWord` is a dispatch interface is encoded by the compiler and passed to `DispCallByIDProc`. This pointer must be set by a routine that calls the OS COM handling routines.

`ErrOutput : Text`

`ErrOutput` is provided for Delphi compatibility.

`ExitCode : LongInt; public 'operatingsystem_result'`

Exit code for the program, will be communicated to the OS on exit.

`FirstDotAtFileNameStartIsExtension : Boolean = False`

`FirstDotAtFileNameStartIsExtension` determines what happens if a filename starts with a dot (.) character. If `True`, then the whole file name will be treated as extension. If `False`, then the extension is empty.

`InOutRes : Word`

Result of last I/O operation. Read-Only.

`Input : Text`

Standard input text file.

`IsConsole : Boolean; public 'operatingsystem_isconsole' = False`

`True` for console applications, `False` for GUI applications.

`IsLibrary : Boolean; public 'operatingsystem_islibrary' = False`

`True` if the current module is a library. Otherwise module is an executable

`NoErrMsg : Boolean = Falseplatform`

Unused, for Delphi compatibility

Output : Text

Standard output text file.

RandSeed : Cardinal

Seed for Random ([1368](#)) function.

ReturnNilIfGrowHeapFails : Boolean

ReturnNilIfGrowHeapFails describes what happens if there is no more memory available from the operating system. if set to True the memory manager will return Nil. If set to False then a run-time error will occur.

softfloat_exception_flags : TFPUEExceptionMask

Current soft float exception flags

softfloat_exception_mask : TFPUEExceptionMask

Current soft float exception mask

softfloat_rounding_mode : TFPURoundingMode

softfloat_rounding_mode determines how the software floating-point emulation routines do the rounding. The value can be one of the following:

float_round_nearest_even Round to nearest even number

float_round_down Round down

float_round_up Round up

float_round_to_zero Round in the direction of zero (down for positive, up for negative)

StackBottom : Pointer

Current stack bottom.

StackLength : SizeUInt

Maximum stack length.

StdErr : Text

Standard diagnostic output text file.

StdOut : Text

Alias for Output ([1264](#)).

ThreadID : TThreadID

Current Thread ID.

UTF8CompareLocale : TSystemCodePage

UTF8CompareLocale is currently present for Delphi compatibility only, it is not used in FPC code.

widestringmanager : TUnicodeStringManager

Contains the current widestring manager. Do not use directly.

WriteErrorsToStdErr : Boolean = True

WriteErrorsToStdErr can be set to True to write error messages (run-time errors, exceptions) to StdErr instead of to standard output. This is the default behaviour. When set to False, error message will be written to standar output.

75.11 Procedures and functions

75.11.1 abs

Synopsis: Calculate absolute value

Declaration: function abs(l: LongInt) : LongInt
 function abs(l: Int64) : Int64
 function abs(d: ValReal) : ValReal

Visibility: default

Description: Abs returns the absolute value of a variable. The result of the function has the same type as its argument, which can be any numerical type.

Errors: None.

See also: Round ([1378](#))

Listing: ./refex/ex1.pp

Program Example1;

{ Program to demonstrate the Abs function. }

Var

 r : real;
 i : integer;

begin

 r:=abs(-1.0); { r:=1.0 }
 i:=abs(-21); { i:=21 }

end.

75.11.2 AbstractError

Synopsis: Generate an abstract error.

Declaration: `procedure AbstractError`

Visibility: default

Description: `AbstractError` generates an abstract error (run-time error 211). If the `AbstractErrorProc` ([1199](#)) constant is set, it will be called instead.

Errors: This routine causes a run-time error 211.

See also: `AbstractErrorProc` ([1199](#))

75.11.3 AcquireExceptionObject

Synopsis: Obtain a reference to the current exception object

Declaration: `function AcquireExceptionObject : Pointer`

Visibility: default

Description: `AcquireExceptionObject` returns the current exception object. It raises the reference count of the exception object, so it will not be freed. Calling this method is only valid within an except block.

The effect of this function is countered by re-raising an exception via `raise`;

To make sure that the exception object is released when it is no longer needed, `ReleaseExceptionObject` ([1372](#)) must be called when the reference is no longer needed.

Errors: If there is no current exception, a run-time error 231 will occur.

See also: `ReleaseExceptionObject` ([1372](#))

75.11.4 add(variant,variant):variant

Synopsis: Implement addition (+) operation on variants.

Declaration: `operator +(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the addition + operation is delegated to the variant manager with operation `opadd`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1194](#))

75.11.5 AddExitProc

Synopsis: Add an exit procedure to the exit procedure chain.

Declaration: `procedure AddExitProc(Proc: TProcedure)`

Visibility: default

Description: `AddExitProc` adds `Proc` to the exit procedure chain. At program exit, all procedures added in this way will be called in reverse order.

Errors: None.

See also: `ExitProc` ([1201](#))

75.11.6 Addr

Synopsis: Return address of a variable

Declaration: `function Addr(X: TAnytype) : Pointer`

Visibility: default

Description: `Addr` returns a pointer to its argument, which can be any type, or a function or procedure name. The returned pointer isn't typed. The same result can be obtained by the `@` operator, which can return a typed pointer (see the programmer's guide).

Errors: None

See also: `SizeOf` ([1392](#))

Listing: `./refex/ex2.pp`

Program `Example2`;

{ Program to demonstrate the Addr function. }

Const `Zero : integer = 0;`

Var `p : pointer;`
`i : Integer;`

begin
`p:=Addr(p); { P points to itself }`
`p:=Addr(i); { P points to i }`
`p:=Addr(Zero); { P points to 'Zero' }`
end.

75.11.7 Align

Synopsis: Return aligned version of an address

Declaration: `function Align(Addr: PtrUInt; Alignment: PtrUInt) : PtrUInt`
`function Align(Addr: Pointer; Alignment: PtrUInt) : Pointer`

Visibility: default

Description: `Align` returns `Address`, aligned to `Alignment` bytes.

Errors: None.

75.11.8 AllocMem

Synopsis: Allocate and clear memory.

Declaration: `function AllocMem(Size: PtrUInt) : pointer`

Visibility: default

Description: `AllocMem` calls `getmem GetMem` ([1331](#)), and clears the allocated memory, i.e. the allocated memory is filled with `Size` zero bytes.

See also: `GetMem` ([1331](#))

75.11.9 AnsiToUtf8

Synopsis: Convert ansi string to UTF-8 string

Declaration: `function AnsiToUtf8(const s: RawByteString) : RawByteString`

Visibility: default

Description: `AnsiToUtf8` converts the ansistring `S` to a UTF-8 format, that is, it converts the string from whatever codepage is currently in use, to UTF-8.

The current codepage is fetched from the system, if internationalization support is enabled. It can be UTF-8, in which case the function simply returns `S`.

Errors: None.

See also: `Utf8toAnsi` ([1412](#))

75.11.10 Append

Synopsis: Open a file in append mode

Declaration: `procedure Append(var t: Text)`

Visibility: default

Description: `Append` opens an existing file in append mode. Any data written to `F` will be appended to the file. Only text files can be opened in append mode. After a call to `Append`, the file `F` becomes write-only. File sharing is not taken into account when calling `Append`.

Errors: If the file doesn't exist when appending, a run-time error will be generated. This behaviour has changed on Windows and Linux platforms, where in versions prior to 1.0.6, the file would be created in append mode.

See also: `Rewrite` ([1374](#)), `Close` ([1298](#)), `Reset` ([1373](#))

Listing: `./refex/ex3.pp`

Program `Example3`;

{ Program to demonstrate the Append function. }

Var `f` : text;

begin

 Assign (`f`, 'test.txt');

Rewrite (`f`); *{ file is opened for write , and emptied }*

```

WriteIn (F, 'This is the first line of text.txt');
close (f);
Append(f);           { file is opened for write , but NOT emptied.
                       any text written to it is appended.}
WriteIn (f, 'This is the second line of text.txt');
close (f);
end.

```

75.11.11 arctan

Synopsis: Calculate inverse tangent

Declaration: `function arctan(d: ValReal) : ValReal`

Visibility: default

Description: `Arctan` returns the Arctangent of X, which can be any Real type. The resulting angle is in radial units.

Errors: None

See also: `Sin` ([1391](#)), `Cos` ([1305](#))

Listing: ./refex/ex4.pp

```

Program Example4;

{ Program to demonstrate the ArcTan function. }

Var R : Real;

begin
  R:=ArcTan(0);      { R:=0 }
  R:=ArcTan(1)/pi;   { R:=0.25 }
end.

```

75.11.12 ArrayStringToPPchar

Synopsis: Convert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of AnsiString;
 reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array S. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1398](#))

75.11.13 Assert

Synopsis: Check validity of a given condition.

Declaration: `procedure Assert (Expr: Boolean)`
`procedure Assert (Expr: Boolean; const Msg: string)`

Visibility: default

Description: With assertions on, `Assert` tests if `expr` is false, and if so, aborts the application with a Runtime error 227 and an optional error message in `msg`. If `expr` is true, program execution continues normally. If assertions are not enabled at compile time, this routine does nothing, and no code is generated for the `Assert` call. Enabling and disabling assertions at compile time is done via the `\$C` or `\$ASSERTIONS` compiler switches. These are global switches. The default behavior of the assert call can be changed by setting a new handler in the `AssertErrorProc` variable. `Sysutils` overrides the default handler to raise a `EAssertionFailed` exception.

Errors: None.

See also: [Halt \(1336\)](#), [Runerror \(1379\)](#)

75.11.14 Assign

Synopsis: Assign a name to a file

Declaration: `procedure Assign(out f: File; const Name: ShortString)`
`procedure Assign(out f: File; const p: PAnsiChar)`
`procedure Assign(out f: File; const c: AnsiChar)`
`procedure Assign(out f: File; const Name: UnicodeString)`
`procedure Assign(out f: File; const Name: RawByteString)`
`procedure Assign(out f: TypedFile; const Name: shortstring)`
`procedure Assign(out f: TypedFile; const p: PAnsiChar)`
`procedure Assign(out f: TypedFile; const c: AnsiChar)`
`procedure Assign(out f: TypedFile; const Name: unicodestring)`
`procedure Assign(out f: TypedFile; const Name: RawByteString)`
`procedure Assign(out t: Text; const s: shortstring)`
`procedure Assign(out t: Text; const p: PAnsiChar)`
`procedure Assign(out t: Text; const c: AnsiChar)`
`procedure Assign(out t: Text; const s: unicodestring)`
`procedure Assign(out t: Text; const s: RawByteString)`

Visibility: default

Description: `Assign` assigns a name to `F`, which can be any file type. This call doesn't open the file, it just assigns a name to a file variable, and marks the file as closed.

Errors: None.

See also: [Reset \(1373\)](#), [Rewrite \(1374\)](#), [Append \(1268\)](#)

Listing: `./refex/ex5.pp`

Program `Example5;`

{ Program to demonstrate the Assign function. }

Var `F : text;`

```

begin
  Assign (F, '');
  Rewrite (f);
  { The following can be put in any file by redirecting it
    from the command line.}
  Writeln (f, 'This goes to standard output !');
  Close (f);
  Assign (F, 'Test.txt');
  rewrite (f);
  writeln (f, 'This doesn''t go to standard output !');
  close (f);
end.

```

75.11.15 assign(ansistring):olevariant

Synopsis:

Declaration: `operator :=(const source: ansistring) : olevariant`

Visibility: default

Description:

75.11.16 assign(ansistring):variant

Synopsis:

Declaration: `operator :=(const source: ansistring) : variant`

Visibility: default

Description:

75.11.17 assign(Boolean):olevariant

Synopsis:

Declaration: `operator :=(const source: Boolean) : olevariant`

Visibility: default

Description:

75.11.18 assign(Boolean):variant

Synopsis:

Declaration: `operator :=(const source: Boolean) : variant`

Visibility: default

Description:

75.11.19 assign(Byte):olevariant

Synopsis:

Declaration: `operator :=(const source: Byte) : olevariant`

Visibility: default

Description:

75.11.20 assign(Byte):variant

Synopsis:

Declaration: `operator :=(const source: Byte) : variant`

Visibility: default

Description:

75.11.21 assign(Char):olevariant

Synopsis:

Declaration: `operator :=(const source: Char) : olevariant`

Visibility: default

Description:

75.11.22 assign(Char):variant

Synopsis:

Declaration: `operator :=(const source: Char) : variant`

Visibility: default

Description:

75.11.23 assign(comp):olevariant

Synopsis: Assign a comp-precision float to an ole-variant

Declaration: `operator :=(const source: comp) : olevariant`

Visibility: default

75.11.24 assign(comp):variant

Synopsis: Assign a comp-precision float to a variant

Declaration: `operator :=(const source: comp) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

75.11.25 assign(currency):olevariant

Synopsis:

Declaration: `operator :=(const source: currency) : olevariant`

Visibility: default

Description:

75.11.26 assign(currency):variant

Synopsis:

Declaration: `operator :=(const source: currency) : variant`

Visibility: default

Description:

75.11.27 assign(Double):olevariant

Synopsis:

Declaration: `operator :=(const source: Double) : olevariant`

Visibility: default

Description:

75.11.28 assign(Double):variant

Synopsis:

Declaration: `operator :=(const source: Double) : variant`

Visibility: default

Description:

75.11.29 assign(DWord):olevariant

Synopsis:

Declaration: `operator :=(const source: DWord) : olevariant`

Visibility: default

Description:

75.11.30 assign(DWord):variant

Synopsis:

Declaration: `operator :=(const source: DWord) : variant`

Visibility: default

Description:

75.11.31 **assign(extended):olevariant**

Synopsis: Assign an extended-precision float to an ole-variant

Declaration: `operator :=(const source: extended) : olevariant`

Visibility: default

75.11.32 **assign(extended):variant**

Synopsis: Assign an extended-precision float to a variant

Declaration: `operator :=(const source: extended) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

75.11.33 **assign(Int64):olevariant**

Synopsis:

Declaration: `operator :=(const source: Int64) : olevariant`

Visibility: default

Description:

75.11.34 **assign(Int64):variant**

Synopsis:

Declaration: `operator :=(const source: Int64) : variant`

Visibility: default

Description:

75.11.35 **assign(longbool):olevariant**

Synopsis:

Declaration: `operator :=(const source: longbool) : olevariant`

Visibility: default

Description:

75.11.36 **assign(longbool):variant**

Synopsis:

Declaration: `operator :=(const source: longbool) : variant`

Visibility: default

Description:

75.11.37 assign(LongInt):olevariant

Synopsis:

Declaration: `operator :=(const source: LongInt) : olevariant`

Visibility: default

Description:

75.11.38 assign(LongInt):variant

Synopsis:

Declaration: `operator :=(const source: LongInt) : variant`

Visibility: default

Description:

75.11.39 assign(olevariant):ansistring

Synopsis:

Declaration: `operator :=(const source: olevariant) : ansistring`

Visibility: default

Description:

75.11.40 assign(olevariant):Boolean

Synopsis:

Declaration: `operator :=(const source: olevariant) : Boolean`

Visibility: default

Description:

75.11.41 assign(olevariant):Byte

Synopsis:

Declaration: `operator :=(const source: olevariant) : Byte`

Visibility: default

Description:

75.11.42 assign(olevariant):Char

Synopsis:

Declaration: `operator :=(const source: olevariant) : Char`

Visibility: default

Description:

75.11.43 assign(olevariant):comp

Synopsis: Assign an ole-variant to a comp-precision float

Declaration: `operator :=(const source: olevariant) : comp`

Visibility: default

75.11.44 assign(olevariant):currency

Synopsis:

Declaration: `operator :=(const source: olevariant) : currency`

Visibility: default

Description:

75.11.45 assign(olevariant):Double

Synopsis:

Declaration: `operator :=(const source: olevariant) : Double`

Visibility: default

Description:

75.11.46 assign(olevariant):DWord

Synopsis:

Declaration: `operator :=(const source: olevariant) : DWord`

Visibility: default

Description:

75.11.47 assign(olevariant):extended

Synopsis: Assign an ole-variant to an extended-precision float

Declaration: `operator :=(const source: olevariant) : extended`

Visibility: default

75.11.48 assign(olevariant):Int64

Synopsis:

Declaration: `operator :=(const source: olevariant) : Int64`

Visibility: default

Description:

75.11.49 assign(olevariant):longbool

Synopsis:

Declaration: `operator :=(const source: olevariant) : longbool`

Visibility: default

Description:

75.11.50 assign(olevariant):LongInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : LongInt`

Visibility: default

Description:

75.11.51 assign(olevariant):QWord

Synopsis:

Declaration: `operator :=(const source: olevariant) : QWord`

Visibility: default

Description:

75.11.52 assign(olevariant):Real

Synopsis: Assign an ole-variant to a real-precision float

Declaration: `operator :=(const source: olevariant) : Real`

Visibility: default

75.11.53 assign(olevariant):ShortInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : ShortInt`

Visibility: default

Description:

75.11.54 assign(olevariant):shortstring

Synopsis:

Declaration: `operator :=(const source: olevariant) : shortstring`

Visibility: default

Description:

75.11.55 assign(olevariant):single

Synopsis: Assign an ole-variant to a single-precision float

Declaration: `operator :=(const source: olevariant) : single`

Visibility: default

75.11.56 assign(olevariant):SmallInt

Synopsis:

Declaration: `operator :=(const source: olevariant) : SmallInt`

Visibility: default

Description:

75.11.57 assign(olevariant):TDateTime

Synopsis:

Declaration: `operator :=(const source: olevariant) : TDateTime`

Visibility: default

Description:

75.11.58 assign(olevariant):TError

Synopsis:

Declaration: `operator :=(const source: olevariant) : TError`

Visibility: default

Description:

75.11.59 assign(olevariant):UnicodeString

Synopsis: Assign an ole-variant to a unicode string

Declaration: `operator :=(const source: olevariant) : UnicodeString`

Visibility: default

75.11.60 assign(olevariant):variant

Synopsis:

Declaration: `operator :=(const source: olevariant) : variant`

Visibility: default

Description:

75.11.61 assign(olevariant):WideChar

Synopsis:

Declaration: `operator :=(const source: olevariant) : WideChar`

Visibility: default

Description:

75.11.62 assign(olevariant):widerstring

Synopsis:

Declaration: `operator :=(const source: olevariant) : widerstring`

Visibility: default

Description:

75.11.63 assign(olevariant):Word

Synopsis:

Declaration: `operator :=(const source: olevariant) : Word`

Visibility: default

Description:

75.11.64 assign(olevariant):wordbool

Synopsis:

Declaration: `operator :=(const source: olevariant) : wordbool`

Visibility: default

Description:

75.11.65 assign(QWord):olevariant

Synopsis:

Declaration: `operator :=(const source: QWord) : olevariant`

Visibility: default

Description:

75.11.66 assign(QWord):variant

Synopsis:

Declaration: `operator :=(const source: QWord) : variant`

Visibility: default

Description:

75.11.67 assign(Real):olevariant

Synopsis: Assign a real-precision float to an ole-variant

Declaration: `operator :=(const source: Real) : olevariant`

Visibility: default

Description: Assign a real-precision float to an ole-variant

75.11.68 assign(Real):variant

Synopsis: Assign a real-precision float to a variant

Declaration: `operator :=(const source: Real) : variant`

Visibility: default

Description: The resulting variant is a double-precision value.

75.11.69 assign(real48):Double

Synopsis:

Declaration: `operator :=(b: real48) : Double`

Visibility: default

Description:

75.11.70 assign(real48):extended

Synopsis:

Declaration: `operator :=(b: real48) : extended`

Visibility: default

Description:

75.11.71 assign(ShortInt):olevariant

Synopsis:

Declaration: `operator :=(const source: ShortInt) : olevariant`

Visibility: default

Description:

75.11.72 assign(ShortInt):variant

Synopsis:

Declaration: `operator :=(const source: ShortInt) : variant`

Visibility: default

Description:

75.11.73 assign(shortstring):olevariant

Synopsis:

Declaration: `operator :=(const source: shortstring) : olevariant`

Visibility: default

Description:

75.11.74 assign(shortstring):variant

Synopsis:

Declaration: `operator :=(const source: shortstring) : variant`

Visibility: default

Description:

75.11.75 assign(single):olevariant

Synopsis: Assign a single-precision float to an ole-variant

Declaration: `operator :=(const source: single) : olevariant`

Visibility: default

75.11.76 assign(single):variant

Synopsis: Assign a single-precision float to a variant

Declaration: `operator :=(const source: single) : variant`

Visibility: default

Description: The resulting variant is a double-precision value

75.11.77 assign(SmallInt):olevariant

Synopsis:

Declaration: `operator :=(const source: SmallInt) : olevariant`

Visibility: default

Description:

75.11.78 assign(SmallInt):variant

Synopsis:

Declaration: `operator :=(const source: SmallInt) : variant`

Visibility: default

Description:

75.11.79 assign(TDateTime):olevariant

Synopsis:

Declaration: `operator :=(const source: TDateTime) : olevariant`

Visibility: default

Description:

75.11.80 assign(TDateTime):variant

Synopsis:

Declaration: `operator :=(const source: TDateTime) : variant`

Visibility: default

Description:

75.11.81 assign(TError):olevariant

Synopsis:

Declaration: `operator :=(const source: TError) : olevariant`

Visibility: default

Description:

75.11.82 assign(TError):variant

Synopsis:

Declaration: `operator :=(const source: TError) : variant`

Visibility: default

Description:

75.11.83 assign(UCS4String):variant

Synopsis: Assign UCS4String to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UCS4String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.84 assign(UnicodeString):olevariant

Synopsis: Assign a unicodestring to an ole-variant

Declaration: `operator :=(const source: UnicodeString) : olevariant`

Visibility: default

75.11.85 assign(UnicodeString):variant

Synopsis: Assign UnicodeString to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UnicodeString) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.86 assign(UTF8String):variant

Synopsis: Assign an UTF-8 string to a variant, performing the necessary conversions

Declaration: `operator :=(const source: UTF8String) : variant`

Visibility: default

Description: The resulting variant is a widestring.

75.11.87 assign(variant):ansistring

Synopsis:

Declaration: `operator :=(const source: variant) : ansistring`

Visibility: default

Description:

75.11.88 assign(variant):Boolean

Synopsis:

Declaration: `operator :=(const source: variant) : Boolean`

Visibility: default

Description:

75.11.89 assign(variant):Byte

Synopsis:

Declaration: `operator :=(const source: variant) : Byte`

Visibility: default

Description:

75.11.90 assign(variant):Char

Synopsis:

Declaration: `operator :=(const source: variant) : Char`

Visibility: default

Description:

75.11.91 assign(variant):comp

Synopsis: Assign a variant to a comp-precision float

Declaration: `operator :=(const source: variant) : comp`

Visibility: default

75.11.92 assign(variant):currency

Synopsis:

Declaration: `operator :=(const source: variant) : currency`

Visibility: default

Description:

75.11.93 assign(variant):Double

Synopsis:

Declaration: `operator :=(const source: variant) : Double`

Visibility: default

Description:

75.11.94 assign(variant):DWord

Synopsis:

Declaration: `operator :=(const source: variant) : DWord`

Visibility: default

Description:

75.11.95 assign(variant):extended

Synopsis: Assign a variant to a extended-precision float

Declaration: `operator :=(const source: variant) : extended`

Visibility: default

75.11.96 assign(variant):Int64

Synopsis:

Declaration: `operator :=(const source: variant) : Int64`

Visibility: default

Description:

75.11.97 assign(variant):longbool

Synopsis:

Declaration: `operator :=(const source: variant) : longbool`

Visibility: default

Description:

75.11.98 assign(variant):LongInt

Synopsis:

Declaration: `operator :=(const source: variant) : LongInt`

Visibility: default

Description:

75.11.99 assign(variant):olevariant

Synopsis:

Declaration: `operator :=(const source: variant) : olevariant`

Visibility: default

Description:

75.11.100 assign(variant):QWord

Synopsis:

Declaration: `operator :=(const source: variant) : QWord`

Visibility: default

Description:

75.11.101 assign(variant):Real

Synopsis: Assign a variant to a real-precision float

Declaration: `operator :=(const source: variant) : Real`

Visibility: default

75.11.102 assign(variant):ShortInt

Synopsis:

Declaration: `operator :=(const source: variant) : ShortInt`

Visibility: default

Description:

75.11.103 assign(variant):shortstring

Synopsis:

Declaration: `operator :=(const source: variant) : shortstring`

Visibility: default

Description:

75.11.104 assign(variant):single

Synopsis: Assign a variant to a single-precision float

Declaration: `operator :=(const source: variant) : single`

Visibility: default

75.11.105 assign(variant):SmallInt

Synopsis:

Declaration: `operator :=(const source: variant) : SmallInt`

Visibility: default

Description:

75.11.106 assign(variant):TDateTime

Synopsis:

Declaration: `operator :=(const source: variant) : TDateTime`

Visibility: default

Description:

75.11.107 assign(variant):TError

Synopsis:

Declaration: `operator :=(const source: variant) : TError`

Visibility: default

Description:

75.11.108 assign(variant):unicodestring

Synopsis: Assign a variant to a unicodestring

Declaration: `operator :=(const source: variant) : unicodestring`

Visibility: default

75.11.109 assign(variant):UTF8String

Synopsis: Assign a variant to an UTF8String

Declaration: `operator :=(const source: variant) : UTF8String`

Visibility: default

75.11.110 assign(variant):WideChar

Synopsis:

Declaration: `operator :=(const source: variant) : WideChar`

Visibility: default

Description:

75.11.111 assign(variant):widestring

Synopsis:

Declaration: `operator :=(const source: variant) : widestring`

Visibility: default

Description:

75.11.112 assign(variant):Word

Synopsis:

Declaration: `operator :=(const source: variant) : Word`

Visibility: default

Description:

75.11.113 assign(variant):wordbool

Synopsis:

Declaration: `operator :=(const source: variant) : wordbool`

Visibility: default

Description:

75.11.114 assign(WideChar):olevariant

Synopsis:

Declaration: `operator :=(const source: WideChar) : olevariant`

Visibility: default

Description:

75.11.115 assign(WideChar):variant

Synopsis:

Declaration: `operator :=(const source: WideChar) : variant`

Visibility: default

Description:

75.11.116 assign(widestring):olevariant

Synopsis:

Declaration: `operator :=(const source: widestring) : olevariant`

Visibility: default

Description:

75.11.117 assign(widestring):variant

Synopsis:

Declaration: `operator :=(const source: widestring) : variant`

Visibility: default

Description:

75.11.118 assign(Word):olevariant

Synopsis:

Declaration: `operator :=(const source: Word) : olevariant`

Visibility: default

Description:

75.11.119 assign(Word):variant

Synopsis:

Declaration: `operator :=(const source: Word) : variant`

Visibility: default

Description:

75.11.120 assign(wordbool):olevariant

Synopsis:

Declaration: `operator :=(const source: wordbool) : olevariant`

Visibility: default

Description:

75.11.121 assign(wordbool):variant

Synopsis:

Declaration: `operator :=(const source: wordbool) : variant`

Visibility: default

Description:

75.11.122 Assigned

Synopsis: Check if a pointer is valid

Declaration: `function Assigned(P: Pointer) : Boolean`

Visibility: default

Description: `Assigned` returns `True` if `P` is non-nil and returns `False` if `P` is nil. The main use of `Assigned` is that Procedural variables, method variables and class-type variables also can be passed to `Assigned`.

Errors: None

See also: `New` ([1360](#))

Listing: `./refex/ex96.pp`

Program `Example96`;

{ Program to demonstrate the Assigned function. }

Var `P : Pointer`;

begin

If Not Assigned(`P`) **then**

Writeln ('Pointer is initially NIL');

`P:=@P`;

If Not Assigned(`P`) **then**

Writeln ('Internal inconsistency')

else

Writeln ('All is well in FPC')

end.

75.11.123 BasicEventCreate

Synopsis: Obsolete. Don't use

Declaration: `function BasicEventCreate(EventAttributes: Pointer;
 AManualReset: Boolean; InitialState: Boolean;
 const Name: ansistring) : PEventState`

Visibility: default

Description: `BasicEventCreate` is obsolete, use `RTLEventCreate` ([1378](#)) instead.

See also: `RTLEventCreate` ([1378](#))

75.11.124 **basiceventdestroy**

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventdestroy(state: PEventState)`

Visibility: default

Description: `basiceventdestroy` is obsolete. Use `RTLEventDestroy` ([1378](#)) instead.

See also: `RTLEventDestroy` ([1378](#))

75.11.125 **basiceventResetEvent**

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventResetEvent(state: PEventState)`

Visibility: default

Description: `basiceventResetEvent` is obsolete. Use `RTLEventResetEvent` ([1379](#)) instead.

See also: `RTLEventResetEvent` ([1379](#))

75.11.126 **basiceventSetEvent**

Synopsis: Obsolete. Don't use

Declaration: `procedure basiceventSetEvent(state: PEventState)`

Visibility: default

Description: `basiceventSetEvent` is obsolete. Use `RTLEventSetEvent` ([1379](#)) instead.

See also: `RTLEventSetEvent` ([1379](#))

75.11.127 **basiceventWaitFor**

Synopsis: Obsolete. Don't use

Declaration: `function basiceventWaitFor(Timeout: Cardinal; state: PEventState)
: LongInt`

Visibility: default

Description: `basiceventwaitfor` is obsolete. Use `RTLEventWaitFor` ([1379](#)) instead.

See also: `RTLEventWaitFor` ([1379](#))

75.11.128 **BeginThread**

Synopsis: Start a new thread.

Declaration: `function BeginThread(sa: Pointer; stacksize: SizeUInt;
ThreadFunction: TThreadFunc; p: pointer;
creationFlags: DWord; var ThreadId: TThreadID)
: TThreadID
function BeginThread(ThreadFunction: TThreadFunc) : TThreadID`

```

function BeginThread(ThreadFunction: TThreadFunc; p: pointer)
    : TThreadID
function BeginThread(ThreadFunction: TThreadFunc; p: pointer;
    var ThreadId: TThreadID) : TThreadID
function BeginThread(ThreadFunction: TThreadFunc; p: pointer;
    var ThreadId: TThreadID; const stacksize: SizeUInt)
    : TThreadID

```

Visibility: default

Description: `BeginThread` starts a new thread and executes `ThreadFunction` in the new thread. If `P` is specified, then it is passed to `ThreadFunction`. If `ThreadId` is specified, it is filled with the thread ID of the newly started thread. If `StackSize` is specified, it is set as the stack size for the new thread. If none is specified, a default stack size of 4MiB is used.

The function returns the thread handle (or ID, on some other operating systems like Linux or OS/2) on success, or 0 if an error occurred. Note that the thread ID and handle are the same on Unix processes, and that the thread ID and thread handle are different on windows systems.

Errors: On error, the value "0" is returned.

See also: `EndThread` ([1313](#))

75.11.129 BEtoN

Synopsis: Convert Big Endian-ordered integer to Native-ordered integer

Declaration:

```

function BEtoN(const AValue: SmallInt) : SmallInt
function BEtoN(const AValue: Word) : Word
function BEtoN(const AValue: LongInt) : LongInt
function BEtoN(const AValue: DWord) : DWord
function BEtoN(const AValue: Int64) : Int64
function BEtoN(const AValue: QWord) : QWord

```

Visibility: default

Description: `BEtoN` will rearrange the bytes in a Big-Endian number to the native order for the current processor. That is, for a big-endian processor, it will do nothing, and for a little-endian processor, it will invert the order of the bytes.

See also: `LEtoN` ([1352](#)), `NtoBE` ([1360](#)), `NtoLE` ([1360](#))

75.11.130 binStr

Synopsis: Convert integer to string with binary representation.

Declaration:

```

function binStr(Val: LongInt; cnt: Byte) : shortstring
function binStr(Val: Int64; cnt: Byte) : shortstring
function binStr(Val: QWord; cnt: Byte) : shortstring

```

Visibility: default

Description: `BinStr` returns a string with the binary representation of `Value`. The string has at most `cnt` characters. (i.e. only the `cnt` rightmost bits are taken into account) To have a complete representation of any longint-type value, 32 bits are needed, i.e. `cnt=32`

Errors: None.

See also: Str ([1395](#)), Val ([1413](#)), HexStr ([1336](#)), OctStr ([1361](#))

Listing: ./refex/ex82.pp

```
Program example82;

{ Program to demonstrate the BinStr function }

Const Value = 45678;

Var I : longint;

begin
  For I:=8 to 20 do
    Writeln ( BinStr(Value,I):20);
end.
```

75.11.131 BlockRead

Synopsis: Read data from an untyped file into memory

Declaration:

```
procedure BlockRead(var f: File; var Buf; count: Int64;
  var Result: Int64)
procedure BlockRead(var f: File; var Buf; count: LongInt;
  var Result: LongInt)
procedure BlockRead(var f: File; var Buf; count: Cardinal;
  var Result: Cardinal)
procedure BlockRead(var f: File; var Buf; count: Word; var Result: Word)
procedure BlockRead(var f: File; var Buf; count: Word;
  var Result: Integer)
procedure BlockRead(var f: File; var Buf; count: Int64)
```

Visibility: default

Description: Blockread reads `count` or less records from file `F`. A record is a block of bytes with size specified by the Rewrite ([1374](#)) or Reset ([1373](#)) statement. The result is placed in `Buffer`, which must contain enough room for `Count` records. The function cannot read partial records. If `Result` is specified, it contains the number of records actually read. If `Result` isn't specified, and less than `Count` records were read, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: Blockwrite ([1293](#)), Close ([1298](#)), Reset ([1373](#)), Assign ([1270](#))

Listing: ./refex/ex6.pp

```
Program Example6;

{ Program to demonstrate the BlockRead and BlockWrite functions. }

Var Fin, fout : File;
    NumRead, NumWritten : Word;
    Buf : Array[1..2048] of byte;
    Total : Longint;

begin
```

```

Assign (Fin, Paramstr(1));
Assign (Fout, Paramstr(2));
Reset (Fin, 1);
Rewrite (Fout, 1);
Total:=0;
Repeat
  BlockRead (Fin, buf, Sizeof(buf), NumRead);
  BlockWrite (Fout, Buf, NumRead, NumWritten);
  inc (Total, NumWritten);
Until (NumRead=0) or (NumWritten<>NumRead);
Write ('Copied ', Total, ' bytes from file ', paramstr(1));
WriteLn (' to file ', paramstr(2));
close(fin);
close(fout);
end.

```

75.11.132 BlockWrite

Synopsis: Write data from memory to an untyped file

Declaration: `procedure BlockWrite(var f: File; const Buf; Count: Int64; var Result: Int64)`
`procedure BlockWrite(var f: File; const Buf; Count: LongInt; var Result: LongInt)`
`procedure BlockWrite(var f: File; const Buf; Count: Cardinal; var Result: Cardinal)`
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Word)`
`procedure BlockWrite(var f: File; const Buf; Count: Word; var Result: Integer)`
`procedure BlockWrite(var f: File; const Buf; Count: LongInt)`

Visibility: default

Description: `BlockWrite` writes `count` records from `buffer` to the file `F`. A record is a block of bytes with size specified by the `Rewrite` (1374) or `Reset` (1373) statement. If the records couldn't be written to disk, a run-time error is generated. This behavior can be controlled by the `{SI}` switch.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Blockread` (1292), `Close` (1298), `Rewrite` (1374), `Assign` (1270)

75.11.133 Break

Synopsis: Exit current loop construct.

Declaration: `procedure Break`

Visibility: default

Description: `Break` jumps to the statement following the end of the current repetitive statement. The code between the `Break` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is NOT evaluated.

This can be used with `For`, `var{repeat}` and `While` statements.

Note that while this is a procedure, `Break` is a compiler intrinsic (i.e. is treated specially) and hence cannot be redefined.

Errors: None.

See also: `Continue` ([1304](#)), `Exit` ([1319](#))

Listing: `./refex/ex87.pp`

Program `Example87`;

{ Program to demonstrate the Break function. }

```

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I>5 Then
        Break;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I>5 Then
      Break;
    Writeln (i);
  Until I>=10;
  For I:=1 to 10 do
    begin
      If I>5 Then
        Break;
      Writeln (i);
    end;
end.

```

75.11.134 BsfByte

Synopsis: Return the position of the rightmost set bit in an 8-bit value

Declaration: `function BsfByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at position 0 (rightmost position) and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1295](#)), `BsfWord` ([1295](#)), `BsfDWord` ([1294](#)), `BsfQWord` ([1295](#))

75.11.135 BsfDWord

Synopsis: Return the position of the rightmost set bit in a 32-bit value

Declaration: `function BsfDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsfDWord` scans the `DWord` `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1294](#)), `BsfWord` ([1295](#)), `BsrDWord` ([1296](#)), `BsfQWord` ([1295](#))

75.11.136 BsfQWord

Synopsis: Return the position of the rightmost set bit in a 64-bit value

Declaration: `function BsfQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord` `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1294](#)), `BsfWord` ([1295](#)), `BsfDWord` ([1294](#)), `BsrQWord` ([1296](#))

75.11.137 BsfWord

Synopsis: Return the position of the rightmost set bit in a 16-bit value

Declaration: `function BsfWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsfWord` scans the word `AValue`, starting at position 0 (rightmost position) , and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1294](#)), `BsrWord` ([1296](#)), `BsfDWord` ([1294](#)), `BsfQWord` ([1295](#))

75.11.138 BsrByte

Synopsis: Return the position of the leftmost set bit in an 8-bit value

Declaration: `function BsrByte(const AValue: Byte) : Byte`

Visibility: default

Description: `BsfByte` scans the byte `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1294](#)), `BsrWord` ([1296](#)), `BsrDWord` ([1296](#)), `BsrQWord` ([1296](#))

75.11.139 BsrDWord

Synopsis: Return the position of the leftmost set bit in a 32-bit value

Declaration: `function BsrDWord(const AValue: DWord) : Cardinal`

Visibility: default

Description: `BsrDWord` scans the `DWord` `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1295](#)), `BsrWord` ([1296](#)), `BsfDWord` ([1294](#)), `BsrQWord` ([1296](#))

75.11.140 BsrQWord

Synopsis: Return the position of the leftmost set bit in a 64-bit value

Declaration: `function BsrQWord(const AValue: QWord) : Cardinal`

Visibility: default

Description: `BsfQWord` scans the `QWord` `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsfByte` ([1294](#)), `BsfWord` ([1295](#)), `BsfDWord` ([1294](#)), `BsrQWord` ([1296](#))

75.11.141 BsrWord

Synopsis: Return the position of the leftmost set bit in a 16-bit value

Declaration: `function BsrWord(const AValue: Word) : Cardinal`

Visibility: default

Description: `BsrWord` scans the word `AValue`, starting at the leftmost position and working towards position 0, and returns the index of the first set bit. The position is measured from the 0-th, rightmost bit.

When the input is 0, the result is 255 (unsigned equivalent of -1).

See also: `BsrByte` ([1295](#)), `BsfWord` ([1295](#)), `BsrDWord` ([1296](#)), `BsrQWord` ([1296](#))

75.11.142 CaptureBacktrace

Synopsis: Return stack trace

Declaration: `function CaptureBacktrace(skipframes: SizeInt; count: SizeInt; frames: PCodePointer) : SizeInt`

Visibility: default

Description: `CaptureBacktrace` will fill the array pointed to by `frames` with the addresses of a backtrace. It will skip `skipframes` frames, and will write at most `count` addresses. `Frames` must point to enough memory to hold the stacktrace, which is `count*sizeof(codepointer)` bytes.

See also: `Get_pc_addr` ([1335](#)), `get_caller_stackinfo` ([1334](#)), `get_caller_addr` ([1334](#)), `get_caller_frame` ([1334](#))

75.11.143 chdir

Synopsis: Change current working directory.

Declaration: `procedure chdir(const s: shortstring); Overload`
`procedure chdir(const s: RawByteString); Overload`
`procedure chdir(const s: unicodestring); Overload`

Visibility: default

Description: `Chdir` changes the working directory of the process to `S`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Mkdir` ([1357](#)), `Rmdir` ([1375](#))

Listing: `./refex/ex7.pp`

Program `Example7;`

{ Program to demonstrate the ChDir function. }

```
begin
  { $I- }
  ChDir (ParamStr(1));
  if IOResult <> 0 then
    Writeln ('Cannot change to directory : ', paramstr (1));
end.
```

75.11.144 chr

Synopsis: Convert byte value to character value

Declaration: `function chr(b: Byte) : Char`

Visibility: default

Description: `Chr` returns the character which has ASCII value `X`.

Historical note:

Originally, Pascal did not have typecasts and `chr` was a necessary function in order to do certain operations on ASCII values of characters. With the arrival of typecasting a generic approach became possible, making `chr` mostly obsolete. However, `chr` is not considered deprecated and remains in wide use today.

Errors: None.

See also: `Ord` ([1362](#)), `Str` ([1395](#))

Listing: `./refex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the Chr function. }

```
begin
  Write (chr(10),chr(13)); { The same effect as Writeln; }
end.
```

75.11.145 Close

Synopsis: Close a file

Declaration: `procedure Close(var f: File)`
`procedure Close(var t: Text)`

Visibility: default

Description: `Close` flushes the buffer of the file `F` and closes `F`. After a call to `Close`, data can no longer be read from or written to `F`. To reopen a file closed with `Close`, it isn't necessary to assign the file again. A call to `Reset` (1373) or `Rewrite` (1374) is sufficient.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Assign` (1270), `Reset` (1373), `Rewrite` (1374), `Flush` (1326)

Listing: `./refex/ex9.pp`

Program `Example9;`

{ Program to demonstrate the Close function. }

Var `F : text;`

begin

`Assign (f, 'Test.txt');`

ReWrite `(F);`

WriteLn `(F, 'Some text written to Test.txt');`

`close (f); { Flushes contents of buffer to disk,`
closes the file. Omitting this may
cause data NOT to be written to disk. }

end.

75.11.146 CloseThread

Synopsis: Close a thread and free up resources used by the thread

Declaration: `function CloseThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `CloseThread` must be called on any thread started with `BeginThread` (1290). It must be called after the thread has ended (either by exiting the thread function or after calling `EndThread` (1313)).

Errors: If no threadmanager is installed, an exception may be raised or runtime error 232 may occur if no exceptions are used.

See also: `BeginThread` (1290), `EndThread` (1313)

75.11.147 CompareByte

Synopsis: Compare 2 memory buffers byte per byte

Declaration: `function CompareByte(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: CompareByte compares two memory regions buf1,buf2 on a byte-per-byte basis for a total of len bytes.

The function returns one of the following values:

less than 0 if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is smaller in buf1 than the byte at the same position in buf2.

0 if the first len bytes in buf1 and buf2 are equal.

greater than 0 if buf1 and buf2 contain different bytes in the first len bytes, and the first such byte is larger in buf1 than the byte at the same position in buf2.

Errors: None.

See also: CompareChar ([1299](#)), CompareChar0 ([1301](#)), CompareWord ([1302](#)), CompareDWord ([1301](#))

Listing: ./refex/ex99.pp

Program Example99;

{ Program to demonstrate the CompareByte function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize Div 2;

Var

 Buf1,Buf2 : **Array**[1..ArraySize] **of** byte;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

 Write('First ',Len,' positions are ');
 if CompareByte(Buf1,Buf2,Len)<>0 **then**
 Write('NOT ');
 Writeln('equal');
 end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:= I;
 If I<=HalfArraySize **Then**
 Buf2[I]:= I
 else
 Buf2[I]:= HalfArraySize-I;
 end;
 CheckPos(HalfArraySize div 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize+1);
 CheckPos(HalfArraySize + HalfArraySize Div 2);
 end.

75.11.148 CompareChar

Synopsis: ompare 2 memory buffers character per character

Declaration: `function CompareChar(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar` compares two memory regions `buf1`, `buf2` on a character-per-character basis for a total of `len` characters.

The `CompareChar0` variant compares `len` bytes, or until a zero character is found.

The function returns one of the following values:

-If `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is smaller in `buf1` than the character at the same position in `buf2`.

0If the first `len` characters in `buf1` and `buf2` are equal.

1If `buf1` and `buf2` contain different characters in the first `len` positions, and the first such character is larger in `buf1` than the character at the same position in `buf2`.

Errors: None.

See also: `CompareByte` ([1298](#)), `CompareChar0` ([1301](#)), `CompareWord` ([1302](#)), `CompareDWord` ([1301](#))

Listing: `./refex/ex100.pp`

Program `Example100`;

{ Program to demonstrate the CompareChar function. }

Const

`ArraySize = 100;`
`HalfArraySize = ArraySize Div 2;`

Var

`Buf1, Buf2 : Array[1..ArraySize] of char;`
`l : longint;`

Procedure `CheckPos(Len : Longint);`

Begin

`Write('First ', Len, ' characters are ');`
`if CompareChar(Buf1, Buf2, Len) <> 0 then`
`Write('NOT ');`
`Writeln('equal');`
`end;`

Procedure `CheckNullPos(Len : Longint);`

Begin

`Write('First ', Len, ' non-null characters are ');`
`if CompareChar0(Buf1, Buf2, Len) <> 0 then`
`Write('NOT ');`
`Writeln('equal');`
`end;`

begin

`For l:=1 to ArraySize do`
`begin`
`Buf1[l]:=chr(l);`
`If l<=HalfArraySize Then`
`Buf2[l]:=chr(l)`

```

    else
        Buf2[i] := chr(HalfArraySize - 1);
    end;
    CheckPos(HalfArraySize div 2);
    CheckPos(HalfArraySize);
    CheckPos(HalfArraySize + 1);
    CheckPos(HalfArraySize + HalfArraySize Div 2);
    For i := 1 to 4 do
        begin
            buf1[Random(ArraySize) + 1] := Chr(0);
            buf2[Random(ArraySize) + 1] := Chr(0);
        end;
    Randomize;
    CheckNullPos(HalfArraySize div 2);
    CheckNullPos(HalfArraySize);
    CheckNullPos(HalfArraySize + 1);
    CheckNullPos(HalfArraySize + HalfArraySize Div 2);
end.

```

75.11.149 CompareChar0

Synopsis: Compare two buffers character by character till a null-character is reached.

Declaration: `function CompareChar0(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareChar0` compares 2 buffers `buf1` and `buf2` for a maximum length of `len` or till a null character is reached in either buffer. The result depends on the contents of the buffers:

- < 0 If `buf1` contains a character less than the corresponding character in `buf2`.
- 0 If both buffers are equal
- > 0 If `buf1` contains a character greater than the corresponding character in `buf2`.

Errors: None.

See also: `CompareByte` ([1298](#)), `CompareChar` ([1299](#)), `CompareDWord` ([1301](#)), `CompareWord` ([1302](#))

75.11.150 CompareDWord

Synopsis: Compare 2 memory buffers DWord per DWord

Declaration: `function CompareDWord(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: `CompareDWord` compares two memory regions `buf1`, `buf2` on a DWord-per-DWord basis for a total of `len` DWords. (A DWord is 4 bytes).

The function returns one of the following values:

- 1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is smaller in `buf1` than the DWord at the same position in `buf2`.
- 0 if the first `len` DWords in `buf1` and `buf2` are equal.
- 1 if `buf1` and `buf2` contain different DWords in the first `len` DWords, and the first such DWord is larger in `buf1` than the DWord at the same position in `buf2`.

Errors: None.

See also: [CompareChar \(1299\)](#), [CompareByte \(1298\)](#), [CompareWord \(1302\)](#)

Listing: ./refex/ex101.pp

Program Example101;

{ Program to demonstrate the CompareDWord function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize **Div** 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** Dword;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' DWords are ');
 if CompareDWord(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal');
 end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:=I;
 If I<=HalfArraySize **Then**
 Buf2[I]:=I
 else
 Buf2[I]:= HalfArraySize-I;
 end;
 CheckPos(HalfArraySize **div** 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize+1);
 CheckPos(HalfArraySize + HalfArraySize **Div** 2);
 end.

75.11.151 CompareWord

Synopsis: Compare 2 memory buffers word per word

Declaration: `function CompareWord(const buf1; const buf2; len: SizeInt) : SizeInt`

Visibility: default

Description: CompareWord compares two memory regions buf1, buf2 on a Word-per-Word basis for a total of len Words. (A Word is 2 bytes).

The function returns one of the following values:

- 1 if buf1 and buf2 contain different Words in the first len Words, and the first such Word is smaller in buf1 than the Word at the same position in buf2.

0if the first len Words in buf1 and buf2 are equal.

1if buf1 and buf2 contain different Words in the first len Words, and the first such Word is larger in buf1 than the Word at the same position in buf2.

Errors: None.

See also: CompareChar ([1299](#)), CompareByte ([1298](#)), CompareDWord ([1301](#))

Listing: ./refex/ex102.pp

Program Example102;

{ Program to demonstrate the CompareWord function. }

Const

 ArraySize = 100;
 HalfArraySize = ArraySize **Div** 2;

Var

 Buf1, Buf2 : **Array**[1..ArraySize] **of** Word;
 I : longint;

Procedure CheckPos(Len : Longint);

Begin

Write('First ', Len, ' words are ');
 if CompareWord(Buf1, Buf2, Len) <> 0 **then**
 Write('NOT ');
 Writeln('equal ');
end;

begin

For I:=1 **to** ArraySize **do**
 begin
 Buf1[I]:= I;
 If I<=HalfArraySize **Then**
 Buf2[I]:= I
 else
 Buf2[I]:= HalfArraySize-I;
 end;
 CheckPos(HalfArraySize **div** 2);
 CheckPos(HalfArraySize);
 CheckPos(HalfArraySize+1);
 CheckPos(HalfArraySize + HalfArraySize **Div** 2);
 end.

75.11.152 Concat

Synopsis: Append one string to another.

Declaration: function Concat(const S1: string; const S2: string; const S3: string;
 const Sn: string) : string

Visibility: default

Description: Concat concatenates the strings S1,S2 etc. to one long string. The resulting string is truncated at a length of 255 bytes. The same operation can be performed with the + operation.

Errors: None.

See also: Copy ([1194](#)), Delete ([1308](#)), Insert ([1345](#)), Pos ([1365](#)), Length ([1194](#))

Listing: ./refex/ex10.pp

Program Example10;

```
{ Program to demonstrate the Concat function. }
Var
  S : String;

begin
  S:=Concat('This can be done', ' Easier ', 'with the + operator !');
end.
```

75.11.153 Continue

Synopsis: Continue with next loop cycle.

Declaration: `procedure Continue`

Visibility: default

Description: `Continue` jumps to the end of the current repetitive statement. The code between the `Continue` call and the end of the repetitive statement is skipped. The condition of the repetitive statement is then checked again.

This can be used with `For`, `repeat` and `While` statements.

Note that while this is a procedure, `Continue` is a compiler intrinsic (i.e. is treated specially) and hence cannot be redefined.

Errors: None.

See also: Break ([1293](#)), Exit ([1319](#))

Listing: ./refex/ex86.pp

Program Example86;

```
{ Program to demonstrate the Continue function. }

Var I : longint;

begin
  I:=0;
  While I<10 Do
    begin
      Inc(I);
      If I<5 Then
        Continue;
      Writeln (i);
    end;
  I:=0;
  Repeat
    Inc(I);
    If I<5 Then
      Continue;
```

```

    Writeln (i);
  Until l >= 10;
  For l := 1 to 10 do
    begin
      If l < 5 Then
        Continue;
      Writeln (i);
    end;
  end.

```

75.11.154 CopyArray

Synopsis: Copy managed-type elements in array

Declaration: `procedure CopyArray(dest: Pointer; source: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `CopyArray` copies `count` elements containing managed types from the array pointed to by `source` to the array pointed to by `dest`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variables are assigned to each other.

See also: `InitializeArray` (1344), `FinalizeArray` (1324), `DynArraySize` (1313), `DynArrayClear` (1311), `DynArrayDim` (1312), `DynArrayBounds` (1311)

75.11.155 cos

Synopsis: Calculate cosine of angle

Declaration: `function cos(d: ValReal) : ValReal`

Visibility: default

Description: `Cos` returns the cosine of `X`, where `X` is an angle, in radians. If the absolute value of the argument is larger than $2\hat{6}3$, then the result is undefined.

Errors: None.

See also: `Arctan` (1269), `Sin` (1391)

Listing: `./refex/ex12.pp`

Program Example12;

```
{ Program to demonstrate the Cos function. }
```

```
Var R : Real;
```

```
begin
  R:=Cos(Pi);      { R:=-1 }
  R:=Cos(Pi/2);    { R:=0 }
  R:=Cos(0);       { R:=1 }
end.
```

75.11.156 Cseg

Synopsis: Return code segment

Declaration: `function Cseg : Word`

Visibility: default

Description: `CSeg` returns the Code segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `Dseg` ([1310](#)), `Seg` ([1383](#)), `Ofs` ([1362](#)), `Ptr` ([1367](#))

Listing: `./refex/ex13.pp`

Program `Example13;`

{ Program to demonstrate the CSeg function. }

var `W : word;`

begin

`W:=CSeg; {W:=0, provided for compatibility ,`
FPC is 32 bit.}

end.

75.11.157 Dec

Synopsis: Decrease value of variable

Declaration: `procedure Dec(var X: TOrdinal)`
`procedure Dec(var X: TOrdinal; Decrement: TOrdinal)`

Visibility: default

Description: `Dec` decreases the value of `X` with `Decrement`. If `Decrement` isn't specified, then 1 is taken as a default.

Errors: A range check can occur, or an underflow error, if an attempt is made to decrease `X` below its minimum value.

See also: `Inc` ([1339](#))

Listing: `./refex/ex14.pp`

Program `Example14;`

{ Program to demonstrate the Dec function. }

Var

`I : Integer;`
`L : Longint;`
`W : Word;`
`B : Byte;`
`Si : ShortInt;`

begin

```

I:=1;
L:=2;
W:=3;
B:=4;
Si:=5;
Dec (i); { i:=0 }
Dec (L,2); { L:=0 }
Dec (W,2); { W:=1 }
Dec (B,-2); { B:=6 }
Dec (Si,0); { Si:=5 }
end.

```

75.11.158 DefaultAnsi2UnicodeMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultAnsi2UnicodeMove(source: PChar; cp: TSystemCodePage;
var dest: unicodestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2UnicodeMove` is the standard callback used for the widestring manager when an ansistring must be converted to a unicodestring. It simply copies over all characters from the ansistring to the unicodestring, no conversion whatsoever is performed.

75.11.159 DefaultAnsi2WideMove

Synopsis: Standard implementation of Ansi to Widestring conversion routine

Declaration: `procedure DefaultAnsi2WideMove(source: PChar; cp: TSystemCodePage;
var dest: widestring; len: SizeInt)`

Visibility: default

Description: `DefaultAnsi2WideMove` simply copies each character of the null-terminated ansi-string `Source` to the corresponding `WideChar` in `Dest`. At most `Len` characters will be copied.

Errors: None.

See also: `DefaultUnicode2AnsiMove` ([1307](#))

75.11.160 DefaultUnicode2AnsiMove

Synopsis: Standard widestring manager callback

Declaration: `procedure DefaultUnicode2AnsiMove(source: PUnicodeChar;
var dest: RawByteString;
cp: TSystemCodePage; len: SizeInt)`

Visibility: default

Description: `DefaultUnicode2AnsiMove` is the standard callback used for the widestring manager when a unicode string must be converted to an ansistring. It replaces all words with value < 256 with their value as ASCII code.

Errors: None.

See also: `WidestringManager` ([1265](#))

75.11.161 Delete

Synopsis: Delete part of a string.

Declaration: `procedure Delete(var s: shortstring; index: SizeInt; count: SizeInt)`
`procedure Delete(var S: RawByteString; Index: SizeInt; Size: SizeInt)`
`procedure Delete(var S: UnicodeString; Index: SizeInt; Size: SizeInt)`
`procedure Delete(var S: WideString; Index: SizeInt; Size: SizeInt)`

Visibility: default

Description: `Delete` removes `Count` characters from string `S`, starting at position `Index`. All characters after the deleted characters are shifted `Count` positions to the left, and the length of the string is adjusted.

Errors: `Shortstring` variant's third parameter is called `Count`, in other overloaded variants it is called `Index`

See also: `Copy` ([1194](#)), `Pos` ([1365](#)), `Insert` ([1345](#))

Listing: `./refex/ex15.pp`

Program `Example15;`

{ Program to demonstrate the Delete function. }

Var

`S : String;`

begin

`S := 'This is not easy !';`

`Delete (S,9,4); { S := 'This is easy !' }`

end.

75.11.162 Dispose

Synopsis: Free dynamically allocated memory

Declaration: `procedure Dispose(P: Pointer)`
`procedure Dispose(P: TypedPointer; Des: TProcedure)`

Visibility: default

Description: The first form `Dispose` releases the memory allocated with a call to `New` ([1360](#)). The pointer `P` must be typed. The released memory is returned to the heap.

The second form of `Dispose` accepts as a first parameter a pointer to an object type, and as a second parameter the name of a destructor of this object. The destructor will be called, and the memory allocated for the object will be freed.

Errors: An runtime error will occur if the pointer doesn't point to a location in the heap.

See also: `New` ([1360](#)), `Getmem` ([1331](#)), `Freemem` ([1328](#))

Listing: `./refex/ex16.pp`

Program `Example16;`

{ Program to demonstrate the Dispose and New functions. }

Type `SS = String[20];`

```

    AnObj = Object
      I : integer;
      Constructor Init;
      Destructor Done;
    end;

Var
  P : ^SS;
  T : ^AnObj;

Constructor Anobj.Init;

begin
  WriteIn ('Initializing an instance of AnObj !');
end;

Destructor AnObj.Done;

begin
  WriteIn ('Destroying an instance of AnObj !');
end;

begin
  New (P);
  P^:= 'Hello , World !';
  Dispose (P);
  { P is undefined from here on !}
  New(T, Init);
  T^.i:=0;
  Dispose (T, Done);
end.

```

75.11.163 divide(variant,variant):variant

Synopsis: Implement division (/) operation on variants.

Declaration: `operator /(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the division / operation is delegated to the variant manager with operation `opDivide`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `*(variant, variant): variant` ([1194](#))

75.11.164 DoneCriticalSection

Synopsis: Clean up a critical section.

Declaration: `procedure DoneCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `DoneCriticalSection` cleans up the critical section CS. After a call to `DoneCriticalSection`, the critical section can no longer be used with `EnterCriticalSection` (1313) or `LeaveCriticalSection` (1351), unless it is again initialized with `InitCriticalSection` (1344)

See also: `InitCriticalSection` (1344), `EnterCriticalSection` (1313), `LeaveCriticalSection` (1351)

75.11.165 DoneThread

Synopsis: End the current thread

Declaration: `procedure DoneThread`

Visibility: default

Description: `DoneThread` should be used to end the current thread. It performs the necessary housekeeping before actually ending the thread. Using the operating system calls to end the thread may result in data corruption or memory leaks.

See also: `BeginThread` (1290)

75.11.166 Dseg

Synopsis: Return data segment

Declaration: `function Dseg : Word`

Visibility: default

Description: `DSeg` returns the data segment register. In Free Pascal, it returns always a zero, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `CSeg` (1306), `Seg` (1383), `Ofs` (1362), `Ptr` (1367)

Listing: `./refex/ex17.pp`

Program Example17;

{ Program to demonstrate the DSeg function. }

Var

W : Word;

begin

W:=**DSeg**; *{W:=0, This function is provided for compatibility ,
FPC is a 32 bit compiler.}*

end.

75.11.167 DumpExceptionBackTrace

Synopsis: Create backtrace

Declaration: `procedure DumpExceptionBackTrace(var f: text)`

Visibility: default

Description: `DumpExceptionBackTrace` writes a backtrace of the current exception to the file `f`. If no exception is currently being raised, nothing is written. As much frames as available are written. If debug info is available, then file names and line numbers will be written as well.

Errors: No check is done to see whether `f` is opened for writing.

See also: `dump_stack` ([1311](#))

75.11.168 Dump_Stack

Synopsis: Dump stack to the given text file.

Declaration: `procedure Dump_Stack(var f: text; fp: pointer; addr: CodePointer)`
`procedure Dump_Stack(var f: text; skipframes: LongInt)`

Visibility: default

Description: `Dump_Stack` prints a stack dump to the file `f`, with base frame pointer `bp`

Errors: The file `f` must be opened for writing or an error will occur.

See also: `get_caller_addr` ([1334](#)), `get_caller_frame` ([1334](#)), `get_frame` ([1335](#))

75.11.169 DynArrayBounds

Synopsis: Return the bounds of the dynamic array

Declaration: `function DynArrayBounds(a: Pointer; typeInfo: Pointer) : TBoundArray`

Visibility: default

Description: `DynArrayBounds` returns the bounds of all the dimensions of the dynamic array `a` with type information `typeInfo`.

The result is an array (zero-based) with the maximum valid index for each dimension in the array: the lower bound is not present in the result, it is always zero.

See also: `InitializeArray` ([1344](#)), `FinalizeArray` ([1324](#)), `CopyArray` ([1305](#)), `DynArraySize` ([1313](#)), `DynArrayClear` ([1311](#)), `DynArrayDim` ([1312](#))

75.11.170 DynArrayClear

Synopsis: Clear dynamical array

Declaration: `procedure DynArrayClear(var a: Pointer; typeInfo: Pointer)`

Visibility: default

Description: `DynArrayClear` clears the array (`a`) using its type info (`typeInfo`). It is equal to setting the length to zero.

See also: `InitializeArray` ([1344](#)), `FinalizeArray` ([1324](#)), `CopyArray` ([1305](#)), `DynArraySize` ([1313](#)), `DynArrayDim` ([1312](#)), `DynArrayBounds` ([1311](#))

75.11.171 DynArrayDim

Synopsis: Return the number of dimensions in a dynamic array

Declaration: `function DynArrayDim(typeInfo: Pointer) : Integer`

Visibility: default

Description: `DynArrayDim` returns the number of dimensions in a dynamic array, using the type information (`typeInfo`) of the array.

See also: [InitializeArray \(1344\)](#), [FinalizeArray \(1324\)](#), [CopyArray \(1305\)](#), [DynArraySize \(1313\)](#), [DynArrayClear \(1311\)](#), [DynArrayBounds \(1311\)](#)

75.11.172 DynArrayIndex

Synopsis: Return pointer to indicated element

Declaration: `function DynArrayIndex(a: Pointer; const indices: Array of SizeInt; typeInfo: Pointer) : Pointer`

Visibility: default

Description: `DynArrayIndex` returns a pointer to the element indicated by `indices` in dynamic array `a` with type information `typeInfo`. The length of `indices` must equal the number of dimensions of the array (as returned by [DynArrayDim \(1312\)](#)).

Errors: No bounds checking is performed, it is therefor possible to get an access violation if one of the indexes is out of range.

See also: [InitializeArray \(1344\)](#), [FinalizeArray \(1324\)](#), [CopyArray \(1305\)](#), [DynArraySize \(1313\)](#), [DynArrayClear \(1311\)](#), [DynArrayBounds \(1311\)](#), [DynArrayDim \(1312\)](#), [IsDynArrayRectangular \(1350\)](#)

75.11.173 DynArraySetLength

Synopsis: Set the length of a dynamic array

Declaration: `procedure DynArraySetLength(var a: Pointer; typeInfo: Pointer; dimCnt: SizeInt; lengthVec: PSizeInt)`

Visibility: default

Description: `DynArraySetLength` sets the length of the dynamical array `a` to the first `dimCnt` lengths specified in the array `lengthVec`. The dynamical array type is described in `typeInfo` which points to a record of type [TDynArrayTypeInfo \(1237\)](#)

It should never be necessary to call this function directly, the standard [SetLength \(1194\)](#) function should be used instead.

Errors: If an invalid pointer is specified, an error may occur.

See also: [SetLength \(1194\)](#), [tdynarraytypeinfo \(1237\)](#)

75.11.174 DynArraySize

Synopsis: Return length of dynamic array

Declaration: `function DynArraySize(a: pointer) : tdynarrayindex`

Visibility: default

Description: `DynArraySize` gets the number of elements in the array (a) the result is equal to `Length` (1194) for dynamic arrays.

See also: `InitializeArray` (1344), `FinalizeArray` (1324), `CopyArray` (1305), `DynArrayClear` (1311), `DynArrayDim` (1312), `DynArrayBounds` (1311)

75.11.175 EmptyMethod

Synopsis: Empty method alias

Declaration: `procedure EmptyMethod`

Visibility: default

Description: `EmptyMethod` is meant for the compiler only. It should not be used directly.

75.11.176 EndThread

Synopsis: End the current thread.

Declaration: `procedure EndThread(ExitCode: DWord)`
`procedure EndThread`

Visibility: default

Description: `EndThread` ends the current thread. If `ExitCode` is supplied, it is returned as the exit code for the thread to a function waiting for the thread to terminate (`WaitForThreadTerminate` (1415)). If it is omitted, zero is used.

This function does not return.

See also: `WaitForThreadTerminate` (1415), `BeginThread` (1290)

75.11.177 EnterCriticalSection

Synopsis: Enter a critical section

Declaration: `procedure EnterCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `EnterCriticalSection` will suspend the current thread if another thread has currently entered the critical section. When the other thread has left the critical section (through `LeaveCriticalSection` (1351)), the current thread resumes execution. The result is that only 1 thread is executing code which is protected by a `EnterCriticalSection` and `LeaveCriticalSection` pair.

The critical section must have been initialized with `InitCriticalSection` (1344) prior to a call to `EnterCriticalSection`.

A call to `EnterCriticalSection` must always be matched by a call to `LeaveCriticalSection` (1351). To avoid problems, it is best to include the code to be execute in a `try . . . finally` block, as follows:

```

EnterCriticalSection(Section);
Try
    // Code to be protected goes here.
Finally
    LeaveCriticalSection(Section);
end;

```

For performance reasons it is best to limit the code between the entering and leaving of a critical section as short as possible.

See also: [InitCriticalSection \(1344\)](#), [DoneCriticalSection \(1309\)](#), [LeaveCriticalSection \(1351\)](#)

75.11.178 EnumResourceLanguages

Synopsis: Enumerate available languages for a resource of given type and name

Declaration: `function EnumResourceLanguages(ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar; ResourceName: PChar;
EnumFunc: EnumResLangProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceLanguages` enumerates the available languages for a resource of given `ResourceName` and type `ResourceType` in the module `ModuleHandle`. For each language available, it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource `ResourceName`, the language ID, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: [EnumResourceTypes \(1315\)](#), [EnumResourceNames \(1314\)](#), [EnumResourceLanguages \(1314\)](#)

75.11.179 EnumResourceNames

Synopsis: Enumerate available resource names for a specified resource type

Declaration: `function EnumResourceNames(ModuleHandle: TFPResourceHMODULE;
ResourceType: PChar;
EnumFunc: EnumResNameProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceNames` enumerates the names of all resources of type `ResourceType` in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource `ResourceType`, the name of the resource, and `lParam`. It returns `False` if no resources are available for the specified resource type and module, or `True` if there are resources available.

Errors: None.

See also: [EnumResourceTypes \(1315\)](#), [EnumResourceLanguages \(1314\)](#)

75.11.180 EnumResourceTypes

Synopsis: Enumerate available resource types

Declaration: `function EnumResourceTypes (ModuleHandle: TFPResourceHMODULE;
EnumFunc: EnumResTypeProc; lParam: PtrInt)
: LongBool`

Visibility: default

Description: `EnumResourceTypes` enumerates the types of all resources in the module `ModuleHandle`. For each resource available it calls `EnumFunc` and passes it `ModuleHandle`, the type of the resource, and `lParam`. It returns `False` if no resources are available for the specified module, or `True` if there are resources available.

Errors: None.

See also: `EnumResourceNames` ([1314](#)), `EnumResourceLanguages` ([1314](#))

75.11.181 EOF

Synopsis: Check for end of file

Declaration: `function EOF (var f: File) : Boolean
function EOF (var t: Text) : Boolean
function EOF : Boolean`

Visibility: default

Description: `Eof` returns `True` if the file-pointer has reached the end of the file, or if the file is empty. In all other cases `Eof` returns `False`. If no file `F` is specified, standard input is assumed.

Note that calling this function may cause your program to wait: to determine whether you are at EOF, it is necessary to read data. If the file descriptor is not a real file (for instance for standard input or sockets), then this call may seem to hang the program while it is waiting for data to appear or for the file descriptor to be closed.

Errors: Depending on the state of the `{ $I }` switch, a runtime error can be generated if there is an error. In the `{ $I- }` state, use `IOResult` to check for errors.

See also: `Eoln` ([1316](#)), `Assign` ([1270](#)), `Reset` ([1373](#)), `Rewrite` ([1374](#))

Listing: `./refex/ex18.pp`

Program `Example18;`

{ Program to demonstrate the Eof function. }

Var `T1,T2 : text;
C : Char;`

begin
 { Set file to read from. Empty means from standard input. }
 `assign (t1,paramstr(1));`
 `reset (t1);`
 { Set file to write to. Empty means to standard output. }
 `assign (t2,paramstr(2));`
 `rewrite (t2);`
 `While not eof(t1) do`

```

begin
  read (t1,C);
  write (t2,C);
end;
Close (t1);
Close (t2);
end.

```

75.11.182 EOLn

Synopsis: Check for end of line

Declaration: `function EOLn(var t: Text) : Boolean`
`function EOLn : Boolean`

Visibility: default

Description: `EOLn` returns `True` if the file pointer has reached the end of a line, which is demarcated by a line-feed character (ASCII value 10), or if the end of the file is reached. In all other cases `EOLn` returns `False`. If no file `F` is specified, standard input is assumed. It can only be used on files of type `Text`.

Errors: None.

See also: `Eof` ([1315](#)), `Assign` ([1270](#)), `Reset` ([1373](#)), `Rewrite` ([1374](#))

Listing: `./refex/ex19.pp`

Program `Example19`;

{ Program to demonstrate the Eoln function. }

```

begin
  { This program waits for keyboard input. }
  { It will print True when an empty line is put in ,
    and false when you type a non-empty line .
    It will only stop when you press enter. }
  While not Eoln do
    Writeln (eoln);
end.

```

75.11.183 equal(variant,variant):Boolean

Synopsis: Implement = (equality) operation on variants.

Declaration: `operator =(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the equality (=) operation is delegated to the variant manager with operation `opcmpeq`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` ([1194](#))

75.11.184 Erase

Synopsis: Delete a file from disk

Declaration: `procedure Erase(var f: File)`
`procedure Erase(var t: Text)`

Visibility: default

Description: `Erase` removes an unopened file from disk. The file should be assigned with `Assign`, but not opened with `Reset` or `Rewrite`

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Assign` ([1270](#))

Listing: `./refex/ex20.pp`

Program `Example20;`

{ Program to demonstrate the Erase function. }

Var `F : Text;`

begin

{ Create a file with a line of text in it }

`Assign (F, 'test.txt');`

`Rewrite (F);`

`Writeln (F, 'Try and find this when I 'm finished !');`

`close (f);`

{ Now remove the file }

`Erase (f);`

end.

75.11.185 Error

Synopsis: Generate run-time error

Declaration: `procedure Error(RunTimeError: TRuntimeError)`

Visibility: default

Description: `Error` generates a run-time error with an exit code corresponding to `RunTimeError`. This function is implemented for Delphi compatibility, and is not used by the Free Pascal Run-Time Library.

See also: `RunError` ([1379](#)), `Halt` ([1336](#))

75.11.186 Exclude

Synopsis: Exclude element from a set if it is present.

Declaration: `procedure Exclude(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Exclude` removes `E` from the set `S` if it is included in the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S-[E];
Exclude(S,E);
```

Errors: If the type of the element *E* is not equal to the base type of the set *S*, the compiler will generate an error.

See also: Include ([1340](#))

Listing: ./refex/ex111.pp

```
program Example111;

{ Program to demonstrate the Include/Exclude functions }

Type
TEnumA = (aOne,aTwo,aThree);
TEnumAs = Set of TEnumA;

Var
SA : TEnumAs;

Procedure PrintSet(S : TEnumAs);

var
B : Boolean;

procedure DoEl(A : TEnumA; Desc : String);

begin
  If A in S then
    begin
      If B then
        Write( ' , ' );
        B:=True;
        Write( Desc );
      end;
    end;

begin
  Write( ' [ ' );
  B:=False;
  DoEl(aOne, 'aOne');
  DoEl(aTwo, 'aTwo');
  DoEl(aThree, 'aThree');
  Writeln( ' ] ' );
end;

begin
  SA:=[];
  Include(SA,aOne);
  PrintSet(SA);
  Include(SA,aThree);
  PrintSet(SA);
  Exclude(SA,aOne);
  PrintSet(SA);
  Exclude(SA,aTwo);
  PrintSet(SA);
  Exclude(SA,aThree);
```

```

    PrintSet(SA);
end.

```

75.11.187 Exit

Synopsis: Exit current subroutine.

Declaration: `procedure Exit(const X: TAnyType)`
`procedure Exit`

Visibility: default

Description: `Exit` exits the current subroutine, and returns control to the calling routine. If invoked in the main program routine, `exit` stops the program. The optional argument `X` allows to specify a return value, in the case `Exit` is invoked in a function. The function result will then be equal to `X`.

In Object Pascal or Delphi modes, if the `Exit` statement is surrounded by one or more `Try .. Finally` constructs, the `Finally` blocks are executed, which means that if the finally blocks are used to free resources, then these resources will also be freed when `Exit` is called.

Errors: None.

See also: [Halt \(1336\)](#)

Listing: `./refex/ex21.pp`

Program Example21;

{ Program to demonstrate the Exit function. }

Procedure DoAnExit (Yes : Boolean);

{ This procedure demonstrates the normal Exit }

begin

Writeln ('Hello from DoAnExit !');

If Yes **then**

begin

Writeln ('Bailing out early.');

exit;

end;

Writeln ('Continuing to the end.');

end;

Function Positive (Which : Integer) : Boolean;

*{ This function demonstrates the extra FPC feature of Exit :
 You can specify a return value for the function }*

begin

if Which > 0 **then**

exit (True)

else

exit (False);

end;

begin

{ This call will go to the end }

```

DoAnExit (False);
{ This call will bail out early }
DoAnExit (True);
if Positive (-1) then
  Writeln ('The compiler is nuts, -1 is not positive.')
else
  Writeln ('The compiler is not so bad, -1 seems to be negative.');
```

end.

75.11.188 exp

Synopsis: Exponentiate

Declaration: `function exp(d: ValReal) : ValReal`

Visibility: default

Description: `Exp` returns the exponent of `X`, i.e. the number `e` to the power `X`.

Errors: None.

See also: `Ln` ([1352](#))

Listing: `./refex/ex22.pp`

Program `Example22;`

```

{ Program to demonstrate the Exp function. }

begin
  Writeln (Exp(1):8:2); { Should print 2.72 }
end.
```

75.11.189 FilePos

Synopsis: Get position in file

Declaration: `function FilePos(var f: File) : Int64`

Visibility: default

Description: `Filepos` returns the current record position of the file-pointer in file `F`. It cannot be invoked with a file of type `Text`. A compiler error will be generated if this is attempted. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1373](#)) isn't specified.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filesize` ([1321](#))

Listing: `./refex/ex23.pp`

Program `Example23;`

```

{ Program to demonstrate the FilePos function. }

Var F : File of Longint;
```

```

    L,FP : longint;

begin
  { Fill a file with data :
    Each position contains the position ! }
  Assign (F, 'test.tmp');
  Rewrite (F);
  For L:=0 to 100 do
    begin
      FP:=FilePos (F);
      Write (F,FP);
    end;
  Close (F);
  Reset (F);
  { If all goes well, nothing is displayed here. }
  While not (Eof(F)) do
    begin
      FP:=FilePos (F);
      Read (F,L);
      if L<>FP then
        WriteLn ('Something wrong: Got ',L,' on pos ',FP);
    end;
  Close (F);
  Erase (f);
end.

```

75.11.190 FileSize

Synopsis: Size of file

Declaration: `function FileSize(var f: File) : Int64`

Visibility: default

Description: `Filesize` returns the total number of records in file `F`. It cannot be invoked with a file of type `Text`. (under Linux and Unix, this also means that it cannot be invoked on pipes). If `F` is empty, 0 is returned. Untyped files have a default record size of 128, if the second parameter to `Reset` ([1373](#)) isn't specified.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Filepos` ([1320](#))

Listing: `./refex/ex24.pp`

Program `Example24`;

```

{ Program to demonstrate the FileSize function. }

```

```

Var F : File Of byte;
    L : File Of Longint;

```

```

begin
  Assign (F,paramstr(1));
  Reset (F);
  WriteLn ('File size in bytes : ',FileSize(F));

```

```

Close (F);
Assign (L, paramstr (1));
Reset (L);
WriteLn ('File size in Longints : ',FileSize(L));
Close (f);
end.

```

75.11.191 FillByte

Synopsis: Fill memory region with 8-bit pattern

Declaration: `procedure FillByte(var x; count: SizeInt; value: Byte)`

Visibility: default

Description: `FillByte` fills the memory starting at `X` with `Count` bytes with value equal to `Value`. This is useful for quickly zeroing out a memory location. When the size of the memory location to be filled out is a multiple of 2 bytes, it is better to use `FillWord` ([1324](#)), and if it is a multiple of 4 bytes it is better to use `FillDWord` ([1323](#)), these routines are optimized for their respective sizes.

Errors: No checking on the size of `X` is done.

See also: `FillChar` ([1322](#)), `FillDWord` ([1323](#)), `FillWord` ([1324](#)), `Move` ([1358](#))

Listing: `./refex/ex103.pp`

Program `Example103`;

{ Program to demonstrate the FillByte function. }

```

Var S : String[10];
    I : Byte;

begin
  For i:=10 downto 0 do
    begin
      { Fill S with i bytes }
      FillByte (S,SizeOf(S),32);
      { Set Length }
      SetLength(S,I);
      WriteLn (s,'*');
    end;
end.

```

75.11.192 FillChar

Synopsis: Fill memory region with certain character

Declaration: `procedure FillChar(var x; count: SizeInt; Value: Byte)`
`procedure FillChar(var x; count: SizeInt; Value: Boolean)`
`procedure FillChar(var x; count: SizeInt; Value: Char)`

Visibility: default

Description: `Fillchar` fills the memory starting at `X` with `Count` bytes or characters with value equal to `Value`.

Errors: No checking on the size of X is done.

See also: Fillword ([1324](#)), Move ([1358](#)), FillByte ([1322](#)), FillDWord ([1323](#))

Listing: ./refex/ex25.pp

Program Example25;

{ Program to demonstrate the FillChar function. }

```

Var S : String[10];
    I : Byte;
begin
    For i:=10 downto 0 do
        begin
            { Fill S with i spaces }
            FillChar (S, SizeOf(S), ' ');
            { Set Length }
            SetLength(S, I);
            Writeln (s, '*');
        end;
    end.

```

75.11.193 FillDWord

Synopsis: Fill memory region with 32-bit pattern

Declaration: `procedure FillDWord(var x; count: SizeInt; value: DWord)`

Visibility: default

Description: Fillword fills the memory starting at X with Count DWords with value equal to Value. A DWord is 4 bytes in size.

Errors: No checking on the size of X is done.

See also: FillByte ([1322](#)), Fillchar ([1322](#)), Fillword ([1324](#)), Move ([1358](#))

Listing: ./refex/ex104.pp

Program Example104;

{ Program to demonstrate the FillDWord function. }

```

Const
    ArraySize = 1000;

Var
    S : Array [1..ArraySize] of DWord;
    I : longint;

begin
    FillDWord(S, ArraySize, 0);
    For I:=1 to ArraySize do
        If S[I]<>0 then
            Writeln('Position ', I, ' not zeroed out');
    end.

```

75.11.194 FillQWord

Synopsis: Fill memory range with QWord (64-bit) values

Declaration: `procedure FillQWord(var x; count: SizeInt; value: QWord)`

Visibility: default

Description: `FillQWord` fills the memory location of `x` with `Count` times `value`. The size of the filled memory location is therefor `8*count` bytes.

Errors: No checks are made to see if `X` actually has a minimum size of `(Count*8)` bytes. Therefor, other variables can be overwritten or the memory may be out of the accessible memory for the program. In the latter case a run-error or exception may be triggered.

See also: `FillChar` ([1322](#)), `FillWord` ([1324](#))

75.11.195 FillWord

Synopsis: Fill memory region with 16-bit pattern

Declaration: `procedure FillWord(var x; count: SizeInt; Value: Word)`

Visibility: default

Description: `Fillword` fills the memory starting at `X` with `Count` words with value equal to `Value`. A word is 2 bytes in size.

Errors: No checking on the size of `X` is done.

See also: `Fillchar` ([1322](#)), `Move` ([1358](#))

Listing: `./refex/ex76.pp`

Program `Example76;`

{ Program to demonstrate the FillWord function. }

Var `W : Array[1..100] of Word;`

begin

{ Quick initialization of array W }
`FillWord(W,100,0);`

end.

75.11.196 FinalizeArray

Synopsis: Finalize managed-type elements in array

Declaration: `procedure FinalizeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `FinalizeArray` dereferences and clears managed types in the array pointed to by `p`. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable containing managed types goes out of scope.

See also: `InitializeArray` ([1344](#)), `CopyArray` ([1305](#)), `DynArraySize` ([1313](#)), `DynArrayClear` ([1311](#)), `DynArrayDim` ([1312](#)), `DynArrayBounds` ([1311](#))

75.11.197 FindResource

Synopsis: Locate a resource and return a handle to it.

Declaration:

```
function FindResource(ModuleHandle: TFPResourceHMODULE;
                    ResourceName: PChar; ResourceType: PChar)
                    : TFPResourceHandle
function FindResource(ModuleHandle: TFPResourceHMODULE;
                    const ResourceName: AnsiString;
                    const ResourceType: AnsiString) : TFPResourceHandle
```

Visibility: default

Description: `FindResource` searches for a resource with name `ResourceName` and of type `ResourceType` in the executable or library identified by `ModuleHandle`. It returns a `TResourceHandle` which can be used to load the resource with `LoadResource` (1354).

Errors: None. In case the resource was not found, 0 is returned.

See also: `FreeResource` (1329), `LoadResource` (1354), `SizeofResource` (1392), `LockResource` (1354), `UnlockResource` (1410), `FreeResource` (1329)

75.11.198 FindResourceEx

Synopsis: Find a resource based on type, name, language

Declaration:

```
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
                    ResourceType: PChar; ResourceName: PChar;
                    Language: Word) : TFPResourceHandle
function FindResourceEx(ModuleHandle: TFPResourceHMODULE;
                    const ResourceType: AnsiString;
                    const ResourceName: AnsiString; Language: Word)
                    : TFPResourceHandle
```

Visibility: default

Description: `FindResourceEx` looks in module `ModuleHandle` for a resource of type `ResourceType` and name `ResourceName` with language ID `Language`. Both `ResourceName` and `ResourceName` can be specified as a null-terminated array of characters, or as an `AnsiString`.

If the requested language/sublanguage is not found, then the search is conducted

1. with only primary language.
2. with the neutral language (`LANG_NEUTRAL`)
3. with the english language

If none of these has returned a match, then the first available language is returned.

If a match is found, a handle to the resource is returned. If none is found, an empty handle (nil or 0) is returned.

Errors: None.

75.11.199 float_raise

Synopsis: Raise floating point exception

Declaration: `procedure float_raise(i: TFPUException)`
`procedure float_raise(i: TFPUExceptionMask)`

Visibility: default

Description: `float_raise` raises the floating point exceptions specified by `softfloat_exception_flags` (1264).

See also: `softfloat_exception_flags` (1264), `softfloat_exception_mask` (1264)

75.11.200 Flush

Synopsis: Write file buffers to disk

Declaration: `procedure Flush(var t: Text)`

Visibility: default

Description: `Flush` empties the internal buffer of an opened file `F` and writes the contents to disk. The file is `\textit{not}` closed as a result of this call.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Close` (1298)

Listing: `./refex/ex26.pp`

Program `Example26;`

{ Program to demonstrate the Flush function. }

Var `F : Text;`

begin

{ Assign F to standard output }

`Assign (F, '');`

Rewrite `(F);`

Writeln `(F, 'This line is written first, but appears later !');`

{ At this point the text is in the internal pascal buffer, and not yet written to standard output }

Writeln `('This line appears first, but is written later !');`

{ A writeln to 'output' always causes a flush – so this text is written to screen }

Flush `(f);`

{ At this point, the text written to F is written to screen. }

Write `(F, 'Finishing ');`

`Close (f);` *{ Closing a file always causes a flush first }*

Writeln `('off.');`

end.

75.11.201 FlushThread

Synopsis: Flush all standard files

Declaration: `procedure FlushThread`

Visibility: default

Description: `FlushThread` flushes any buffers from standard file descriptors such as standard input/output/error. It should normally not be called by user code, but is executed when a thread exits.

See also: `EndThread` ([1313](#))

75.11.202 FMADouble

Synopsis: Internal function, do not use

Declaration: `function FMADouble(d1: Double; d2: Double; d3: Double) : Double`

Visibility: default

75.11.203 FMAExtended

Synopsis: Internal function, do not use

Declaration: `function FMAExtended(e1: extended; e2: extended; e3: extended)
: extended`

Visibility: default

75.11.204 FMASingle

Synopsis: Internal function, do not use

Declaration: `function FMASingle(s1: single; s2: single; s3: single) : single`

Visibility: default

75.11.205 fpc_SarInt64

Synopsis: SAR (int64)

Declaration: `function fpc_SarInt64(const AValue: Int64; const Shift: Byte) : Int64`

Visibility: default

Description: `fpc_SarInt64` is a FPC helper function which should not be used directly.

75.11.206 FPower10

Synopsis: Fast multiply with a power of 10

Declaration: `function FPower10(val: Extended; Power: LongInt) : Extended`

Visibility: default

Description: `FPower10` multiplies `val` with 10 to the power `Power`. It uses a fast algorithm to calculate the result.

75.11.207 frac

Synopsis: Return fractional part of floating point value.

Declaration: `function frac(d: ValReal) : ValReal`

Visibility: default

Description: `Frac` returns the non-integer part of `X`.

Errors: None.

See also: `Round` ([1378](#)), `Int` ([1345](#))

Listing: `./refex/ex27.pp`

Program `Example27;`

{ Program to demonstrate the Frac function. }

Var `R : Real;`

begin

WriteLn (**Frac** (123.456):0:3); *{ Prints 0.456 }*

WriteLn (**Frac** (-123.456):0:3); *{ Prints -0.456 }*

end.

75.11.208 Freemem

Synopsis: Release allocated memory

Declaration: `procedure Freemem(p: pointer; Size: PtrUInt)`
 `function Freemem(p: pointer) : PtrUInt`

Visibility: default

Description: `Freemem` releases the memory occupied by the pointer `P`, of size `Count` (in bytes), and returns it to the heap. `P` should point to the memory allocated to a dynamic variable.

Errors: An error will occur when `P` doesn't point to the heap.

See also: `Getmem` ([1331](#)), `New` ([1360](#)), `Dispose` ([1308](#))

Listing: `./refex/ex28.pp`

Program `Example28;`

{ Program to demonstrate the FreeMem and GetMem functions. }

Var `P : Pointer;`

`MM : Longint;`

begin

{ Get memory for P }

GetMem (P,80);

FillChar (P^,80,' ');

FreeMem (P,80);

end.

75.11.209 Freememory

Synopsis: Alias for FreeMem ([1328](#))

Declaration: `procedure Freememory(p: pointer; Size: PtrUInt)`
`function Freememory(p: pointer) : PtrUInt`

Visibility: default

Description: FreeMemory is an alias for FreeMem ([1328](#)).

See also: FreeMem ([1328](#))

75.11.210 FreeResource

Synopsis: Free a loaded resource

Declaration: `function FreeResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: FreeResource unloads the resource identified by ResData from memory. The resource must have been loaded by LoadResource ([1354](#)). It returns True if the operation was succesful, False otherwise.

Errors: On error, False is returned.

See also: FindResource ([1325](#)), LoadResource ([1354](#)), SizeofResource ([1392](#)), LockResource ([1354](#)), UnlockResource ([1410](#)), FreeResource ([1329](#))

75.11.211 Get8087CW

Declaration: `function Get8087CW : Word`

Visibility: default

75.11.212 GetCpuCount

Synopsis: Return the number of cores on the system

Declaration: `function GetCpuCount : LongWord`

Visibility: default

Description: GetCpuCount returns the number of CPU cores on the system. Whether these are physically separate CPUs or cores on a single CPU is deliberately undefined.

See also: CpuCount ([1194](#))

75.11.213 GetCurrentThreadId

Synopsis: Return the id of the currently running thread.

Declaration: `function GetCurrentThreadId : TThreadId`

Visibility: default

Description: `GetCurrentThreadId` returns the ID of the currently running thread. It can be used in calls such as `KillThread` ([1351](#)) or `ThreadSetPriority` ([1405](#))

Errors: None.

See also: `KillThread` ([1351](#)), `ThreadSetPriority` ([1405](#))

75.11.214 `getdir`

Synopsis: Return the current directory

Declaration: `procedure getdir(drivenr: Byte; var dir: shortstring); Overload`
`procedure getdir(drivenr: Byte; var dir: RawByteString); Overload`
`procedure getdir(drivenr: Byte; var dir: unicodestring); Overload`

Visibility: default

Description: `Getdir` returns in `dir` the current directory on the drive `drivenr`, where {`drivenr`} is 1 for the first floppy drive, 3 for the first hard disk etc. A value of 0 returns the directory on the current disk. On Linux and Unix systems, `drivenr` is ignored, as there is only one directory tree.

Errors: An error is returned under dos, if the drive requested isn't ready.

See also: `Chdir` ([1297](#))

Listing: `./refex/ex29.pp`

Program `Example29`;

{ Program to demonstrate the GetDir function. }

Var `S : String`;

begin
 `GetDir` (0,S);
 `WriteLn` ('Current directory is : ',S);
end.

75.11.215 `GetFPCHeapStatus`

Synopsis: Return FPC heap manager status information

Declaration: `function GetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: Return FPC heap manager status information

75.11.216 `GetHeapStatus`

Synopsis: Return the memory manager heap status.

Declaration: `function GetHeapStatus : THeapStatus`

Visibility: default

75.11.217 GetMem

Synopsis: Allocate new memory on the heap

Declaration: `procedure Getmem(out p: pointer; Size: PtrUInt)`
`function GetMem(size: PtrUInt) : pointer`

Visibility: default

Description: `Getmem` reserves `Size` bytes memory on the heap, and returns a pointer to this memory in `p`. What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapFails` (1264): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated. The default value is `False`, so by default an error is generated.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` (1322) or `FillWord` (1324).

For an example, see `Freemem` (1328).

Errors: None.

See also: `Freemem` (1328), `Dispose` (1308), `New` (1360), `returnnilifgrowheapfails` (1264)

75.11.218 GetMemory

Synopsis: Alias for `GetMem` (1331)

Declaration: `procedure Getmemory(out p: pointer; Size: PtrUInt)`
`function GetMemory(size: PtrUInt) : pointer`

Visibility: default

Description: `Getmemory` is an alias for `GetMem` (1331).

See also: `GetMem` (1331)

75.11.219 GetMemoryManager

Synopsis: Return current memory manager

Declaration: `procedure GetMemoryManager(var MemMgr: TMemoryManager)`

Visibility: default

Description: `GetMemoryManager` stores the current Memory Manager record in `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `SetMemoryManager` (1386), `IsMemoryManagerSet` (1350)

75.11.220 GetMXCSR

Declaration: `function GetMXCSR : DWord`

Visibility: default

75.11.221 GetProcessID

Synopsis: Get the current process ID

Declaration: `function GetProcessID : SizeUInt`

Visibility: default

Description: `GetProcessID` returns the current process ID. The meaning of the return value of this call is system dependent.

Errors: None.

See also: `GetThreadID` ([1333](#))

75.11.222 GetResourceManager

Synopsis: Return the currently active resource manager

Declaration: `procedure GetResourceManager (var Manager: TResourceManager)`

Visibility: default

Description: `GetResourceManager` returns the currently active resource manager record in `Manager`. There is always an active resource manager record.

Errors: None.

See also: `TResourceManager` ([1245](#)), `SetResourceManager` ([1387](#))

75.11.223 GetSSECSR

Declaration: `function GetSSECSR : DWord`

Visibility: default

75.11.224 GetTextCodePage

Synopsis: Get the codepage used in a text file.

Declaration: `function GetTextCodePage (var T: Text) : TSystemCodePage`

Visibility: default

Description: `GetTextCodePage` returns the codepage that the text file `T` uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to `CP_ACP`.

Errors: None.

See also: `TextRec` ([1239](#)), `SetTextCodePage` ([1389](#))

75.11.225 GetThreadID

Synopsis: Get the current Thread ID.

Declaration: `function GetThreadID : TThreadID`

Visibility: default

Description: `GetThreadID` returns the current process ID. The meaning of the return value of this call is system dependent.

See also: `GetProcessID` ([1332](#))

75.11.226 GetThreadManager

Synopsis: Return the current thread manager

Declaration: `function GetThreadManager (var TM: TThreadManager) : Boolean`

Visibility: default

Description: `GetThreadManager` returns the currently used thread manager in TM.

For more information about thread programming, see the programmer's guide.

See also: `SetThreadManager` ([1390](#)), `TThreadManager` ([1250](#))

75.11.227 GetUnicodeStringManager

Synopsis: Return a copy of the currently active unicodetring manager.

Declaration: `procedure GetUnicodeStringManager (var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetUnicodeStringManager` returns a copy of the currently active unicode string manager in `Old`

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `UnicodeStringManager` record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetUnicodeStringManager` ([1390](#)), `TUnicodeStringManager` ([1252](#))

75.11.228 GetVariantManager

Synopsis: Return the current variant manager.

Declaration: `procedure GetVariantManager (var VarMgr: tvariantmanager)`

Visibility: default

Description: `GetVariantManager` returns the current variant manager in `varmgr`.

See also: `SetVariantManager` ([1390](#))

75.11.229 GetWideStringManager

Synopsis: Return a copy of the currently active widestring manager.

Declaration: `procedure GetWideStringManager(var Manager: TUnicodeStringManager)`

Visibility: default

Description: `GetWideStringManager` returns a copy of the currently active heap manager in `Old`

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a `WideString` manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `SetWideStringManager` ([1391](#)), `TWideStringManager` ([1259](#))

75.11.230 get_caller_addr

Synopsis: Return the address of the caller.

Declaration: `function get_caller_addr(framebp: pointer; addr: CodePointer)
: CodePointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to address (the return address) of the caller of the routine which has as frame `framebp`.

See also: `get_frame` ([1335](#)), `get_caller_frame` ([1334](#)), `Dump_Stack` ([1311](#))

75.11.231 get_caller_frame

Synopsis: Return the frame pointer of the caller

Declaration: `function get_caller_frame(framebp: pointer; addr: CodePointer) : pointer`

Visibility: default

Description: `get_caller_frame` returns a pointer to the frame of the caller of the routine which has as frame `framebp`.

See also: `get_caller_addr` ([1334](#)), `get_frame` ([1335](#)), `Dump_Stack` ([1311](#))

75.11.232 get_caller_stackinfo

Synopsis: Return caller stack infomation

Declaration: `procedure get_caller_stackinfo(var framebp: pointer;
var addr: CodePointer)`

Visibility: default

Description: `get_caller_stackinfo` returns caller address in `addr` and frame base pointer in `framebp`.

See also: `CaptureBacktrace` ([1296](#)), `Get_pc_addr` ([1335](#)), `get_caller_addr` ([1334](#)), `get_caller_frame` ([1334](#))

75.11.233 `get_frame`

Synopsis: Return the current frame

Declaration: `function get_frame : pointer`

Visibility: default

Description: `get_frame` returns a pointer to the current stack frame.

See also: `get_caller_addr` ([1334](#)), `get_caller_frame` ([1334](#))

75.11.234 `Get_pc_addr`

Synopsis: Get Program Counter address

Declaration: `function Get_pc_addr : CodePointer`

Visibility: default

Description: `Get_pc_addr` returns the program counter address (current execution address).

See also: `CaptureBacktrace` ([1296](#)), `get_caller_stackinfo` ([1334](#)), `get_caller_addr` ([1334](#)), `get_caller_frame` ([1334](#))

75.11.235 `greaterthan(variant,variant):Boolean`

Synopsis: Implement `>` (greater than) operation on variants.

Declaration: `operator >(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than" comparison (`>`) operation is delegated to the variant manager with operation `opcmpgt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` ([1194](#))

75.11.236 `greaterthanorequal(variant,variant):Boolean`

Synopsis: Implement `>=` (greater than or equal) operation on variants.

Declaration: `operator >=(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "greater than or equal" comparison (`>=`) operation is delegated to the variant manager with operation `opcmpge`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator <(variant, variant): boolean` ([1194](#))

75.11.237 halt

Synopsis: Stop program execution.

Declaration: `procedure halt (errnum: LongInt)`
`procedure halt`

Visibility: default

Description: `Halt` stops program execution and returns control to the calling program. The optional argument `Errnum` specifies an exit value. If omitted, zero is returned.

Note that this skips any try/finally (implicit or explicit) or try/except blocks, thus may result in memory leaks. Finalization sections of units will be executed.

Errors: None.

See also: `Exit` ([1319](#))

Listing: `./refex/ex30.pp`

Program `Example30;`

{ Program to demonstrate the Halt function. }

```
begin
  Writeln ('Before Halt. ');
  Halt (1); { Stop with exit code 1 }
  Writeln ('After Halt doesn't get executed. ');
end.
```

75.11.238 hexStr

Synopsis: Convert integer value to string with hexadecimal representation.

Declaration: `function hexStr(Val: LongInt; cnt: Byte) : shortstring`
`function hexStr(Val: Int64; cnt: Byte) : shortstring`
`function hexStr(Val: QWord; cnt: Byte) : shortstring`
`function hexStr(Val: Pointer) : shortstring`

Visibility: default

Description: `HexStr` returns a string with the hexadecimal representation of `Value`. The string has exactly `cnt` characters. (i.e. only the `cnt` rightmost nibbles are taken into account) To have a complete representation of a `Longint`-type value, 8 nibbles are needed, i.e. `cnt=8`.

Errors: None.

See also: `Str` ([1395](#)), `Val` ([1413](#)), `BinStr` ([1291](#))

Listing: `./refex/ex81.pp`

Program `example81;`

{ Program to demonstrate the HexStr function }

Const `Value = 45678;`

Var `l : longint;`

```

begin
  For I:=1 to 10 do
    Writeln (HexStr(Value,I));
  end.

```

75.11.239 hi

Synopsis: Return high byte/word/nibble of value.

Declaration: function hi(b: Byte) : Byte
 function hi(i: Integer) : Byte
 function hi(w: Word) : Byte
 function hi(l: LongInt) : Word
 function hi(l: DWord) : Word
 function hi(i: Int64) : DWord
 function hi(q: QWord) : DWord

Visibility: default

Description: Hi returns the high nibble, byte or word from X, depending on the size of X. If the size of X is 4, then the high word is returned. If the size is 2 then the high byte is returned. If the size is 1, the high nibble is returned.

Errors: None

See also: Lo ([1353](#))

Listing: ./refex/ex31.pp

```

Program Example31;

{ Program to demonstrate the Hi function. }

var
  L : Longint;
  W : Word;
  B : Byte;

begin
  L:=1 Shl 16;      { = $10000 }
  W:=1 Shl 8;       { = $100 }
  B:=1 Shl 4;       { = $10 }
  Writeln (Hi(L)); { Prints 1 }
  Writeln (Hi(W)); { Prints 1 }
  Writeln (Hi(B)); { Prints 1 }
end.

```

75.11.240 High

Synopsis: Return highest index of open array or enumerated

Declaration: function High(Arg: TypeOrVariable) : TOrdinal

Visibility: default

Description: The return value of `High` depends on it's argument:

- 1.If the argument is an ordinal type, `High` returns the highest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `High` returns the highest possible value of it's index. For dynamic arrays, it returns the same as `Length -1`, meaning that it reports -1 for empty arrays.
- 3.If the argument is an open array identifier in a function or procedure, then `High` returns the highest index of the array, as if the array has a zero-based index. If the array is empty, then -1 is returned.
- 4.If the argument is a set type then it returns the highest value of the underlying ordinal type.

The return type is always the same type as the type of the argument (This can lead to some nasty surprises !).

Errors: None.

See also: `Low` ([1356](#)), `Ord` ([1362](#)), `Pred` ([1366](#)), `Succ` ([1400](#))

Listing: `./refex/ex80.pp`

Program `example80`;

{ Example to demonstrate the High and Low functions. }

Type `TEnum = (North , East , South , West);`
 `TRange = 14..55;`
 `TArray = Array [2..10] of Longint;`

Function `Average (Row : Array of Longint) : Real;`

Var `I : longint;`
 `Temp : Real;`

begin
 `Temp := Row[0];`
 For `I := 1 to High(Row) do`
 `Temp := Temp + Row[i];`
 `Average := Temp / (High(Row)+1);`
end;

Var `A : TEnum;`
 `B : TRange;`
 `C : TArray;`
 `I : longint;`

begin
 `Writeln ('TEnum goes from : ', Ord(Low(TEnum)), ' to ', Ord(high(TEnum)), '.');`
 `Writeln ('A goes from : ', Ord(Low(A)), ' to ', Ord(high(A)), '.');`
 `Writeln ('TRange goes from : ', Ord(Low(TRange)), ' to ', Ord(high(TRange)), '.');`
 `Writeln ('B goes from : ', Ord(Low(B)), ' to ', Ord(high(B)), '.');`
 `Writeln ('TArray index goes from : ', Ord(Low(TArray)), ' to ', Ord(high(TArray)), '.');`
 `Writeln ('C index goes from : ', Low(C), ' to ', high(C), '.');`
 For `I:=Low(C) to High(C) do`
 `C[i]:=I;`
 `Writeln ('Average : ', Average(c));`

```

    Write ('Type of return value is always same as type of argument:');
    Writeln(high(high(word)));
end.

```

75.11.241 HINSTANCE

Synopsis: Windows compatibility type for use in resources

Declaration: `function HINSTANCE : TFPResourceHMODULE`

Visibility: default

Description: This is an opaque type.

75.11.242 Inc

Synopsis: Increase value of integer variable

Declaration: `procedure Inc(var X: TOrdinal)`
`procedure Inc(var X: TOrdinal; Increment: TOrdinal)`

Visibility: default

Description: `Inc` increases the value of `X` with `Increment`. If `Increment` isn't specified, then 1 is taken as a default.

Errors: If range checking is on, then A range check can occur, or an overflow error, when an attempt is made to increase `X` over its maximum value.

See also: `Dec` ([1306](#))

Listing: `./refex/ex32.pp`

Program Example32;

{ Program to demonstrate the Inc function. }

Const

```

C : Cardinal  = 1;
L : Longint   = 1;
I : Integer   = 1;
W : Word      = 1;
B : Byte      = 1;
SI : ShortInt = 1;
CH : Char     = 'A';

```

begin

```

Inc (C);      { C:=2    }
Inc (L,5);    { L:=6    }
Inc (I,-3);   { I:=-2   }
Inc (W,3);    { W:=4    }
Inc (B,100);  { B:=101  }
Inc (SI,-3);  { SI:=-2  }
Inc (CH,1);   { ch:='B' }

```

end.

75.11.243 Include

Synopsis: Include element in set if it was not yet present.

Declaration: `procedure Include(var S: TSetType; E: TSetElement)`

Visibility: default

Description: `Include` includes `E` in the set `S` if it is not yet part of the set. `E` should be of the same type as the base type of the set `S`.

Thus, the two following statements do the same thing:

```
S:=S+[E];
Include(S,E);
```

For an example, see `Exclude` ([1317](#))

Errors: If the type of the element `E` is not equal to the base type of the set `S`, the compiler will generate an error.

See also: `Exclude` ([1317](#))

75.11.244 IndexByte

Synopsis: Search for a byte in a memory range.

Declaration: `function IndexByte(const buf; len: SizeInt; b: Byte) : SizeInt`

Visibility: default

Description: `IndexByte` searches the memory at `buf` for maximally `len` positions for the byte `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexChar` ([1341](#)), `IndexDWord` ([1342](#)), `IndexWord` ([1343](#)), `CompareByte` ([1298](#))

Listing: `./refex/ex105.pp`

Program `Example105;`

{ Program to demonstrate the IndexByte function. }

Const

```
  ArraySize = 256;
  MaxValue = 256;
```

Var

```
  Buffer : Array[1..ArraySize] of Byte;
  I,J : longint;
  K : Byte;
```

begin

```
  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=Random(MaxValue);
  For I:=1 to 10 do
    begin
      K:=Random(MaxValue);
```

```

J:=IndexByte ( Buffer , ArraySize ,K);
if J=-1 then
  WriteLn('Value ',K,' was not found in buffer.')
else
  WriteLn('Found ',K,' at position ',J,' in buffer');
end;
end.

```

75.11.245 IndexChar

Synopsis: Search for a character in a memory range.

Declaration: `function IndexChar(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar` searches the memory at `buf` for maximally `len` positions for the character `b` and returns it's position if it found one. If `b` is not found then -1 is returned. The position is zero-based. The `IndexChar0` variant stops looking if a null character is found, and returns -1 in that case.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1340](#)), `IndexDWord` ([1342](#)), `IndexWord` ([1343](#)), `CompareChar` ([1299](#))

Listing: `./refex/ex108.pp`

Program `Example108;`

{ Program to demonstrate the IndexChar function. }

Const

```

  ArraySize = 1000;
  MaxValue = 26;

```

Var

```

  Buffer : Array[1..ArraySize] of Char;
  I,J : longint;
  K : Char;

```

begin

```

  Randomize;
  For I:=1 To ArraySize do
    Buffer[I]:=chr(Ord('A')+Random(MaxValue));
  For I:=1 to 10 do
    begin
      K:=chr(Ord('A')+Random(MaxValue));
      J:=IndexChar ( Buffer , ArraySize ,K);
      if J=-1 then
        WriteLn('Value ',K,' was not found in buffer.')
      else
        WriteLn('Found ',K,' at position ',J,' in buffer');
      end;
    end;

```

end.

75.11.246 IndexChar0

Synopsis: Return index of a character in null-terminated array of char.

Declaration: `function IndexChar0(const buf; len: SizeInt; b: Char) : SizeInt`

Visibility: default

Description: `IndexChar0` returns the index of the character `b` in the null-terminated array `Buf`. At most `len` characters will be searched, or the null character if it is encountered first. If the character is not found, -1 is returned.

Errors: On error, -1 is returned.

See also: `IndexByte` ([1340](#)), `IndexChar` ([1341](#)), `IndexWord` ([1343](#)), `IndexDWord` ([1342](#)), `CompareChar0` ([1301](#))

75.11.247 IndexDWord

Synopsis: Search for a DWord value in a memory range.

Declaration: `function IndexDWord(const buf; len: SizeInt; b: DWord) : SizeInt`

Visibility: default

Description: `IndexDWord` searches the memory at `buf` for maximally `len` positions for the DWord `DW` and returns it's position if it found one. If `DW` is not found then -1 is returned. The position is zero-based.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1340](#)), `IndexChar` ([1341](#)), `IndexWord` ([1343](#)), `CompareDWord` ([1301](#))

Listing: `./refex/ex106.pp`

Program `Example106;`

{ Program to demonstrate the IndexDWord function. }

Const

`ArraySize = 1000;`
`MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of DWord;`
`I, J : longint;`
`K : DWord;`

begin

`Randomize;`

For `I:=1 To ArraySize do`

`Buffer[I]:=Random(MaxValue);`

For `I:=1 to 10 do`

begin

`K:=Random(MaxValue);`

`J:=IndexDWord(Buffer, ArraySize, K);`

if `J=-1 then`

`Writeln('Value ', K, ' was not found in buffer.')`

else

`Writeln('Found ', K, ' at position ', J, ' in buffer');`

end;

end.

75.11.248 IndexQWord

Synopsis: Return the position of a QWord in a memory range

Declaration: `function IndexQWord(const buf; len: SizeInt; b: QWord) : SizeInt`

Visibility: default

Description: `IndexQWord` checks the first `len` qwords starting at `Buf`, and returns the position (zero-based) of `b`. If `b` does not appear in the first `len` qwords, then -1 is returned.

Note that the search is done on QWord boundaries, but that the address of `buf` need not be on a QWord boundary.

Errors: No check is done to see whether the indicated memory range is valid. If it is not, a run-error or exception may be triggered.

See also: `IndexDWord` ([1342](#))

75.11.249 Indexword

Synopsis: Search for a WORD value in a memory range.

Declaration: `function Indexword(const buf; len: SizeInt; b: Word) : SizeInt`

Visibility: default

Description: `IndexWord` searches the memory at `buf` for maximally `len` positions for the Word `W` and returns it's position if it found one. If `W` is not found then -1 is returned.

Errors: `Buf` and `Len` are not checked to see if they are valid values.

See also: `IndexByte` ([1340](#)), `IndexDWord` ([1342](#)), `IndexChar` ([1341](#)), `CompareWord` ([1302](#))

Listing: `./refex/ex107.pp`

Program `Example107;`

{ Program to demonstrate the IndexWord function. }

Const

`ArraySize = 1000;`
`MaxValue = 1000;`

Var

`Buffer : Array[1..ArraySize] of Word;`
`I, J : longint;`
`K : Word;`

begin

`Randomize;`
`For I:=1 To ArraySize do`
`Buffer[I]:=Random(MaxValue);`
`For I:=1 to 10 do`
`begin`
`K:=Random(MaxValue);`
`J:=IndexWord(Buffer, ArraySize, K);`
`if J=-1 then`
`WriteLn('Value ', K, ' was not found in buffer.')`
`else`

```

    WriteLn('Found ',K,' at position ',J,' in buffer');
end;
end.

```

75.11.250 InitCriticalSection

Synopsis: Initialize a critical section

Declaration: `procedure InitCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `InitCriticalSection` initializes a critical section CS for use. Before using a critical section with `EnterCriticalSection` (1313) or `LeaveCriticalSection` (1351) the critical section should be initialized with `InitCriticalSection`.

When a critical section is no longer used, it should be disposed of with `DoneCriticalSection` (1309)

See also: `DoneCriticalSection` (1309), `EnterCriticalSection` (1313), `LeaveCriticalSection` (1351)

75.11.251 InitializeArray

Synopsis: Initialize managed-type elements in array

Declaration: `procedure InitializeArray(p: Pointer; typeInfo: Pointer; count: SizeInt)`

Visibility: default

Description: `InitializeArray` initializes managed types in the array pointed to by p. For this, it uses the type information of the elements as specified in `typeinfo`.

Under normal circumstances, this procedure should not be used, it is called automatically by the compiler when an array-typed variable is declared and the array contains elements with managed types.

See also: `FinalizeArray` (1324), `CopyArray` (1305)

75.11.252 InitThread

Synopsis: Initialize a thread

Declaration: `procedure InitThread(stklen: SizeUInt)`

Visibility: default

Description: Do not use, this is used internally by the thread manager.

75.11.253 InitThreadVars

Synopsis: Initialize threadvars

Declaration: `procedure InitThreadVars(RelocProc: TRelocateThreadVarHandler)`

Visibility: default

Description: This routine should be called when threading is started. It is called by the compiler and should never be called manually, only from a thread manager.

Errors: None.

See also: `TThreadManager` (1250)

75.11.254 Insert

Synopsis: Insert one string in another.

Declaration: `procedure Insert(const source: shortstring; var s: shortstring;
 index: SizeInt)
 procedure Insert(source: Char; var s: shortstring; index: SizeInt)
 procedure Insert(const Source: RawByteString; var S: RawByteString;
 Index: SizeInt)
 procedure Insert(const Source: UnicodeString; var S: UnicodeString;
 Index: SizeInt)
 procedure Insert(const Source: WideString; var S: WideString;
 Index: SizeInt)`

Visibility: default

Description: `Insert` inserts string `Source` in string `S`, at position `Index`, shifting all characters after `Index` to the right. The resulting string is truncated at 255 characters, if needed. (i.e. for shortstrings)

Errors: None.

See also: `Delete` ([1308](#)), `Copy` ([1194](#)), `Pos` ([1365](#))

Listing: `./refex/ex33.pp`

Program `Example33;`

{ Program to demonstrate the Insert function. }

Var `S : String;`

begin

`S:= 'Free Pascal is difficult to use !';`

`Insert ('NOT ',S,pos('difficult',S));`

`writeln (s);`

end.

75.11.255 int

Synopsis: Calculate integer part of floating point value.

Declaration: `function int(d: ValReal) : ValReal`

Visibility: default

Description: `Int` returns the integer part of any Real `X`, as a Real.

Errors: None.

See also: `Frac` ([1328](#)), `Round` ([1378](#))

Listing: `./refex/ex34.pp`

Program `Example34;`

{ Program to demonstrate the Int function. }

begin

```

Writeln (Int(123.456):0:1); { Prints 123.0 }
Writeln (Int(-123.456):0:1); { Prints -123.0 }
end.

```

75.11.256 **intdivide(variant,variant):variant**

Synopsis: Implement `div` (integer division) operation on variants.

Declaration: `operator div(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the integer division `Div` operation is delegated to the variant manager with operation `opintdivide`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator mod(variant, variant): variant` ([1194](#))

75.11.257 **InterlockedCompareExchange**

Synopsis: Conditional exchange

Declaration:

```

function InterlockedCompareExchange(var Target: LongInt;
                                     NewValue: LongInt;
                                     Comperand: LongInt) : LongInt

function InterlockedCompareExchange(var Target: Pointer;
                                     NewValue: Pointer;
                                     Comperand: Pointer) : Pointer

function InterlockedCompareExchange(var Target: Cardinal;
                                     NewValue: Cardinal;
                                     Comperand: Cardinal) : Cardinal

```

Visibility: default

Description: `InterlockedCompareExchange` does an compare-and-exchange operation on the specified values in a thread-safe way. The function compares `Target` and `Comperand` and exchanges `Target` with `NewValue` if `Target` and `Comperand` are equal. It returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1347](#)), `InterLockedIncrement` ([1348](#)), `InterLockedExchange` ([1347](#)), `InterLockedExchangeAdd` ([1348](#))

75.11.258 **InterlockedCompareExchange64**

Declaration:

```

function InterlockedCompareExchange64(var Target: Int64;
                                       NewValue: Int64; Comperand: Int64)
                                       : Int64

function InterlockedCompareExchange64(var Target: QWord;
                                       NewValue: QWord; Comperand: QWord)
                                       : Int64

```

Visibility: default

75.11.263 InterLockedExchangeAdd

Synopsis: Thread-safe add and exchange of 2 values

Declaration: `function InterLockedExchangeAdd(var Target: LongInt; Source: LongInt)
: LongInt
function InterLockedExchangeAdd(var Target: Pointer; Source: Pointer)
: Pointer
function InterLockedExchangeAdd(var Target: Cardinal; Source: Cardinal)
: Cardinal`

Visibility: default

Description: `InterLockedExchangeAdd` adds to `Target` the value of `Source` in a thread-safe way, and returns the old value of `Target`. This is done in a thread-safe way, i.e., only one processor is accessing the `Target` variable at a time.

Errors: None.

See also: `InterLockedDecrement` ([1347](#)), `InterLockedIncrement` ([1348](#)), `InterLockedExchange` ([1347](#)), `InterlockedCompareExchange` ([1346](#))

75.11.264 InterLockedExchangeAdd64

Declaration: `function InterLockedExchangeAdd64(var Target: Int64; Source: Int64)
: Int64
function InterLockedExchangeAdd64(var Target: QWord; Source: QWord)
: QWord`

Visibility: default

75.11.265 InterLockedIncrement

Synopsis: Thread-safe increment

Declaration: `function InterLockedIncrement(var Target: LongInt) : LongInt
function InterLockedIncrement(var Target: Pointer) : Pointer
function InterLockedIncrement(var Target: Cardinal) : Cardinal`

Visibility: default

Description: `InterLockedIncrement` increments `Target` with 1 and returns the result. This is done in a thread-safe way (i.e. only one processor is accessing the variable at a time).

Errors: None.

See also: `InterLockedDecrement` ([1347](#)), `InterLockedExchange` ([1347](#)), `InterLockedExchangeAdd` ([1348](#)), `InterlockedCompareExchange` ([1346](#))

75.11.266 InterLockedIncrement64

Declaration: `function InterLockedIncrement64(var Target: Int64) : Int64
function InterLockedIncrement64(var Target: QWord) : QWord`

Visibility: default

75.11.267 IOResult

Synopsis: Return result of last file IO operation

Declaration: `function IOResult : Word`

Visibility: default

Description: IOResult contains the result of any input/output call, when the `{\Si-}` compiler directive is active, disabling IO checking. When the flag is read, it is reset to zero. If IOResult is zero, the operation completed successfully. If non-zero, an error occurred. The following errors can occur:

dos errors :

- 2**File not found.
- 3**Path not found.
- 4**Too many open files.
- 5**Access denied.
- 6**Invalid file handle.
- 12**Invalid file-access mode.
- 15**Invalid disk number.
- 16**Cannot remove current directory.
- 17**Cannot rename across volumes.

I/O errors :

- 100**Error when reading from disk.
- 101**Error when writing to disk.
- 102**File not assigned.
- 103**File not open.
- 104**File not opened for input.
- 105**File not opened for output.
- 106**Invalid number.

Fatal errors :

- 150**Disk is write protected.
- 151**Unknown device.
- 152**Drive not ready.
- 153**Unknown command.
- 154**CRC check failed.
- 155**Invalid drive specified..
- 156**Seek error on disk.
- 157**Invalid media type.
- 158**Sector not found.
- 159**Printer out of paper.
- 160**Error when writing to device.
- 161**Error when reading from device.
- 162**Hardware failure.

Errors: None.

Listing: ./refex/ex35.pp

Program Example35;

```
{ Program to demonstrate the IOResult function. }
```

Var F : text;

begin

```
  Assign (f,paramstr(1));
  {$i-}
  Reset (f);
  {$i+}
  If IOresult<>0 then
    writeln ('File ',paramstr(1),' doesn't exist')
  else
    writeln ('File ',paramstr(1),' exists');
end.
```

75.11.268 IsDynArrayRectangular

Synopsis: Check whether all dimensions have the same size

Declaration: `function IsDynArrayRectangular(a: Pointer; typeInfo: Pointer) : Boolean`

Visibility: default

Description: `IsDynArrayRectangular` returns `True` if all dimensions of the dynamic array `a` with type information `typeinfo` have the same bounds. It returns `True` if the array is empty.

See also: `InitializeArray` ([1344](#)), `FinalizeArray` ([1324](#)), `CopyArray` ([1305](#)), `DynArraySize` ([1313](#)), `DynArrayClear` ([1311](#)), `DynArrayBounds` ([1311](#)), `DynArrayDim` ([1312](#))

75.11.269 IsMemoryManagerSet

Synopsis: Is the memory manager set

Declaration: `function IsMemoryManagerSet : Boolean`

Visibility: default

Description: `IsMemoryManagerSet` will return `True` if the memory manager has been set to another value than the system heap manager, it will return `False` otherwise.

Errors: None.

See also: `SetMemoryManager` ([1386](#)), `GetMemoryManager` ([1331](#))

75.11.270 Is_IntResource

Synopsis: Check whether a resource is an internal resource

Declaration: `function Is_IntResource(aStr: PChar) : Boolean`

Visibility: default

Description: `Is_IntResource` returns `True` if the resource type is internal (system predefined) resource or `false` if it is a user-defined resource type.

Errors: None.

75.11.271 KillThread

Synopsis: Kill a running thread

Declaration: `function KillThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `KillThread` causes a running thread to be aborted. The thread is identified by its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `WaitForThreadTerminate` ([1415](#)), `EndThread` ([1313](#)), `SuspendThread` ([1400](#))

75.11.272 LeaveCriticalSection

Synopsis: Leave a critical section

Declaration: `procedure LeaveCriticalSection(var cs: TRTLCriticalSection)`

Visibility: default

Description: `LeaveCriticalSection` signals that the current thread is exiting the critical section `CS` it has entered with `EnterCriticalSection` ([1313](#)).

The critical section must have been initialized with `InitCriticalSection` ([1344](#)) prior to a call to `EnterCriticalSection` and `LeaveCriticalSection`.

See also: `InitCriticalSection` ([1344](#)), `DoneCriticalSection` ([1309](#)), `EnterCriticalSection` ([1313](#))

75.11.273 leftshift(variant,variant):variant

Synopsis: Implement binary `shl` operation on variants.

Declaration: `operator shl(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `shl` operation is delegated to the variant manager with operation `opshiftright`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: `operator shr(variant, variant): variant` ([1194](#))

75.11.274 lessthan(variant,variant):Boolean

Synopsis: Implement < (less than) operation on variants.

Declaration: `operator <(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "less than" comparison (<) operation is delegated to the variant manager with operation `opcmlt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `>(variant, variant): boolean` ([1194](#))

75.11.275 lessthanorequal(variant,variant):Boolean

Synopsis: Implement <= (less than or equal) operation on variants.

Declaration: `operator <=(const op1: variant; const op2: variant) : Boolean`

Visibility: default

Description: The implementation of the "less than or equal" comparison (<=) operation is delegated to the variant manager with operation `opcmlt`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `<(variant, variant): boolean` ([1194](#))

75.11.276 LEtoN

Synopsis: Convert Little Endian-ordered integer to Native-ordered integer

Declaration: `function LEtoN(const AValue: SmallInt) : SmallInt`
`function LEtoN(const AValue: Word) : Word`
`function LEtoN(const AValue: LongInt) : LongInt`
`function LEtoN(const AValue: DWord) : DWord`
`function LEtoN(const AValue: Int64) : Int64`
`function LEtoN(const AValue: QWord) : QWord`

Visibility: default

Description: `LEtoN` will rearrange the bytes in a Little-Endian number to the native order for the current processor. That is, for a little-endian processor, it will do nothing, and for a big-endian processor, it will invert the order of the bytes.

See also: `BEtoN` ([1291](#)), `NtoBE` ([1360](#)), `NtoLE` ([1360](#))

75.11.277 ln

Synopsis: Calculate logarithm

Declaration: `function ln(d: ValReal) : ValReal`

Visibility: default

Description: `Ln` returns the natural logarithm of the Real parameter `X`. `X` must be positive.

Errors: An run-time error will occur when `X` is negative.

See also: `Exp` ([1320](#))

Listing: `./refex/ex37.pp`

Program `Example37`;

{ Program to demonstrate the Ln function. }

```
begin
  Writeln (Ln(1));      { Prints 0 }
  Writeln (Ln(Exp(1))); { Prints 1 }
end.
```

75.11.278 `lo`

Synopsis: Return low nibble/byte/word of value.

Declaration: `function lo(B: Byte) : Byte`
`function lo(i: Integer) : Byte`
`function lo(w: Word) : Byte`
`function lo(l: LongInt) : Word`
`function lo(l: DWord) : Word`
`function lo(i: Int64) : DWord`
`function lo(q: QWord) : DWord`

Visibility: default

Description: `Lo` returns the low byte of its argument if this is of size 2 (such as `Word` or `SmallInt`), or the low nibble if the size is 1 (such as `byte`). It returns the low word of its argument if this is of type `Longint` or `Cardinal`.

Errors: None.

See also: `Ord` ([1362](#)), `Chr` ([1297](#)), `Hi` ([1337](#))

Listing: `./refex/ex38.pp`

Program `Example38`;

{ Program to demonstrate the Lo function. }

```
Var L : Longint;
    W : Word;
    B : Byte;
begin
  L:=(1 Shl 16) + (1 Shl 4); { $10010 }
  Writeln (Lo(L));          { Prints 16 }
  W:=(1 Shl 8) + (1 Shl 4); { $110 }
  Writeln (Lo(W));          { Prints 16 }
  B:=$EF;
  Writeln (Lo(B));          { Prints 15 }
end.
```

75.11.279 LoadResource

Synopsis: Load a resource for use

Declaration: `function LoadResource (ModuleHandle: TFPResourceHMODULE;
ResHandle: TFPResourceHandle) : TFPResourceHGLOBAL`

Visibility: default

Description: `LoadResource` loads a resource identified by `ResHandle` from a module identified by `ModuleHandle` into memory. It returns a handle to the resource.

Loaded resources must be unloaded again using the `FreeResource` (1329) function.

Errors: On error, 0 is returned.

See also: `FindResource` (1325), `FreeResource` (1329), `SizeofResource` (1392), `LockResource` (1354), `UnlockResource` (1410), `FreeResource` (1329)

75.11.280 LockResource

Synopsis: Lock a resource

Declaration: `function LockResource (ResData: TFPResourceHGLOBAL) : Pointer`

Visibility: default

Description: `LockResource` locks a resource previously loaded by `LoadResource` into memory. This means that any attempt to modify the resource will fail while it is locked. The function returns a pointer to the resource location in memory.

The resource can be freed again using the `UnlockResource` (1410) function.

Errors: if the function fails, `Nil` is returned.

See also: `FindResource` (1325), `FreeResource` (1329), `SizeofResource` (1392), `LoadResource` (1354), `UnlockResource` (1410), `FreeResource` (1329)

75.11.281 logicaland(variant,variant):variant

Synopsis: Implement logical/binary and operation on variants

Declaration: `operator and(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `and` operation is delegated to the variant manager with operation `opand`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `or(variant, variant): variant` (1194), operator `xor(variant, variant): variant` (1194), operator `not(variant): variant` (1194)

75.11.282 logicalnot(variant):variant

Synopsis: Implement logical/binary `not` operation on variants

Declaration: `operator not (const op: variant) : variant`

Visibility: default

Description: The implementation of the `not` operation is delegated to the variant manager with operation `opnot`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `and(variant, variant): variant` ([1194](#)), operator `or(variant, variant): variant` ([1194](#)), operator `xor(variant, variant): variant` ([1194](#))

75.11.283 logicalor(variant,variant):variant

Synopsis: Implement logical/binary `or` operation on variants

Declaration: `operator or (const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `or` operation is delegated to the variant manager with operation `opor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `and(variant, variant): variant` ([1194](#)), operator `xor(variant, variant): variant` ([1194](#)), operator `not(variant): variant` ([1194](#))

75.11.284 logicalxor(variant,variant):variant

Synopsis: Implement logical/binary `xor` operation on variants

Declaration: `operator xor (const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `xor` operation is delegated to the variant manager with operation `opxor`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `or(variant, variant): variant` ([1194](#)), operator `and(variant, variant): variant` ([1194](#)), operator `not(variant): variant` ([1194](#))

75.11.285 longjmp

Synopsis: Jump to address.

Declaration: `procedure longjmp (var S: jmp_buf; value: LongInt)`

Visibility: default

Description: `LongJump` jumps to the address in the `envjmp_buf`, and restores the registers that were stored in it at the corresponding `SetJump` (1385) call. In effect, program flow will continue at the `SetJump` call, which will return `value` instead of 0. If a `value` equal to zero is passed, it will be converted to 1 before passing it on. The call will not return, so it must be used with extreme care. This can be used for error recovery, for instance when a segmentation fault occurred.

For an example, see `SetJump` (1385)

Errors: None.

See also: `SetJump` (1385)

75.11.286 Low

Synopsis: Return lowest index of open array or enumerated

Declaration: `function Low(Arg: TypeOrVariable) : TOrdinal`

Visibility: default

Description: The return value of `Low` depends on it's argument:

- 1.If the argument is an ordinal type, `Low` returns the lowest value in the range of the given ordinal type.
- 2.If the argument is an array type or an array type variable then `Low` returns the lowest possible value of it's index.
- 3.If the argument is an open array identifier in a function or procedure, then `Low` returns the lowest element of the array, which is always zero.
- 4.If the argument is a set type then it returns the lowest value of the underlying ordinal type.

The return type is always the same type as the type of the argument.

for an example, see `High` (1337).

Errors: None.

See also: `High` (1337), `Ord` (1362), `Pred` (1366), `Succ` (1400)

75.11.287 lowerCase

Synopsis: Return lowercase version of a string.

Declaration: `function lowerCase(const s: shortstring) : shortstring; Overload`
`function lowerCase(c: Char) : Char; Overload`
`function lowercase(const s: ansistring) : ansistring`
`function LowerCase(const s: UnicodeString) : UnicodeString`
`function LowerCase(c: UnicodeChar) : UnicodeChar`

Visibility: default

Description: `Lowercase` returns the lowercase version of its argument `C`. If its argument is a string, then the complete string is converted to lowercase. The type of the returned value is the same as the type of the argument.

`Lowercase` does not change the number of characters (or bytes) in an `ansistring`.

Errors: None.

See also: Upcase ([1410](#))

Listing: ./refex/ex73.pp

```

program Example73;

  { Program to demonstrate the Lowercase function. }

  var c:char;

  begin
    for c:= 'A' to 'Z' do
      write(lowercase(c));
      Writeln;
      Writeln(Lowercase( 'ABCDEFGHIJKLMNOPQRSTUVWXYZ' ));
  end.
```

75.11.288 MakeLangID

Synopsis: Create a language ID

Declaration: `function MakeLangID(primary: Word; sub: Word) : Word`

Visibility: default

Description: MakeLangID creates a language ID from the primary and sub language IDs.

75.11.289 MemSize

Synopsis: Return the size of a memory block.

Declaration: `function MemSize(p: pointer) : PtrUInt`

Visibility: default

Description: MemSize returns the size of a memory block on the heap.

Errors: Passing an invalid pointer may lead to run-time errors (access violations).

See also: GetMem ([1331](#)), FreeMem ([1328](#))

75.11.290 mkdir

Synopsis: Create a new directory.

Declaration: `procedure mkdir(const s: shortstring); Overload`
`procedure mkdir(const s: RawByteString); Overload`
`procedure mkdir(const s: unicodestring); Overload`

Visibility: default

Description: Mkdir creates a new directory S.

For an example, see Rmdir ([1375](#)).

Errors: Depending on the state of the {\$I} switch, a runtime error can be generated if there is an error. In the {\$I-} state, use IOResult to check for errors.

See also: Chdir ([1297](#)), Rmdir ([1375](#))

75.11.291 modulus(variant,variant):variant

Synopsis: Implement mod (modulo) operation on variants.

Declaration: `operator mod(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the modulo Mod operation is delegated to the variant manager with operation `opModulus`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `div(variant, variant): variant` ([1194](#))

75.11.292 Move

Synopsis: Move data from one location in memory to another

Declaration: `procedure Move(const source; var dest; count: SizeInt)`

Visibility: default

Description: `Move` moves `Count` bytes from `Source` to `Dest`.

Errors: If either `Dest` or `Source` is outside the accessible memory for the process, then a run-time error will be generated.

See also: `Fillword` ([1324](#)), `Fillchar` ([1322](#))

Listing: `./refex/ex42.pp`

Program `Example42;`

{ Program to demonstrate the Move function. }

Var `S1,S2 : String [30];`

begin

`S1:= 'Hello World !';`

`S2:= 'Bye, bye !';`

`Move (S1,S2,Sizeof(S1));`

`Writeln (S2);`

end.

75.11.293 MoveChar0

Synopsis: Move data till first zero character

Declaration: `procedure MoveChar0(const buf1; var buf2; len: SizeInt)`

Visibility: default

Description: `MoveChar0` moves `Count` bytes from `buf1` to `buf2`, and stops moving if a zero character is found.

Errors: No checking is done to see if `Count` stays within the memory allocated to the process.

See also: [Move \(1358\)](#)

Listing: ./refex/ex109.pp

```

Program Example109;

{ Program to demonstrate the MoveChar0 function. }

Var
  Buf1, Buf2 : Array[1..80] of char;
  I : longint;

begin
  Randomize;
  For I := low(buf1) to high(buf1) do
    Buf1[I] := chr(Random(16) + Ord( 'A' ));
  WriteIn( 'Original buffer' );
  writeln( Buf1 );
  Buf1[Random(80) + 1] := #0;
  MoveChar0( Buf1, Buf2, 80 );
  WriteIn( 'Randomly zero-terminated Buffer' );
  WriteIn( Buf2 );
end.

```

75.11.294 multiply(variant,variant):variant

Synopsis: Implement multiplication (*****) operation on variants.

Declaration: operator *****(const op1: variant; const op2: variant) : variant

Visibility: default

Description: The implementation of the multiplication ***** operation is delegated to the variant manager with operation opMultiply.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator **/**(variant, variant): variant ([1194](#))

75.11.295 negative(variant):variant

Synopsis: Implement **-** (unary minus, negation) operation on variants.

Declaration: operator **-**(const op: variant) : variant

Visibility: default

Description: The implementation of the unary minus (**-**) operation is delegated to the variant manager with operation varNeg.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator **-**(variant, variant): variant ([1194](#))

75.11.296 New

Synopsis: Dynamically allocate memory for variable

Declaration: `procedure New(var P: Pointer)`
`procedure New(var P: Pointer; Cons: TProcedure)`

Visibility: default

Description: `New` allocates a new instance of the type pointed to by `P`, and puts the address in `P`. If `P` is an object, then it is possible to specify the name of the constructor with which the instance will be created.

The newly allocated memory is not initialized in any way, and may contain garbage data. It must be cleared with a call to `FillChar` (1322) or `FillWord` (1324).

For an example, see `Dispose` (1308).

Errors: What happens if no more memory is available, depends on the value of the variable `ReturnNilIfGrowHeapfails` (1264): if the variable is `True` then `Nil` is returned. If the variable is `False`, a run-time error is generated.

See also: `Dispose` (1308), `Freemem` (1328), `Getmem` (1331), `ReturnNilIfGrowHeapfails` (1264)

75.11.297 NtoBE

Synopsis: Convert Native-ordered integer to a Big Endian-ordered integer

Declaration: `function NtoBE(const AValue: SmallInt) : SmallInt`
`function NtoBE(const AValue: Word) : Word`
`function NtoBE(const AValue: LongInt) : LongInt`
`function NtoBE(const AValue: DWord) : DWord`
`function NtoBE(const AValue: Int64) : Int64`
`function NtoBE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoBE` will rearrange the bytes in a natively-ordered number to the Big-Endian order. That is, for a Little-Endian processor, it will invert the order of the bytes and for a big-endian processor, it will do nothing.

See also: `BEtoN` (1291), `LEtoN` (1352), `NtoLE` (1360)

75.11.298 NtoLE

Synopsis: Convert Native-ordered integer to a Little Endian-ordered integer

Declaration: `function NtoLE(const AValue: SmallInt) : SmallInt`
`function NtoLE(const AValue: Word) : Word`
`function NtoLE(const AValue: LongInt) : LongInt`
`function NtoLE(const AValue: DWord) : DWord`
`function NtoLE(const AValue: Int64) : Int64`
`function NtoLE(const AValue: QWord) : QWord`

Visibility: default

Description: `NtoLE` will rearrange the bytes in a natively-ordered number to the little-Endian order. That is, for a Big-Endian processor, it will invert the order of the bytes and for a Little-Endian processor, it will do nothing.

See also: `BEtoN` (1291), `LEtoN` (1352), `NtoBE` (1360)

75.11.299 Null

Synopsis: Null variant

Declaration: `function Null : Variant`

Visibility: default

75.11.300 OctStr

Synopsis: Convert integer to a string with octal representation.

Declaration: `function OctStr(Val: LongInt; cnt: Byte) : shortstring`
`function OctStr(Val: Int64; cnt: Byte) : shortstring`
`function OctStr(Val: QWord; cnt: Byte) : shortstring`

Visibility: default

Description: `OctStr` returns a string with the octal representation of `Value`. The string has exactly `cnt` characters.

Errors: None.

See also: `Str` ([1395](#)), `Val` ([1413](#)), `BinStr` ([1291](#)), `HexStr` ([1336](#))

Listing: `./refex/ex112.pp`

```

Program example112;

  { Program to demonstrate the OctStr function }

  Const Value = 45678;

  Var I : longint;

  begin
    For I:=1 to 10 do
      Writeln (OctStr(Value, I));
    For I:=1 to 16 do
      Writeln (OctStr(I, 3));
  end.

```

75.11.301 odd

Synopsis: Is a value odd or even ?

Declaration: `function odd(l: LongInt) : Boolean`
`function odd(l: LongWord) : Boolean`
`function odd(l: Int64) : Boolean`
`function odd(l: QWord) : Boolean`

Visibility: default

Description: `Odd` returns `True` if `X` is odd, or `False` otherwise.

Errors: None.

See also: `Abs` ([1265](#)), `Ord` ([1362](#))

Listing: ./refex/ex43.pp

Program Example43;

```
{ Program to demonstrate the Odd function. }

begin
  If Odd(1) Then
    Writeln ( 'Everything OK with 1 !');
  If Not Odd(2) Then
    Writeln ( 'Everything OK with 2 !');
end.
```

75.11.302 Ofs

Synopsis: Return offset of a variable.

Declaration: `function Ofs(var X) : LongInt`

Visibility: default

Description: `Ofs` returns the offset of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always the complete address of the variable, since Free Pascal is a 32/64 bit compiler.

Errors: None.

See also: `DSeg` ([1310](#)), `CSeg` ([1306](#)), `Seg` ([1383](#)), `Ptr` ([1367](#))

Listing: ./refex/ex44.pp

Program Example44;

```
{ Program to demonstrate the Ofs function. }

Var W : Pointer;

begin
  W:=Pointer(Ofs(W)); { W contains its own offset. }
end.
```

75.11.303 Ord

Synopsis: Return ordinal value of an ordinal type.

Declaration: `function Ord(X: TOrdinal) : LongInt`

Visibility: default

Description: `Ord` returns the Ordinal value of a ordinal-type variable X.

Historical note:

Originally, Pascal did not have typecasts and `ord` was a necessary function in order to do certain operations on non-integer ordinal types. With the arrival of typecasting a generic approach became possible, making `ord` mostly obsolete. However `ord` is not considered deprecated and remains in wide use today.

Errors: None.

See also: Chr ([1297](#)), Succ ([1400](#)), Pred ([1366](#)), High ([1337](#)), Low ([1356](#))

Listing: ./refex/ex45.pp

Program Example45;

{ Program to demonstrate the Ord, Pred, Succ functions. }

Type

TEnum = (Zero, One, Two, Three, Four);

Var

X : Longint;

Y : TEnum;

begin

X:=125;

WriteIn (Ord(X)); { Prints 125 }

X:=Pred(X);

WriteIn (Ord(X)); { prints 124 }

Y:= One;

WriteIn (Ord(y)); { Prints 1 }

Y:=Succ(Y);

WriteIn (Ord(Y)); { Prints 2 }

end.

75.11.304 ParamCount

Synopsis: Return number of command-line parameters passed to the program.

Declaration: `function ParamCount : LongInt`

Visibility: default

Description: `Paramcount` returns the number of command-line arguments. If no arguments were given to the running program, 0 is returned.

Errors: None.

See also: Paramstr ([1364](#))

Listing: ./refex/ex46.pp

Program Example46;

{ Program to demonstrate the ParamCount and ParamStr functions. }

Var

I : Longint;

begin

WriteIn (paramstr(0), ' : Got ', ParamCount, ' command-line parameters: ');

For i:=1 **to** ParamCount **do**

WriteIn (ParamStr (i));

end.

75.11.305 ParamStr

Synopsis: Return value of a command-line argument.

Declaration: `function ParamStr(L: LongInt) : string`

Visibility: default

Description: `ParamStr` returns the L-th command-line argument. L must be between 0 and `Paramcount`, these values included. The zeroth argument is the path and file name with which the program was started.

The command-line parameters will be truncated to a length of 255, even though the operating system may support bigger command-lines. The `Objpas` unit (used in `objfpc` or `delphi` mode) defines versions of `ParamStr` which return the full-length command-line arguments, using `ansistrings`.

In the interest of portability, the `ParamStr` function tries to behave the same on all operating systems: like the original `ParamStr` function in Turbo Pascal. This means even on Unix, `paramstr(0)` returns the full path to the program executable. A notable exception is Mac OS X, where the return value depends on how the application was started. It may be that just the name of the application is returned (in case of a command-line launch)

In general, it's a bad idea to rely on the location of the binary. Often, this goes against best OS practices. Configuration data should (or can) not be stored next to the binary, but on designated locations. What locations these are, is very much operating system dependent. Therefore, `ParamStr(0)` should be used with care.

For an example, see `Paramcount` ([1363](#)).

Errors: None.

See also: `Paramcount` ([1363](#))

75.11.306 pi

Synopsis: Return the value of PI.

Declaration: `function pi : ValReal`

Visibility: default

Description: `Pi` returns the value of Pi (3.1415926535897932385).

Errors: None.

See also: `Cos` ([1305](#)), `Sin` ([1391](#))

Listing: `./refex/ex47.pp`

Program `Example47`;

{ Program to demonstrate the Pi function. }

```
begin
  Writeln (Pi);           {3.1415926}
  Writeln (Sin(Pi));
end.
```

CHAPTER 75. REFERENCE FOR UNIT 'SYSTEM'

Synopsis: Count number of set bits

```
Declaration: function PopCnt(const AValue: Byte) : Byte
             function PopCnt(const AValue: Word) : Word
             function PopCnt(const AValue: DWord) : DWord
             function PopCnt(const AValue: QWord) : QWord
```

Visibility: default

Description: `PopCnt` (population count) counts the number of set bits in `AValue`.

75.11.308 Pos

Synopsis: Search for substring in a string.

```

Declaration:function Pos(const substr: shortstring; const s: shortstring) : SizeInt
function Pos(C: Char; const s: shortstring) : SizeInt
function Pos(const Substr: ShortString; const Source: RawByteString)
: SizeInt
function pos(const substr: shortstring; c: Char) : SizeInt
function Pos(const Substr: RawByteString; const Source: RawByteString)
: SizeInt
function Pos(c: AnsiChar; const s: RawByteString) : SizeInt
function Pos(const Substr: UnicodeString; const Source: UnicodeString)
: SizeInt
function Pos(c: Char; const s: UnicodeString) : SizeInt
function Pos(c: UnicodeChar; const s: UnicodeString) : SizeInt
function Pos(const c: RawByteString; const s: UnicodeString) : SizeInt
function Pos(const c: UnicodeString; const s: RawByteString) : SizeInt
function Pos(const c: ShortString; const s: UnicodeString) : SizeInt
function Pos(const Substr: WideString; const Source: WideString)
: SizeInt
function Pos(c: Char; const s: WideString) : SizeInt
function Pos(c: WideChar; const s: WideString) : SizeInt
function Pos(c: WideChar; const s: RawByteString) : SizeInt
function Pos(const c: RawByteString; const s: WideString) : SizeInt
function Pos(const c: WideString; const s: RawByteString) : SizeInt
function Pos(const c: ShortString; const s: WideString) : SizeInt
function Pos(c: Char; const v: Variant) : SizeInt
function Pos(s: ShortString; const v: Variant) : SizeInt
function Pos(const a: AnsiString; const v: Variant) : SizeInt
function Pos(const w: WideString; const v: Variant) : SizeInt
function Pos(const w: UnicodeString; const v: Variant) : SizeInt
function Pos(const v: Variant; const c: Char) : SizeInt
function Pos(const v: Variant; const s: ShortString) : SizeInt
function Pos(const v: Variant; const a: AnsiString) : SizeInt
function Pos(const v: Variant; const w: WideString) : SizeInt
function Pos(const v: Variant; const w: UnicodeString) : SizeInt
function Pos(const v1: Variant; const v2: Variant) : SizeInt

```

Visibility: default

Description: Pos returns the index of Substr in S, if S contains Substr. In case Substr isn't found, 0 is returned. The search is case-sensitive.

Errors: None

See also: Length ([1194](#)), Copy ([1194](#)), Delete ([1308](#)), Insert ([1345](#))

Listing: ./refex/ex48.pp

Program Example48;

{ Program to demonstrate the Pos function. }

Var

S : String;

begin

S:= 'The first space in this sentence is at position : ';

WriteLn (S,pos(' ',S));

S:= 'The last letter of the alphabet doesn't appear in this sentence ';

If (Pos ('Z',S)=0) and (Pos('z',S)=0) then

WriteLn (S);

end.

75.11.309 power(variant,variant):variant

Synopsis: Implement power (**) operation on variants.

Declaration: operator ** (const op1: variant; const op2: variant) : variant

Visibility: default

Description: The implementation of the power ** operation is delegated to the variant manager with operation opPower.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator *(variant, variant): variant ([1194](#))

75.11.310 Pred

Synopsis: Return previous element for an ordinal type.

Declaration: function Pred(X: TOrdinal) : TOrdinal

Visibility: default

Description: Pred returns the element that precedes the element that was passed to it. If it is applied to the first value of the ordinal type, and the program was compiled with range checking on ({ \$R+ }), then a run-time error will be generated.

For an example, see Ord ([1362](#))

Errors: Run-time error 201 is generated when the result is out of range.

See also: Ord ([1362](#)), Succ ([1400](#)), High ([1337](#)), Low ([1356](#))

75.11.311 prefetch

Synopsis: Prefetch a memory location

Declaration: `procedure prefetch(const mem)`

Visibility: default

Description: `Prefetch` can be used to optimize the CPU behaviour by already loading a memory location. It is mainly used as a hint for those processors that support it.

Errors: None.

75.11.312 ptr

Synopsis: Combine segment and offset to pointer

Declaration: `function ptr(sel: LongInt; off: LongInt) : FarPointer`

Visibility: default

Description: `Ptr` returns a pointer, pointing to the address specified by segment `Sel` and offset `Off`.

Remark:

1. In the 32/64-bit flat-memory model supported by Free Pascal, this function is obsolete.
2. The returned address is simply the offset.

Errors: None.

See also: `Addr` ([1267](#))

Listing: `./refex/ex59.pp`

Program `Example59;`

{ Program to demonstrate the Ptr (compatibility) function. }

type `pString = ^String;`

Var `P : pString;`
`S : String;`

begin

`S := 'Hello , World !';`
`P := pString (Ptr (Seg (S), Longint (Ofs (S))));`
{ P now points to S ! }
`Writeln (P^);`

end.

75.11.313 RaiseList

Synopsis: List of currently raised exceptions.

Declaration: `function RaiseList : PExceptObject`

Visibility: default

Description: `RaiseList` returns a pointer to the list of currently raised exceptions (i.e. a pointer to the first exception block).

75.11.314 Random

Synopsis: Generate random number

Declaration: `function Random(l: LongInt) : LongInt`
`function Random(l: Int64) : Int64`
`function Random : extended`

Visibility: default

Description: `Random` returns a random number larger or equal to 0 and strictly less than `L`. If the argument `L` is omitted, a Real number between 0 and 1 is returned (0 included, 1 excluded).

Remark: The Free Pascal implementation of the `Random` routine uses the Mersenne Twister to simulate randomness. This implementation has a better statistical distribution than for example a Linear Congruential generator algorithm, but is considerably slower than the latter. If speed is an issue, then alternate random number generators should be considered.

Errors: None.

See also: `Randomize` ([1368](#))

Listing: `./refex/ex49.pp`

Program `Example49`;

{ Program to demonstrate the Random and Randomize functions. }

Var `l, Count, guess : Longint;`
`R : Real;`

begin

`Randomize`; *{ This way we generate a new sequence every time the program is run }*

`Count:=0;`

For `i:=1 to 1000 do`

`If Random>0.5 then inc(Count);`

`Writeln ('Generated ',Count,' numbers > 0.5');`

`Writeln ('out of 1000 generated numbers.');`

`count:=0;`

For `i:=1 to 5 do`

`begin`

`write ('Guess a number between 1 and 5 : ');`

`readln(Guess);`

`If Guess=Random(5)+1 then inc(count);`

`end;`

`Writeln ('You guessed ',Count,' out of 5 correct.');`

end.

75.11.315 Randomize

Synopsis: Initialize random number generator

Declaration: `procedure Randomize`

Visibility: default

Description: `Randomize` initializes the random number generator of Free Pascal, by giving a value to `Randseed`, calculated with the system clock.

For an example, see `Random` ([1368](#)).

Errors: None.

See also: [Random \(1368\)](#)

75.11.316 Read

Synopsis: Read from a text file into variable

Declaration: `procedure Read(var F: Text; Args: Arguments)`
`procedure Read(Args: Arguments)`

Visibility: default

Description: Read reads one or more values from a file F, and stores the result in V1, V2, etc.; If no file F is specified, then standard input is read. If F is of type Text, then the variables V1, V2 etc. must be of type Char, Integer, Real, String. If F is a typed file, then each of the variables must be of the type specified in the declaration of F. Untyped files are not allowed as an argument.

In earlier versions of FPC, it was also allowed to read Pchar null-terminated strings, but this has been removed, since there is no buffer checking possible.

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: [ReadLn \(1370\)](#), [Blockread \(1292\)](#), [Write \(1194\)](#), [Blockwrite \(1293\)](#)

Listing: ./refex/ex50.pp

Program Example50;

```
{ Program to demonstrate the Read(Ln) function. }

Var S : String;
    C : Char;
    F : File of char;

begin
  Assign (F, 'ex50.pp');
  Reset (F);
  C:= 'A';
  Writeln ('The characters before the first space in ex50.pp are : ');
  While not Eof(f) and (C<>' ') do
    Begin
      Read (F,C);
      Write (C);
    end;
  Writeln;
  Close (F);
  Writeln ('Type some words. An empty line ends the program. ');
  repeat
    ReadLn (S);
  until S= '';
end.
```

75.11.317 ReadBarrier

Synopsis: Memory Read Barrier

Declaration: `procedure ReadBarrier`

Visibility: `default`

Description: `ReadBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads before the instruction will be finished before this instruction, before memory reads after the instruction occur.

See also: `ReadDependencyBarrier` ([1370](#)), `ReadWriteBarrier` ([1370](#)), `WriteBarrier` ([1416](#))

75.11.318 ReadDependencyBarrier

Synopsis: Memory Read Dependency Barrier

Declaration: `procedure ReadDependencyBarrier`

Visibility: `default`

Description: `ReadDependencyBarrier` is a low-level instruction to force a read barrier in the CPU: all memory reads (loads) depending on previous loads are separate from the ones following the instruction.

See also: `ReadBarrier` ([1369](#)), `ReadWriteBarrier` ([1370](#)), `WriteBarrier` ([1416](#))

75.11.319 ReadLn

Synopsis: Read from a text file into variable and goto next line

Declaration: `procedure ReadLn(var F: Text; Args: Arguments)`
`procedure ReadLn(Args: Arguments)`

Visibility: `default`

Description: `Read` reads one or more values from a file `F`, and stores the result in `V1`, `V2`, etc. After that it goes to the next line in the file. The end of the line is marked by any of the supported line ending styles, independent of the platform on which the code is running (supported line ending styles are CRLF, LF or CR). The end-of-line marker is not considered part of the line and is ignored.

If no file `F` is specified, then standard input is read. The variables `V1`, `V2` etc. must be of type `Char`, `Integer`, `Real`, `String` or `PChar`.

For an example, see `Read` ([1369](#)).

Errors: If no data is available, empty values are returned (0 for ordinal values, empty strings for string values)

See also: `Read` ([1369](#)), `Blockread` ([1292](#)), `Write` ([1194](#)), `Blockwrite` ([1293](#))

75.11.320 ReadWriteBarrier

Synopsis: Memory read/write barrier

Declaration: `procedure ReadWriteBarrier`

Visibility: `default`

Description: `ReadWriteBarrier` is a low-level instruction to force a read/write barrier in the CPU: both read (Loads) and write (stores) operations before and after the barrier are separate.

See also: `ReadBarrier` ([1369](#)), `ReadDependencyBarrier` ([1370](#)), `WriteBarrier` ([1416](#))

75.11.321 Real2Double

Synopsis: Convert Turbo Pascal style real to double.

Declaration: `function Real2Double(r: real48) : Double`

Visibility: default

Description: The `Real2Double` function converts a Turbo Pascal style real (6 bytes long) to a native Free Pascal double type. It can be used e.g. to read old binary TP files with FPC and convert them to Free Pascal binary files.

Note that the assignment operator has been overloaded so a `Real48` type can be assigned directly to a double or extended.

Errors: None.

Listing: `./refex/ex110.pp`

```

program Example110;

{ Program to demonstrate the Real2Double function. }

Var
  i : integer;
  R : Real48;
  D : Double;
  E : Extended;
  F : File of Real48;

begin
  Assign(F, 'reals.dat');
  Reset(f);
  For i:=1 to 10 do
    begin
      Read(F,R);
      D:=Real2Double(R);
      WriteLn('Real ',i,' : ',D);
      D:=R;
      WriteLn('Real (direct to double) ',i,' : ',D);
      E:=R;
      WriteLn('Real (direct to Extended) ',i,' : ',E);
    end;
  Close(f);
end.
```

75.11.322 ReAllocMem

Synopsis: Re-allocate memory on the heap

Declaration: `function ReAllocMem(var p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMem` resizes the memory pointed to by `P` so it has size `Size`. The value of `P` may change during this operation. The contents of the memory pointed to by `P` (if any) will be copied to the new location, but may be truncated if the newly allocated memory block is smaller in size. If a larger block is allocated, only the used memory is initialized, extra memory will not be zeroed out.

Note that `P` may be `nil`, in that case the behaviour of `ReAllocMem` is equivalent to `Getmem`.

See also: [GetMem \(1331\)](#), [FreeMem \(1328\)](#)

75.11.323 ReAllocMemory

Synopsis: Alias for [ReAllocMem \(1371\)](#)

Declaration: `function ReAllocMemory(p: pointer; Size: PtrUInt) : pointer`

Visibility: default

Description: `ReAllocMemory` is an alias for [ReAllocMem \(1371\)](#).

See also: [ReAllocMem \(1371\)](#)

75.11.324 ReleaseExceptionObject

Synopsis: Decrease the reference count of the current exception object.

Declaration: `procedure ReleaseExceptionObject`

Visibility: default

Description: `ReleaseExceptionObject` decreases the reference count of the current exception object. This should be called whenever a reference to the exception object was obtained via the [AcquireExceptionObject \(1266\)](#) call.

Calling this method is only valid within an except block.

Errors: If there is no current exception object, a run-time error 231 will occur.

See also: [AcquireExceptionObject \(1266\)](#)

75.11.325 Rename

Synopsis: Rename file on disk

Declaration: `procedure Rename(var f: File; const s: ShortString)`
`procedure Rename(var f: File; const p: PAnsiChar)`
`procedure Rename(var f: File; const c: AnsiChar)`
`procedure Rename(var f: File; const s: UnicodeString)`
`procedure Rename(var f: File; const s: RawByteString)`
`procedure Rename(var t: Text; const s: shortstring)`
`procedure Rename(var t: Text; const p: PAnsiChar)`
`procedure Rename(var t: Text; const c: AnsiChar)`
`procedure Rename(var t: Text; const s: unicodestring)`
`procedure Rename(var t: Text; const s: RawByteString)`

Visibility: default

Description: `Rename` changes the name of the assigned file `F` to `S`. `F` must be assigned, but not opened.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: [Erase \(1317\)](#)

Listing: `./refex/ex77.pp`

Program Example77;

```
{ Program to demonstrate the Rename function. }
Var F : Text;

begin
    Assign (F,paramstr(1));
    Rename (F,paramstr(2));
end.
```

75.11.326 Reset

Synopsis: Open file for reading

Declaration: `procedure Reset (var f: File; l: LongInt)`
`procedure Reset (var f: File)`
`procedure Reset (var f: TypedFile)`
`procedure Reset (var t: Text)`

Visibility: default

Description: `Reset` opens a file `F` for reading. `F` can be any file type. If `F` is a text file, or refers to standard I/O (e.g. `”) then it is opened read-only, otherwise it is opened using the mode specified in filemode. If F is an untyped file, the record size can be specified in the optional parameter L. A default value of 128 is used. File sharing is not taken into account when calling Reset.`

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: Rewrite ([1374](#)), Assign ([1270](#)), Close ([1298](#)), Append ([1268](#))

Listing: `./refex/ex51.pp`

Program Example51;

```
{ Program to demonstrate the Reset function. }

Function FileExists (Name : String) : boolean;

Var F : File;

begin
    {SI-}
    Assign (F,Name);
    Reset (F);
    {SI+}
    FileExists := (IOResult=0) and (Name<>' ');
    if FileExists then
        Close (f);
end;

begin
    if FileExists (Paramstr(1)) then
        Writeln ('File found')
    else
        Writeln ('File NOT found');
end.
```

75.11.327 ResumeThread

Synopsis: Resume a suspended thread.

Declaration: `function ResumeThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `ResumeThread` causes a suspended thread (using `SuspendThread` (1400)) to resume its execution. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `SuspendThread` (1400), `KillThread` (1351)

75.11.328 Rewrite

Synopsis: Open file for writing

Declaration: `procedure Rewrite(var f: File; l: LongInt)`
`procedure Rewrite(var f: File)`
`procedure Rewrite(var f: TypedFile)`
`procedure Rewrite(var t: Text)`

Visibility: default

Description: `Rewrite` opens a file `F` for writing. `F` can be any file type. If `F` is an untyped or typed file, then it is opened for reading and writing. If `F` is an untyped file, the record size can be specified in the optional parameter `L`. Default a value of 128 is used. if `Rewrite` finds a file with the same name as `F`, this file is truncated to length 0. If it doesn't find such a file, a new file is created. Contrary to Turbo Pascal, Free Pascal opens the file with mode `fmoutput`. If it should be opened in `fminout` mode, an extra call to `Reset` (1373) is needed. File sharing is not taken into account when calling `Rewrite`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Reset` (1373), `Assign` (1270), `Close` (1298), `Flush` (1326), `Append` (1268)

Listing: `./refex/ex52.pp`

Program `Example52`;

{ Program to demonstrate the Rewrite function. }

Var `F : File`;
`l : longint`;

begin

`Assign (F, 'Test.tmp');`
{ Create the file. Recordsize is 4 }
`Rewrite (F, Sizeof(l));`
For `l:=1 to 10 do`
`BlockWrite (F,l,1);`
`close (f);`
{ F contains now a binary representation of
10 longints going from 1 to 10 }

end.

75.11.329 rightshift(variant,variant):variant

Synopsis: Implement binary `shr` operation on variants.

Declaration: `operator shr(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the `shr` operation is delegated to the variant manager with operation `opshiftright`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `shl(variant, variant): variant` ([1194](#))

75.11.330 rmdir

Synopsis: Remove directory when empty.

Declaration: `procedure rmdir(const s: shortstring); Overload`
`procedure rmdir(const s: RawByteString); Overload`
`procedure rmdir(const s: unicodestring); Overload`

Visibility: default

Description: `Rmdir` removes the directory `S`.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Chdir` ([1297](#)), `Mkdir` ([1357](#))

Listing: `./refex/ex53.pp`

Program `Example53;`

{ Program to demonstrate the Mkdir and Rmdir functions. }

Const `D : String[8] = 'TEST.DIR';`

Var `S : String;`

begin

```

  WriteLn ('Making directory ',D);
  Mkdir (D);
  WriteLn ('Changing directory to ',D);
  ChDir (D);
  GetDir (0,S);
  WriteLn ('Current Directory is : ',S);
  WriteLn ('Going back');
  ChDir ('..');
  WriteLn ('Removing directory ',D);
  Rmdir (D);

```

end.

75.11.331 RolByte

Synopsis: Rotate bits of a byte value to the left

Declaration: `function RolByte(const AValue: Byte) : Byte`
`function RolByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: `RolByte` rotates the bits of the byte `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1377](#)), `RolWord` ([1376](#)), `RolDWord` ([1376](#)), `RolQWord` ([1376](#))

75.11.332 RolDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the left

Declaration: `function RolDWord(const AValue: DWord) : DWord`
`function RolDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: `RolDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1376](#)), `RolWord` ([1376](#)), `RorDWord` ([1377](#)), `RolQWord` ([1376](#))

75.11.333 RolQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the left

Declaration: `function RolQWord(const AValue: QWord) : QWord`
`function RolQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the left. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1376](#)), `RolWord` ([1376](#)), `RolDWord` ([1376](#)), `RorQWord` ([1377](#))

75.11.334 RolWord

Synopsis: Rotate bits of a word value to the left

Declaration: `function RolWord(const AValue: Word) : Word`
`function RolWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RolWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1376](#)), `RorWord` ([1377](#)), `RolDWord` ([1376](#)), `RolQWord` ([1376](#))

75.11.335 RorByte

Synopsis: Rotate bits of a byte value to the right

Declaration: `function RorByte(const AValue: Byte) : Byte`
`function RorByte(const AValue: Byte; const Dist: Byte) : Byte`

Visibility: default

Description: `RorByte` rotates the bits of the byte `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RolByte` ([1376](#)), `RorWord` ([1377](#)), `RorDWord` ([1377](#)), `RorQWord` ([1377](#))

75.11.336 RorDWord

Synopsis: Rotate bits of a DWord (cardinal) value to the right

Declaration: `function RorDWord(const AValue: DWord) : DWord`
`function RorDWord(const AValue: DWord; const Dist: Byte) : DWord`

Visibility: default

Description: `RorDWord` rotates the bits of the DWord (cardinal) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1377](#)), `RolDWord` ([1376](#)), `RorWord` ([1377](#)), `RorQWord` ([1377](#))

75.11.337 RorQWord

Synopsis: Rotate bits of a QWord (64-bit) value to the right

Declaration: `function RorQWord(const AValue: QWord) : QWord`
`function RorQWord(const AValue: QWord; const Dist: Byte) : QWord`

Visibility: default

Description: `RorQWord` rotates the bits of the QWord (64-bit) `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1377](#)), `RorWord` ([1377](#)), `RorDWord` ([1377](#)), `RolQWord` ([1376](#))

75.11.338 RorWord

Synopsis: Rotate bits of a word value to the right

Declaration: `function RorWord(const AValue: Word) : Word`
`function RorWord(const AValue: Word; const Dist: Byte) : Word`

Visibility: default

Description: `RorWord` rotates the bits of the word `AValue` with `Dist` positions to the right. If `Dist` is not specified, then 1 is assumed.

Errors: None.

See also: `RorByte` ([1377](#)), `RolWord` ([1376](#)), `RorDWord` ([1377](#)), `RorQWord` ([1377](#))

75.11.339 round

Synopsis: Round floating point value to nearest integer number.

Declaration: `function round(d: ValReal) : Int64`

Visibility: default

Description: Round rounds X to the closest integer, which may be bigger or smaller than X.

In the case of .5, the algorithm uses "banker's rounding": .5 values are always rounded towards the even number.

Errors: None.

See also: [Frac \(1328\)](#), [Int \(1345\)](#), [Trunc \(1406\)](#)

Listing: `./refex/ex54.pp`

Program Example54;

{ Program to demonstrate the Round function. }

begin

```
Writeln (Round(1234.56)); { Prints 1235 }
Writeln (Round(-1234.56)); { Prints -1235 }
Writeln (Round(12.3456)); { Prints 12 }
Writeln (Round(-12.3456)); { Prints -12 }
Writeln (Round(2.5)); { Prints 2 (down) }
Writeln (Round(3.5)); { Prints 4 (up) }
```

end.

75.11.340 RTLEventCreate

Synopsis: Create a new RTL event

Declaration: `function RTLEventCreate : PRTLEvent`

Visibility: default

Description: RTLEventCreate creates and initializes a new RTL event. RTL events are used to notify other threads that a certain condition is met, and to notify other threads of condition changes (conditional variables).

The function returns an initialized RTL event, which must be disposed of with RTLEventdestroy ([1378](#))

RTLEvent is used mainly for the synchronize method.

See also: [RTLEventDestroy \(1378\)](#), [RTLEventSetEvent \(1379\)](#), [RTLEventReSetEvent \(1379\)](#), [RTLEventWaitFor \(1379\)](#)

75.11.341 RTLeventdestroy

Synopsis: Destroy a RTL Event

Declaration: `procedure RTLeventdestroy(state: PRTLEvent)`

Visibility: default

Description: `RTLeventdestroy` destroys the RTL event `State`. After a call to `RTLeventdestroy`, the `State` RTL event may no longer be used.

See also: `RTLeventCreate` ([1378](#)), `RTLeventResetEvent` ([1379](#)), `RTLeventSetEvent` ([1379](#))

75.11.342 RTLeventResetEvent

Synopsis: Reset an event

Declaration: `procedure RTLeventResetEvent (state: PRTLEvent)`

Visibility: `default`

Description: `RTLeventResetEvent` resets the event: this should be used to undo the signaled state of an event. Resetting an event that is not set (or was already reset) has no effect.

See also: `RTLeventCreate` ([1378](#)), `RTLeventDestroy` ([1378](#)), `RTLeventSetEvent` ([1379](#)), `RTLeventWaitFor` ([1379](#))

75.11.343 RTLeventSetEvent

Synopsis: Notify threads of the event.

Declaration: `procedure RTLeventSetEvent (state: PRTLEvent)`

Visibility: `default`

Description: `RTLeventSetEvent` notifies other threads which are listening, that the event has occurred.

See also: `RTLeventCreate` ([1378](#)), `RTLeventResetEvent` ([1379](#)), `RTLeventDestroy` ([1378](#)), `RTLeventWaitFor` ([1379](#))

75.11.344 RTLeventWaitFor

Synopsis: Wait for an event.

Declaration: `procedure RTLeventWaitFor (state: PRTLEvent)`
`procedure RTLeventWaitFor (state: PRTLEvent; timeout: LongInt)`

Visibility: `default`

Description: `RTLeventWaitFor` suspends the thread till the event occurs. The event will occur when another thread calls `RTLeventSetEvent` ([1379](#)) on `State`.

By default, the thread will be suspended indefinitely. However, if `TimeOut` is specified, then the thread will resume after timeout milliseconds have elapsed.

See also: `RTLeventCreate` ([1378](#)), `RTLeventDestroy` ([1378](#)), `RTLeventSetEvent` ([1379](#)), `RTLeventWaitFor` ([1379](#))

75.11.345 RunError

Synopsis: Generate a run-time error.

Declaration: `procedure RunError (w: Word)`
`procedure RunError`

Visibility: `default`

Description: `RunError` stops the execution of the program, and generates a run-time error `ErrorCode`.

Errors: None.

See also: `Exit` ([1319](#)), `Halt` ([1336](#))

Listing: `./refex/ex55.pp`

Program `Example55`;

```
{ Program to demonstrate the RunError function. }

begin
  { The program will stop and emit a run-error 106 }
  RunError (106);
end.
```

75.11.346 SarInt64

Synopsis: 64-bit Shift Arithmetic Right

Declaration: `function SarInt64(const AValue: Int64) : Int64`
`function SarInt64(const AValue: Int64; Shift: Byte) : Int64`

Visibility: default

Description: `SarInt64` performs an arithmetic right shift for `Shift` positions on a 64-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1380](#)), `SarSmallInt` ([1381](#)), `SarLongInt` ([1380](#))

75.11.347 SarLongint

Synopsis: 32-bit Shift Arithmetic Right

Declaration: `function SarLongint(const AValue: LongInt; const Shift: Byte) : LongInt`

Visibility: default

Description: `SarLongint` performs an arithmetic right shift for `Shift` positions on a 32-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortInt` ([1380](#)), `SarSmallInt` ([1381](#)), `SarInt64` ([1380](#))

75.11.348 SarShortint

Synopsis: 8-bit Shift Arithmetic Right

Declaration: `function SarShortint(const AValue: ShortInt; const Shift: Byte)`
`: ShortInt`

Visibility: default

Description: `SarShortint` performs an arithmetic right shift for `Shift` positions on an 8-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarSmallint` ([1381](#)), `SarLongint` ([1380](#)), `SarInt64` ([1380](#))

75.11.349 SarSmallint

Synopsis: 16-bit Shift Arithmetic Right

Declaration: `function SarSmallint(const AValue: SmallInt; const Shift: Byte)
: SmallInt`

Visibility: default

Description: `SarSmallint` performs an arithmetic right shift for `Shift` positions on an 16-bit integer `AValue` and returns the result. `Shift` is optional, and is 1 by default. The difference with the regular `Shr` shift operation is that the leftmost bit is preserved during the shift operation.

See also: `SarShortint` ([1380](#)), `SarLongint` ([1380](#)), `SarInt64` ([1380](#))

75.11.350 Seek

Synopsis: Set file position

Declaration: `procedure Seek(var f: File; Pos: Int64)`

Visibility: default

Description: `Seek` sets the file-pointer for file `F` to record `Nr. Count`. The first record in a file has `Count=0`. `F` can be any file type, except `Text`. If `F` is an untyped file, with no record size specified in `Reset` ([1373](#)) or `Rewrite` ([1374](#)), 128 is assumed.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Eof` ([1315](#)), `SeekEof` ([1382](#)), `SeekEoln` ([1382](#))

Listing: `./refex/ex56.pp`

Program `Example56;`

```
{ Program to demonstrate the Seek function. }

Var
  F : File;
  I, J : longint;

begin
  { Create a file and fill it with data }
  Assign (F, 'test.tmp');
  Rewrite(F); { Create file }
  Close(f);
  FileMode:=2;
  ReSet (F, Sizeof(i)); { Opened read/write }
  For I:=0 to 10 do
    BlockWrite (F, I, 1);
  { Go Back to the begining of the file }
  Seek(F, 0);
  For I:=0 to 10 do
    begin
      BlockRead (F, J, 1);
      If J<>I then
        Writeln ('Error: expected ', i, ', got ', j);
    end;
```

```

    Close (f);
end.

```

75.11.351 SeekEOF

Synopsis: Set file position to end of file

Declaration: `function SeekEOF (var t: Text) : Boolean`
`function SeekEOF : Boolean`

Visibility: default

Description: `SeekEof` returns `True` if the file-pointer is at the end of the file. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-file marker is reached.

If the end-of-file marker is reached, `True` is returned. Otherwise, `False` is returned.

If the parameter `F` is omitted, standard `Input` is assumed.

Remark: The `SeekEOF` function can only be used on real textfiles: when assigning the file to other kinds of (virtual) text files, the function may fail, although it will perform a number of tests to guard against wrong usage.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1315](#)), `SeekEoln` ([1382](#)), `Seek` ([1381](#))

Listing: `./refex/ex57.pp`

Program `Example57`;

```

{ Program to demonstrate the SeekEof function. }
Var C : Char;

begin
  { this will print all characters from standard input except
    Whitespace characters. }
  While Not SeekEof do
    begin
      Read (C);
      Write (C);
    end;
end.

```

75.11.352 SeekEOLn

Synopsis: Set file position to end of line

Declaration: `function SeekEOLn (var t: Text) : Boolean`
`function SeekEOLn : Boolean`

Visibility: default

Description: `SeekEoln` returns `True` if the file-pointer is at the end of the current line. It ignores all whitespace. Calling this function has the effect that the file-position is advanced until the first non-whitespace character or the end-of-line marker is reached. If the end-of-line marker is reached, `True` is returned. Otherwise, `False` is returned. The end-of-line marker is defined as `#10`, the `LineFeed` character. If the parameter `F` is omitted, standard `Input` is assumed.

Errors: A run-time error is generated if the file `F` isn't opened.

See also: `Eof` ([1315](#)), `SeekEof` ([1382](#)), `Seek` ([1381](#))

Listing: `./refex/ex58.pp`

Program `Example58`;

```
{ Program to demonstrate the SeekEoln function. }
Var
  C : Char;

begin
  { This will read the first line of standard output and print
  all characters except whitespace. }
  While not SeekEoln do
    Begin
      Read (c);
      Write (c);
    end;
end.
```

75.11.353 Seg

Synopsis: Return segment

Declaration: `function Seg(var X) : LongInt`

Visibility: default

Description: `Seg` returns the segment of the address of a variable. This function is only supported for compatibility. In Free Pascal, it returns always 0, since Free Pascal uses a flat 32/64 bit memory model. In such a memory model segments have no meaning.

Errors: None.

See also: `DSeg` ([1310](#)), `CSeg` ([1306](#)), `Ofs` ([1362](#)), `Ptr` ([1367](#))

Listing: `./refex/ex60.pp`

Program `Example60`;

```
{ Program to demonstrate the Seg function. }
Var
  W : Word;

begin
  W:=Seg(W); { W contains its own Segment }
end.
```

75.11.354 SemaphoreDestroy

Synopsis: Destroy a semaphore

Declaration: `procedure SemaphoreDestroy(const sem: Pointer)`

Visibility: default

Description: `SemaphoreDestroy` destroys a semaphore, created with `SemaphoreInit` (1384).

The use of semaphores requires thread support (use `#rtl.threads` (527) unit on unices).

Errors: If no thread support is compiled in, then calling this function will result in a run-time error 232.

See also: `#rtl.threads` (527), `SemaphoreWait` (1384), `SemaphorePost` (1384), `SemaphoreInit` (1384)

75.11.355 SemaphoreInit

Synopsis: Create a new semaphore

Declaration: `function SemaphoreInit : Pointer`

Visibility: default

Description: `SemaphoreInit` creates a new semaphore, which can be used in thread synchronization. The semaphore can be used with `SemaphoreWait` (1384) and `SemaphorePost` (1384), and must be destroyed with `SemaphoreDestroy` (1383).

The result is an untyped pointer (thread support is platform dependent).

The use of semaphores requires thread support (use `#rtl.threads` (527) unit on unices).

Errors: On error, `Pointer(-1)` is returned. If no thread support is compiled in, then calling this function will result in a run-time error 232.

See also: `#rtl.threads` (527), `SemaphoreWait` (1384), `SemaphorePost` (1384), `SemaphoreDestroy` (1383)

75.11.356 SemaphorePost

Synopsis: Make semaphore available

Declaration: `procedure SemaphorePost(const sem: Pointer)`

Visibility: default

Description: `SemaphorePost` makes the semaphore `FSem` to available. Any threads that were waiting for the semaphore `FSem` to become available (using `SemaphoreWait` (1384), will continue to execute.

The use of semaphores requires thread support (use `#rtl.threads` (527) unit on unices).

Errors: If no thread support is compiled in, then calling this function will result in a run-time error 232.

See also: `#rtl.threads` (527), `SemaphoreInit` (1384), `SemaphoreWait` (1384), `SemaphoreDestroy` (1383)

75.11.357 SemaphoreWait

Synopsis: Wait for semaphore to become available

Declaration: `procedure SemaphoreWait(const sem: Pointer)`

Visibility: default

Description: `SemaphoreWait` waits (indefinitely) for the semaphore `FSem` to become available.

The use of semaphores requires thread support (use `#rtl.threads` (527) unit on unices).

Errors: If no thread support is compiled in, then calling this function will result in a run-time error 232.

See also: `#rtl.threads` (527), `SemaphoreInit` (1384), `SemaphorePost` (1384), `SemaphoreDestroy` (1383)

75.11.358 Set8087CW

Declaration: `procedure Set8087CW(cw: Word)`

Visibility: default

75.11.359 SetCodePage

Synopsis: Set the codepage of a string

Declaration: `procedure SetCodePage(var s: RawByteString; CodePage: TSystemCodePage;
Convert: Boolean)`

Visibility: default

Description: `SetCodePage` sets the codepage of a string `S` to `CodePage`. If `Convert` is `True` then the string will be transcoded to the new codepage. The resulting string will have reference count 1.

See also: `StringCodePage` ([1396](#))

75.11.360 Setjmp

Synopsis: Save current execution point.

Declaration: `function Setjmp(var S: jmp_buf) : LongInt`

Visibility: default

Description: `SetJmp` fills `env` with the necessary data for a jump back to the point where it was called. It returns zero if called in this way. If the function returns nonzero, then it means that a call to `LongJmp` ([1355](#)) with `env` as an argument was made somewhere in the program.

Errors: None.

See also: `LongJmp` ([1355](#))

Listing: `./refex/ex79.pp`

```

program example79;

{ Program to demonstrate the setjmp, longjmp functions }

procedure dojmp(var env : jmp_buf; value : longint);
begin
    value:=2;
    Writeln ('Going to jump !');
    { This will return to the setjmp call,
      and return value instead of 0 }
    longjmp(env,value);
end;

var env : jmp_buf;

begin
    if setjmp(env)=0 then
        begin
            writeln ('Passed first time.');
```

```

            dojmp(env,2);
```

```

    end
  else
    writeln ('Passed second time. ');
  end.

```

75.11.361 SetMemoryManager

Synopsis: Set a memory manager

Declaration: `procedure SetMemoryManager(const MemMgr: TMemoryManager)`

Visibility: default

Description: `SetMemoryManager` sets the current memory manager record to `MemMgr`.

For an example, see the programmer's guide.

Errors: None.

See also: `GetMemoryManager` ([1331](#)), `IsMemoryManagerSet` ([1350](#))

75.11.362 SetMultiByteConversionCodePage

Synopsis: Set codepage for conversions from multi-byte strings to single-byte strings

Declaration: `procedure SetMultiByteConversionCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteConversionCodePage` sets `DefaultSystemCodePage` ([1262](#)) to `CodePage`. The effect of this change is that the default codepage used to translate multi-byte (UTF-16) strings to single-byte codepage-aware strings changes, and code page conversions will be done to the new codepage.

Do not set `DefaultSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `DefaultSystemCodePage` ([1262](#)), `SetMultiByteFileSystemCodePage` ([1386](#)), `SetMultiByteRTLFileSystemCodePage` ([1387](#))

75.11.363 SetMultiByteFileSystemCodePage

Synopsis: Set codepage used when passing strings to OS single-byte filesystem APIs

Declaration: `procedure SetMultiByteFileSystemCodePage(CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteFileSystemCodePage` sets the codepage used in single-byte OS filesystem APIs to `CodePage`. The effect of this change is that the default codepage used to translate multi-byte (UTF-16) strings to single-byte codepage-aware strings used in Filesystem APIs changes, and strings passed to the codepage-aware filesystem APIs will be passed using the new codepage.

This constant is not used if the filesystem API of the OS is multi-byte (such as on Windows).

Do not set `DefaultFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `DefaultFileSystemCodePage` ([1261](#)), `SetMultiByteConversionCodePage` ([1386](#)), `SetMultiByteRTLFileSystemCodePage` ([1387](#))

75.11.364 SetMultiByteRTLFileSystemCodePage

Synopsis: Set codepage used when interpreting strings from OS single-byte filesystem APIs

Declaration: `procedure SetMultiByteRTLFileSystemCodePage (CodePage: TSystemCodePage)`

Visibility: default

Description: `SetMultiByteRTLFileSystemCodePage` sets the codepage used to interpret strings returned by single-byte OS filesystem APIs to `CodePage`.

The effect of this change is that the default codepage used to translate single byte strings obtained from the OS to single-byte codepage-aware strings or multi-byte strings changes, and strings obtained from the codepage-aware filesystem APIs will be interpreted using the new codepage.

this constant is not used if the filesystem API of the OS is multi-byte (such as on Windows).

Do not set `DefaultRTLFileSystemCodePage` directly, as additional actions may need to be done when changing the code page.

See also: `SetMultiByteFileSystemCodePage` ([1386](#)), `SetMultiByteConversionCodePage` ([1386](#)), `SetMultiByteRTLFileSystemCodePage` ([1387](#))

75.11.365 SetMXCSR

Declaration: `procedure SetMXCSR (w: DWord)`

Visibility: default

75.11.366 SetResourceManager

Synopsis: Set the resource manager

Declaration: `procedure SetResourceManager (const New: TResourceManager)`

Visibility: default

Description: `SetResourceManager` sets the active resource manager to `Manager`. After a call to `SetResourceManager`, the functions in the `Manager` record will be used to handle resources.

Note that it is not supported to change resource managers on-the-fly: any resources or information about resources obtained should be discarded prior to a call to `SetResourceManager`. Typically, `SetResourceManager` should be called once, at program startup.

Errors: None.

See also: `TResourceManager` ([1245](#)), `GetResourceManager` ([1332](#))

75.11.367 SetSSECSR

Declaration: `procedure SetSSECSR (w: DWord)`

Visibility: default

75.11.368 SetString

Synopsis: Set length of a string and copy buffer.

Declaration: `procedure SetString(out S: AnsiString; Buf: PAnsiChar; Len: SizeInt)`
`procedure SetString(out S: AnsiString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: Shortstring; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PUnicodeChar;`
`Len: SizeInt)`
`procedure SetString(out S: UnicodeString; Buf: PChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PWideChar; Len: SizeInt)`
`procedure SetString(out S: WideString; Buf: PChar; Len: SizeInt)`

Visibility: default

Description: `SetString` sets the length of the string `S` to `Len` and if `Buf` is non-nil, copies `Len` characters from `Buf` into `S`. `S` can be an ansistring, a short string or a widestring. For `ShortStrings`, `Len` can maximally be 255.

Errors: None.

See also: `SetLength` ([1194](#))

75.11.369 SetTextBuf

Synopsis: Set size of text file internal buffer

Declaration: `procedure SetTextBuf(var f: Text; var Buf)`
`procedure SetTextBuf(var f: Text; var Buf; Size: SizeInt)`

Visibility: default

Description: `SetTextBuf` assigns an I/O buffer to a text file. The new buffer is located at `Buf` and is `Size` bytes long. If `Size` is omitted, then `SizeOf(Buf)` is assumed. The standard buffer of any text file is 128 bytes long. For heavy I/O operations this may prove too slow. The `SetTextBuf` procedure allows to set a bigger buffer for the I/O of the application, thus reducing the number of system calls, and thus reducing the load on the system resources. The maximum size of the newly assigned buffer is 65355 bytes.

Remark:

- Never assign a new buffer to an opened file. A new buffer can be assigned immediately after a call to `Rewrite` ([1374](#)), `Reset` ([1373](#)) or `Append`, but not after the file was read from/written to. This may cause loss of data. If a new buffer must be assigned after read/write operations have been performed, the file should be flushed first. This will ensure that the current buffer is emptied.
- Take care that the assigned buffer is always valid. If a local variable is assigned as a buffer, then after the program exits the local program block, the buffer will no longer be valid, and stack problems may occur.

Errors: No checking on `Size` is done.

See also: `Assign` ([1270](#)), `Reset` ([1373](#)), `Rewrite` ([1374](#)), `Append` ([1268](#))

Listing: `./refex/ex61.pp`

Program Example61;

{ Program to demonstrate the SetTextBuf function. }

Var

Fin, Fout : Text;
Ch : Char;
Bufin, Bufout : **Array**[1..10000] **of** byte;

begin

Assign (Fin, **paramstr**(1));
Reset (Fin);
Assign (Fout, **paramstr**(2));
Rewrite (Fout);
{ This is harmless before IO has begun }
{ Try this program again on a big file ,
after commenting out the following 2
lines and recompiling it. }
SetTextBuf (Fin, Bufin);
SetTextBuf (Fout, Bufout);
While not eof(Fin) **do**
 begin
 Read (Fin, ch);
 write (Fout, ch);
 end;
 Close (Fin);
 Close (Fout);

end.

75.11.370 SetTextCodePage

Synopsis: Set the codepage used in a text file.

Declaration: `procedure SetTextCodePage(var T: Text; CodePage: TSystemCodePage)`

Visibility: default

Description: `SetTextCodePage` sets the codepage that the text file T uses. All strings written to the file will be converted to the indicated codepage. By default, the codepage is set to CP_ACP.

Errors: None.

See also: `TextRec` ([1239](#)), `GetTextCodePage` ([1332](#))

75.11.371 SetTextLineEnding

Synopsis: Set the end-of-line character for the given text file.

Declaration: `procedure SetTextLineEnding(var f: Text; Ending: string)`

Visibility: default

Description: `SetTextLineEnding` sets the end-of-line character for the text file F to Ending. By default, this is the string indicated by `DefaultTextLineBreakStyle` ([1194](#)).

Errors: None.

See also: `DefaultTextLineBreakStyle` ([1194](#)), `TTextLineBreakStyle` ([1248](#))

75.11.372 SetThreadManager

Synopsis: Set the thread manager, optionally return the current thread manager.

Declaration:

```
function SetThreadManager(const NewTM: TThreadManager;
                        var OldTM: TThreadManager) : Boolean
function SetThreadManager(const NewTM: TThreadManager) : Boolean
```

Visibility: default

Description: `SetThreadManager` sets the thread manager to `NewTM`. If `OldTM` is given, `SetThreadManager` uses it to return the previously used thread manager.

The function returns `True` if the threadmanager was set succesfully, `False` if an error occurred.

For more information about thread programming, see the programmer's guide.

Errors: If an error occurred cleaning up the previous manager, or an error occurred initializing the new manager, `False` is returned.

See also: `GetThreadManager` ([1333](#)), `TThreadManager` ([1250](#))

75.11.373 SetUnicodeStringManager

Synopsis: Set the unicodestring manager

Declaration:

```
procedure SetUnicodeStringManager(const New: TUnicodeStringManager)
procedure SetUnicodeStringManager(const New: TUnicodeStringManager;
                                var Old: TUnicodeStringManager)
```

Visibility: default

Description: `SetUnicodeStringManager` sets the current unicodestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

UnicodeStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a Unicode-String manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom unicodestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TUnicodeStringManager` ([1252](#))

75.11.374 SetVariantManager

Synopsis: Set the current variant manager.

Declaration:

```
procedure SetVariantManager(const VarMgr: tvariantmanager)
```

Visibility: default

Description: `SetVariantManager` sets the variant manager to `varmgr`.

See also: `GetVariantManager` ([1333](#))

75.11.375 SetWideStringManager

Synopsis: Set the widestring manager

Declaration: `procedure SetWideStringManager(const New: TUnicodeStringManager)
 procedure SetWideStringManager(const New: TUnicodeStringManager;
 var Old: TUnicodeStringManager)`

Visibility: default

Description: `SetWideStringManager` sets the current widestring manager to `New`. Optionally, it returns the currently active widestring manager in `Old`.

WideStrings are implemented in different ways on different platforms. Therefore, the Free Pascal Runtime library has no fixed implementation of widestring routines. Instead, it defines a WideString manager record, with callbacks that can be set to an implementation which is most efficient on the current platform. On windows, standard Windows routines will be used. On Unix and Linux, an implementation based on the C library is available (in unit `cwstring`).

It is possible to implement a custom widestring manager, optimized for the current application, without having to recompile the complete Run-Time Library.

See also: `TWideStringManager` ([1259](#))

75.11.376 ShortCompareText

Synopsis: Compare 2 shortstrings

Declaration: `function ShortCompareText(const S1: shortstring; const S2: shortstring)
 : SizeInt`

Visibility: default

Description: `ShortCompareText` compares two shortstrings, `S1` and `S2`, and returns the following result:

<0 if `S1 < S2`.

0 if `S1 = S2`.

>0 if `S1 > S2`.

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `CompareText` ([1495](#))

75.11.377 sin

Synopsis: Calculate sine of angle

Declaration: `function sin(d: ValReal) : ValReal`

Visibility: default

Description: `Sin` returns the sine of its argument `X`, where `X` is an angle in radians. If the absolute value of the argument is larger than $2\hat{6}3$, then the result is undefined.

Errors: None.

See also: Cos ([1305](#)), Pi ([1364](#)), Exp ([1320](#)), Ln ([1352](#))

Listing: ./refex/ex62.pp

Program Example62;

```
{ Program to demonstrate the Sin function. }

begin
  Writeln (Sin(Pi):0:1); { Prints 0.0 }
  Writeln (Sin(Pi/2):0:1); { Prints 1.0 }
end.
```

75.11.378 SizeOf

Synopsis: Return size of a variable or type.

Declaration: function SizeOf(X: TAnyType) : LongInt

Visibility: default

Description: SizeOf returns the size, in bytes, of any variable or type-identifier.

Remark: This isn't really a RTL function. Its result is calculated at compile-time, and hard-coded in the executable.

Errors: None.

See also: Addr ([1267](#))

Listing: ./refex/ex63.pp

Program Example63;

```
{ Program to demonstrate the SizeOf function. }
Var
  I : Longint;
  S : String [10];

begin
  Writeln (SizeOf(I)); { Prints 4 }
  Writeln (SizeOf(S)); { Prints 11 }
end.
```

75.11.379 SizeofResource

Synopsis: Return the size of a particular resource

Declaration: function SizeofResource(ModuleHandle: TFPResourceHMODULE;
ResHandle: TFPResourceHandle) : LongWord

Visibility: default

Description: SizeOfResource returns the size of the resource identified by ResHandle in module identified by ModuleHandle. ResHandle should be obtained from a call to LoadResource ([1354](#))

Errors: In case of an error, 0 is returned.

See also: FindResource ([1325](#)), FreeResource ([1329](#)), LoadResource ([1354](#)), LockResource ([1354](#)), UnlockResource ([1410](#)), FreeResource ([1329](#))

75.11.380 Space

Synopsis: Return a string of spaces

Declaration: `function Space(b: Byte) : shortstring`

Visibility: default

Description: `Space` returns a shortstring with length B, consisting of spaces.

See also: `StringOfChar` ([1397](#))

75.11.381 Sptr

Synopsis: Return current stack pointer

Declaration: `function Sptr : Pointer`

Visibility: default

Description: `Sptr` returns the current stack pointer.

Errors: None.

See also: `SSeg` ([1394](#))

Listing: `./refex/ex64.pp`

```

program Example64;

  { Program to demonstrate the sptr function. }

  var p: ptruint;

  begin
    p := ofs(stackbottom); { P Contains now the current stack position. }
  end.
```

75.11.382 sqr

Synopsis: Calculate the square of a value.

Declaration: `function sqr(l: LongInt) : LongInt`
`function sqr(l: Int64) : Int64`
`function sqr(l: QWord) : QWord`
`function sqr(d: ValReal) : ValReal`

Visibility: default

Description: `Sqr` returns the square of its argument X.

Errors: None.

See also: `Sqrt` ([1394](#)), `Ln` ([1352](#)), `Exp` ([1320](#))

Listing: `./refex/ex65.pp`

Program Example65;

```
{ Program to demonstrate the Sqr function. }
Var i : Integer;

begin
  For i:=1 to 10 do
    writeln (Sqr(i):3);
  end.
```

75.11.383 sqrt

Synopsis: Calculate the square root of a value

Declaration: `function sqrt(d: ValReal) : ValReal`

Visibility: default

Description: `Sqrt` returns the square root of its argument X, which must be positive.

Errors: If X is negative, then a run-time error is generated.

See also: `Sqr` ([1393](#)), `Ln` ([1352](#)), `Exp` ([1320](#))

Listing: `./refex/ex66.pp`

Program Example66;

```
{ Program to demonstrate the Sqrt function. }

begin
  Writeln (Sqrt(4):0:3); { Prints 2.000 }
  Writeln (Sqrt(2):0:3); { Prints 1.414 }
end.
```

75.11.384 Sseg

Synopsis: Return stack segment register value.

Declaration: `function Sseg : Word`

Visibility: default

Description: `Sseg` returns the Stack Segment. This function is only supported for compatibility reasons, as `Sptr` returns the correct contents of the stackpointer.

Errors: None.

See also: `Sptr` ([1393](#))

Listing: `./refex/ex67.pp`

Program Example67;

```
{ Program to demonstrate the SSeg function. }
Var W : Longint;
```

```
begin
  W:=SSeg;
end.
```

75.11.385 StackTop

Synopsis: Top location of the stack.

Declaration: `function StackTop : Pointer`

Visibility: default

Description: `StackTop` contains the top of the stack for the current process. It is used to check the heap on some operating systems, and is set by the system unit initialization code. Do not use or modify this value.

See also: `StackBottom` ([1264](#)), `StackLength` ([1264](#))

75.11.386 Str

Synopsis: Convert a numerical or enumeration value to a string.

Declaration: `procedure Str(var X: TNumericType; var S: string)`

Visibility: default

Description: `Str` returns a string which represents the value of X. X can be any numerical or enumerated type. The actual declaration of `Str` is not according to pascal syntax, and should be

```
procedure Str(var X: TNumericType[:NumPlaces[:Decimals]];var S: String)
```

Where the optional `NumPlaces` and `Decimals` specifiers control the formatting of the string: `NumPlaces` gives the total width of the string, and `Decimals` the number of decimals after the decimal separator char.

`Str` can also be used to convert an enumerated type value to a string representation of the declared enumeration value. That means that the following will work:

```
Type
  TMyEnum = (OnE);

Var
  S : String;
begin
  Str(one, s);
  Writeln(S);
end.
```

This will write `OnE` on the screen, which is consistent with the following - equivalent - program:

```
Type
  TMyEnum = (OnE);

Var
```


Visibility: default

Description: `StringCodePage` returns the code page of a string (*S*), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, `DefaultSystemCodePage` (1262) is returned.

See also: `DefaultSystemCodePage` (1262), `StringElementSize` (1397), `StringRefCount` (1398), `SetCodePage` (1385)

75.11.388 `StringElementSize`

Synopsis: Get the character size of a string.

Declaration: `function StringElementSize(const S: RawByteString) : Word; Overload`
`function StringElementSize(const S: UnicodeString) : Word; Overload`

Visibility: default

Description: `StringCodePage` returns the character size of a string (*S*), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, `SizeOf(AnsiChar)` (normally 1) is returned.

See also: `StringCodePage` (1396), `StringRefCount` (1398)

75.11.389 `StringOfChar`

Synopsis: Return a string consisting of 1 character repeated *N* times.

Declaration: `function StringOfChar(c: AnsiChar; l: SizeInt) : AnsiString`

Visibility: default

Description: `StringOfChar` creates a new `String` of length *l* and fills it with the character *c*.

It is equivalent to the following calls:

```
SetLength(StringOfChar, l);
FillChar(Pointer(StringOfChar)^, Length(StringOfChar), c);
```

Errors: None.

See also: `SetLength` (1194)

Listing: `./refex/ex97.pp`

Program `Example97`;

{ \$H+ }

{ Program to demonstrate the StringOfChar function. }

Var *S* : **String**;

begin

S := `StringOfChar(' ', 40)` + 'Aligned at column 41.';

WriteLn(*s*);

end.

75.11.390 StringRefCount

Synopsis: Get the reference count of a string

Declaration: `function StringRefCount(const S: RawByteString) : SizeInt; Overload`
`function StringRefCount(const S: UnicodeString) : SizeInt; Overload`

Visibility: default

Description: `StringRefCount` returns the reference count of a string (`S`), regardless of the string type. It accesses the internal structures of the string to retrieve this information. For an empty string, 0 is returned.

See also: `StringCodePage` ([1396](#)), `StringElementSize` ([1397](#))

75.11.391 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: `function StringToPPChar(var S: AnsiString; ReserveEntries: Integer)`
`: PPChar`
`function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar`

Visibility: default

Description: `StringToPPChar` splits the string `S` in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in `S`. This array is terminated by a `Nil` pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of `PChar`; The caller is responsible for freeing this memory.

This function is only available on certain platforms.

Errors: None.

See also: `ArrayStringToPPchar` ([1269](#))

75.11.392 StringToUnicodeChar

Synopsis: Convert an ansistring to a null-terminated array of unicode characters.

Declaration: `function StringToUnicodeChar(const Src: RawByteString;`
`Dest: PUnicodeChar; DestSize: SizeInt)`
`: PUnicodeChar`

Visibility: default

Description: `StringToUnicodeChar` converts the ansistring `S` to a unicodestring and places the result in `Dest`. The size of the memory location pointed to by `Dest` must be given in `DestSize`. If the result string is longer than the available size, the result string will be truncated.

The function always returns `Dest`.

Errors: No check is performed to see whether `Dest` points to a valid memory location.

See also: `UnicodeCharToString` ([1409](#)), `UnicodeCharLenToString` ([1408](#))

75.11.393 StringToWideChar

Synopsis: Convert a string to an array of widechars.

Declaration: `function StringToWideChar(const Src: RawByteString; Dest: PWideChar; DestSize: SizeInt) : PWideChar`

Visibility: default

Description: `StringToWideChar` converts an ansistring `Src` to a null-terminated array of `WideChars`. The destination for this array is pointed to by `Dest`, and contains room for at least `DestSize` widechars.

Errors: No validity checking is performed on `Dest`.

See also: `WideCharToString` ([1416](#)), `WideCharToStrVar` ([1416](#)), `WideCharLenToStrVar` ([1415](#)), `WideCharLenToString` ([1415](#))

75.11.394 strlen

Synopsis: Length of a null-terminated string.

Declaration: `function strlen(p: PChar) : SizeInt`

Visibility: default

Description: Returns the length of the null-terminated string `P`.

Errors: None.

75.11.395 strpas

Synopsis: Convert a null-terminated string to a shortstring.

Declaration: `function strpas(p: PChar) : shortstring`

Visibility: default

Description: Converts a null terminated string in `P` to a Pascal string, and returns this string. The string is truncated at 255 characters.

Errors: None.

75.11.396 subtract(variant,variant):variant

Synopsis: Implement subtraction (–) operation on variants.

Declaration: `operator -(const op1: variant; const op2: variant) : variant`

Visibility: default

Description: The implementation of the subtraction – operation is delegated to the variant manager with operation `opSubtract`.

Errors: Execution of this operator may result in an exception if no variant manager is installed or if the types of the operand are not suitable for the operation.

See also: operator `-(variant, variant): variant` ([1194](#))

75.11.397 Succ

Synopsis: Return next element of ordinal type.

Declaration: `function Succ(X: TOrdinal) : TOrdinal`

Visibility: default

Description: `Succ` returns the element that succeeds the element that was passed to it. If it is applied to the last value of the ordinal type, and the program was compiled with range checking on (`{ $R+ }`), then a run-time error will be generated.

for an example, see `Ord` ([1362](#)).

Errors: Run-time error 201 is generated when the result is out of range.

See also: `Ord` ([1362](#)), `Pred` ([1366](#)), `High` ([1337](#)), `Low` ([1356](#))

75.11.398 SuspendThread

Synopsis: Suspend a running thread.

Declaration: `function SuspendThread(threadHandle: TThreadID) : DWord`

Visibility: default

Description: `SuspendThread` suspends a running thread. The thread is identified with its handle or ID `threadHandle`.

The function returns zero if successful. A nonzero return value indicates failure.

Errors: If a failure occurred, a nonzero result is returned. The meaning is system dependent.

See also: `ResumeThread` ([1374](#)), `KillThread` ([1351](#))

75.11.399 Swap

Synopsis: Swap high and low bytes/words of a variable

Declaration: `function swap(X: Word) : Word`
`function Swap(X: Integer) : Integer`
`function swap(X: LongInt) : LongInt`
`function Swap(X: Cardinal) : Cardinal`
`function Swap(X: QWord) : QWord`
`function swap(X: Int64) : Int64`

Visibility: default

Description: `Swap` swaps the high and low order bytes of `X` if `X` is of type `Word` or `Integer`, or swaps the high and low order words of `X` if `X` is of type `Longint` or `Cardinal`. The return type is the type of `X`

Errors: None.

See also: `Lo` ([1353](#)), `Hi` ([1337](#))

Listing: `./refex/ex69.pp`

Program Example69;

```
{ Program to demonstrate the Swap function. }
Var W : Word;
    L : Longint;

begin
    W:=$1234;
    W:=Swap(W);
    if W<>$3412 then
        writeln ('Error when swapping word !');
    L:=$12345678;
    L:=Swap(L);
    if L<>$56781234 then
        writeln ('Error when swapping Longint !');
end.
```

75.11.400 SwapEndian

Synopsis: Swap endianness of the argument

Declaration: function SwapEndian(const AValue: SmallInt) : SmallInt
function SwapEndian(const AValue: Word) : Word
function SwapEndian(const AValue: LongInt) : LongInt
function SwapEndian(const AValue: DWord) : DWord
function SwapEndian(const AValue: Int64) : Int64
function SwapEndian(const AValue: QWord) : QWord

Visibility: default

Description: SwapEndian will swap the endianness of the bytes in its argument.

Errors: None.

See also: hi ([1337](#)), lo ([1353](#)), swap ([1400](#)), BEToN ([1291](#)), NToBE ([1360](#)), NToLE ([1360](#)), LEToN ([1352](#))

75.11.401 SysAllocMem

Synopsis: System memory manager: Allocate memory

Declaration: function SysAllocMem(size: PtrUInt) : Pointer

Visibility: default

Description: SysFreeMemSize is the system memory manager implementation for AllocMem ([1268](#))

See also: AllocMem ([1268](#))

75.11.402 SysAssert

Synopsis: Standard Assert failure implementation

Declaration: procedure SysAssert(const Msg: ShortString; const FName: ShortString;
LineNo: LongInt; ErrorAddr: Pointer)

Visibility: default

Description: `SysAssert` is the standard implementation of the assertion failed code. It is the default value of the `AssertErrorProc` constant. It will print the assert message `Msg` together with the filename `FName` and linenumber `LineNo` to standard error output (`StdErr`) and will halt the program with exit code 227. The error address `ErrorAddr` is ignored.

See also: `AssertErrorProc` ([1200](#))

75.11.403 SysBackTraceStr

Synopsis: Format an address suitable for inclusion in a backtrace

Declaration: `function SysBackTraceStr(Addr: CodePointer) : ShortString`

Visibility: default

Description: `SysBackTraceStr` will create a string representation of the address `Addr`, suitable for inclusion in a stack backtrace.

Errors: None.

75.11.404 SysFlushStdIO

Synopsis: Flush all standard IO file descriptors

Declaration: `procedure SysFlushStdIO`

Visibility: default

Description: `SysFlushStdIO` calls `flush` ([1326](#)) on all standard file descriptors: output ([1264](#)), stdout ([1264](#)), stderr ([1264](#)), erroutput ([1263](#))

See also: output ([1264](#)), stdout ([1264](#)), stderr ([1264](#)), erroutput ([1263](#)), flush ([1326](#))

75.11.405 SysFreemem

Synopsis: System memory manager free routine.

Declaration: `function SysFreemem(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeem` is the system memory manager implementation for `FreeMem` ([1328](#))

See also: `FreeMem` ([1328](#))

75.11.406 SysFreememSize

Synopsis: System memory manager free routine.

Declaration: `function SysFreememSize(p: pointer; Size: PtrUInt) : PtrUInt`

Visibility: default

Description: `SysFreeSize` is the system memory manager implementation for `FreeMem` ([1328](#))

See also: `MemSize` ([1357](#))

75.11.407 SysGetFPCHeapStatus

Synopsis: Return the status of the FPC heapmanager

Declaration: `function SysGetFPCHeapStatus : TFPCHeapStatus`

Visibility: default

Description: `SysGetFPCHeapStatus` returns the status of the default FPC heapmanager. It is set as the default value of the corresponding `GetFPCHeapStatus` (1330) function.

Errors: None. The result of this function is bogus information if the current heapmanager is not the standard FPC heapmanager.

See also: `GetFPCHeapStatus` (1330)

75.11.408 SysGetHeapStatus

Synopsis: System implementation of `GetHeapStatus` (1330)

Declaration: `function SysGetHeapStatus : THeapStatus`

Visibility: default

Description: `SysGetHeapStatus` is the system implementation of the `GetHeapStatus` (1330) call.

See also: `GetHeapStatus` (1330)

75.11.409 SysGetmem

Synopsis: System memory manager memory allocator.

Declaration: `function SysGetmem(Size: PtrUInt) : Pointer`

Visibility: default

Description: `SysGetmem` is the system memory manager implementation for `GetMem` (1331)

See also: `GetMem` (1331), `GetMemory` (1331)

75.11.410 SysInitExceptions

Synopsis: Initialize exceptions.

Declaration: `procedure SysInitExceptions`

Visibility: default

Description: `SysInitExceptions` initializes the exception system. This procedure should never be called directly, it is taken care of by the RTL.

75.11.411 SysInitFPU

Synopsis: Initialize the FPU

Declaration: `procedure SysInitFPU`

Visibility: default

Description: `SysInitFPU` initializes (resets) the floating point unit, if one is available. It is called for instance when a new thread is started.

See also: `BeginThread` ([1290](#))

75.11.412 SysInitStdIO

Synopsis: Initialize standard input and output.

Declaration: `procedure SysInitStdIO`

Visibility: default

Description: `SysInitStdIO` initializes the standard input and output files: Output ([1264](#)), Input ([1263](#)) and StdErr ([1264](#)). This routine is called by the initialization code of the system unit, there should be no need to call it directly.

75.11.413 SysMemSize

Synopsis: System memory manager: free size.

Declaration: `function SysMemSize(p: pointer) : PtrUInt`

Visibility: default

Description: `SysFreeMemSize` is the system memory manager implementation for `MemSize` ([1357](#))

See also: `MemSize` ([1357](#))

75.11.414 SysReAllocMem

Synopsis: System memory manager: Reallocate memory

Declaration: `function SysReAllocMem(var p: pointer; size: PtrUInt) : Pointer`

Visibility: default

Description: `SysReallocMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1371](#)).

See also: `ReAllocMem` ([1371](#))

75.11.415 SysResetFPU

Synopsis: Reset the floating point unit.

Declaration: `procedure SysResetFPU`

Visibility: default

Description: `SysResetFPU` resets the floating point unit. There should normally be no need to call this unit; the compiler itself takes care of this.

75.11.416 SysSetCtrlBreakHandler

Synopsis: System CTRL-C handler

Declaration: `function SysSetCtrlBreakHandler (Handler: TCtrlBreakHandler)
: TCtrlBreakHandler`

Visibility: default

Description: `SysSetCtrlBreakHandler` sets the CTRL-C handler to the `Handler` callback, and returns the previous value of the handler.

See also: `TCtrlBreakHandler` ([1237](#))

75.11.417 SysTryResizeMem

Synopsis: System memory manager: attempt to resize memory.

Declaration: `function SysTryResizeMem (var p: pointer; size: PtrUInt) : Boolean`

Visibility: default

Description: `SysTryResizeMem` is a help routine for the system memory manager implementation for `ReAllocMem` ([1371](#)), `SysReAllocMem` ([1404](#))

See also: `SysReAllocMem` ([1404](#)), `ReAllocMem` ([1371](#))

75.11.418 ThreadGetPriority

Synopsis: Return the priority of a thread.

Declaration: `function ThreadGetPriority (threadHandle: TThreadID) : LongInt`

Visibility: default

Description: `ThreadGetPriority` returns the priority of thread `TThreadID` to `Prio`. The returned priority is a value between -15 and 15.

Errors: None.

See also: `ThreadSetPriority` ([1405](#))

75.11.419 ThreadSetPriority

Synopsis: Set the priority of a thread.

Declaration: `function ThreadSetPriority (threadHandle: TThreadID; Prio: LongInt)
: Boolean`

Visibility: default

Description: `ThreadSetPriority` sets the priority of thread `TThreadID` to `Prio`. Priority is a value between -15 and 15.

Errors: None.

See also: `ThreadGetPriority` ([1405](#))

75.11.420 ThreadSwitch

Synopsis: Signal possibility of thread switch

Declaration: `procedure ThreadSwitch`

Visibility: default

Description: `ThreadSwitch` signals the operating system that the thread should be suspended and that another thread should be executed.

This call is a hint only, and may be ignored.

See also: `SuspendThread` ([1400](#)), `ResumeThread` ([1374](#)), `KillThread` ([1351](#))

75.11.421 ToSingleByteFileSystemEncodedFileName

Synopsis: Convert string to encoding for use in single-byte filesystem API

Declaration: `function ToSingleByteFileSystemEncodedFileName(const Str: UnicodeString)
: RawByteString
function ToSingleByteFileSystemEncodedFileName
(const arr: Array of WideChar)
: RawByteString
function ToSingleByteFileSystemEncodedFileName(const Str: RawByteString)
: RawByteString`

Visibility: default

Description: `ToSingleByteFileSystemEncodedFileName` converts the argument (`Str` or `Arr`) to a single-byte string, encoded using the codepage used by the single-byte filesystem API.

This routine is simply an auxiliary routine, which converts the argument to a single-byte string using `DefaultFileSystemCodePage` ([1261](#)) as a codepage.

See also: `DefaultFileSystemCodePage` ([1261](#))

75.11.422 trunc

Synopsis: Truncate a floating point value.

Declaration: `function trunc(d: ValReal) : Int64`

Visibility: default

Description: `Trunc` returns the integer part of `X`, which is always smaller than (or equal to) `X` in absolute value.

Errors: None.

See also: `Frac` ([1328](#)), `Int` ([1345](#)), `Round` ([1378](#))

Listing: `./refex/ex70.pp`

Program `Example70;`

{ Program to demonstrate the Trunc function. }

```
begin
  Writeln (Trunc(123.456)); { Prints 123 }
  Writeln (Trunc(-123.456)); { Prints -123 }
```

```

Writeln (Trunc(12.3456)); { Prints 12 }
Writeln (Trunc(-12.3456)); { Prints -12 }
end.

```

75.11.423 Truncate

Synopsis: Truncate the file at position

Declaration: `procedure Truncate(var F: File)`

Visibility: default

Description: `Truncate` truncates the (opened) file `F` at the current file position.

Errors: Depending on the state of the `{SI}` switch, a runtime error can be generated if there is an error. In the `{SI-}` state, use `IOResult` to check for errors.

See also: `Append` ([1268](#)), `Filepos` ([1320](#)), `Seek` ([1381](#))

Listing: `./refex/ex71.pp`

Program Example71;

{ Program to demonstrate the Truncate function. }

```

Var F : File of longint;
    I,L : Longint;

```

```

begin
  Assign (F, 'test.tmp');
  Rewrite (F);
  For I:=1 to 10 Do
    Write (F,I);
  Writeln ('Filesize before Truncate : ',FileSize(F));
  Close (f);
  Reset (F);
  Repeat
    Read (F,I);
  Until i=5;
  Truncate (F);
  Writeln ('Filesize after Truncate : ',FileSize(F));
  Close (f);
end.

```

75.11.424 TryEnterCriticalSection

Synopsis: Try entering a critical section

Declaration: `function TryEnterCriticalSection(var cs: TRTLCriticalSection) : LongInt`

Visibility: default

Description: `TryEnterCriticalSection` attempts to enter critical section `cs`. It returns at once. The return value is zero if another thread owns the critical section, or nonzero if the current thread already owns or successfully obtained the critical section.

75.11.425 UCS4StringToUnicodeString

Synopsis: Convert a UCS-4 encoded string to a unicode string

Declaration: `function UCS4StringToUnicodeString(const s: UCS4String) : UnicodeString`

Visibility: default

Description: `UCS4StringToUnicodeString` converts the UCS-4 encoded string `S` to a unicode string and returns the resulting string.

This function requires the widestring manager.

See also: `UnicodeStringToUCS4String` ([1409](#))

75.11.426 UCS4StringToWideString

Synopsis:

Declaration: `function UCS4StringToWideString(const s: UCS4String) : WideString`

Visibility: default

Description:

75.11.427 Unassigned

Synopsis: Unassigned variant.

Declaration: `function Unassigned : Variant`

Visibility: default

75.11.428 UnicodeCharLenToString

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `function UnicodeCharLenToString(S: PUnicodeChar; Len: SizeInt)
: UnicodeString`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` ([1398](#)), `UnicodeCharToString` ([1409](#))

75.11.429 UnicodeCharLenToStrVar

Synopsis: Convert a memory buffer with unicode characters to an ansistring

Declaration: `procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: UnicodeString)
procedure UnicodeCharLenToStrVar(Src: PUnicodeChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` with at most `len` bytes length, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharLenToString` (1408).

Errors: No checking is done to see if the pointer `S` or length `len` are valid.

See also: `StringToUnicodeChar` (1398), `UnicodeCharToString` (1409), `UnicodeCharLenToString` (1408), `UnicodeCharToStrVar` (1409)

75.11.430 UnicodeCharToString

Synopsis: Convert unicode character to string

Declaration: `function UnicodeCharToString(S: PUnicodeChar) : UnicodeString`

Visibility: default

Description: `UnicodeCharToString` converts a null-word-terminated array of unicode characters in `S` to an `AnsiString` value. It simply calls `UnicodeCharLenToString` (1408) with the length of the string `S`.

This function requires the use of a widestring manager.

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1398), `UnicodeCharLenToString` (1408), `WidestringManager` (1265)

75.11.431 UnicodeCharToStrVar

Synopsis: Convert a null-terminated memory buffer with unicode characters to an ansistring

Declaration: `procedure UnicodeCharToStrVar(S: PUnicodeChar; out Dest: AnsiString)`

Visibility: default

Description: `UnicodeCharLenToString` converts the unicode characters in buffer `S` up to the first null word, to an ansistring and returns the result in `Dest`

This function does the same as `UnicodeCharToString` (1409).

Errors: No checking is done to see if the pointer `S` is valid.

See also: `StringToUnicodeChar` (1398), `UnicodeCharToString` (1409), `UnicodeCharLenToString` (1408), `UnicodeCharToString` (1409)

75.11.432 UnicodeStringToUCS4String

Synopsis: Convert a unicode string to a UCS-4 string.

Declaration: `function UnicodeStringToUCS4String(const s: UnicodeString) : UCS4String`

Visibility: default

Description: `UnicodeStringToUCS4String` converts a unicode string `S` to a UCS-4 encoded string, and returns the resulting string.

This function requires the widestring manager.

See also: `UCS4StringToUnicodeString` (1408)

75.11.433 UnicodeToUtf8

Synopsis:

Declaration: `function UnicodeToUtf8(Dest: PChar; Source: PUnicodeChar;
 MaxBytes: SizeInt) : SizeInt`
`function UnicodeToUtf8(Dest: PChar; MaxDestBytes: SizeUInt;
 Source: PUnicodeChar; SourceChars: SizeUInt)
 : SizeUInt`

Visibility: default

Description:

75.11.434 UniqueString

Synopsis: Make sure reference count of string is 1

Declaration: `procedure UniqueString(var S: RawByteString)`
`procedure UniqueString(var S: UnicodeString)`
`procedure UniqueString(var S: WideString)`

Visibility: default

Description: `UniqueString` ensures that the ansistring `S` has reference count 1. It makes a copy of `S` if this is necessary, and returns the copy in `S`

Errors: None.

75.11.435 UnlockResource

Synopsis: Unlock a previously locked resource

Declaration: `function UnlockResource(ResData: TFPResourceHGLOBAL) : LongBool`

Visibility: default

Description: `UnlockResource` unlocks a previously locked resource. Note that this function does not exist on windows, it's only needed on other platforms.

Errors: The function returns `False` if it failed.

See also: `FindResource` ([1325](#)), `FreeResource` ([1329](#)), `SizeofResource` ([1392](#)), `LoadResource` ([1354](#)), `lockResource` ([1354](#)), `FreeResource` ([1329](#))

75.11.436 upCase

Synopsis: Convert a string to all uppercase.

Declaration: `function upCase(const s: shortstring) : shortstring`
`function upCase(c: Char) : Char`
`function upcase(const s: ansistring) : ansistring`
`function UpCase(const s: UnicodeString) : UnicodeString`
`function UpCase(c: UnicodeChar) : UnicodeChar`
`function UpCase(const s: WideString) : WideString`

Visibility: default

Description: `Uppcase` returns the uppercase version of its argument `C`. If its argument is a string, then the complete string is converted to uppercase. The type of the returned value is the same as the type of the argument.

`UppCase` does not change the number of characters in the string.

Errors: None.

See also: `Lowercase` ([1356](#))

Listing: `./refex/ex72.pp`

```

program Example72;

{ Program to demonstrate the upcase function. }

var c:char;

begin
  for c:= 'a' to 'z' do
    write(upcase(c));
  Writeln;
  { This doesn't work in TP, but it does in Free Pascal }
  Writeln(upcase('abcdefghijklmnopqrstuvwxyz'));
end.

```

75.11.437 Utf8CodePointLen

Synopsis: Length of an UTF-8 codepoint.

Declaration: `function Utf8CodePointLen(P: PAnsiChar; MaxLookAhead: SizeInt; IncludeCombiningDiacriticalMarks: Boolean) : SizeInt`

Visibility: default

Description: `Utf8CodePointLen` returns the length of the UTF-8 codepoint starting at the beginning of `P`. It will look at at most `MaxLookAhead` bytes to do create this codepoint. If `IncludeCombiningDiacriticalMarks` is true, combining diacritical marks trailing the first codepoint (which itself can also be such a mark) will be considered to be part of the codepoint.

If the function returns a value > 0 , then this is the number of bytes occupied by the codepoint and, if requested, the trailing combining diacritical marks. If the result $= 0$, this means that all bytes within the requested `MaxLookAhead` could be part of a single valid codepoint and, if requested, its trailing diacritical marks, but that the codepoint is incomplete and more bytes need to be looked at. If the result is < 0 , then the function determined that the codepoint was invalid after processing the number of bytes equal to the absolute value of the function result.

If `IncludeCombiningDiacriticalMarks` is True, then

- If the function processes all `MaxLookAhead` bytes, it will return the value `MaxLookAhead` rather than 0, even though in theory more combining diacritical marks might follow if more bytes would be looked at. Therefore, in order to ascertain that all combining diacritical marks are processed, pass all bytes at once to this function.
- If an invalid sequence is detected while processing a potential combining diacritical mark after a valid codepoint has been found already, the function will return the length of this valid codepoint (plus that of any preceding valid combining diacritical marks) as a positive value. The

idea is that this invalid sequence at the end is by definition not a combining diacritical mark (since all of those are valid sequences) and hence should not render the preceding codepoint invalid.

Errors: None.

75.11.438 UTF8Decode

Synopsis: Convert an UTF-8 encoded ansistring to a unicodestring

Declaration: `function UTF8Decode(const s: RawByteString) : UnicodeString`

Visibility: default

Description: `UTF8Decode` converts the UTF-8 encoded ansistring *S* to a unicodestring and returns the resulting string. It calls the low-level `Utf8ToUnicode` (1413) function to do the actual work.

See also: `UTF8Encode` (1412), `Utf8ToAnsi` (1412), `SetWideStringManager` (1391), `Utf8ToUnicode` (1413)

75.11.439 UTF8Encode

Synopsis: Convert a widestring or unicodestring to an UTF-8 encoded ansistring

Declaration: `function UTF8Encode(const s: RawByteString) : RawByteString`
`function UTF8Encode(const s: UnicodeString) : RawByteString`
`function UTF8Encode(const s: WideString) : RawByteString`

Visibility: default

Description: `UTF8Encode` converts an ansistring or widestring *S* to the equivalent UTF-8 encoded unicode string and returns this resulting string. It calls the low-level `UnicodeToUTF8` (1410) function to do the actual work.

The resulting string has code page `CP_UTF8`.

See also: `UTF8Decode` (1412), `Utf8ToAnsi` (1412), `UnicodeToUtf8` (1410), `SetWideStringManager` (1391)

75.11.440 Utf8ToAnsi

Synopsis: Convert a UTF-8 encoded unicode string to an ansistring

Declaration: `function Utf8ToAnsi(const s: RawByteString) : RawByteString`

Visibility: default

Description: `Utf8ToAnsi` converts an utf8-encode unicode string to an ansistring. It converts the string to a widestring and then converts the widestring to an ansistring.

For this function to work, a widestring manager must be installed.

See also: `UTF8Encode` (1412), `UTF8Decode` (1412), `SetWideStringManager` (1391)

75.11.441 Utf8ToUnicode

Synopsis: Convert a buffer with UTF-8 characters to widestring characters

Declaration: `function Utf8ToUnicode(Dest: PUnicodeChar; Source: PChar;
 MaxChars: SizeInt) : SizeInt
 function Utf8ToUnicode(Dest: PUnicodeChar; MaxDestChars: SizeUInt;
 Source: PChar; SourceBytes: SizeUInt) : SizeUInt`

Visibility: default

Description: `Utf8ToUnicode` converts the buffer in `Source` with a length of `SourceBytes` or for a maximum length of `MaxChars` (or `MaxDestChars`) widestring characters to the buffer pointed to by `Dest`.

The function returns the number of copied widestring characters.

Errors: On error, -1 is returned.

See also: `UTF8Encode` ([1412](#)), `UTF8Decode` ([1412](#)), `Utf8ToAnsi` ([1412](#)), `SetWideStringManager` ([1391](#))

75.11.442 Val

Synopsis: Calculate numerical/enumerated value of a string.

Declaration: `procedure Val(const S: string; var V; var Code: Word)`

Visibility: default

Description: `Val` converts the value represented in the string `S` to a numerical value or an enumerated value, and stores this value in the variable `V`, which can be of type `Longint`, `Real` and `Byte` or any enumerated type. If the conversion isn't succesfull, then the parameter `Code` contains the index of the character in `S` which prevented the conversion. The string `S` is allowed to contain spaces in the beginning.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

For hexadecimal values, the prefix `'0x'` or `'x'` (case insensitive) may be used as well.

The conversion to enumerated exists only as of version 2.3.1 (or later) of the compiler.

Errors: If the conversion doesn't succeed, the value of `Code` indicates the position where the conversion went wrong. The value of `V` is then undefined.

See also: `Str` ([1395](#))

Listing: `./refex/ex74.pp`

Program `Example74;`

```
{ Program to demonstrate the Val function. }
Var I, Code : Integer;

begin
  Val (ParamStr (1), I, Code);
  If Code<>0 then
    Writeln ('Error at position ', code, ' : ', Paramstr(1)[Code])
  else
    Writeln ('Value : ', I);
end.
```

75.11.443 VarArrayGet

Synopsis:

Declaration: `function VarArrayGet(const A: Variant; const Indices: Array of LongInt)
: Variant`

Visibility: default

Description:

75.11.444 VarArrayPut

Synopsis: Put a value in a single cell of a variant array

Declaration: `procedure VarArrayPut(var A: Variant; const Value: Variant;
const Indices: Array of LongInt)`

Visibility: default

Description: `VarArrayPut` puts `Value` in the variant array `A` at the location indicated by `Indices`. Thus the statement

```
VarArrayPut (A,B, [2,1]) ;
```

is equivalent to

```
A[2,1] :=B;
```

The difference is that the previous is usable when the amount of indices is not known at compile time.

Errors: If the number of indices is wrong (or out of range) an exception may be raised.

See also: `VarArrayGet` ([1414](#))

75.11.445 VarArrayRedim

Synopsis: Redimension a variant array

Declaration: `procedure VarArrayRedim(var A: Variant; HighBound: SizeInt)`

Visibility: default

Description: `VarArrayRedim` re-sizes the first dimension of the variant array `A`, giving it a new high bound `HighBound`. Obviously, `A` must be a variant array for this function to work.

75.11.446 VarCast

Synopsis: Cast a variant to a certain type

Declaration: `procedure VarCast(var dest: variant; const source: variant;
vartype: LongInt)`

Visibility: default

Description: `VarCast` converts the variant in `Source` to the type indicated in `VarType` and returns the result in `dest`. The `VarType` must be one of the pre-defined `VarNNN` constants.

Errors: If the conversion is not possible because the value cannot be correctly casted, then a run-time error or an exception may occur.

75.11.447 WaitForThreadTerminate

Synopsis: Wait for a thread to terminate.

Declaration: `function WaitForThreadTerminate(threadHandle: TThreadID;
TimeoutMs: LongInt) : DWord`

Visibility: default

Description: `WaitForThreadTerminate` waits for a thread to finish its execution. The thread is identified by its handle or ID `threadHandle`. If the thread does not exit within `TimeoutMs` milliseconds, the function will return with an error value.

The function returns the exit code of the thread.

Not all platforms support the timeout parameter: the Unix platforms (with threads support based on `pthread`s) do not support timeout, and will wait indefinitely for the thread to exit.

See also: `EndThread` ([1313](#)), `KillThread` ([1351](#))

75.11.448 WideCharLenToString

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `function WideCharLenToString(S: PWideChar; Len: SizeInt) : UnicodeString`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `S`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1399](#)), `WideCharToString` ([1416](#)), `WideCharToStrVar` ([1416](#)), `WideCharLenToStrVar` ([1415](#))

75.11.449 WideCharLenToStrVar

Synopsis: Convert a length-limited array of widechar to an ansistring

Declaration: `procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: UnicodeString)
procedure WideCharLenToStrVar(Src: PWideChar; Len: SizeInt;
out Dest: AnsiString)`

Visibility: default

Description: `WideCharLenToString` converts at most `Len` widecharacters from the null-terminated widechar array `Src` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer may lead to access violations.

See also: `StringToWideChar` ([1399](#)), `WideCharToString` ([1416](#)), `WideCharToStrVar` ([1416](#)), `WideCharLenToString` ([1415](#))

75.11.450 WideCharToString

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `function WideCharToString(S: PWideChar) : UnicodeString`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring.

Errors: No validity checking is performed on `Src`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` ([1399](#)), `WideCharToStrVar` ([1416](#)), `WideCharLenToStrVar` ([1415](#)), `WideCharLenToString` ([1415](#))

75.11.451 WideCharToStrVar

Synopsis: Convert a null-terminated array of widechar to an ansistring

Declaration: `procedure WideCharToStrVar(S: PWideChar; out Dest: UnicodeString)`
`procedure WideCharToStrVar(S: PWideChar; out Dest: AnsiString)`

Visibility: default

Description: `WideCharToString` converts the null-terminated widechar array `S` to an ansistring, and returns the ansistring in `Dest`.

Errors: No validity checking is performed on `S`. Passing an invalid pointer, or an improperly terminated array may lead to access violations.

See also: `StringToWideChar` ([1399](#)), `WideCharToString` ([1416](#)), `WideCharToStrVar` ([1416](#)), `WideCharLenToString` ([1415](#))

75.11.452 WideStringToUCS4String

Synopsis: Convert a widestring to a UCS-4 encoded string.

Declaration: `function WideStringToUCS4String(const s: WideString) : UCS4String`

Visibility: default

Description: Convert a widestring to a UCS-4 encoded string.

75.11.453 WriteBarrier

Synopsis: Memory write barrier

Declaration: `procedure WriteBarrier`

Visibility: default

Description: `WriteBarrier` is a low-level instruction to force a write barrier in the CPU: write (store) operations before and after the barrier are separate.

See also: `ReadBarrier` ([1369](#)), `ReadDependencyBarrier` ([1370](#)), `ReadWriteBarrier` ([1370](#))

75.12 TDoubleRec

```

TDoubleRec = packed record
private
  function GetExp : QWord;
  procedure
    SetExp(e: QWord);
  function GetSign : Boolean;
  procedure SetSign
    (s: Boolean);
  function GetFrac : QWord;
  procedure SetFrac(e: QWord
    );
public
  function Mantissa : QWord;
  function Fraction : ValReal
    ;
  function Exponent : LongInt;
  property Sign : Boolean;
  property
    Exp : QWord;
  property Frac : QWord;
  function SpecialType : TFloatSpecial
    ;
case Byte of
0: (
  Bytes : Array[0..7] of Byte;
);
1: (
  Words
    : Array[0..3] of Word;
);
2: (
  Data : QWord;
);
3: (
  Value :
    Double;
);
end

```

TDoubleRec models the memory layout of a double value when using software floating point math.

75.12.1 Method overview

Page	Method	Description
1418	Exponent	Exponent of the floating point value
1418	Fraction	Fraction of the floating point value
1418	Mantissa	Mantissa of the floating point value
1418	SpecialType	Is the floating point value special ?

75.12.2 Property overview

Page	Properties	Access	Description
1419	Exp	rw	Exponent bitpattern representation
1419	Frac	rw	Fractional part of double
1419	Sign	rw	Sign of the floating point value

75.12.3 TDoubleRec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa : QWord`

Visibility: `public`

Description: `Mantissa` returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: `TDoubleRec.Fraction` ([1418](#)), `TDoubleRec.Exponent` ([1418](#)), `TDoubleRec.SpecialType` ([1418](#))

75.12.4 TDoubleRec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: `public`

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TDoubleRec.Mantissa` ([1418](#)), `TDoubleRec.Exponent` ([1418](#)), `TDoubleRec.SpecialType` ([1418](#))

75.12.5 TDoubleRec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: `public`

Description: `Exponent` returns the exponent (X in $m \times 2^X$ representation) of the floating point value.

See also: `TDoubleRec.Fraction` ([1418](#)), `TDoubleRec.Mantissa` ([1418](#)), `TDoubleRec.SpecialType` ([1418](#))

75.12.6 TDoubleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: `public`

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1239](#)) for an explanation of the various special values.

See also: `TDoubleRec.Fraction` ([1418](#)), `TDoubleRec.Mantissa` ([1418](#)), `TDoubleRec.Exponent` ([1418](#)), `TFloatSpecial` ([1239](#))

75.12.7 TDoubleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: `public`

Access: `Read,Write`

75.12.8 TDoubleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Exp` returns the internal bit representation of the exponent of the floating point value.

See also: `TDoubleRec.Sign` ([1419](#)), `TDoubleRec.Exponent` ([1418](#))

75.12.9 TDoubleRec.Frac

Synopsis: Fractional part of double

Declaration: `Property Frac : QWord`

Visibility: `public`

Access: `Read,Write`

Description: `Frac` is the fractional part of the Double. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: `Frac` ([1328](#))

75.13 TExtended80Rec

```

TExtended80Rec = packed record
private
    function GetExp : QWord;
    procedure SetExp(e: QWord);
    function GetSign : Boolean;
    procedure
        SetSign(s: Boolean);
public
    function Mantissa : QWord;
    function
        Fraction : Extended;
    function Exponent : LongInt;
    property Sign
        : Boolean;
    property Exp : QWord;

```

```

    function SpecialType : TFloatSpecial
    ;
case Byte of
0: (
    Bytes : Array[0..9] of Byte;
);
1: (
    Words
    : Array[0..4] of Word;
);
2: (
    _Exp : Word;
    Frac : QWord;
);
    3: (
    Value : Extended;
);
end

```

TExtended80Rec models the memory layout of an extended value when using software floating point math.

75.13.1 Method overview

Page	Method	Description
1421	Exponent	Exponent of the floating point value
1420	Fraction	Fraction of the floating point value
1420	Mantissa	Mantissa of the floating point value
1421	SpecialType	Is the floating point value special ?

75.13.2 Property overview

Page	Properties	Access	Description
1421	Exp	rw	Exponent representation
1421	Sign	rw	Sign of the floating point value

75.13.3 TExtended80Rec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa : QWord`

Visibility: public

Description: Mantissa returns the Mantissa part (bit pattern of the significand, skipping the hidden bit) of the floating point value.

See also: TExtended80Rec.Fraction ([1420](#)), TExtended80Rec.Exponent ([1421](#)), TExtended80Rec.SpecialType ([1421](#))

75.13.4 TExtended80Rec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : Extended`

Visibility: `public`

Description: `Fraction` returns the fraction (value after decimal) of the floating point value.

See also: `TExtended80Rec.Mantissa` ([1420](#)), `TExtended80Rec.Exponent` ([1421](#)), `TExtended80Rec.SpecialType` ([1421](#))

75.13.5 TExtended80Rec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: `public`

Description: `Exponent` returns the exponent (the X in the $m \times 2^X$ representation) of the floating point value.

See also: `TExtended80Rec.Fraction` ([1420](#)), `TExtended80Rec.Mantissa` ([1420](#)), `TExtended80Rec.SpecialType` ([1421](#))

75.13.6 TExtended80Rec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: `public`

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1239](#)) for an explanation of the various special values.

See also: `TExtended80Rec.Fraction` ([1420](#)), `TExtended80Rec.Mantissa` ([1420](#)), `TExtended80Rec.Exponent` ([1421](#)), `TFloatSpecial` ([1239](#))

75.13.7 TExtended80Rec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: `public`

Access: Read,Write

75.13.8 TExtended80Rec.Exp

Synopsis: Exponent representation

Declaration: `Property Exp : QWord`

Visibility: `public`

Access: Read,Write

Description: `Exponent` returns the internal bit representation of the exponent of the floating point value.

See also: `TExtended80Rec.Sign` ([1421](#)), `TExtended80Rec.Exponent` ([1421](#))

75.14 TSingleRec

```

TSingleRec = packed record
private
  function GetExp : QWord;
  procedure
    SetExp(e: QWord);
  function GetSign : Boolean;
  procedure SetSign
    (s: Boolean);
  function GetFrac : QWord;
  procedure SetFrac(e: QWord
    );
public
  function Mantissa : QWord;
  function Fraction : ValReal
    ;
  function Exponent : LongInt;
  property Sign : Boolean;
  property
    Exp : QWord;
  property Frac : QWord;
  function SpecialType : TFloatSpecial
    ;
case Byte of
0: (
  Bytes : Array[0..3] of Byte;
);
1: (
  Words
    : Array[0..1] of Word;
);
2: (
  Data : DWord;
);
3: (
  Value :
    Single;
);
end

```

TSingleRec models the memory layout of a double value when using software floating point math.

75.14.1 Method overview

Page	Method	Description
1423	Exponent	Exponent of the floating point value
1423	Fraction	Fraction of the floating point value
1423	Mantissa	Mantissa of the floating point value
1423	SpecialType	Is the floating point value special ?

75.14.2 Property overview

Page	Properties	Access	Description
1424	Exp	rw	Exponent bitpattern representation
1424	Frac	rw	Fractional part of single
1424	Sign	rw	Sign of the floating point value

75.14.3 TSingleRec.Mantissa

Synopsis: Mantissa of the floating point value

Declaration: `function Mantissa : QWord`

Visibility: `public`

Description: `Mantissa` returns the Mantissa part (significand bitpattern without hidden bit) of the floating point value.

See also: `TsingleRec.Fraction` ([1423](#)), `TsingleRec.Exponent` ([1423](#)), `TsingleRec.SpecialType` ([1423](#))

75.14.4 TSingleRec.Fraction

Synopsis: Fraction of the floating point value

Declaration: `function Fraction : ValReal`

Visibility: `public`

Description: `Fraction` returns the fraction (after decimal) of the floating point value.

See also: `TsingleRec.Mantissa` ([1423](#)), `TsingleRec.Exponent` ([1423](#)), `TsingleRec.SpecialType` ([1423](#))

75.14.5 TSingleRec.Exponent

Synopsis: Exponent of the floating point value

Declaration: `function Exponent : LongInt`

Visibility: `public`

Description: `Exponent` returns the exponent (X in $m \cdot 2^X$ representation) of the floating point value.

See also: `TsingleRec.Fraction` ([1423](#)), `TsingleRec.Mantissa` ([1423](#)), `TsingleRec.SpecialType` ([1423](#))

75.14.6 TSingleRec.SpecialType

Synopsis: Is the floating point value special ?

Declaration: `function SpecialType : TFloatSpecial`

Visibility: `public`

Description: `SpecialType` returns special characteristics of the floating point value, if any. See `TFloatSpecial` ([1239](#)) for an explanation of the various special values.

See also: `TsingleRec.Fraction` ([1423](#)), `TsingleRec.Mantissa` ([1423](#)), `TsingleRec.Exponent` ([1423](#)), `TFloatSpecial` ([1239](#))

75.14.7 TSingleRec.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

75.14.8 TSingleRec.Exp

Synopsis: Exponent bitpattern representation

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` returns the internal bit representation of the exponent of the floating point value.

See also: `TSingleRec.Sign` ([1424](#)), `TSingleRec.Exponent` ([1423](#))

75.14.9 TSingleRec.Frac

Synopsis: Fractional part of single

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the fractional part of the Single. This is the bit pattern representing the fractional part including the preceding 1. (The mantissa is that bit pattern without the preceding 1)

See also: `Frac` ([1328](#))

75.15 IDispatch

75.15.1 Description

`IDispatch` is the pascal definition of the Windows Dispatch interface definition.

See also: `IUnknown` ([1428](#))

75.15.2 Method overview

Page	Method	Description
1425	<code>GetIDsOfNames</code>	Return IDs of named procedures
1425	<code>GetTypeInfo</code>	Return type information about properties
1425	<code>GetTypeInfoCount</code>	Return number of properties.
1425	<code>Invoke</code>	Invoke a dispatch method

75.15.3 IDispatch.GetTypeInfoCount

Synopsis: Return number of properties.

Declaration: `function GetTypeInfoCount(out count: LongInt) : HRESULT`

Visibility: default

75.15.4 IDispatch.GetTypeInfo

Synopsis: Return type information about properties

Declaration: `function GetTypeInfo(Index: LongInt; LocaleID: LongInt; out TypeInfo) : HRESULT`

Visibility: default

75.15.5 IDispatch.GetIDsOfNames

Synopsis: Return IDs of named procedures

Declaration: `function GetIDsOfNames(const iid: TGuid; names: Pointer; NameCount: LongInt; LocaleID: LongInt; DispIDs: Pointer) : HRESULT`

Visibility: default

Description: Return the ID of a procedure.

75.15.6 IDispatch.Invoke

Synopsis: Invoke a dispatch method

Declaration: `function Invoke(DispID: LongInt; const iid: TGuid; LocaleID: LongInt; Flags: Word; var params; VarResult: pointer; ExcepInfo: pointer; ArgErr: pointer) : HRESULT`

Visibility: default

75.16 IEnumerable

75.16.1 Description

`IEnumerable` can be used to get an enumerator from a class. If a class implements `IEnumerable`, it can return an enumerator interface `IEnumerator` ([1426](#)).

See also: `IEnumerator` ([1426](#))

75.16.2 Method overview

Page	Method	Description
1426	<code>GetEnumerator</code>	Return an enumerator interface for this class

75.16.3 IEnumerable.GetEnumerator

Synopsis: Return an enumerator interface for this class

Declaration: `function GetEnumerator : IEnumerator`

Visibility: default

Description: `GetEnumerator` returns a new `IEnumerator` ([1426](#)) interface for this class. This is called by the compiler whenever a `for in` loop is encountered in the source code to retrieve the enumerator instance.

See also: `IEnumerator` ([1426](#))

75.17 IEnumerator

75.17.1 Description

`IEnumerator` is the interface needed by the `For ... in ...` language construct, when operating on classes. It contains all methods that the compiler needs to implement a loop.

A `for in` loop like the following:

```
For O in MyObject do
  begin
    // do things
  end;
```

is treated by the compiler as equivalent to the following code:

```
Var
  I : IEnumerator;
  O : TObject;

begin
  I:=MyObject.GetEnumerator;
  While I.MoveNext do
    begin
      O:=I.GetCurrent;
      // Do things
    end;
  end.
```

Any class that implements the `IEnumerable` interface must be able to return an `IEnumerator` instance for the compiler to use in a `For in` loop.

See also: `IEnumerable` ([1425](#))

75.17.2 Method overview

Page	Method	Description
1427	<code>GetCurrent</code>	Returns the current element in the iteration cycle
1427	<code>MoveNext</code>	Move to the next value
1427	<code>Reset</code>	Reset the pointer

75.17.3 Property overview

Page	Properties	Access	Description
1427	Current	r	Return the current item

75.17.4 IEnumerator.GetCurrent

Synopsis: Returns the current element in the iteration cycle

Declaration: `function GetCurrent : TObject`

Visibility: default

Description: `GetCurrent` should return the object instance representing the current value in the `for in` loop. `GetCurrent` will always be called immediately after `IEnumerator.MoveNext` ([1427](#)) returned `True`.

Remark: The actual return type of the interface should not necessarily be `TObject`, it can be any type. The compiler will check the actual return type with the type of the loop variable, and they should match.

See also: `IEnumerator.MoveNext` ([1427](#)), `IEnumerator.Reset` ([1427](#))

75.17.5 IEnumerator.MoveNext

Synopsis: Move to the next value

Declaration: `function MoveNext : Boolean`

Visibility: default

Description: `MoveNext` should move the current item pointer to the next available item. It should return `True` if an item is available, `False` if no more items are available. The first time it is called it will be called at the beginning of the `for` loop, so it should position the enumerator on the first value (if there is one). After `MoveNext` has returned `True`, `IEnumerator.GetCurrent` ([1427](#)) will be called to retrieve the item.

See also: `IEnumerator.Reset` ([1427](#)), `IEnumerator.GetCurrent` ([1427](#))

75.17.6 IEnumerator.Reset

Synopsis: Reset the pointer

Declaration: `procedure Reset`

Visibility: default

Description: `Reset` can be implemented to put the pointer at the start of the list. It is not mandatory to implement this method, the compiler does not use it.

See also: `IEnumerator.GetCurrent` ([1427](#)), `IEnumerator.MoveNext` ([1427](#))

75.17.7 IEnumerator.Current

Synopsis: Return the current item

Declaration: `Property Current : TObject`

Visibility: default

Access: Read

Description: `Current` simply is the redefinition of `IEnumerator.GetCurrent` ([1427](#)) as a property. It is read-only.

See also: `IEnumerator.GetCurrent` ([1427](#)), `IEnumerator.MoveNext` ([1427](#))

75.18 IInvokable

75.18.1 Description

`IInvokable` is a descendent of `IInterface` ([1223](#)), compiled in the { \$M+ } state, so Run-Time Type Information (RTTI) is generated for it.

See also: `IDispatch` ([1424](#)), `IInterface` ([1223](#))

75.19 IUnknown

75.19.1 Description

`IUnknown` is defined by windows. It's the basic interface which all COM objects must implement. The definition does not contain any code.

See also: `IInterface` ([1223](#)), `IDispatch` ([1424](#)), `IInvokable` ([1428](#))

75.19.2 Method overview

Page	Method	Description
1428	<code>QueryInterface</code>	Return pointer to VMT table of interface
1428	<code>_AddRef</code>	Increase reference count of the interface
1429	<code>_Release</code>	Decrease reference count of the interface

75.19.3 IUnknown.QueryInterface

Synopsis: Return pointer to VMT table of interface

Declaration: `function QueryInterface(const iid: TGuid; out obj) : LongInt`

Visibility: default

75.19.4 IUnknown._AddRef

Synopsis: Increase reference count of the interface

Declaration: `function _AddRef : LongInt`

Visibility: default

See also: `IUnknown._Release` ([1429](#))

75.19.5 IUnknown._Release

Synopsis: Decrease reference count of the interface

Declaration: `function _Release : LongInt`

Visibility: default

See also: `IUnknown._AddRef` ([1428](#))

75.20 TAggregatedObject

75.20.1 Description

`TAggregatedObject` implements an object whose lifetime is governed by an external object (or interface). It does not implement the `IUnknown` interface by itself, but delegates all methods to the controller object, as exposed in the `Controller` ([1430](#)) property. In effect, the reference count of the aggregated object is the same as that of its controller, and additionally, all interfaces of the controller are exposed by the aggregated object.

Note that the aggregated object maintains a non-counted reference to the controller.

Aggregated objects should be used when using delegation to implement reference counted objects: the delegated interfaces can be implemented safely by `TAggregatedObject` descendents.

See also: `Create` ([1429](#)), `Controller` ([1430](#))

75.20.2 Method overview

Page	Method	Description
1429	<code>Create</code>	Create a new instance of <code>TAggregatedObject</code>

75.20.3 Property overview

Page	Properties	Access	Description
1430	<code>Controller</code>	<code>r</code>	Controlling instance

75.20.4 TAggregatedObject.Create

Synopsis: Create a new instance of `TAggregatedObject`

Declaration: `constructor Create(const aController: IUnknown)`

Visibility: public

Description: `Create` creates a new instance of `TAggregatedObject` on the heap, and stores a reference to `aController`, so it can be exposed in the `Controller` ([1430](#)) property.

Errors: If not enough memory is present on the heap, an exception will be raised. If the `aController` is `Nil`, exceptions will occur when any of the `TAggregatedObject` methods (actually, the `IUnknown` methods) are used.

See also: `Controller` ([1430](#))

75.20.5 TAggregatedObject.Controller

Synopsis: Controlling instance

Declaration: `Property Controller : IUnknown`

Visibility: public

Access: Read

Description: `Controller` exposes the controlling object, with all interfaces it has.

The value of the controller is set when the `TAggregatedObject` instance is created.

See also: `TAggregatedObject.Create` ([1429](#))

75.21 TContainedObject

75.21.1 Description

`TContainedObject` is the base class for contained objects, i.e. objects that do not implement a reference counting mechanism themselves, but are owned by some other object which handles the reference counting mechanism. It implements the `IUnknown` interface and, more specifically, the `QueryInterface` method of `IUnknown`.

See also: `IInterface` ([1223](#))

75.21.2 Interfaces overview

Page	Interfaces	Description
1223	<code>IInterface</code>	Basic interface for all COM based interfaces

75.22 TInterfacedObject

75.22.1 Description

`TInterfacedObject` is a descendent of `TObject` ([1432](#)) which implements the `IUnknown` ([1428](#)) interface. It can be used as a base class for all classes which need reference counting.

See also: `IUnknown` ([1428](#)), `TObject` ([1432](#))

75.22.2 Interfaces overview

Page	Interfaces	Description
1428	<code>IUnknown</code>	Basic interface for all COM-based interfaces

75.22.3 Method overview

Page	Method	Description
1431	<code>AfterConstruction</code>	Handle reference count properly.
1431	<code>BeforeDestruction</code>	Check reference count.
1431	<code>NewInstance</code>	Create a new instance

75.22.4 Property overview

Page	Properties	Access	Description
1431	RefCount	r	Return the current reference count

75.22.5 TInterfacedObject.AfterConstruction

Synopsis: Handle reference count properly.

Declaration: `procedure AfterConstruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds some additional reference count handling.

Errors: None.

See also: `BeforeDestruction` ([1431](#))

75.22.6 TInterfacedObject.BeforeDestruction

Synopsis: Check reference count.

Declaration: `procedure BeforeDestruction; Override`

Visibility: `public`

Description: `AfterConstruction` overrides the basic method in `TObject` and adds a reference count check: if the reference count is not zero, an error occurs.

Errors: A runtime-error 204 will be generated if the reference count is nonzero when the object is destroyed.

See also: `AfterConstruction` ([1431](#))

75.22.7 TInterfacedObject.NewInstance

Synopsis: Create a new instance

Declaration: `class function NewInstance : TObject; Override`

Visibility: `public`

Description: `NewInstance` initializes a new instance of `TInterfacedObject` ([1430](#))

Errors: None.

75.22.8 TInterfacedObject.RefCount

Synopsis: Return the current reference count

Declaration: `Property RefCount : LongInt`

Visibility: `public`

Access: Read

Description: `RefCount` returns the current reference count. This reference count cannot be manipulated, except through the methods of `IUnknown` ([1428](#)). When it reaches zero, the class instance is destroyed.

See also: `IUnknown` ([1428](#))

75.23 TObject

75.23.1 Description

`TObject` is the parent root class for all classes in Object Pascal. If a class has no parent class explicitly declared, it is dependent on `TObject`. `TObject` introduces class methods that deal with the class' type information, and contains all necessary methods to create an instance at runtime, and to dispatch messages to the correct method (both string and integer messages).

See also: `TClass` ([1236](#))

75.23.2 Method overview

Page	Method	Description
1438	<code>AfterConstruction</code>	Method called after the constructor was called.
1438	<code>BeforeDestruction</code>	Method called before the destructor is called.
1435	<code>ClassInfo</code>	Return a pointer to the type information for this class.
1435	<code>ClassName</code>	Return the current class name.
1436	<code>ClassNameIs</code>	Check whether the class name equals the given name.
1436	<code>ClassParent</code>	Return the parent class.
1435	<code>ClassType</code>	Return a "class of" pointer for the current class
1435	<code>CleanupInstance</code>	Finalize the class instance.
1433	<code>Create</code>	<code>TObject</code> Constructor
1434	<code>DefaultHandler</code>	Default handler for integer message handlers.
1438	<code>DefaultHandlerStr</code>	Default handler for string messages.
1433	<code>Destroy</code>	<code>TObject</code> destructor.
1438	<code>Dispatch</code>	Dispatch an integer message
1439	<code>DispatchStr</code>	Dispatch a string message.
1441	<code>Equals</code>	Check if two objects are equal.
1437	<code>FieldAddress</code>	Return the address of a field.
1434	<code>Free</code>	Check for <code>Nil</code> and call destructor.
1433	<code>FreeInstance</code>	Clean up instance and free the memory reserved for the instance.
1441	<code>GetHashCode</code>	Return a hash code for the object
1439	<code>GetInterface</code>	Return a reference to an interface
1439	<code>GetInterfaceByStr</code>	Return an interface based on its GUID
1440	<code>GetInterfaceEntry</code>	Return the interface table entry by GUID
1440	<code>GetInterfaceEntryByStr</code>	Return the interface table entry by string
1440	<code>GetInterfaceTable</code>	Return a pointer to the table of implemented interfaces for a class
1440	<code>GetInterfaceWeak</code>	Get a reference to an interface, not increasing the reference count
1436	<code>InheritsFrom</code>	Check whether class is an ancestor.
1434	<code>InitInstance</code>	Initialize a new class instance.
1436	<code>InstanceSize</code>	Return the size of an instance.
1437	<code>MethodAddress</code>	Return the address of a method
1437	<code>MethodName</code>	Return the name of a method.
1433	<code>newinstance</code>	Allocate memory on the heap for a new instance
1434	<code>SafeCallException</code>	Handle exception object
1437	<code>StringMessageTable</code>	Return a pointer to the string message table.
1441	<code>ToString</code>	Return a string representation for the object
1441	<code>UnitName</code>	Unit name

75.23.3 TObject.Create

Synopsis: TObject Constructor

Declaration: constructor Create

Visibility: public

Description: Create creates a new instance of TObject. Currently it does nothing. It is also not virtual, so there is in principle no need to call it directly.

See also: Destroy ([1433](#))

75.23.4 TObject.Destroy

Synopsis: TObject destructor.

Declaration: destructor Destroy; Virtual

Visibility: public

Description: Destroy is the destructor of TObject. It will clean up the memory assigned to the instance. Descendent classes should override destroy if they want to do additional clean-up. No other destructor should be implemented.

It is bad programming practice to call Destroy directly. It is better to call the Free ([1434](#)) method, because that one will check first if Self is different from Nil.

To clean up an instance and reset the refence to the instance, it is best to use the FreeAndNil ([1547](#)) function.

See also: Create ([1433](#)), Free ([1434](#))

75.23.5 TObject.newinstance

Synopsis: Allocate memory on the heap for a new instance

Declaration: class function newInstance : TObject; Virtual

Visibility: public

Description: NewInstance allocates memory on the heap for a new instance of the current class. If the memory was allocated, the class will be initialized by a call to InitInstance ([1434](#)). The function returns the newly initialized instance.

This method can be overridden to implement e.g. object pooling. Note that the method is responsible for correctly initializing the object, i.e. zeroing out the new instance.

Errors: If not enough memory is available, a Nil pointer may be returned, or an exception may be raised.

See also: Create ([1433](#)), InitInstance ([1434](#)), InstanceSize ([1436](#)), FreeInstance ([1433](#))

75.23.6 TObject.FreeInstance

Synopsis: Clean up instance and free the memory reserved for the instance.

Declaration: procedure FreeInstance; Virtual

Visibility: public

Description: `FreeInstance` cleans up an instance of the current class, and releases the heap memory occupied by the class instance.

See also: `Destroy` ([1433](#)), `InitInstance` ([1434](#)), `NewInstance` ([1433](#))

75.23.7 TObject.SafeCallException

Synopsis: Handle exception object

Declaration: `function SafeCallException(exceptobject: TObject;
exceptaddr: CodePointer) : HRESULT; Virtual`

Visibility: public

Description: `SafeCallException` should be overridden to handle exceptions in a method marked with the `savecall` directive. The implementation in `TObject` simply returns zero.

75.23.8 TObject.DefaultHandler

Synopsis: Default handler for integer message handlers.

Declaration: `procedure DefaultHandler(var message); Virtual`

Visibility: public

Description: `DefaultHandler` is the default handler for messages. If a message has an unknown message ID (i.e. does not appear in the table with integer message handlers), then it will be passed to `DefaultHandler` by the `Dispatch` ([1438](#)) method.

See also: `Dispatch` ([1438](#)), `DefaultHandlerStr` ([1438](#))

75.23.9 TObject.Free

Synopsis: Check for `Nil` and call destructor.

Declaration: `procedure Free`

Visibility: public

Description: `Free` will check the `Self` pointer and calls `Destroy` ([1433](#)) if it is different from `Nil`. This is a safer method than calling `Destroy` directly. If a reference to the object must be reset as well (a recommended technique), then the function `FreeAndNil` ([1547](#)) should be called.

Errors: None.

See also: `Destroy` ([1433](#)), `FreeAndNil` ([1547](#))

75.23.10 TObject.InitInstance

Synopsis: Initialize a new class instance.

Declaration: `class function InitInstance(instance: pointer) : TObject`

Visibility: public

Description: `InitInstance` initializes the memory pointer to by `Instance`. This means that the VMT is initialized, and the interface pointers are set up correctly. The function returns the newly initialized instance.

See also: `NewInstance` ([1433](#)), `Create` ([1433](#))

75.23.11 TObject.CleanupInstance

Synopsis: Finalize the class instance.

Declaration: `procedure CleanupInstance`

Visibility: `public`

Description: `CleanUpInstance` finalizes the instance, i.e. takes care of all reference counted objects, by decreasing their reference count by 1, and freeing them if their count reaches zero.

Normally, `CleanupInstance` should never be called, it is called automatically when the object is freed with it's constructor.

Errors: None.

See also: `Destroy` ([1433](#)), `Free` ([1434](#)), `InitInstance` ([1434](#))

75.23.12 TObject.ClassType

Synopsis: Return a "class of" pointer for the current class

Declaration: `class function ClassType : TClass`

Visibility: `public`

Description: `ClassType` returns a `TClass` ([1236](#)) class type reference for the current class.

See also: `TClass` ([1236](#)), `ClassInfo` ([1435](#)), `ClassName` ([1435](#))

75.23.13 TObject.ClassInfo

Synopsis: Return a pointer to the type information for this class.

Declaration: `class function ClassInfo : pointer`

Visibility: `public`

Description: `ClassInfo` returns a pointer to the type information for this class. This pointer can be used in the various type information routines.

75.23.14 TObject.ClassName

Synopsis: Return the current class name.

Declaration: `class function ClassName : shortstring`

Visibility: `public`

Description: `ClassName` returns the class name for the current class, in all-uppercase letters. To check for the class name, use the `ClassNameIs` ([1436](#)) class method.

Errors: None.

See also: `ClassInfo` ([1435](#)), `ClassType` ([1435](#)), `ClassNameIs` ([1436](#))

75.23.15 TObject.ClassNameIs

Synopsis: Check whether the class name equals the given name.

Declaration: `class function ClassNameIs(const name: string) : Boolean`

Visibility: public

Description: `ClassNameIs` checks whether `Name` equals the class name. It takes of case sensitivity, i.e. it converts both names to uppercase before comparing.

See also: `ClassInfo` ([1435](#)), `ClassType` ([1435](#)), `ClassName` ([1435](#))

75.23.16 TObject.ClassParent

Synopsis: Return the parent class.

Declaration: `class function ClassParent : TClass`

Visibility: public

Description: `ClassParent` returns the class of the parent class of the current class. This is always different from `Nil`, except for `TObject`.

Errors: None.

See also: `ClassInfo` ([1435](#)), `ClassType` ([1435](#)), `ClassNameIs` ([1435](#))

75.23.17 TObject.InstanceSize

Synopsis: Return the size of an instance.

Declaration: `class function InstanceSize : SizeInt`

Visibility: public

Description: `InstanceSize` returns the number of bytes an instance takes in memory. This is Just the memory occupied by the class structure, and does not take into account any additional memory that might be allocated by the constructor of the class.

Errors: None.

See also: `InitInstance` ([1434](#)), `ClassName` ([1435](#)), `ClassInfo` ([1435](#)), `ClassType` ([1435](#))

75.23.18 TObject.InheritsFrom

Synopsis: Check whether class is an ancestor.

Declaration: `class function InheritsFrom(aClass: TClass) : Boolean`

Visibility: public

Description: `InheritsFrom` returns `True` if `AClass` is an ancestor class from the current class, and returns `false` if it is not.

See also: `ClassName` ([1435](#)), `ClassInfo` ([1435](#)), `ClassType` ([1435](#)), `TClass` ([1236](#))

75.23.19 TObject.StringMessageTable

Synopsis: Return a pointer to the string message table.

Declaration: `class function StringMessageTable : pstringmessagetable`

Visibility: public

Description: `StringMessageTable` returns a pointer to the string message table, which can be used to look up methods for dispatching a string message. It is used by the `DispatchStr` (1439) method.

Errors: If there are no string message handlers, nil is returned.

See also: `DispatchStr` (1439), `Dispatch` (1438)

75.23.20 TObject.MethodAddress

Synopsis: Return the address of a method

Declaration: `class function MethodAddress(const name: shortstring) : CodePointer`

Visibility: public

Description: `MethodAddress` returns the address of a method, searching the method by its name. The `Name` parameter specifies which method should be taken. The search is conducted in a case-insensitive manner.

Errors: If no matching method is found, `Nil` is returned.

See also: `MethodName` (1437), `FieldAddress` (1437)

75.23.21 TObject.MethodName

Synopsis: Return the name of a method.

Declaration: `class function MethodName(address: CodePointer) : shortstring`

Visibility: public

Description: `MethodName` searches the VMT for a method with the specified address and returns the name of the method.

Errors: If no method with the matching address is found, an empty string is returned.

See also: `MethodAddress` (1437), `FieldAddress` (1437)

75.23.22 TObject.FieldAddress

Synopsis: Return the address of a field.

Declaration: `function FieldAddress(const name: shortstring) : pointer`

Visibility: public

Description: `FieldAddress` returns the address of the field with name `name`. The address is the address of the field in the current class instance.

Errors: If no field with the specified name is found, `Nil` is returned.

See also: `MethodAddress` (1437), `MethodName` (1437)

75.23.23 TObject.AfterConstruction

Synopsis: Method called after the constructor was called.

Declaration: `procedure AfterConstruction; Virtual`

Visibility: `public`

Description: `AfterConstruction` is a method called after the constructor was called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed after the constructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `BeforeDestruction` ([1438](#)), `Create` ([1433](#))

75.23.24 TObject.BeforeDestruction

Synopsis: Method called before the destructor is called.

Declaration: `procedure BeforeDestruction; Virtual`

Visibility: `public`

Description: `BeforeDestruction` is a method called before the destructor is called. It does nothing in the implementation of `TObject` and must be overridden by descendent classes to provide specific behaviour that is executed before the destructor has finished executing. (for instance, call an event handler)

Errors: None.

See also: `AfterConstruction` ([1438](#)), `Destroy` ([1433](#)), `Free` ([1434](#))

75.23.25 TObject.DefaultHandlerStr

Synopsis: Default handler for string messages.

Declaration: `procedure DefaultHandlerStr(var message); Virtual`

Visibility: `public`

Description: `DefaultHandlerStr` is called for string messages which have no handler associated with them in the string message handler table. The implementation of `DefaultHandlerStr` in `TObject` does nothing and must be overridden by descendent classes to provide specific message handling behaviour.

See also: `DispatchStr` ([1439](#)), `Dispatch` ([1438](#)), `DefaultHandler` ([1434](#))

75.23.26 TObject.Dispatch

Synopsis: Dispatch an integer message

Declaration: `procedure Dispatch(var message); Virtual`

Visibility: `public`

Description: `Dispatch` looks in the message handler table for a handler that handles `message`. The message is identified by the first dword (cardinal) in the message structure.

If no matching message handler is found, the message is passed to the `DefaultHandler` (1434) method, which can be overridden by descendent classes to add custom handling of messages.

See also: `DispatchStr` (1439), `DefaultHandler` (1434)

75.23.27 TObject.DispatchStr

Synopsis: Dispatch a string message.

Declaration: `procedure DispatchStr(var message); Virtual`

Visibility: public

Description: `DispatchStr` extracts the message identifier from `Message` and checks the message handler table to see if a handler for the message is found, and calls the handler, passing along the message. If no handler is found, the default `DefaultHandlerStr` (1438) is called.

Errors: None.

See also: `DefaultHandlerStr` (1438), `Dispatch` (1438), `DefaultHandler` (1434)

75.23.28 TObject.GetInterface

Synopsis: Return a reference to an interface

Declaration: `function GetInterface(const iid: TGuid; out obj) : Boolean`
`function GetInterface(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterface` scans the interface tables and returns a reference to the interface `iid`. The reference is stored in `Obj` which should be an interface reference. It returns `True` if the interface was found, `False` if not.

The reference count of the interface is increased by this call.

Errors: If no interface was found, `False` is returned.

See also: `GetInterfaceByStr` (1439)

75.23.29 TObject.GetInterfaceByStr

Synopsis: Return an interface based on its GUID

Declaration: `function GetInterfaceByStr(const iidstr: shortstring; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceByStr` returns in `obj` a pointer to the interface identified by `iidstr`. The function returns `True` if the interface is indeed implemented by the class, or `False` otherwise.

The `iidstr` is the unique GUID by which the interface was declared.

Errors: The function returns false if the requested interface is not implemented.

See also: `TObject.GetInterfaceEntry` (1440), `TObject.GetInterfaceEntryByStr` (1440)

75.23.30 TObject.GetInterfaceWeak

Synopsis: Get a reference to an interface, not increasing the reference count

Declaration: `function GetInterfaceWeak(const iid: TGuid; out obj) : Boolean`

Visibility: public

Description: `GetInterfaceWeak` performs the same function as `GetInterface` (1439), but unlike the latter, it will not increase the reference count of the interface.

See also: `TObject.GetInterface` (1439)

75.23.31 TObject.GetInterfaceEntry

Synopsis: Return the interface table entry by GUID

Declaration: `class function GetInterfaceEntry(const iid: TGuid) : pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntry` returns the internal interface table entry for the interface identified by `iid` (the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1439), `TObject.GetInterfaceEntryByStr` (1440)

75.23.32 TObject.GetInterfaceEntryByStr

Synopsis: Return the interface table entry by string

Declaration: `class function GetInterfaceEntryByStr(const iidstr: shortstring)
: pinterfaceentry`

Visibility: public

Description: `GetInterfaceEntryByStr` returns the internal interface table entry for the interface identified by `iidstr` (A string representation of the GUID used in the declaration of the interface). If the interface is not implemented by the class, the function returns `Nil`.

See also: `TObject.GetInterfaceByStr` (1439), `TObject.GetInterfaceEntry` (1440)

75.23.33 TObject.GetInterfaceTable

Synopsis: Return a pointer to the table of implemented interfaces for a class

Declaration: `class function GetInterfaceTable : pinterfacetable`

Visibility: public

Description: `GetInterfaceTable` returns a pointer to the internal table of implemented interfaces for a class. The result will always point to a valid address, if the class implements no interfaces the `EntryCount` field of the interface table will be zero.

See also: `TObject.GetInterfaceByStr` (1439), `TObject.GetInterfaceEntry` (1440)

75.23.34 TObject.UnitName

Synopsis: Unit name

Declaration: `class function UnitName : ansistring`

Visibility: public

Description: `UnitName` returns the unit name in which the class was defined. The name is obtained from the class definition data the compiler generates for each class.

75.23.35 TObject.Equals

Synopsis: Check if two objects are equal.

Declaration: `function Equals (Obj: TObject) : Boolean; Virtual`

Visibility: public

Description: `Equals` returns `True` if the object instance pointer (`Self`) equals the instance pointer `Obj`.

Descendent classes can override to check properties etc. in case the instance pointers are different.

See also: `TObject.GetHashCode` ([1441](#)), `TObject.ToString` ([1441](#))

75.23.36 TObject.GetHashCode

Synopsis: Return a hash code for the object

Declaration: `function GetHashCode : PtrInt; Virtual`

Visibility: public

Description: `GetHashCode` should return a hash code for the object. By default, the numerical (integer) address of `Self` is returned.

Descendent classes can use this to generate better suitable values to be used in a hash table.

See also: `TObject.ToString` ([1441](#)), `TObject.Equals` ([1441](#))

75.23.37 TObject.ToString

Synopsis: Return a string representation for the object

Declaration: `function ToString : ansistring; Virtual`

Visibility: public

Description: `ToString` returns by default the class name of the object. It is useful during sending of debug messages.

Descendent classes can override this method to give a better description of the object than just the class name.

See also: `TObject.GetHashCode` ([1441](#)), `TObject.Equals` ([1441](#))

Chapter 76

Reference for unit 'sysutils'

76.1 Used units

Table 76.1: Used units by unit 'sysutils'

Name	Page
errors	662
Linux	871
sysconst	??
System	1194
Unix	1840
unixtype	1879

76.2 Overview

This documentation describes the `sysutils` unit. The `sysutils` unit was started by Gertjan Schouten, and completed by Michael Van Canneyt. It aims to be compatible to the Delphi `sysutils` unit, but in contrast with the latter, it is designed to work on multiple platforms. It is implemented on all supported platforms.

76.3 Type Helpers for basic types

The `sysutils` unit contains type helpers for basic language types: boolean, ordinals (shortint, smallint, byte, word, integer, cardinal, int64, wqord, nativeint, nativeuint), strings, floating-point and GUID values. They can be used as-is, or they can be descended from to form your own type helpers.

See also: `TGuidHelper` ([1656](#)), `TStringHelper` ([1691](#)), `TByteHelper` ([1632](#)), `TShortIntHelper` ([1677](#)), `TSmallIntHelper` ([1689](#)), `TWordHelper` ([1718](#)), `TCardinalHelper` ([1635](#)), `TIntegerHelper` ([1660](#)), `TInt64Helper` ([1658](#)), `TQWordHelper` ([1674](#)), `TNativeIntHelper` ([1668](#)), `TBooleanHelper` ([1629](#)), `TByteBoolHelper` ([1630](#)), `TWordBoolHelper` ([1717](#)), `TLongBoolHelper` ([1663](#)), `TSingleHelper` ([1681](#)), `TDoubleHelper` ([1638](#)), `TExtendedHelper` ([1650](#))

76.4 Localization support

Localization support depends on various constants and structures being initialized correctly. On Windows and OS/2 this is done automatically: a widestring manager is installed by default which helps taking care of the current locale when performing various operations on strings. The various internationalization settings (date/time format, currency, language etc) are also initialized correctly on these platforms.

On unixes, the widestring support is in a separate unit: `cwstring`, which loads the various needed functions from the C library. It should be added manually to the `uses` clause of your program. No internationalization (or localisation) settings are applied by this unit, these must be initialized separately by including the `locale` unit in the `uses` clause of your program.

76.5 Unicode and codepage awareness

The many functions that deal with filenames in the `sysutils` routines have been changed from `AnsiString` to `RawByteString` so they do not perform implicit codepage conversions to the ansi code page. At the same time, overloaded versions that accept a unicode string have been created.

For routines that access actual OS functions using single-byte string APIs, the strings are converted to ensure that the OS routine receives a string with the correct encoding when using single-byte strings. This encoding is normally the `DefaultFileSystemCodePage` (1261) encoding.

On systems with a unicode I/O API (2-byte strings), the native API is used, meaning that unicode strings will be passed on as-is, but single-byte strings will be converted (implicitly) to Unicode.

The following is a minimal list of functions that have been changed and duplicated:

Table 76.2:

Name	Description
<code>CreateFile</code> (1519)	Create a new file and return a handle to it.
<code>OpenFile</code> (1523)	Open an existing file and return a filehandle
<code>FileExists</code> (1521)	Check whether a particular file exists in the filesystem.
<code>DirectoryExists</code> (1505)	Check whether a directory exists in the file system.
<code>FileSetDate</code> (1527)	Set the date of a file.
<code>FileGetAttr</code> (1521)	Return attributes of a file.
<code>FileSetAttr</code> (1527)	Set the attributes of a file.
<code>DeleteFile</code> (1505)	Delete a file from the filesystem.
<code>RenameFile</code> (1565)	Rename a file.
<code>FileSearch</code> (1525)	Search for a file in a path.
<code>ExeSearch</code> (1512)	Search for an executable
<code>FindFirst</code> (1529)	Start a file search and return a findhandle
<code>FindNext</code> (1530)	Find the next entry in a findhandle.
<code>FindClose</code> (1528)	Close a find handle
<code>FileIsReadOnly</code> (1523)	Check whether a file is read-only.
<code>GetCurrentDir</code> (1549)	Return the current working directory of the application.
<code>SetCurrentDir</code> (1568)	Set the current directory of the application.

The following functions do not interact with the OS, but may nevertheless change the codepage of the strings involved in their operation:

Table 76.3:

Name	Description
ChangeFileExt (1492)	Change the extension of a filename.
ExtractFilePath (1516)	Extract the path from a filename.
ExtractFileDrive (1515)	Extract the drive part from a filename.
ExtractFileName (1516)	Extract the filename part from a full path filename.
ExtractFileExt (1516)	Return the extension from a filename.
ExtractFileDir (1515)	Extract the drive and directory part of a filename.
ExtractShortPathName (1517)	Returns a 8.3 path name
ExpandFileName (1513)	Expand a relative filename to an absolute filename.
ExpandFileNameCase (1513)	Expand a filename entered as case insensitive to the full path as stored on the disk.
ExtractRelativepath (1517)	Extract a relative path from a filename, given a base directory.
ExpandUNCFileName (1514)	Expand a relative filename to an absolute UNC filename.
IncludeTrailingPathDelimiter (1556)	Add trailing directory separator to a pathname, if needed.
IncludeTrailingBackslash (1556)	Add trailing directory separator to a pathname, if needed.
ExcludeTrailingBackslash (1511)	Strip trailing directory separator from a pathname, if needed.
ExcludeTrailingPathDelimiter (1511)	Strip trailing directory separator from a pathname, if needed.
IncludeLeadingPathDelimiter (1555)	Prepend a path delimiter if there is not already one.
ExcludeLeadingPathDelimiter (1511)	Strip the leading path delimiter of a path
IsPathDelimiter (1560)	Is the character at the given position a pathdelimiter ?
DoDirSeparators (1507)	Convert known directory separators to the current directory separator.
SetDirSeparators (1568)	Set the directory separators to the known directory separators.
GetDirs (1549)	Return a list of directory names from a path.
ConcatPaths (1496)	Concatenate an array of paths to form a single path
GetEnvironmentVariable (1551)	Return the value of an environment variable.

76.6 Miscellaneous conversion routines

Functions for various conversions.

Table 76.4:

Name	Description
BCDToInt (1490)	Convert BCD number to integer
CompareMem (1493)	Compare two memory regions
FloatToStrF (1533)	Convert float to formatted string
FloatToStr (1532)	Convert float to string
FloatToText (1535)	Convert float to string
FormatFloat (1546)	Format a floating point value
GetDirs (1549)	Split string in list of directories
IntToHex (1557)	return hexadecimal representation of integer
IntToStr (1558)	return decumal representation of integer
StrToIntDef (1592)	Convert string to integer with default value
StrToInt (1590)	Convert string to integer
StrToFloat (1589)	Convert string to float
TextToFloat (1596)	Convert null-terminated string to float

76.7 Date/time routines

Functions for date and time handling.

Table 76.5:

Name	Description
<code>DateTimeToFileDate</code> (1499)	Convert <code>DateTime</code> type to file date
<code>DateTimeToStr</code> (1500)	Construct string representation of <code>DateTime</code>
<code>DateTimeToString</code> (1500)	Construct string representation of <code>DateTime</code>
<code>DateTimeToSystemTime</code> (1501)	Convert <code>DateTime</code> to system time
<code>DateTimeToTimeStamp</code> (1502)	Convert <code>DateTime</code> to timestamp
<code>DateToStr</code> (1502)	Construct string representation of date
<code>Date</code> (1499)	Get current date
<code>DayOfWeek</code> (1503)	Get day of week
<code>DecodeDate</code> (1503)	Decode <code>DateTime</code> to year month and day
<code>DecodeTime</code> (1504)	Decode <code>DateTime</code> to hours, minutes and seconds
<code>EncodeDate</code> (1508)	Encode year, day and month to <code>DateTime</code>
<code>EncodeTime</code> (1509)	Encode hours, minutes and seconds to <code>DateTime</code>
<code>FormatDateTime</code> (1545)	Return string representation of <code>DateTime</code>
<code>IncMonth</code> (1556)	Add 1 to month
<code>IsLeapYear</code> (1559)	Determine if year is leap year
<code>MSecsToTimeStamp</code> (1563)	Convert nr of milliseconds to timestamp
<code>Now</code> (1564)	Get current date and time
<code>StrToDateTime</code> (1587)	Convert string to <code>DateTime</code>
<code>StrToDate</code> (1586)	Convert string to date
<code>StrToTime</code> (1593)	Convert string to time
<code>SystemTimeToDateTime</code> (1595)	Convert system time to datetime
<code>TimeStampToDateTime</code> (1598)	Convert time stamp to <code>DateTime</code>
<code>TimeStampToMSecs</code> (1598)	Convert Timestamp to number of milliseconds
<code>TimeToStr</code> (1599)	return string representation of Time
<code>Time</code> (1597)	Get current time

76.8 FileName handling routines

Functions for file manipulation.

Table 76.6:

Name	Description
AnsiCompareFileName (1475)	Compare 2 filenames
AnsiLowerCaseFileName (1480)	Create lowercase filename
AnsiUpperCaseFileName (1488)	Create uppercase filename
AddDisk (1474)	Add disk to list of disk drives
ChangeFileExt (1492)	Change extension of file name
CreateDir (1497)	Create a directory
DeleteFile (1505)	Delete a file
DiskFree (1506)	Free space on disk
DiskSize (1506)	Total size of disk
ExpandFileName (1513)	Create full file name
ExpandFileNameCase (1513)	Create full file name case insensitively
ExpandUNCFileName (1514)	Create full UNC file name
ExtractFileDir (1515)	Extract drive and directory part of filename
ExtractFileDrive (1515)	Extract drive part of filename
ExtractFileExt (1516)	Extract extension part of filename
ExtractFileName (1516)	Extract name part of filename
ExtractFilePath (1516)	Extract path part of filename
ExtractRelativePath (1517)	Construct relative path between two files
FileAge (1518)	Return file age
FileDateToDateTime (1520)	Convert file date to system date
FileExists (1521)	Determine whether a file exists on disk
FileGetAttr (1521)	Get attributes of file
FileGetDate (1522)	Get date of last file modification
FileSearch (1525)	Search for file in path
FileSetAttr (1527)	Get file attributes
FileSetDate (1527)	Get file dates
FindFirst (1529)	Start finding a file
FindNext (1530)	Find next file
GetCurrentDir (1549)	Return current working directory
RemoveDir (1565)	Remove a directory from disk
RenameFile (1565)	Rename a file on disk
SameFileName (1567)	Check whether 2 filenames are the same
SetCurrentDir (1568)	Set current working directory
SetDirSeparators (1568)	Set directory separator characters
FindClose (1528)	Stop searching a file
DoDirSeparators (1507)	Replace directory separator characters

76.9 File input/output routines

Functions for reading/writing to file.

Table 76.7:

Name	Description
FileCreate (1519)	Create a file and return handle
FileOpen (1523)	Open file and return handle
FileRead (1524)	Read from file
FileSeek (1526)	Set file position
FileTruncate (1528)	Truncate file length
FileWrite (1528)	Write to file
FileClose (1518)	Close file handle

76.10 PChar related functions

Most PChar functions are the same as their counterparts in the STRINGS unit. The following functions are the same :

1. StrCat (1571) : Concatenates two PChar strings.
2. StrComp (1572) : Compares two PChar strings.
3. StrCopy (1572) : Copies a PChar string.
4. StrECopy (1573) : Copies a PChar string and returns a pointer to the terminating null byte.
5. StrEnd (1574) : Returns a pointer to the terminating null byte.
6. StrIComp (1575) : Case insensitive compare of 2 PChar strings.
7. StrLCat (1577) : Appends at most L characters from one PChar to another PChar.
8. StrLComp (1578) : Case sensitive compare of at most L characters of 2 PChar strings.
9. StrLCopy (1578) : Copies at most L characters from one PChar to another.
10. StrLen (1579) : Returns the length (exclusive terminating null byte) of a PChar string.
11. StrLIComp (1580) : Case insensitive compare of at most L characters of 2 PChar strings.
12. StrLower (1581) : Converts a PChar to all lowercase letters.
13. StrMove (1581) : Moves one PChar to another.
14. StrNew (1582) : Makes a copy of a PChar on the heap, and returns a pointer to this copy.
15. StrPos (1584) : Returns the position of one PChar string in another?
16. StrRScan (1584) : returns a pointer to the last occurrence of on PChar string in another one.
17. StrScan (1584) : returns a pointer to the first occurrence of on PChar string in another one.
18. StrUpper (1594) : Converts a PChar to all uppercase letters.

The subsequent functions are different from their counterparts in STRINGS, although the same examples can be used.

76.11 Date and time formatting characters

Various date and time formatting routines accept a format string to format the date and or time. The following characters can be used to control the date and time formatting:

c Formats date using `shortdateformat` and formats time using `longtimeformat` if the time is not zero.

f Same as **c**, but adds the time even if it is zero.

d day of month

dd day of month (leading zero)

ddd day of week (abbreviation)

dddd day of week (full)

dddddd `shortdateformat`

ddddddd `longdateformat`

m month or minutes if preceded by **h** or **hh** specifiers.

mm month or minutes if preceded by **h** or **hh** specifiers, with leading zero.

mmm month (abbreviation)

mmmm month (full)

y year (2 digits)

yy year (two digits)

yyyy year (with century)

h hour

hh hour (leading zero)

n minute

nn minute (leading zero)

s second

ss second (leading zero)

t `shorttimeformat`

tt `longtimeformat`

am/pm use 12 hour clock and display am and pm accordingly

a/p use 12 hour clock and display a and p accordingly

/ insert date separator

: insert time separator

"xx" literal text

'xx' literal text

z milliseconds

zzz milliseconds(leading zero)

[h] hours including the hours of the full days (i.e. can be > 24).

[hh] hours with leading zero, including the hours of the full days (i.e. can be > 24)

[n] minutes including the minutes of the full hours and days

[nn] minutes with leading zero, including the minutes of the full hours and days

[s] seconds including the seconds of the full minutes, hours and days.

[ss] seconds with leading zero, including the seconds of the full minutes, hours and days.

The forms in square brackets are only allowed if the `fdPeriod` option is included in the `Options` argument of `FormatDateTime`.

The date and time separators are taken from the `DefaultFormatSettings` (1469) record, unless a `TFormatSettings` (1464) record is passed to the `FormatDateTime` (1545) function.

Note that to include any of the above characters literally in the result string, they must be enclosed in double quotes.

See also: `DefaultFormatSettings` (1469), `TFormatSettings` (1464), `FormatDateTime` (1545)

76.12 Formatting strings

Functions for formatting strings.

Table 76.8:

Name	Description
<code>AdjustLineBreaks</code> (1475)	Convert line breaks to line breaks for system
<code>FormatBuf</code> (1544)	Format a buffer
<code>Format</code> (1537)	Format arguments in string
<code>FmtStr</code> (1536)	Format buffer
<code>QuotedStr</code> (1564)	Quote a string
<code>StrFmt</code> (1575)	Format arguments in a string
<code>StrLFmt</code> (1579)	Format maximum L characters in a string
<code>TrimLeft</code> (1600)	Remove whitespace at the left of a string
<code>TrimRight</code> (1600)	Remove whitespace at the right of a string
<code>Trim</code> (1599)	Remove whitespace at both ends of a string

76.13 String functions

Functions for handling strings.

Table 76.9:

Name	Description
AnsiCompareStr (1476)	Compare two strings
AnsiCompareText (1477)	Compare two strings, case insensitive
AnsiExtractQuotedStr (1478)	Removes quotes from string
AnsiLastChar (1479)	Get last character of string
AnsiLowerCase (1479)	Convert string to all-lowercase
AnsiQuotedStr (1480)	Quotes a string
AnsiStrComp (1481)	Compare strings case-sensitive
AnsiStrIComp (1482)	Compare strings case-insensitive
AnsiStrLComp (1484)	Compare L characters of strings case sensitive
AnsiStrLIComp (1484)	Compare L characters of strings case insensitive
AnsiStrLastChar (1483)	Get last character of string
AnsiStrLower (1485)	Convert string to all-lowercase
AnsiStrUpper (1487)	Convert string to all-uppercase
AnsiUpperCase (1487)	Convert string to all-uppercase
AppendStr (1488)	Append 2 strings
AssignStr (1489)	Assign value of strings on heap
CompareStr (1494)	Compare two strings case sensitive
CompareText (1495)	Compare two strings case insensitive
DisposeStr (1507)	Remove string from heap
IsValidIdent (1560)	Is string a valid pascal identifier
LastDelimiter (1561)	Last occurrence of character in a string
LeftStr (1561)	Get first N characters of a string
LoadStr (1562)	Load string from resources
LowerCase (1562)	Convert string to all-lowercase
NewStr (1563)	Allocate new string on heap
RightStr (1567)	Get last N characters of a string
StrAlloc (1570)	Allocate memory for string
StrBufSize (1570)	Reserve memory for a string
StrDispose (1573)	Remove string from heap
StrPas (1583)	Convert PChar to pascal string
StrPCopy (1583)	Copy pascal string
StrPLCopy (1583)	Copy N bytes of pascal string
UpperCase (1609)	Convert string to all-uppercase

76.14 Constants, types and variables

76.14.1 Constants

`ConfigExtension : string = '.cfg'`

`ConfigExtension` is the default extension used by the `GetAppConfigFile (1548)` call. It can be set to any valid extension for the current OS.

`CPUEndian = TEndian.Big`

`CPUEndian` describes whether the current CPU is little or big endian.

`DateDelta = 693594`

Days between 1/1/0001 and 12/31/1899

`DriveDelim = DriveSeparator`

`DriveDelim` refers to the system unit's `DriveSeparator` constant, it is for Delphi compatibility only.

`EmptyStr : string = ''`

Empty String Constant

`EmptyWideStr : WideString = ''`

Empty wide string.

`faAnyFile = $000001FF`

Use this attribute in the `FindFirst` (1529) call to find all matching files.

`faArchive = $00000020`

Attribute of a file, meaning the file has the archive bit set. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`faCompressed = $00000800platform`

`faTemporary` can be returned by `FindFirst` (1529) or `FindNext` (1530) to indicate that a returned file is compressed (on filesystems that support this).

`faDirectory = $00000010`

Attribute of a file, meaning the file is a directory. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`faEncrypted = $00004000platform`

`faEncrypted` can be returned by `FindFirst` (1529) or `FindNext` (1530) to indicate that a returned file is encrypted (on filesystems that support this).

`faHidden = $00000002platform`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`faNormal = $00000080`

`faNormal` can be used in `FindFirst` (1529) to indicate that normal files must be included in the result.

`faReadOnly = $00000001`

Attribute of a file, meaning the file is read-only. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`faSymLink = $00000400platform`

`faSymLink` means the file (as returned e.g. by `FindFirst` (1529)/`FindNext` (1530)), is a symlink. It's ignored under Windows.

`faSysFile = $00000004platform`

Attribute of a file, meaning the file is a system file. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`faTemporary = $00000100platform`

`faTemporary` can be returned by `FindFirst` (1529) or `FindNext` (1530) to indicate that a returned file is a temporary file.

`faVirtual = $00010000platform`

`faVirtual` can be returned by `FindFirst` (1529) or `FindNext` (1530) to indicate that a returned file is virtual (on filesystems that support this).

`faVolumeId = $00000008deprecated; platform`

Attribute of a file, meaning the entry contains the volume ID. Used in `TSearchRec` (1466) and `FindFirst` (1529)

`feInvalidHandle : THandle = (-1)`

`feInvalidHandle` is the return value of `FileOpen` (1523) in case of an error.

`fmOpenRead = $0000`

`fmOpenRead` is used in the `FileOpen` (1523) call to open a file in read-only mode.

`fmOpenReadWrite = $0002`

`fmOpenReadWrite` is used in the `FileOpen` (1523) call to open a file in read-write mode.

`fmOpenWrite = $0001`

`fmOpenWrite` is used in the `FileOpen` (1523) call to open a file in write-only mode.

`fmShareCompat = $0000`

`fmOpenShareCompat` is used in the `FileOpen` (1523) call OR-ed together with one of `fmOpenReadWrite` (1452), `fmOpenRead` (1452) or `fmOpenWrite` (1452), to open a file in a sharing modus that is equivalent to sharing implemented in MS-DOS.

`fmShareDenyNone = $0040`

`fmShareDenyNone` is used in the `FileOpen` (1523) call OR-ed together with one of `fmOpenReadWrite` (1452), `fmOpenRead` (1452) or `fmOpenWrite` (1452), to open a file so other processes can read/write the file as well.

```
fmShareDenyRead = $0030
```

`fmOpenShareRead` is used in the `FileOpen` (1523) call OR-ed together with one of `fmOpenReadWrite` (1452), `fmOpenRead` (1452) or `fmOpenWrite` (1452), to open a file so other processes cannot read from it.

This constant only works on Windows, because other operating systems do not support this constants.

```
fmShareDenyWrite = $0020
```

`fmOpenShareDenyWrite` is used in the `FileOpen` (1523) call OR-ed together with one of `fmOpenReadWrite` (1452), `fmOpenRead` (1452) or `fmOpenWrite` (1452), to open a file so other processes cannot write to it, they can only read.

```
fmShareExclusive = $0010
```

`fmOpenShareExclusive` is used in the `FileOpen` (1523) call OR-ed together with one of `fmOpenReadWrite` (1452), `fmOpenRead` (1452) or `fmOpenWrite` (1452), to open a file exclusively.

```
fsFromBeginning = 0
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1526) call that a seek operation should be started at the start of the file.

```
fsFromCurrent = 1
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1526) call that a seek operation should be started at the current position in the file.

```
fsFromEnd = 2
```

`fsFromBeginning` is used to indicate in the `FileSeek` (1526) call that a seek operation should be started at the last position in the file.

```
GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'
```

NULL GUID constant

```
HexDisplayPrefix : string = '$'
```

`HexDisplayPrefix` is used by the formatting routines to indicate that the number which follows the prefix is in Hexadecimal notation.

```
HoursPerDay = 24
```

Number of hours in a day.

```
JulianEpoch = (-2415018.5)
```

Starting point of the Julian calendar

```
LeadBytes : Set of Char = []
```

LeadBytes contains the set of bytes that serve as lead byte in a MBCS string.

MaxCurrency : Currency = 922337203685477.5807

Maximum currency value

MaxDateTime : TDateTime = 2958465.999999999

Maximum TDateTime value.

MAX_PATH = MaxPathLen

MAX_PATH is the maximum number of characters that a filename (including path) can contain on the current operating system.

MinCurrency : Currency = -922337203685477.5808

Minimum Currency value

MinDateTime : TDateTime = -693593.0

Minimum TDateTime value.

MinsPerDay = HoursPerDay * MinsPerHour

Number of minutes per day.

MinsPerHour = 60

Number of minutes per hour.

MonthDays : Array[Boolean] of TDayTable = ((31, 28, 31, 30, 31, 30, 31, 31, 30, 31, 30, 31), (31, 29, 31, 30, 31, 30, 31, 31, 30, 31, 30, 31))

Array with number of days in the months for leap and non-leap years.

MSecsPerDay = SecsPerDay * MSecsPerSec

Number of milliseconds per day

MSecsPerSec = 1000

Number of milliseconds per second

NullStr : PString = @EmptyStr

Pointer to an empty string

PathDelim = DirectorySeparator

`PathDelim` refers to the system unit's `DirectorySeparator` constant, it is for Delphi compatibility only.

`PathSep = PathSeparator`

`PathSep` refers to the system unit's `PathSeparator` constant, it is for Delphi compatibility only.

`pfBCB4Produced = $08000000`

Not used in Free Pascal.

`pfDelphi4Produced = $0C000000`

Not used in Free Pascal.

`pfDesignOnly = $00000002`

Package is a design-time only package

`pfExeModule = $00000000`

Package is an executable

`pfIgnoreDupUnits = $00000008`

Ignore duplicate units in package

`pfLibraryModule = $80000000`

Package is a library

`pfModuleTypeMask = $C0000000`

Mask for module type flags

`pfNeverBuild = $00000001`

Never-build flag was specified when compiling package

`pfPackageModule = $40000000`

Package is a real package (not exe)

`pfProducerMask = $0C000000`

Mask for producer flags

`pfProducerUndefined = $04000000`

Not used in Free Pascal.

`pfRunOnly = $00000004`

Package is a run-time only package

`pfV3Produced = $00000000`

Not used in Free Pascal.

`RTL_SIGBUS = 4`

Bus error signal number (Unix only)

`RTL_SIGDEFAULT = -1`

Default signal handler (Unix only)

`RTL_SIGFPE = 1`

Floating Point Error signal number (Unix only)

`RTL_SIGILL = 3`

Illegal instruction signal number (Unix only)

`RTL_SIGINT = 0`

INTERRUPT signal number (Unix only)

`RTL_SIGLAST = RTL_SIGQUIT`

Last signal number (Unix only)

`RTL_SIGQUIT = 5`

QUIT signal number (Unix only)

`RTL_SIGSEGV = 2`

Segmentation fault signal number (Unix only)

`SecsPerDay = MinsPerDay * SecsPerMin`

Number of seconds per day

`SecsPerMin = 60`

Number of seconds per minute

`SwitchChars = [' - ']`

The characters in this set will be used by the FindCmdLineSwitch (1529) function to determine whether a command-line argument is a switch (an option) or a value. If the first character of an argument is in SwitchChars, it will be considered an option or switch.

```
SysConfigDir : string = ''
```

SysConfigDir is the default system configuration directory. It is set at application startup by the sysutils initialization routines.

This directory may be returned by the GetAppConfigDir (1548) call on some systems.

```
ufImplicitUnit = $10
```

Unit was implicitly imported into package (did not appear in package contains list)

```
ufMainUnit = $01
```

Unit is the main unit of the package

```
ufOrgWeakUnit = $08
```

Unit is the original weak packaged unit

```
ufPackageUnit = $02
```

Unit is a packaged unit (appeared in package contains list)

```
ufWeakPackageUnit = ufPackageUnit or ufWeakUnit
```

Weak (original or not) packaged unit

```
ufWeakUnit = $04
```

Unit is a weak packaged unit

```
UnixDateDelta = (UnixEpoch)
```

Number of days between 1.1.1900 and 1.1.1970

```
UnixEpoch = JulianEpoch + (2440587.5)
```

Starting point of the unix calendar (1/1/1970)

76.14.2 Types

```
EHeapException = EHeapMemoryError
```

EHeapMemoryError is raised when an error occurs in the heap management routines.

```
ExceptClass = Class of Exception
```

ExceptClass is a [Exception \(1623\)](#) class reference.

```
Int128Rec = packed record
case Integer of
0: (
    Hi : QWord;
    Lo
    : QWord;
);
1: (
    DWords : Array[0..3] of DWord;
);
2: (
    Words
    : Array[0..7] of Word;
);
3: (
    Bytes : Array[0..15] of Byte;
)
;
end
```

Int128Rec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
Int64Rec = packed record
case Integer of
0: (
    Hi : Cardinal;
    Lo
    : Cardinal;
);
1: (
    Words : Array[0..3] of Word;
);
2: (
    Bytes
    : Array[0..7] of Byte;
);
end
```

Int64Rec can be used to extract the parts of a Int64: the high and low cardinal, or a zero-based array of 4 words, or a zero based array of 8 bytes. Note that the meaning of the High and Low parts are different on various CPUs.

```
LongRec = packed record
case Integer of
0: (
    Hi : Word;
    Lo : Word
    ;
);
1: (
```

```

    Bytes : Array[0..3] of Byte;
  );
end

```

LongRec can be used to extract the parts of an long Integer: the high and low word, or the 4 separate bytes as a zero-based array of bytes. Note that the meaning of High and Low parts are different on various CPUs.

```

OWordRec = packed record
case Integer of
0: (
    Hi : QWord;
    Lo
      : QWord;
);
1: (
    DWords : Array[0..3] of DWord;
);
2: (
    Words
      : Array[0..7] of Word;
);
3: (
    Bytes : Array[0..15] of Byte;
)
;
end

```

OWordRec is a record defining a 128-bit integer. It is made up of 2 QWords or 4 DWords or 8 words or 16 bytes.

```
PByteArray = ^TByteArray
```

Generic pointer to TByteArray ([1460](#)). Use to access memory regions as a byte array.

```
PDayTable = ^TDayTable
```

Pointer to TDayTable type.

```
PString = ObjPas.PString
```

Pointer to a ansistring

```
PSysCharSet = ^TSysCharSet
```

Pointer to TSysCharSet ([1466](#)) type.

```
PWordarray = ^TWordArray
```

Generic pointer to TWordArray ([1468](#)). Use to access memory regions as a word array.

```
TArray = Array of T
```

TArray is a generic array. It can be used to define dynamic arrays in generic functions or classes.

This definition is provided for Delphi compatibility only, it is not needed in Free Pascal, where 2 array types are equal if they element types are equal.

TBeepHandler = procedure

TBeepHandler is the prototype used by the OnBeep (1471) handler. This in turn is called by the Beep (1490) call to actually implement the beep functionality. The call takes no arguments.

TByteArray = Array[0..32767] of Byte

TByteArray is a generic array definition, mostly for use as a base type of the PByteArray (1459) type.

TBytes = Array of Byte

TBytes defines a dynamic array of bytes. This can be used to typecast e.g. strings to manipulate them byte for byte.

TCharArray = Array of Char

TCharArray is a dynamic array of characters.

TCompareOption = system.TCompareOption

TCompareOption is an alias for System.TCompareOption (1236).

TCompareOptions = system.TCompareOptions

TCompareOptions is an alias for System.TCompareOptions (1237).

TCreateGUIDFunc = function(out GUID: TGuid) : Integer

TCreateGUIDFunc is the prototype for a GUID creation handler. On return, the GUID argument should contain a new (unique) GUID. The return value of the function should be zero for success, nonzero for failure.

TDayTable = Array[1..12] of Word

Array of day names.

TEndian = (Little, Big)

Table 76.10: Enumeration values for type TEndian

Value	Explanation
Big	Big endian (MSB first)
Little	Little endian (LSB first)

TEndian indicates whether the platform is little endian (LSB first), or big endian (MSB first).

```
TEventType = (etCustom,etInfo,etWarning,etError,etDebug)
```

Table 76.11: Enumeration values for type TEventType

Value	Explanation
etCustom	Custom log event, with application-specific meaning
etDebug	Debug message.
etError	Error condition message
etInfo	General information event message
etWarning	Warning message

TEventType is a type to be used by logging mechanisms (in particular, the TCustomApplication and TEventLog classes. It can be used to filter events, and write only certain types of event to the event log.

```
TEventTypes = Set of TEventType
```

TEventTypes is a set type of TEventType, defined for convenience. It is used in the custom application classes for logging purposes.

```
TExecuteFlags= Set of (ExecInheritsHandles)
```

Table 76.12: Enumeration values for type

Value	Explanation
ExecInheritsHandles	The new process inherits all (file) handles owned by the current process

TExecuteFlags is a set of flags to influence the behaviour of the ExecuteProcess (1512) call.

```
TFilename = String
```

TFileName is used in the TSearchRec (1466) definition.

```
TFilenameCaseMatch = (mkNone,mkExactMatch,mkSingleMatch,mkAmbiguous
)
```

Table 76.13: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1513) found the file.

```
TFilenameCaseMatch = (mkNone, mkExactMatch, mkSingleMatch, mkAmbiguous
)
```

Table 76.14: Enumeration values for type TFilenameCaseMatch

Value	Explanation
mkAmbiguous	More than one file will match the filename in a case-insensitive way
mkExactMatch	The filename can be used to refer to a file on the system (findFirst will find it).
mkNone	No file was found
mkSingleMatch	Exactly one match was found, but case didn't match.

TFilenameCaseMatch describes how ExpandFileNameCase (1513) found the file.

```
TFileRec = FileRec
```

Alias for FileRec (1442) for Delphi compatibility.

```
TFileSearchOption = (sfoImplicitCurrentDir, sfoStripQuotes)
```

Table 76.15: Enumeration values for type TFileSearchOption

Value	Explanation
sfoImplicitCurrentDir	Always search the current directory first, even if it is not specified.
sfoStripQuotes	Strip quotes from the components in the search path.

TFileSearchOption enumerates the options that can be used in the FileSearch call to control the behaviour of the search mechanism

```
TFileSearchOptions = Set of TFileSearchOption
```

TFileSearchOptions is a set of TFileSearchOption (1462) values, used in the FileSearch (1525) call when searching for files.

```
TFloatFormat = (ffGeneral, ffExponent, ffFixed, ffNumber, ffCurrency)
```

Table 76.16: Enumeration values for type TFloatFormat

Value	Explanation
ffCurrency	Monetary format.
ffExponent	Scientific format.
ffFixed	Fixed point format.
ffGeneral	General number format.
ffNumber	Fixed point format with thousand separator

TFloatFormat is used to determine how a float value should be formatted in the FloatToText (1535) function.

```

TFloatRec = record
  Exponent : Integer;
  Negative : Boolean;
  Digits
    : Array[0..18] of Char;
end

```

TFloatRec is used to describe a floating point value by the FloatToDecimal ([1531](#)) function.

```

TFloatValue = (fvExtended, fvCurrency, fvSingle, fvReal, fvDouble, fvComp
)

```

Table 76.17: Enumeration values for type TFloatValue

Value	Explanation
fvComp	Comp value
fvCurrency	Currency value
fvDouble	Double value
fvExtended	Extended value
fvReal	Real value
fvSingle	Single value

TFloatValue determines which kind of value should be returned in the (untyped) buffer used by the TextToFloat ([1596](#)) function.

```

TFormatDateTimeOption = (fdoInterval)

```

Table 76.18: Enumeration values for type TFormatDateTimeOption

Value	Explanation
fdoInterval	Format the time as an interval, 24+hours are presented as such

TFormatDateTimeOption enumerates possible options to the FormatDateTime ([1545](#)) routine.

```

TFormatDateTimeOptions = Set of TFormatDateTimeOption

```

TFormatDateTimeOptions is a set of TFormatDateTimeOptions ([1463](#)), and is used in the last argument of FormatDateTime ([1545](#))

```

TFormatSettings = record
  CurrencyFormat : Byte;
  NegCurrFormat
    : Byte;
  ThousandSeparator : Char;
  DecimalSeparator : Char;
  CurrencyDecimals : Byte;
  DateSeparator : Char;
  TimeSeparator

```



```

: Char;
ListSeparator : Char;
CurrencyString : string;
ShortDateFormat
: string;
LongDateFormat : string;
TimeAMString : string;
TimePMString
: string;
ShortTimeFormat : string;
LongTimeFormat : string;
ShortMonthNames : TMonthNameArray;
LongMonthNames : TMonthNameArray
;
ShortDayNames : TWeekNameArray;
LongDayNames : TWeekNameArray
;
TwoDigitYearCenturyWindow : Word;
end

```

TFormatSettings is a record that contains a copy of all variables which determine formatting in the various string formatting routines. It is used to pass local copies of these values to the various formatting routines in a thread-safe way.

```
TGetAppNameEvent = function : string
```

This callback type is used by the OnGetApplicationName ([1471](#)) to return an alternative application name.

```
TGetTempDirEvent = function(Global: Boolean) : string
```

Function prototype for OnGetTempDir ([1472](#)) handler.

```

TGetTempFileEvent = function(const Dir: string; const Prefix: string
)
: string

```

Function prototype for OnGetTempFile ([1472](#)) handler.

```
TGetVendorNameEvent = function : string
```

TGetVendorNameEvent is the function prototype for the OnGetVendorName ([1472](#)) callback, used by the VendorName ([1610](#)) function.

```
THandle = System.THandle
```

THandle refers to the definition of THandle in the system unit, and is provided for backward compatibility only.

```
TIntegerSet = Set of
```

TIntegerSet is a generic integer subrange set definition whose size fits in a single integer.

```
TMbcsByteType = (mbSingleByte, mbLeadByte, mbTrailByte)
```

Table 76.19: Enumeration values for type TMbcsByteType

Value	Explanation
mbLeadByte	Uses lead-byte
mbSingleByte	Single bytes
mbTrailByte	Uses trailing byte

Type of multi-byte character set.

```
TMonthNameArray = Array[1..12] of string
```

TMonthNameArray is used in the month long and short name arrays.

```
TProcedure = procedure
```

TProcedure is a general definition of a procedural callback.

```
TRawbyteSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr
    : LongInt;
  Name : RawByteString;
  ExcludeAttr : LongInt;
  FindHandle
    : Pointer;
  Mode : TMode;
end
```

TRawbyteSearchRec is a search handle description record using single-byte strings. It is initialized by a call to FindFirst (1529) and can be used to do subsequent calls to FindNext (1530). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1528).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

Remark: Note that for files with unicode filenames this is a converted value from the unicode filename. Depending on the codepage, this may or may not be a correct rendering of the correct unicode filename.

```
TReplaceFlags= Set of (rfReplaceAll, rfIgnoreCase)
```

Table 76.20: Enumeration values for type

Value	Explanation
rfIgnoreCase	Search case insensitive.
rfReplaceAll	Replace all occurrences of the search string with the replacement string.

TReplaceFlags determines the behaviour of the StringReplace (1576) function.

TSearchRec = TRawbyteSearchRec

TSearchRec is a search handle description record. It is initialized by a call to FindFirst (1529) and can be used to do subsequent calls to FindNext (1530). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1528).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

TSignalState = (ssNotHooked, ssHooked, ssOverridden)

Table 76.21: Enumeration values for type TSignalState

Value	Explanation
ssHooked	A signal handler is set by the RTL code for the signal.
ssNotHooked	No signal handler is set for the signal.
ssOverridden	A signal handler was set for the signal by third-party code.

TSignalState indicates the state of a signal handler in a unix system for a particular signal.

TStringArray = Array of string

TStringArray is a dynamic array of strings.

TStringSplitOptions = (None, ExcludeEmpty)

Table 76.22: Enumeration values for type TStringSplitOptions

Value	Explanation
ExcludeEmpty	Do not include empty strings in the result.
None	No options specified. The default

TStringSplitOptions describes the possible options for TStringHelper.Split (1708).

TSysCharSet = Set of AnsiChar

Generic set of characters type.

```
TSysLocale = record
  DefaultLCID : Integer;
  PriLangID : Integer
;
  SubLangID : Integer;
case Byte of
1: (
  FarEast : Boolean;
  MiddleEast : Boolean;
);
```

```

2: (
  MBCS : Boolean;
  RightToLeft : Boolean
;
);
end

```

TSysLocale describes the current locale. If Fareast or MBCS is True, then the current locale uses a Multi-Byte Character Set. If MiddleEast or RightToLeft is True then words and sentences are read from right to left.

```

TSystemTime = record
  Year : Word;
  Month : Word;
  Day : Word;
  DayOfWeek : Word;
  Hour : Word;
  Minute : Word;
  Second : Word
;
  MilliSecond : Word;
end

```

The System time structure contains the date/time in a human-understandable format.

```

TTerminateProc = function : Boolean

```

TTerminateProc is the procedural type which should be used when adding exit procedures.

```

TTextRec = TextRec

```

Alias for TextRec ([1442](#)) for Delphi compatibility.

```

TTimeStamp = record
  Time : LongInt;
  Date : LongInt;
end

```

TTimeStamp contains a timestamp, with the date and time parts specified as separate TDateTime values.

```

TUnicodeCharArray = Array of UnicodeChar

```

TUnicodeCharArray is a definition of an array of UnicodeChar elements.

```

TUnicodeSearchRec = record
  Time : LongInt;
  Size : Int64;
  Attr
  : LongInt;
  Name : UnicodeString;

```

```

ExcludeAttr : LongInt;
FindHandle
: Pointer;
Mode : TMode;
end

```

TRawbyteSearchRec is a search handle description record using multi-byte strings. It is initialized by a call to FindFirst (1529) and can be used to do subsequent calls to FindNext (1530). It contains the result of these function calls. It must be used to close the search sequence with a call to FindClose (1528).

Remark: Not all fields of this record should be used. Some of the fields are for internal use only. (PathOnly for example, is only provided for Kylix compatibility)

```
TUseBoolStrs = (False, True)
```

Table 76.23: Enumeration values for type TUseBoolStrs

Value	Explanation
False	Numerical values should be used (0 and 1)
True	String representations should be used.

TUseBoolStrs is an enumerated type which indicates whether bool strs must be used when converting boolean to strings.

```
TWeekNameArray = Array[1..7] of string
```

TWeekNameArray is used in the day long and short name arrays.

```
TWordArray = Array[0..16383] of Word
```

TWordArray is a generic array definition, mostly for use as a base type of the PWordArray (1459) type.

```

WordRec = packed record
  Hi : Byte;
  Lo : Byte;
end

```

LongRec can be used to extract the parts of a word: the high and low byte. Note that the meaning of the High and Low parts are different on various CPUs.

76.14.3 Variables

```
CurrencyDecimals : Bytedeprecated
```

CurrencyDecimals is the number of decimals to be used when formatting a currency. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyFormat (1469) instead.

CurrencyFormat : Bytedeprecated

CurrencyFormat is the default format string for positive currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyFormat (1469) instead.

CurrencyString : stringdeprecated

CurrencyString is the currency symbol for the current locale. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.CurrencyString (1469) instead.

DateSeparator : Chardeprecated

DateSeparator is the character used by various date/time conversion routines as the character that separates the day from the month and the month from the year in a date notation. It is used by the date formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.DateSeparator (1469) instead.

DecimalSeparator : Chardeprecated

DecimalSeparator is used to display the decimal symbol in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the SysUtils unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use DefaultFormatSettings.DecimalSeparator (1469) instead.

```
DefaultFormatSettings : TFormatSettings = (CurrencyFormat: 1; NegCurrFormat
    : 5; ThousandSeparator: ','; DecimalSeparator: '.'; CurrencyDecimals
    : 2; DateSeparator: '-'; TimeSeparator: ':'; ListSeparator: ','; CurrencyString
    : '$'; ShortDateFormat: 'd/m/y'; LongDateFormat: 'dd" "mmmm" "yyyy'
    ; TimeAMString: 'AM'; TimePMString: 'PM'; ShortTimeFormat: 'hh:nn'
    ; LongTimeFormat: 'hh:nn:ss'; ShortMonthNames: ('Jan', 'Feb', 'Mar'
    , 'Apr', 'May', 'Jun', 'Jul', 'Aug', 'Sep', 'Oct', 'Nov', 'Dec');
    LongMonthNames: ('January', 'February', 'March', 'April', 'May',
    'June', 'July', 'August', 'September', 'October', 'November', 'December'
    ); ShortDayNames: ('Sun', 'Mon', 'Tue', 'Wed', 'Thu', 'Fri', 'Sat'
    ); LongDayNames: ('Sunday', 'Monday', 'Tuesday', 'Wednesday', 'Thursday'
    , 'Friday', 'Saturday'); TwoDigitYearCenturyWindow: 50)
```

DefaultFormatSettings contains the default settings for all type of formatting constants. If no thread-specific values are specified when a formatting function is called, this record is used as a default.

All other formatting constants refer to the fields of this variable using absolute addressing.

FalseBoolStrs : Array of string

`FalseBoolStrs` contains the strings that will result in a `False` return value by `StrToBool` (1585).

`FormatSettings` : `TFormatSettings`

`FormatSettings` is provided for Delphi compatibility, and refers to the `DefaultFormatSettings` (1469) variable.

`ListSeparator` : `Char` deprecated

`ListSeparator` is the character used in lists of values. It is locale dependent.

`LongDateFormat` : `string` deprecated

`LongDateFormat` contains a template to format a date in a long format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongDateFormat` (1469) instead.

`LongDayNames` : `TWeekNameArray` deprecated

`LongDayNames` is an array with the full names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.LongDayNames` (1469) instead.

`LongMonthNames` : `TMonthNameArray` deprecated

`LongMonthNames` is an array with the full names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongMonthNames` (1469) instead.

`LongTimeFormat` : `string` deprecated

`LongTimeFormat` contains a template to format a time in full notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.LongTimeFormat` (1469) instead.

`NegCurrFormat` : `Byte` deprecated

`CurrencyFormat` is the default format string for negative currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default:

0 Left parenthesis, currency symbol, amount, right parenthesis. Ex: (\$1.2)

1 Negative sign, currency symbol, amount. Ex: -\$1.2

- 2 Monetary symbol, negative sign, amount. Ex: \$-1.2
- 3 Monetary symbol, amount, negative sign. Ex: \$1.2-
- 4 Left parenthesis, amount, currency symbol, right parenthesis. Ex: (1.2\$)
- 5 Negative sign, amount, currency symbol. Ex: -1.2\$
- 5 6Amount, negative sign, currency symbol. Ex: 1.2-\$
- 5 7Amount, currency symbol, negative sign. Ex: 1.2\$-
- 5 8Negative sign, amount, space, currency symbol (as #5, adding a space before the currency symbol). Ex: -1.2 \$
- 9 Negative sign, currency symbol, space, amount (as #1, adding a space after the currency symbol). Ex: -\$ 1.2
- 10 Amount, space, currency symbol, negative sign (as #7, adding a space before the currency symbol). Ex: 1.2 \$-
- 11 Monetary symbol, space, amount, negative sign (as #3, adding a space after the currency symbol). Ex: \$ 1.2-
- 12 Monetary symbol, space, negative sign, amount (as #2, adding a space after the currency symbol). Ex: \$ -1.2
- 13 Amount, negative sign, space, currency symbol (as #6, adding a space before the currency symbol). Ex: 1.2- \$
- 14 Left parenthesis, currency symbol, space, amount, right parenthesis (as #0, adding a space after the currency symbol). Ex: (\$ 1.2)
- 15 Left parenthesis, amount, space, currency symbol, right parenthesis (as ##4, adding a space before the currency symbol). Ex: (1.2 \$)

`OnBeep : TBeepHandler = Nil`

`OnBeep` is called whenever `Beep` is called. `Beep` contains no implementation to actually produce a beep, since there is no way to implement beep in a meaningful way for all possible implementations.

`OnCreateGUID : TCreateGUIDFunc = Nil`

`OnCreateGUID` can be set to point to a custom routine that creates GUID values. If set, the `CreateGUID` (1497) function will use it to obtain a GUID value. If it is not set, a default implementation using random values will be used to create the unique value. The function should return a valid GUID in the GUID parameter, and should return zero in case of success.

`OnGetApplicationName : TGetAppNameEvent`

By default, the configuration file routines `GetAppConfigDir` (1548) and `GetAppConfigFile` (1548) use a default application name to construct a directory or filename. This callback can be used to provide an alternative application name.

Since the result of this callback will be used to construct a filename, care should be taken that the returned name does not contain directory separator characters or characters that cannot appear in a filename.

`OnGetTempDir : TGetTempDirEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempDir` (1553) function. Note that the returned name should have a trailing directory delimiter character.

`OnGetTempFile : TGetTempFileEvent`

`OnGetTempDir` can be used to provide custom behaviour for the `GetTempFileName` (1553) function. Note that the values for `Prefix` and `Dir` should be observed.

`OnGetVendorName : TGetVendorNameEvent`

`OnGetVendorName` must be set in order for `VendorName` (1610) to return a value. It will then be used in `GetAppConfigDir` (1548) and `GetAppConfigFile` (1548) to determine the configuration directory. Set it to a callback that returns the actual vendor name for the application.

`OnShowException : procedure(Msg: ShortString)`

`OnShowException` is the callback that `ShowException` (1569) uses to display a message in a GUI application. For GUI applications, this variable should always be set. Note that no memory may be available when this callback is called, so the callback should already have all resources it needs, when the callback is set.

`ShortDateFormat : stringdeprecated`

`ShortDateFormat` contains a template to format a date in a short format. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDateFormat` (1469) instead.

`ShortDayNames : TWeekNameArraydeprecated`

`ShortDayNames` is an array with the abbreviated names of days. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

The array is indexed by values as returned by the `DayOfWeek` function.

This constant is deprecated. You should use `DefaultFormatSettings.ShortDayNames` (1469) instead.

`ShortMonthNames : TMonthNameArraydeprecated`

`ShortMonthNames` is an array with the abbreviated names of months. It is used by the date formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortMonthNames` (1469) instead.

`ShortTimeFormat : stringdeprecated`

`ShortTimeFormat` contains a template to format a time in a short notation. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ShortTimeFormat` (1469) instead.

`SysLocale` : `TSysLocale`

`SysLocale` is initialized by the initialization code of the `SysUtils` unit. For an explanation of the fields, see `TSysLocale` ([1467](#))

`ThousandSeparator` : `Char`~~deprecated~~

`ThousandSeparator` is used to separate groups of thousands in floating point numbers or currencies. It is used by the float formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.ThousandSeparator` ([1469](#)) instead.

`TimeAMString` : ~~string~~deprecated

`TimeAMString` is used to display the AM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimeAMString` ([1469](#)) instead.

`TimePMString` : ~~string~~deprecated

`TimePMString` is used to display the PM symbol in the time formatting routines. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

This constant is deprecated. You should use `DefaultFormatSettings.TimePMString` ([1469](#)) instead.

`TimeSeparator` : `Char`~~deprecated~~

`TimeSeparator` is used by the time formatting routines to separate the hours from the minutes and the minutes from the seconds. It is used by the time formatting routines. The initialization routines of the `SysUtils` unit initialize this string with a value conforming to the regional preferences of the user or system regional default.

`TrueBoolStrs` : Array of `string`

`TrueBoolStrs` contains the strings that will result in a `True` return value by `StrToBool` ([1585](#)).

`TwoDigitYearCenturyWindow` : `Word`

Window to determine what century 2 digit years are in.

76.15 Procedures and functions

76.15.1 `AbandonSignalHandler`

Synopsis: Abandon the signal handler

Declaration: `procedure AbandonSignalHandler(RtlSigNum: Integer)`

Visibility: default

Description: `AbandonSignalHandler` tells the system routines that they should not re-install the signal handler for signal `RtlSigNum` under any circumstances. Normally, signal handlers are re-set when they are called. If `AbandonSignalHandler` has been called for a signal that is handled by the system code, the signal will not be re-set again.

76.15.2 Abort

Synopsis: Abort program execution.

Declaration: `procedure Abort`

Visibility: default

Description: `Abort` raises an `EAbort` (1614) exception.

See also: `EAbort` (1614)

76.15.3 AddDisk

Synopsis: Add a disk to the list of known disks (Unix only)

Declaration: `function AddDisk(const path: string) : Byte`

Visibility: default

Description: On Unix-like platforms both the `DiskFree` (1506) and `DiskSize` (1506) functions need a file on the specified drive, since is required for the `statfs` system call.

These filenames are set in `drivestr[0..26]`, and the first 4 have been preset to :

Disk 0 ' . ' default drive - hence current directory is used.

Disk 1 ' /fd0/ . ' floppy drive 1.

Disk 2 ' /fd1/ . ' floppy drive 2.

Disk 3 ' / C: equivalent of DOS is the root partition.

Drives 4..26 can be set by your own applications with the `AddDisk` call.

The `AddDisk` call adds `Path` to the names of drive files, and returns the number of the disk that corresponds to this drive. If you add more than 21 drives, the count is wrapped to 4.

Errors: None.

See also: `DiskFree` (1506), `DiskSize` (1506)

76.15.4 AddTerminateProc

Synopsis: Add a procedure to the exit chain.

Declaration: `procedure AddTerminateProc(TermProc: TTerminateProc)`

Visibility: default

Description: `AddTerminateProc` adds `TermProc` to the list of exit procedures. When the program exits, the list of exit procedures is run over, and all procedures are called one by one, in the reverse order that they were added to the exit chain.

Errors: If no memory is available on the heap, an exception may be raised.

See also: `TTerminateProc` (1467), `CallTerminateProcs` (1492)

76.15.5 AdjustLineBreaks

Synopsis: Convert possible line-endings to the currently valid line ending.

Declaration: `function AdjustLineBreaks(const S: string) : string`
`function AdjustLineBreaks(const S: string; Style: TTextLineBreakStyle)`
`: string`

Visibility: default

Description: `AdjustLineBreaks` will change all occurrences of `#13` and `#10` characters with the correct line-ending characters for the current platform. This is `#13#10` on Windows and Dos. On Unix-like platforms, this is `#10` and for Mac OS X it is `#13`.

Errors: None.

See also: `AnsiCompareStr` ([1476](#)), `AnsiCompareText` ([1477](#))

Listing: `./sysutex/ex48.pp`

Program `Example48`;

{ This program demonstrates the AdjustLineBreaks function }

Uses `sysutils`;

Const

`S = 'This is a string'#13'with embedded'#10'linefeed and'+`
`#13'CR characters';`

Begin

`WriteLn (AdjustLineBreaks(S));`

End.

76.15.6 AnsiCompareFileName

Synopsis: Compare 2 filenames.

Declaration: `function AnsiCompareFileName(const S1: string; const S2: string)`
`: SizeInt`

Visibility: default

Description: `AnsiCompareFileName` compares 2 filenames `S1` and `S2`, and returns

`< 0` if `S1 < S2`.

`= 0` if `S1 = S2`.

`> 0` if `S1 > S2`.

The function actually checks `FileNameCaseSensitive` and returns the result of `AnsiCompareStr` ([1476](#)) or `AnsiCompareText` ([1477](#)) depending on whether `FileNameCaseSensitive` is `True` or `False`

Errors: None.

See also: `AnsiCompareStr` ([1476](#)), `AnsiCompareText` ([1477](#)), `AnsiLowerCaseFileName` ([1480](#))

76.15.7 AnsiCompareStr

Synopsis: Compare 2 ansistrings, case sensitive, ignoring accents characters.

Declaration: `function AnsiCompareStr(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareStr` compares two strings and returns the following result:

< 0 if `S1 < S2`.

0 if `S1 = S2`.

> 0 if `S1 > S2`.

The comparison takes into account Ansi characters, i.e. it takes care of strange accented characters.

Contrary to `AnsiCompareText` (1477), the comparison is case sensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1475), `AnsiCompareText` (1477)

Listing: `./sysutex/ex49.pp`

Program Example49;

```
{ This program demonstrates the AnsiCompareStr function }
{$H+}
```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

 R:=**AnsiCompareStr**(S1,S2);

Write (' ',S1, ' is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

Writeln (' ',S2, ' ');

end;

Begin

 TestIt('One string ', 'One smaller string ');

 TestIt('One string ', 'one string ');

 TestIt('One string ', 'One string ');

 TestIt('One string ', 'One tall string ');

End.

76.15.8 AnsiCompareText

Synopsis: Compare 2 ansistrings, case insensitive, ignoring accents characters.

Declaration: `function AnsiCompareText(const S1: string; const S2: string) : Integer`

Visibility: default

Description: `AnsiCompareText` compares two strings and returns the following result:

`<0` if `S1<S2`.

`0` if `S1=S2`.

`>0` if `S1>S2`.

the comparison takes into account Ansi characters, i.e. it takes care of strange accented characters.

Contrary to `AnsiCompareStr` (1476), the comparison is case insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AdjustLineBreaks` (1475), `AnsiCompareText` (1477)

Listing: `./sysutex/ex50.pp`

Program Example49;

```
{ This program demonstrates the AnsiCompareText function }
{$H+}
```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

begin

 R:=**AnsiCompareText**(S1,S2);

Write (' ',S1, ' is ');

If R<0 **then**

write ('less than ')

else If R=0 **then**

Write ('equal to ')

else

Write ('larger than ');

Writeln (' ',S2, ' ');

end;

Begin

 TestIt('One string ', 'One smaller string ');

 TestIt('One string ', 'one string ');

 TestIt('One string ', 'One string ');

 TestIt('One string ', 'One tall string ');

End.

76.15.9 AnsiDequotedStr

Synopsis: Extract string without quotes

Declaration: `function AnsiDequotedStr(const S: string; AQuote: Char) : string`

Visibility: default

Description: `AnsiDequotedStr` is, similar to `AnsiExtractQuotedStr` (1478), a method to extract a string that was quoted using `AnsiQuotedStr` (1480). The string `S` must start and end with the quote character `AQuote` (they will be removed from the result) and all double occurrences of the quote character `AQuote` will be reduced to a single quote character.

Errors: If the string does not start and end with the quote character or has length less than 2, the original string is returned.

See also: `AnsiExtractQuotedStr` (1478), `AnsiQuotedStr` (1480)

76.15.10 AnsiExtractQuotedStr

Synopsis: Removes the first quoted string from a string.

Declaration: `function AnsiExtractQuotedStr(var Src: PChar; Quote: Char) : string`

Visibility: default

Description: `AnsiExtractQuotedStr` returns the first quoted string in `Src`, and deletes the result from `Src`. The resulting string has with `Quote` characters removed from the beginning and end of the string (if they are present), and double `Quote` characters replaced by a single `Quote` characters. As such, it reverses the action of `AnsiQuotedStr` (1480).

Errors: None.

See also: `AnsiQuotedStr` (1480)

Listing: `./sysutex/ex51.pp`

```

Program Example51;
{ This program demonstrates the AnsiQuotedStr function }
Uses sysutils;

Var
  S : AnsiString;
  P : PChar;

Begin
  S:= 'He said "Hello" and walked on';
  P:= Pchar(S);
  S:= AnsiQuotedStr(P, '"');
  WriteLn (S);
  P:= Pchar(S);
  WriteLn (AnsiExtractQuotedStr(P, '"'));
End.

```

76.15.11 AnsiLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiLastChar(const S: string) : PChar`

Visibility: default

Description: This function returns a pointer to the last character of S.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

Errors: None.

See also: `AnsiStrLastChar` ([1483](#))

Listing: `./sysutex/ex52.pp`

Program Example52;

{ This program demonstrates the AnsiLastChar function }

Uses sysutils;

Var S : AnsiString;
L : Longint;

Begin

S := 'This is an ansistring.';

WriteLn ('Last character of S is : ', AnsiLastChar(S));

L := Longint(AnsiLastChar(S)) - Longint(@S[1]) + 1;

WriteLn ('Length of S is : ', L);

End.

76.15.12 AnsiLowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function AnsiLowerCase(const s: string) : string`

Visibility: default

Description: `AnsiLowerCase` converts the string S to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` ([1487](#)), `AnsiStrLower` ([1485](#)), `AnsiStrUpper` ([1487](#))

Listing: `./sysutex/ex53.pp`

Program Example53;

{ This program demonstrates the AnsiLowerCase function }

Uses sysutils;

Procedure Testit (S : **String**);

```
begin
  WriteLn (S, ' -> ', AnsiLowerCase(S))
end;
```

```
Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.
```

76.15.13 AnsiLowerCaseFileName

Synopsis: Convert filename to lowercase.

Declaration: `function AnsiLowerCaseFileName(const s: string) : string`

Visibility: default

Description: `AnsiLowerCaseFileName` simply returns the result of

```
AnsiLowerCase(S);
```

See also: `AnsiLowerCase` ([1479](#)), `AnsiCompareFileName` ([1475](#)), `AnsiUpperCaseFileName` ([1488](#))

76.15.14 AnsiPos

Synopsis: Return Position of one anstring in another.

Declaration: `function AnsiPos(const substr: string; const s: string) : SizeInt`

Visibility: default

Description: `AnsiPos` does the same as the standard `Pos` function.

See also: `AnsiStrPos` ([1486](#)), `AnsiStrScan` ([1486](#)), `AnsiStrRScan` ([1486](#))

76.15.15 AnsiQuotedStr

Synopsis: Return a quoted version of a string.

Declaration: `function AnsiQuotedStr(const S: string; Quote: Char) : string`

Visibility: default

Description: `AnsiQuotedString` quotes the string `S` and returns the result. This means that it puts the `Quote` character at both the beginning and end of the string and replaces any occurrence of `Quote` in `S` with 2 `Quote` characters. The action of `AnsiQuotedString` can be reversed by `AnsiExtractQuotedStr` ([1478](#)).

For an example, see `AnsiExtractQuotedStr` ([1478](#))

Errors: None.

See also: `AnsiExtractQuotedStr` ([1478](#))

76.15.16 AnsiSameStr

Synopsis: Checks whether 2 strings are the same (case sensitive)

Declaration: `function AnsiSameStr(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareStr` (1476) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareStr` (1476), `SameText` (1568), `AnsiSameText` (1481)

76.15.17 AnsiSameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function AnsiSameText(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `AnsiCompareText` (1477) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

See also: `AnsiCompareText` (1477), `SameText` (1568), `AnsiSameStr` (1481)

76.15.18 AnsiStrComp

Synopsis: Compare two null-terminated strings. Case sensitive.

Declaration: `function AnsiStrComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrComp` compares 2 `PChar` strings, and returns the following result:

<0 if `S1 < S2`.

0 if `S1 = S2`.

>0 if `S1 > S2`.

The comparison of the two strings is case-sensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` (1477), `AnsiCompareStr` (1476)

Listing: `./sysutex/ex54.pp`

```

Program Example54;

{ This program demonstrates the AnsiStrComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin
  R:=AnsiStrComp(S1,S2);
  Write ( ' ',S1, ' is ' );
  If R<0 then
    write ( 'less than ' )
  else If R=0 then
    Write ( 'equal to ' )
  else
    Write ( 'larger than ' );
  Writeln ( ' ',S2, ' ' );
end;

Begin
  Testit('One string','One smaller string');
  Testit('One string','one string');
  Testit('One string','One string');
  Testit('One string','One tall string');
End.

```

76.15.19 AnsiStrIComp

Synopsis: Compare two null-terminated strings. Case insensitive.

Declaration: `function AnsiStrIComp(S1: PChar; S2: PChar) : Integer`

Visibility: default

Description: `AnsiStrIComp` compares 2 `PChar` strings, and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

The comparison of the two strings is case-insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1477](#)), `AnsiCompareStr` ([1476](#))

Listing: `./sysutex/ex55.pp`

```

Program Example55;

{ This program demonstrates the AnsiStrIComp function }

```

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar);

Var R : Longint;

begin

R:=AnsiStrlComp(S1,S2);

Write ('',S1,' is ');

If R<0 **then**

write ('less than ');

else If R=0 **then**

Write ('equal to ');

else

Write ('larger than ');

WriteIn ('',S2,' ');

end;

Begin

Testit('One string','One smaller string');

Testit('One string','one string');

Testit('One string','One string');

Testit('One string','One tall string');

End.

76.15.20 AnsiStrLastChar

Synopsis: Return a pointer to the last character of a string.

Declaration: `function AnsiStrLastChar(Str: PChar) : PChar`

Visibility: default

Description: Return a pointer to the last character of the null-terminated string.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets. If none is installed, this function is the same as `@S[Length[S]]`.

Errors: None.

See also: [AnsiCompareText \(1477\)](#), [AnsiCompareStr \(1476\)](#)

Listing: ./sysutex/ex56.pp

Program Example56;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : Pchar; L : longint);

Var R : Longint;

begin

R:=AnsiStrLComp(S1,S2,L);

Write ('First ',L,' characters of ',S1,' are ');

```

If R<0 then
  write ( 'less than ' )
else If R=0 then
  Write ( 'equal to ' )
else
  Write ( 'larger than ' );
  Writeln ( 'those of " ',S2, ' "' );
end;

Begin
  Testit( 'One string ', 'One smaller string ',255);
  Testit( 'One string ', 'One String ',4);
  Testit( 'One string ', '1 string ',0);
  Testit( 'One string ', 'One string. ',9);
End.

```

76.15.21 AnsiStrLComp

Synopsis: Compare a limited number of characters of 2 strings

Declaration: `function AnsiStrLComp(S1: PChar; S2: PChar; MaxLen: Cardinal) : Integer`

Visibility: default

Description: `AnsiStrLComp` functions the same as `AnsiStrComp` ([1481](#)), but compares at most `MaxLen` characters. If the first `MaxLen` characters in both strings are the same, then zero is returned.

Note that this function processes embedded null characters, treating them as a normal character.

Errors: None.

See also: `AnsiStrComp` ([1481](#)), `AnsiStrIComp` ([1482](#)), `AnsiStrLComp` ([1484](#))

76.15.22 AnsiStrLIComp

Synopsis: Compares a given number of characters of a string, case insensitive.

Declaration: `function AnsiStrLIComp(S1: PChar; S2: PChar; MaxLen: Cardinal) : Integer`

Visibility: default

Description: `AnsiStrLIComp` compares the first `Maxlen` characters of 2 `PChar` strings, `S1` and `S2`, and returns the following result:

<0 if `S1<S2`.

0 if `S1=S2`.

>0 if `S1>S2`.

The comparison of the two strings is case-insensitive.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiCompareText` ([1477](#)), `AnsiCompareStr` ([1476](#))

Listing: `./sysutex/ex57.pp`

```

Program Example57;

{ This program demonstrates the AnsiStrLComp function }

Uses sysutils;

Procedure TestIt (S1,S2 : PChar; L : longint);

Var R : Longint;

begin
  R:=AnsiStrLComp(S1,S2,L);
  Write ( 'First ',L,' characters of "',S1,'" are ');
  If R<0 then
    write ( 'less than ')
  else If R=0 then
    Write ( 'equal to ')
  else
    Write ( 'larger than ');
  Writeln ( 'those of "',S2,'" ');
end;

Begin
  TestIt('One string','One smaller string',255);
  TestIt('ONE STRING','one String',4);
  TestIt('One string','1 STRING',0);
  TestIt('One STRING','one string.',9);
End.

```

76.15.23 AnsiStrLower

Synopsis: Convert a null-terminated string to all-lowercase characters.

Declaration: `function AnsiStrLower(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrLower` converts the `PChar Str` to lowercase characters and returns the resulting `pchar`. Note that `Str` itself is modified, not a copy, as in the case of `AnsiLowerCase` (1479). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` (1487), `AnsiLowerCase` (1479)

Listing: `./sysutex/ex59.pp`

```

Program Example59;

{ This program demonstrates the AnsiStrLower function }

Uses sysutils;

```

```
Procedure Testit (S : PChar);  
  
begin  
  WriteLn (S, ' → ', AnsiStrLower(S))  
end;  
  
Begin  
  Testit('AN UPPERCASE STRING');  
  Testit('Some mixed STring');  
  Testit('a lowercase string');  
End.
```

76.15.24 AnsiStrPos

Synopsis: Return position of one null-terminated substring in another

Declaration: `function AnsiStrPos(str: PChar; substr: PChar) : PChar`

Visibility: default

Description: `AnsiStrPos` returns a pointer to the first occurrence of `SubStr` in `Str`. If `SubStr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if either `Str` or `SubStr` point to invalid memory.

See also: `AnsiPos` ([1480](#)), `AnsiStrScan` ([1486](#)), `AnsiStrRScan` ([1486](#))

76.15.25 AnsiStrRScan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function AnsiStrRScan(Str: PChar; Chr: Char) : PChar`

Visibility: default

Description: `AnsiStrRScan` returns a pointer to the *last* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1480](#)), `AnsiStrScan` ([1486](#)), `AnsiStrPos` ([1486](#))

76.15.26 AnsiStrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function AnsiStrScan(Str: PChar; Chr: Char) : PChar`

Visibility: default

Description: `AnsiStrScan` returns a pointer to the *first* occurrence of the character `Chr` in `Str`. If `Chr` does not occur in `Str` then `Nil` is returned.

Errors: An access violation may occur if `Str` points to invalid memory.

See also: `AnsiPos` ([1480](#)), `AnsiStrScan` ([1486](#)), `AnsiStrPos` ([1486](#))

76.15.27 AnsiStrUpper

Synopsis: Convert a null-terminated string to all-uppercase characters.

Declaration: `function AnsiStrUpper(Str: PChar) : PChar`

Visibility: default

Description: `AnsiStrUpper` converts the `PCharStr` to uppercase characters and returns the resulting string. Note that `Str` itself is modified, not a copy, as in the case of `AnsiUpperCase` (1487). It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiUpperCase` (1487), `AnsiStrLower` (1485), `AnsiLowerCase` (1479)

Listing: `./sysutex/ex60.pp`

Program Example60;

{ This program demonstrates the AnsiStrUpper function }

Uses sysutils;

Procedure Testit (S : Pchar);

begin

 WriteLn (S, ' → ', AnsiStrUpper(S))

end;

Begin

 Testit('AN UPPERCASE STRING');

 Testit('Some mixed STring');

 Testit('a lowercase string');

End.

76.15.28 AnsiUpperCase

Synopsis: Return an uppercase version of a string, taking into account special characters.

Declaration: `function AnsiUpperCase(const s: string) : string`

Visibility: default

Description: `AnsiUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: A widestring manager must be installed in order for this function to work correctly with various character sets.

Errors: None.

See also: `AnsiStrUpper` (1487), `AnsiStrLower` (1485), `AnsiLowerCase` (1479)

Listing: `./sysutex/ex61.pp`

```

Program Example60;

{ This program demonstrates the AnsiUpperCase function }

Uses sysutils;

Procedure Testit (S : String);

begin
  WriteLn (S, ' → ',AnsiUpperCase(S))
end;

Begin
  Testit('AN UPPERCASE STRING');
  Testit('Some mixed STring');
  Testit('a lowercase string');
End.

```

76.15.29 AnsiUpperCaseFileName

Synopsis: Convert filename to uppercase.

Declaration: `function AnsiUpperCaseFileName(const s: string) : string`

Visibility: default

Description: `AnsiUpperCaseFileName` simply returns the result of

```
AnsiUpperCase(S);
```

See also: `AnsiUpperCase` ([1487](#)), `AnsiCompareFileName` ([1475](#)), `AnsiLowerCaseFileName` ([1480](#))

76.15.30 AppendStr

Synopsis: Append one ansistring to another.

Declaration: `procedure AppendStr(var Dest: string; const S: string)`

Visibility: default

Description: `AppendStr` appends `S` to `Dest`.

This function is provided for Delphi compatibility only, since it is completely equivalent to `Dest := Dest + S`.

Errors: None.

See also: `AssignStr` ([1489](#)), `NewStr` ([1563](#)), `DisposeStr` ([1507](#))

Listing: `./sysutex/ex62.pp`

```

Program Example62;

{ This program demonstrates the AppendStr function }

Uses sysutils;

Var S : AnsiString;

```

```

Begin
  S:= 'This is an ';
  AppendStr(S, 'AnsiString');
  Writeln ('S = "', S, '"');
End.

```

76.15.31 ApplicationName

Synopsis: Return a default application name

Declaration: `function ApplicationName : string`

Visibility: default

Description: `ApplicationName` returns the name of the current application. Standard this is equal to the filename part minus extension of `ParamStr(0)`, but it can be customized by setting the `OnGetApplicationName` (1471) callback.

Note that the returned value is only the name portion. It does not contain any path or file extension.

Errors: None.

See also: `GetAppConfigDir` (1548), `OnGetApplicationName` (1471), `GetAppConfigFile` (1548), `ConfigExtension` (1450)

76.15.32 AssignStr

Synopsis: Assigns an ansistring to a null-terminated string.

Declaration: `procedure AssignStr(var P: PString; const S: string)`

Visibility: default

Description: `AssignStr` allocates `S` to `P`. The old value of `P` is disposed of.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

Errors: None.

See also: `NewStr` (1563), `AppendStr` (1488), `DisposeStr` (1507)

Listing: `./sysutex/ex63.pp`

Program Example63;

```

{ This program demonstrates the AssignStr function }
{$H+}

```

Uses sysutils;

Var P : PString;

Begin

```

P:=NewStr('A first AnsiString');
Writeln ('Before: P = "', P^, '"');
AssignStr(P, 'A Second ansistring');
Writeln ('After : P = "', P^, '"');

```

```

DisposeStr(P);
End.

```

76.15.33 BCDToInt

Synopsis: Convert a BCD coded integer to a normal integer.

Declaration: `function BCDToInt(Value: Integer) : Integer`

Visibility: default

Description: `BCDToInt` converts a BCD coded integer to a normal integer.

Errors: None.

See also: `StrToInt` ([1590](#)), `IntToStr` ([1558](#))

Listing: `./sysutex/ex64.pp`

Program `Example64`;

{ This program demonstrates the BCDToInt function }

Uses `sysutils`;

Procedure `Testit (L : longint);`
begin
 WriteLn (L, ' → ', `BCDToInt(L)`);
end;

Begin
 `Testit(10);`
 `Testit(100);`
 `TestIt(23);`
End.

76.15.34 Beep

Synopsis: Sound the system bell.

Declaration: `procedure Beep`

Visibility: default

Description: `Beep` sounds the system bell, if one is available. The actual beep is produced by the `OnBeep` ([1471](#)) callback. The `Sysutils` unit itself contains no implementation of this call.

76.15.35 BoolToStr

Synopsis: Convert a boolean value to a string.

Declaration: `function BoolToStr(B: Boolean; UseBoolStrs: Boolean) : string`
 `function BoolToStr(B: Boolean; const TrueS: string;`
 `const FalseS: string) : string`

Visibility: default

Description: `BoolToStr` converts the boolean `B` to one of the strings ' TRUE' or ' FALSE'

Errors: None.

See also: `StrToBool` ([1585](#))

76.15.36 ByteLength

Synopsis: Length (in bytes) of a unicodestring

Declaration: `function ByteLength(const S: UnicodeString) : Integer`

Visibility: default

Description: `ByteLength` returns the length of a unicodestring in bytes. This equals the character length of the string (`Length` ([1442](#))) multiplied by the number of bytes per character (2).

See also: `Length` ([1442](#))

76.15.37 BytesOf

Synopsis: Return the bytes in a string

Declaration: `function BytesOf(const Val: RawByteString) : TBytes`
`function BytesOf(const Val: AnsiChar) : TBytes`
`function BytesOf(const Val: UnicodeString) : TBytes; Overload`
`function BytesOf(const Val: WideChar) : TBytes; Overload`

Visibility: default

Description: `BytesOf` returns a copy of the string's content as an array of bytes. For an empty string, zero bytes are returned (i.e. `length(BytesOf(S))=0`).

See also: `TBytes` ([1460](#))

76.15.38 ByteToCharIndex

Synopsis: Convert a character index in Bytes to an Index in characters

Declaration: `function ByteToCharIndex(const S: string; Index: Integer) : Integer`

Visibility: default

Description: `ByteToCharIndex` returns the index (in characters) of the `Index`-th byte in `S`.

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1493](#)), `ByteToCharLen` ([1491](#))

76.15.39 ByteToCharLen

Synopsis: Convert a length in bytes to a length in characters.

Declaration: `function ByteToCharLen(const S: string; MaxLen: Integer) : Integer`

Visibility: default

Description: `ByteToCharLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `CharToByteLen` ([1493](#)), `ByteToCharIndex` ([1491](#))

76.15.40 ByteType

Synopsis: Return the type of byte in an ansistring for a multi-byte character set

Declaration: `function ByteType(const S: string; Index: Integer) : TMbcsByteType`

Visibility: default

Description: `ByteType` returns the type of byte in the ansistring `S` at (1-based) position `Index`.

Errors: No checking on the index is performed.

See also: `TMbcsByteType` ([1465](#)), `StrByteType` ([1571](#))

76.15.41 CallTerminateProcs

Synopsis: Call the exit chain procedures.

Declaration: `function CallTerminateProcs : Boolean`

Visibility: default

Description: `CallTerminateProcs` is run on program exit. It executes all terminate procedures that were added to the exit chain with `AddTerminateProc` ([1474](#)), and does this in reverse order.

Errors: If one of the exit procedure raises an exception, it is *not* caught, and the remaining exit procedures will not be executed.

See also: `TTerminateProc` ([1467](#)), `AddTerminateProc` ([1474](#))

76.15.42 ChangeFileExt

Synopsis: Change the extension of a filename.

Declaration: `function ChangeFileExt(const FileName: UnicodeString;
 const Extension: UnicodeString) : UnicodeString
function ChangeFileExt(const FileName: RawByteString;
 const Extension: RawByteString) : RawByteString`

Visibility: default

Description: `ChangeFileExt` changes the file extension in `FileName` to `Extension`. The extension `Extension` includes the starting `.` (dot). The previous extension of `FileName` are all characters after the last `.`, the `.` character included.

If `FileName` doesn't have an extension, `Extension` is just appended.

Errors: None.

See also: `ExtractFileExt` ([1516](#)), `ExtractFileName` ([1516](#)), `ExtractFilePath` ([1516](#)), `ExpandFileName` ([1513](#))

76.15.43 CharInSet

Synopsis: Check whether a char is in a set of characters

Declaration: `function CharInSet(Ch: AnsiChar; const CSet: TSysCharSet) : Boolean
function CharInSet(Ch: WideChar; const CSet: TSysCharSet) : Boolean`

Visibility: default

Description: `CharInSet` returns `True` if `Ch` matches one of the characters in `CSet`, it returns `False` otherwise. It is equivalent to

`Ch in CSet`

Later versions of this function may take `WideChar` into account.

76.15.44 CharToByteLen

Synopsis: Convert a length in characters to a length in bytes.

Declaration: `function CharToByteLen(const S: string; MaxLen: Integer) : Integer`

Visibility: `default`

Description: `CharToByteLen` returns the number of bytes in `S`, but limits the result to `MaxLen`

Errors: This function does not take into account MBCS yet.

See also: `ByteToCharLen` ([1491](#)), `ByteToCharIndex` ([1491](#))

76.15.45 CodePageNameToCodePage

Synopsis: Return a numeric identifier for the codepage.

Declaration: `function CodePageNameToCodePage(const cpname: AnsiString)
: TSystemCodePage`

Visibility: `default`

Description: `CodePageNameToCodePage` returns the code page number for the specified codepage `cpname`.

Errors: If the code page is not found in the list of code pages, `$FFFF` is returned.

See also: `CodePageToCodePageName` ([1493](#))

76.15.46 CodePageToCodePageName

Synopsis: Convert a numeric codepage identifier to a codepage name

Declaration: `function CodePageToCodePageName(cp: TSystemCodePage) : AnsiString`

Visibility: `default`

Description: `CodePageToCodePageName` returns the name of the codepage `cp`.

Errors: If no matching codepage is found in the list of codepages, an empty string is returned.

See also: `CodePageNameToCodePage` ([1493](#))

76.15.47 CompareMem

Synopsis: Compare two memory areas.

Declaration: `function CompareMem(P1: Pointer; P2: Pointer; Length: PtrUInt) : Boolean`

Visibility: `default`

Description: `CompareMem` compares, byte by byte, 2 memory areas pointed to by `P1` and `P2`, for a length of `L` bytes.

The function returns `True` if all `L` bytes are the same, and `False` otherwise.

76.15.48 CompareMemRange

Synopsis: Compare 2 memory locations

Declaration: `function CompareMemRange(P1: Pointer; P2: Pointer; Length: PtrUInt)
: Integer`

Visibility: default

Description: `CompareMemRange` compares the 2 memory locations pointed to by `P1` and `P2` byte per byte. It stops comparing after `Length` bytes have been compared, or when it has encountered 2 different bytes. The result is then

`>0` if a byte in range `P1` was found that is bigger than the corresponding byte in range `P2`.

`0` if all bytes in range `P1` are the same as the corresponding bytes in range `P2`.

`<0` if a byte in range `P1` was found that is less than the corresponding byte in range `P2`.

Errors: None.

See also: `SameText` ([1568](#))

76.15.49 CompareStr

Synopsis: Compare 2 ansistrings case-sensitively, ignoring special characters.

Declaration: `function CompareStr(const S1: string; const S2: string) : Integer
; Overload`

Visibility: default

Description: `CompareStr` compares two strings, `S1` and `S2`, and returns the following result:

`<0` if `S1 < S2`.

`0` if `S1 = S2`.

`>0` if `S1 > S2`.

The comparison of the two strings is case-sensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `AnsiCompareText` ([1477](#)), `AnsiCompareStr` ([1476](#)), `CompareText` ([1495](#))

Listing: `./sysutex/ex65.pp`

Program `Example65`;

```
{ This program demonstrates the CompareStr function }  
{ $H+ }
```

Uses `sysutils`;

Procedure `TestIt (S1, S2 : String)`;

Var `R : Longint`;

begin

`R := CompareStr(S1, S2)`;

```

Write ( '', S1, ' is ' );
If R<0 then
  write ( 'less than ' )
else If R=0 then
  Write ( 'equal to ' )
else
  Write ( 'larger than ' );
WriteLn ( '', S2, ' ' );
end;

Begin
  Testit( 'One string', 'One smaller string' );
  Testit( 'One string', 'one string' );
  Testit( 'One string', 'One string' );
  Testit( 'One string', 'One tall string' );
End.

```

76.15.50 CompareText

Synopsis: Compare 2 ansistrings case insensitive.

Declaration: `function CompareText(const S1: string; const S2: string) : Integer`

Visibility: default

Description: CompareText compares two strings, S1 and S2, and returns the following result:

```

<0if S1<S2.
0if S1=S2.
>0if S1>S2.

```

The comparison of the two strings is case-insensitive. The function does not take internationalization settings into account, it simply compares ASCII values.

Errors: None.

See also: `AnsiCompareText` ([1477](#)), `AnsiCompareStr` ([1476](#)), `CompareStr` ([1494](#))

Listing: `./sysutex/ex66.pp`

Program Example66;

```

{ This program demonstrates the CompareText function }
{$H+}

```

Uses sysutils;

Procedure TestIt (S1,S2 : **String**);

Var R : Longint;

```

begin
  R:=CompareText(S1,S2);
  Write ( '', S1, ' is ' );
  If R<0 then
    write ( 'less than ' )
  else If R=0 then

```



```

Write ( ' equal to ' )
else
  Write ( ' larger than ' );
WriteLn ( '""', S2, '""');
end;

Begin
  Testit( 'One string', 'One smaller string' );
  Testit( 'One string', 'one string' );
  Testit( 'One string', 'One string' );
  Testit( 'One string', 'One tall string' );
End.

```

76.15.51 ComposeDateTime

Synopsis: Add a date and time

```
Declaration: function ComposeDateTime(Date: TDateTime; Time: TDateTime) : TDateTime
```

Visibility: default

Description: `ComposeDateTime` correctly adds `Date` and `Time`, also for dates before 1899-12-31. For dates after this date, it is just the mathematical addition.

Errors: None.

See also: `#rtl.dateutils.EncodeDateTime` ([553](#))

76.15.52 ConcatPaths

Synopsis: Concatenate an array of paths to form a single path

```
Declaration: function ConcatPaths(const Paths: Array of UnicodeString)
              : UnicodeString
function ConcatPaths(const Paths: Array of RawByteString)
              : RawByteString
```

Visibility: default

Description: `ConcatPaths` will concatenate the different path components in `Paths` to a single path. It will insert directory separators between the various components of the path as needed. No directory separators will be added to the beginning or the end of the path, and none will be taken away.

See also: IncludeTrailingPathDelimiter (1556), IncludeLeadingPathDelimiter (1555), ExcludeTrailingPathDelimiter (1511), IncludeTrailingPathDelimiter (1556)

Listing: ./sysutex/ex96.pp

```
program ex96;

{ This program demonstrates the Concatpaths function }

uses sysutils;

begin
    // will write /this/path/more/levels/
    WriteLn(ConcatPaths([' /this/', 'path', 'more/levels/']));
end
```

```
// will write this/path/more/levels/
WriteLn(ConcatPaths(['this/', 'path', 'more/levels/']));
// will write this/path/more/levels
WriteLn(ConcatPaths(['this/', 'path', 'more/levels']));
end.
```

76.15.53 CreateDir

Synopsis: Create a new directory

Declaration: `function CreateDir(const NewDir: RawByteString) : Boolean`
`function CreateDir(const NewDir: UnicodeString) : Boolean`

Visibility: default

Description: `CreateDir` creates a new directory with name `NewDir`. If the directory doesn't contain an absolute path, then the directory is created below the current working directory.

The function returns `True` if the directory was successfully created, `False` otherwise.

Errors: In case of an error, the function returns `False`.

See also: `RemoveDir` ([1565](#))

Listing: `./sysutex/ex26.pp`

Program `Example26`;

```
{ This program demonstrates the CreateDir and RemoveDir functions }
{ Run this program twice in the same directory }
```

Uses `sysutils`;

Begin

```
  If Not DirectoryExists('NewDir') then
    If Not CreateDir('NewDir') Then
      WriteLn('Failed to create directory !')
    else
      WriteLn('Created "NewDir" directory')
  Else
    If Not RemoveDir('NewDir') Then
      WriteLn('Failed to remove directory !')
    else
      WriteLn('Removed "NewDir" directory');
```

End.

76.15.54 CreateGUID

Synopsis: Create a new GUID

Declaration: `function CreateGUID(out GUID: TGUID) : Integer`

Visibility: default

Description: `CreateGUID` can be called to create a new GUID (Globally Unique Identifier) value. The function returns the new GUID value in `GUID` and returns zero in case the GUID was created successfully. If no GUID was created, a nonzero error code is returned.

The default mechanism for creating a new GUID is system dependent. If operating system support is available, it is used. If none is available, a default implementation using random numbers is used.

The `OnCreateGUID` callback can be set to hook a custom mechanism behind the `CreateGUID` function. This can be used to let the GUID be created by an external GUID creation library.

Errors: On error, a nonzero return value is returned.

See also: `GUIDCase` ([1554](#)), `IsEqualGUID` ([1559](#)), `StringToGUID` ([1577](#)), `TryStringToGUID` ([1602](#)), `GUIDToString` ([1554](#))

76.15.55 CurrentYear

Synopsis: Return the current year

Declaration: `function CurrentYear : Word`

Visibility: default

Description: `CurrentYear` returns the current year as a 4-digit number.

Errors: None.

See also: `Date` ([1499](#)), `Time` ([1597](#)), `Now` ([1564](#))

76.15.56 CurrToStr

Synopsis: Convert a currency value to a string.

Declaration: `function CurrToStr(Value: Currency) : string`
`function CurrToStr(Value: Currency;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `CurrToStr` will convert a currency value to a string with a maximum of 15 digits, and precision 2. Calling `CurrToStr` is equivalent to calling `FloatToStrF` ([1533](#)):

```
FloatToStrF(Value, ffNumber, 15, 2);
```

Errors: None.

See also: `FloatToStrF` ([1533](#)), `StrToCurr` ([1585](#))

76.15.57 CurrToStrF

Synopsis: Format a currency to a string

Declaration: `function CurrToStrF(Value: Currency; Format: TFloatFormat;`
`Digits: Integer) : string`
`function CurrToStrF(Value: Currency; Format: TFloatFormat;`
`Digits: Integer;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `CurrToStrF` formats the currency `Value` according to the value in `Format`, using the number of digits specified in `Digits`, and a precision of 19. This function simply calls `FloatToStrF` ([1533](#)).

See also: `FloatToStrF` ([1533](#))

76.15.58 Date

Synopsis: Return the current date.

Declaration: `function Date : TDateTime`

Visibility: default

Description: `Date` returns the current date in `TDateTime` format.

Errors: None.

See also: `Time` ([1597](#)), `Now` ([1564](#))

Listing: `./sysutex/ex1.pp`

Program `Example1`;

{ This program demonstrates the Date function }

uses `sysutils`;

Var `YY,MM,DD : Word`;

Begin

`WriteLn ('Date : ',Date);`

`DeCodeDate (Date,YY,MM,DD);`

`WriteLn (format ('Date is (DD/MM/YY): %d/%d/%d ',[dd,mm,yy]));`

End.

76.15.59 DateTimeToFileDate

Synopsis: Convert a `TDateTime` value to a file age (integer)

Declaration: `function DateTimeToFileDate(DateTime: TDateTime) : LongInt`

Visibility: default

Description: `DateTimeToFileDate` function converts a date/time indication in `TDateTime` format to a file-date function, such as returned for instance by the `FileAge` ([1518](#)) function.

Errors: None.

See also: `Time` ([1597](#)), `Date` ([1499](#)), `FileDateToDateTime` ([1520](#)), `DateTimeToSystemTime` ([1501](#)), `DateTimeToTimeStamp` ([1502](#))

Listing: `./sysutex/ex2.pp`

Program `Example2`;

{ This program demonstrates the DateTimeToFileDate function }

Uses `sysutils`;

Begin

`WriteLn ('FileTime of now would be: ',DateTimeToFileDate (Now));`

End.

76.15.60 DateTimeToStr

Synopsis: Converts a `TDateTime` value to a string using a predefined format.

Declaration:

```
function DateTimeToStr(DateTime: TDateTime; ForceTimeIfZero: Boolean)
    : string
function DateTimeToStr(DateTime: TDateTime;
    const FormatSettings: TFormatSettings;
    ForceTimeIfZero: Boolean) : string
```

Visibility: default

Description: `DateTimeToStr` returns a string representation of `DateTime` using the formatting specified in `LongDateTimeFormat`. It corresponds to a call to `FormatDateTime('c', DateTime)` (see [formatchars \(1448\)](#)).

Note that if the time part is 0 (i.e. midnight), no time is appended.

Errors: None.

See also: `FormatDateTime` ([1545](#))

Listing: `./sysutex/ex3.pp`

Program `Example3`;

{ This program demonstrates the DateTimeToStr function }

Uses `sysutils`;

Begin

`WriteLn ('Today is : ', DateTimeToStr(Now));`

`WriteLn ('Today is : ', FormatDateTime('c', Now));`

End.

76.15.61 DateTimeToString

Synopsis: Converts a `TDateTime` value to a string with a given format.

Declaration:

```
procedure DateTimeToString(out Result: string; const FormatStr: string;
    const DateTime: TDateTime;
    Options: TFormatDateTimeOptions)
procedure DateTimeToString(out Result: string; const FormatStr: string;
    const DateTime: TDateTime;
    const FormatSettings: TFormatSettings;
    Options: TFormatDateTimeOptions)
```

Visibility: default

Description: `DateTimeToString` returns in `Result` a string representation of `DateTime` using the formatting specified in `FormatStr`.

for a list of characters that can be used in the `FormatStr` formatting string, see [formatchars \(1448\)](#).

Note that for 'c', if the time part is 0 (i.e. midnight), no time is appended.

Errors: In case a wrong formatting character is found, an `EConvertError` ([1616](#)) is raised.

See also: `FormatDateTime` ([1545](#)), `formatchars` ([1448](#)), `EConvertError` ([1616](#))

Listing: ./sysutex/ex4.pp

Program Example4;

{ This program demonstrates the DateTimeToString function }

Uses sysutils;

Procedure today (Fmt : **string**);

Var S : AnsiString;

begin

DateTimeToString (S,Fmt,**Date**);

WriteLn (S);

end;

Procedure Now (Fmt : **string**);

Var S : AnsiString;

begin

DateTimeToString (S,Fmt,**Time**);

WriteLn (S);

end;

Begin

 Today ('"Today is "dddd dd mmm y');

 Today ('"Today is "d mmm yy');

 Today ('"Today is "d/mmm/yy');

Now ('' 'The time is ' 'am/pmh:n:s');

Now ('' 'The time is ' 'hh:nn:ssam/pm');

Now ('' 'The time is ' 'tt');

End.

76.15.62 DateTimeToSystemTime

Synopsis: Converts a TDateTime value to a systemtime structure.

Declaration: procedure DateTimeToSystemTime (DateTime: TDateTime;
 out SystemTime: TSystemTime)

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a system time SystemTime.

Errors: None.

See also: DateTimeToFileDate ([1499](#)), SystemTimeToDateTime ([1595](#)), DateTimeToTimeStamp ([1502](#))

Listing: ./sysutex/ex5.pp

Program Example5;

{ This program demonstrates the DateTimeToSystemTime function }

```

Uses sysutils;

Var ST : TSystemTime;

Begin
  DateTimeToSystemTime(Now,ST);
  With St do
    begin
      Writeln ('Today is ',year,'/',month,'/',Day);
      Writeln ('The time is ',Hour,':',minute,':',Second,'.',MilliSecond);
    end;
End.

```

76.15.63 DateTimeToTimeStamp

Synopsis: Converts a TDateTime value to a TimeStamp structure.

Declaration: function DateTimeToTimeStamp(DateTime: TDateTime) : TTimeStamp

Visibility: default

Description: DateTimeToSystemTime converts a date/time pair in DateTime, with TDateTime format to a TTimeStamp format.

Errors: None.

See also: DateTimeToFileDate ([1499](#)), SystemTimeToDateTime ([1595](#)), DateTimeToSystemTime ([1501](#))

Listing: ./sysutex/ex6.pp

Program Example6;

{ This program demonstrates the DateTimeToTimeStamp function }

```

Uses sysutils;

Var TS : TTimeStamp;

Begin
  TS:=DateTimeToTimeStamp (Now);
  With TS do
    begin
      Writeln ('Now is ',time,' millisecond past midnight');
      Writeln ('Today is ',Date,' days past 1/1/0001');
    end;
End.

```

76.15.64 DateToStr

Synopsis: Converts a TDateTime value to a date string with a predefined format.

Declaration: function DateToStr(Date: TDateTime) : string
 function DateToStr(Date: TDateTime;
 const FormatSettings: TFormatSettings) : string

Visibility: default

Description: `DateToStr` converts `Date` to a string representation. It uses `ShortDateFormat` as it's formatting string. It is hence completely equivalent to a `FormatDateTime('dddd', Date)`.

Errors: None.

See also: `TimeToStr` ([1599](#)), `DateTimeToStr` ([1500](#)), `FormatDateTime` ([1545](#)), `StrToDate` ([1586](#))

Listing: `./sysutex/ex7.pp`

Program `Example7;`

{ This program demonstrates the DateToStr function }

Uses `sysutils;`

Begin

`WriteLn (Format ('Today is: %s', [DateToStr (Date)]));`
End.

76.15.65 DayOfWeek

Synopsis: Returns the day of the week.

Declaration: `function DayOfWeek (DateTime: TDateTime) : Integer`

Visibility: `default`

Description: `DayOfWeek` returns the day of the week from `DateTime`. Sunday is counted as day 1, Saturday is counted as day 7. The result of `DayOfWeek` can serve as an index to the `LongDayNames` constant array, to retrieve the name of the day.

Errors: None.

See also: `Date` ([1499](#)), `DateToStr` ([1502](#))

Listing: `./sysutex/ex8.pp`

Program `Example8;`

{ This program demonstrates the DayOfWeek function }

Uses `sysutils;`

Begin

`WriteLn ('Today's day is ', LongDayNames[DayOfWeek (Date)]);`
End.

76.15.66 DecodeDate

Synopsis: Decode a `TDateTime` to a year,month,day triplet

Declaration: `procedure DecodeDate (Date: TDateTime; out Year: Word; out Month: Word;
out Day: Word)`

Visibility: `default`

Description: `DecodeDate` decodes the Year, Month and Day stored in `Date`, and returns them in the Year, Month and Day variables.

Errors: None.

See also: `EncodeDate` ([1508](#)), `DecodeTime` ([1504](#))

Listing: `./sysutex/ex9.pp`

Program `Example9`;

{ This program demonstrates the DecodeDate function }

Uses `sysutils`;

Var `YY,MM,DD` : `Word`;

Begin

`DecodeDate (Date ,YY,MM,DD);`

`WriteLn (Format ('Today is %d/%d/%d' ,[dd,mm,yy]));`

End.

76.15.67 DecodeDateFully

Synopsis: Decode a date with additional date of the week.

Declaration: `function DecodeDateFully(const DateTime: TDateTime; out Year: Word;
 out Month: Word; out Day: Word; out DOW: Word)
 : Boolean`

Visibility: default

Description: `DecodeDateFully`, like `DecodeDate` ([1503](#)), decodes `DateTime` in its parts and returns these in Year, Month, Day but in addition returns the day of the week in DOW.

Errors: None.

See also: `EncodeDate` ([1508](#)), `TryEncodeDate` ([1601](#)), `DecodeDate` ([1503](#))

76.15.68 DecodeTime

Synopsis: Decode a `TDateTime` to a hour,minute,second,millisecond quartet

Declaration: `procedure DecodeTime(Time: TDateTime; out Hour: Word; out Minute: Word;
 out Second: Word; out MilliSecond: Word)`

Visibility: default

Description: `DecodeTime` decodes the hours, minutes, second and milliseconds stored in `Time`, and returns them in the Hour, Minute and Second and MilliSecond variables.

Errors: None.

See also: `EncodeTime` ([1509](#)), `DecodeDate` ([1503](#))

Listing: `./sysutex/ex10.pp`

Program Example10;

{ This program demonstrates the DecodeTime function }

Uses sysutils;

Var HH,MM,SS,MS: Word;

Begin

DecodeTime(**Time**,HH,MM,SS,MS);

WriteLn (**format**('The time is %d:%d:%d.%d' ,[hh,mm,ss,ms]));

End.

76.15.69 DeleteFile

Synopsis: Delete a file from the filesystem.

Declaration: function DeleteFile(const FileName: UnicodeString) : Boolean
function DeleteFile(const FileName: RawByteString) : Boolean

Visibility: default

Description: DeleteFile deletes file FileName from disk. The function returns True if the file was successfully removed, False otherwise.

Errors: On error, False is returned.

See also: FileCreate ([1519](#)), FileExists ([1521](#))

Listing: ./sysutex/ex31.pp

Program Example31;

{ This program demonstrates the DeleteFile function }

Uses sysutils;

Var

 Line : **String**;

 F,I : Longint;

Begin

 F:=FileCreate('test.txt');

 Line:='Some string line.'#10;

For I:=1 **to** 10 **do**

 FileWrite (F,Line[I],**Length**(Line));

FileClose(F);

DeleteFile('test.txt');

End.

76.15.70 DirectoryExists

Synopsis: Check whether a directory exists in the file system.

Declaration: function DirectoryExists(const Directory: UnicodeString) : Boolean
function DirectoryExists(const Directory: RawByteString) : Boolean

Visibility: default

Description: `DirectoryExists` checks whether `Directory` exists in the filesystem and is actually a directory. If this is the case, the function returns `True`, otherwise `False` is returned.

See also: `FileExists` ([1521](#))

76.15.71 DiskFree

Synopsis: Return the amount of free disk space

Declaration: `function DiskFree(drive: Byte) : Int64`

Visibility: default

Description: `DiskFree` returns the free space (in bytes) on disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` and `DiskSize` ([1506](#)) functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` ([1474](#)).

Errors: On error, `-1` is returned.

See also: `DiskSize` ([1506](#)), `AddDisk` ([1474](#))

Listing: `./sysutex/ex27.pp`

Program `Example27`;

{ This program demonstrates the DiskFree function }

Uses `sysutils`;

Begin

```
Write ('Size of current disk      : ', DiskSize(0));
WriteLn (' (= ', DiskSize(0) div 1024, 'k) ');
Write ('Free space of current disk : ', Diskfree(0));
WriteLn (' (= ', Diskfree(0) div 1024, 'k) ');
```

End.

76.15.72 DiskSize

Synopsis: Return the total amount of disk space.

Declaration: `function DiskSize(drive: Byte) : Int64`

Visibility: default

Description: `DiskSize` returns the size (in bytes) of disk `Drive`. `Drive` is the number of the disk drive:

- 0** for the current drive.
- 1** for the first floppy drive.
- 2** for the second floppy drive.
- 3** for the first hard-disk partition.
- 4-26** for all other drives and partitions.

Remark: Under Linux, and Unix in general, the concept of disk is different than the dos one, since the filesystem is seen as one big directory tree. For this reason, the `DiskFree` (1506) and `DiskSize` functions must be mimicked using filenames that reside on the partitions. For more information, see `AddDisk` (1474)

For an example, see `DiskFree` (1506).

Errors: On error, `-1` is returned.

See also: `DiskFree` (1506), `AddDisk` (1474)

76.15.73 DisposeStr

Synopsis: Dispose an anstring from the heap.

Declaration: `procedure DisposeStr(S: PString); Overload`
`procedure DisposeStr(S: PShortString); Overload`

Visibility: default

Description: `DisposeStr` removes the dynamically allocated string `S` from the heap, and releases the occupied memory.

This function is provided for Delphi compatibility only. `AnsiStrings` are managed on the heap and should be preferred to the mechanism of dynamically allocated strings.

For an example, see `DisposeStr` (1507).

Errors: None.

See also: `NewStr` (1563), `AppendStr` (1488), `AssignStr` (1489)

76.15.74 DoDirSeparators

Synopsis: Convert known directory separators to the current directory separator.

Declaration: `procedure DoDirSeparators(var FileName: UnicodeString)`
`procedure DoDirSeparators(var FileName: RawByteString)`

Visibility: default

Description: This function replaces all known directory separators in `FileName` to the directory separator character for the current system. The list of known separators is specified in the `AllowDirectorySeparators` (1194) constant.

Errors: None.

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516)

Listing: `./sysutex/ex32.pp`

Program Example32;

```
{ This program demonstrates the DoDirSeparators function }
{$H+}
```

Uses sysutils;

Procedure Testit (F : **String**);

begin

WriteLn ('Before : ',F);

 DoDirSeparators (F);

WriteLn ('After : ',F);

end;

Begin

 Testit (GetCurrentDir);

 Testit ('c:\pp\bin\win32');

 Testit ('/usr/lib/fpc');

 Testit ('\usr\lib\fpcc');

End.

76.15.75 EncodeDate

Synopsis: Encode a Year,Month,Day to a TDateTime value.

Declaration: function EncodeDate(Year: Word; Month: Word; Day: Word) : TDateTime

Visibility: default

Description: EncodeDate encodes the Year, Month and Day variables to a date in TDateTime format. It does the opposite of the DecodeDate (1503) procedure.

The parameters must lie within valid ranges (boundaries included):

Year must be between 1 and 9999.

Month must be within the range 1-12.

Day must be between 1 and 31.

Errors: In case one of the parameters is out of its valid range, an EConvertError (1616) exception is raised.

See also: EncodeTime (1509), DecodeDate (1503)

Listing: ./sysutex/ex11.pp

Program Example11;

```
{ This program demonstrates the EncodeDate function }
```

Uses sysutils;

Var YY,MM,DD : Word;

Begin

 DecodeDate (Date,YY,MM,DD);

WriteLn ('Today is : ',FormatDateTime ('dd mmm yyyy ',EncodeDate(YY,Mm,Dd)));

End.

76.15.76 EncodeTime

Synopsis: Encode a Hour,Min,Sec,millisecond to a TDateTime value.

Declaration: `function EncodeTime (Hour: Word; Minute: Word; Second: Word; MilliSecond: Word) : TDateTime`

Visibility: default

Description: `EncodeTime` encodes the Hour, Minute, Second, MilliSecond variables to a TDateTime format result. It does the opposite of the `DecodeTime` (1504) procedure.

The parameters must have a valid range (boundaries included):

Hour must be between 0 and 23.

Minute,second must both be between 0 and 59.

Millisecond must be between 0 and 999.

Errors: In case one of the parameters is out of it's valid range, an `EConvertError` (1616) exception is raised.

See also: `EncodeDate` (1508), `DecodeTime` (1504)

Listing: ./sysutex/ex12.pp

Program Example12;

{ This program demonstrates the EncodeTime function }

Uses sysutils;

Var Hh,MM,SS,MS : Word;

Begin

DeCodeTime (Time, Hh,MM,SS,MS);

WriteIn ('Present Time is : ', **FormatDateTime** ('hh:mm:ss', **EnCodeTime** (HH,MM,SS,MS)));

End.

76.15.77 ExceptAddr

Synopsis: Current exception address.

Declaration: `function ExceptAddr : CodePointer`

Visibility: default

Description: `ExceptAddr` returns the address from the currently treated exception object when an exception is raised, and the stack is unwound.

See also: `ExceptObject` (1510), `ExceptionErrorMessage` (1510), `ShowException` (1569)

76.15.78 ExceptFrameCount

Synopsis: Number of frames included in an exception backtrace

Declaration: `function ExceptFrameCount : LongInt`

Visibility: default

Description: `ExceptFrameCount` returns the number of frames that are included in an exception stack frame backtrace. The function returns 0 if there is currently no exception being handled. (i.e. it only makes sense to call this function in an `finally . . end` or `except . . end` block.

Errors: None.

See also: `ExceptFrames` ([1510](#)), `ExceptAddr` ([1509](#)), `ExceptObject` ([1510](#)), `#rtl.system.ExceptProc` ([1201](#))

76.15.79 ExceptFrames

Synopsis: Return the current exception stack frames

Declaration: `function ExceptFrames : PCodePointer`

Visibility: `default`

Description: `ExceptFrames` returns the current list frames on the exception stack. If there is no exception in progress, `Nil` is returned.

See also: `ExceptFrameCount` ([1509](#)), `ExceptAddr` ([1509](#)), `ExceptObject` ([1510](#)), `#rtl.system.ExceptProc` ([1201](#))

76.15.80 ExceptionErrorMessage

Synopsis: Return a message describing the exception.

Declaration: `function ExceptionErrorMessage(ExceptObject: TObject;
ExceptAddr: Pointer; Buffer: PChar;
Size: Integer) : Integer`

Visibility: `default`

Description: `ExceptionErrorMessage` creates a string that describes the exception object `ExceptObject` at address `ExceptAddr`. It can be used to display exception messages. The string will be stored in the memory pointed to by `Buffer`, and will at most have `Size` characters.

The routine checks whether `ExceptObject` is a `Exception` ([1623](#)) object or not, and adapts the output accordingly.

See also: `ExceptObject` ([1510](#)), `ExceptAddr` ([1509](#)), `ShowException` ([1569](#))

76.15.81 ExceptObject

Synopsis: Current Exception object.

Declaration: `function ExceptObject : TObject`

Visibility: `default`

Description: `ExceptObject` returns the currently treated exception object when an exception is raised, and the stack is unwound.

Errors: If there is no exception, the function returns `Nil`

See also: `ExceptAddr` ([1509](#)), `ExceptionErrorMessage` ([1510](#)), `ShowException` ([1569](#))

76.15.82 ExcludeLeadingPathDelimiter

Synopsis: Strip the leading path delimiter of a path

```
Declaration: function ExcludeLeadingPathDelimiter(const Path: UnicodeString)
              : UnicodeString
function ExcludeLeadingPathDelimiter(const Path: RawByteString)
              : RawByteString
```

Visibility: default

Description: `ExcludeLeadingPathDelimiter` will remove any path delimiter on the first position of `Path` if there is one. if there is none (or the path is empty), it is left untouched.

See also: [IncludeTrailingPathDelimiter \(1556\)](#), [IncludeLeadingPathDelimiter \(1555\)](#), [ExcludeTrailingPathDelimiter \(1511\)](#), [ConcatPaths \(1496\)](#)

Listing: ./sysutex/ex95.pp

Program Example95;

```
{ This program demonstrates the IncludeLeadingPathDelimiter function }
```

Uses sysutils;

Begin

```
// Will print "/this/path"
WriteLn(IncludeLeadingPathDelimiter('this/path'));
// The same result
WriteLn(IncludeLeadingPathDelimiter('/this/path'));
End.
```

76.15.83 ExcludeTrailingBackslash

Synopsis: Strip trailing directory separator from a pathname, if needed.

```
Declaration: function ExcludeTrailingBackslash(const Path: UnicodeString)
              : UnicodeString
function ExcludeTrailingBackslash(const Path: RawByteString)
              : RawByteString
```

Visibility: default

Description: `ExcludeTrailingBackslash` is provided for backwards compatibility with Delphi. Use `ExcludeTrailingPathDelimiter` (1511) instead.

See also: IncludeTrailingPathDelimiter (1556), ExcludeTrailingPathDelimiter (1511), PathDelim (1455), IsPathDelimiter (1560)

76.15.84 ExcludeTrailingPathDelimiter

Synopsis: Strip trailing directory separator from a pathname, if needed.

[illegible]

Visibility: default

Description: `ExcludeTrailingPathDelimiter` removes the trailing path delimiter character (`PathDelim` (1455)) from `Path` if it is present, and returns the result.

See also: `ExcludeTrailingBackslash` (1511), `IncludeTrailingPathDelimiter` (1556), `PathDelim` (1455), `IsPathDelimiter` (1560)

76.15.85 ExecuteProcess

Synopsis: Execute another process (program).

Declaration:

```
function ExecuteProcess(const Path: AnsiString;
                        const ComLine: AnsiString; Flags: TExecuteFlags)
                        : Integer
function ExecuteProcess(const Path: AnsiString;
                        const ComLine: Array of AnsiString;
                        Flags: TExecuteFlags) : Integer
```

Visibility: default

Description: `ExecuteProcess` will execute the program in `Path`, passing it the arguments in `ComLine`. `ExecuteProcess` will then wait for the program to finish, and will return the exit code of the executed program. In case `ComLine` is a single string, it will be split out in an array of strings, taking into account common whitespace and quote rules.

The program specified in `Path` is not searched in the searchpath specified in the `PATH` environment variable, so the full path to the executable must be specified in `Path`, although some operating systems may perform this search anyway (notably, windows)

`Flags` can be used to control the passing of file handles: if `ExecInheritsHandles` is included, the file handles of the current process will be passed on to the newly executed process.

Errors: In case the program could not be executed or an other error occurs, an `EOSError` (1620) exception will be raised.

See also: `TExecuteFlags` (1461), `EOSError` (1620)

76.15.86 ExeSearch

Synopsis: Search for an executable

Declaration:

```
function ExeSearch(const Name: UnicodeString;
                  const DirList: UnicodeString) : UnicodeString
function ExeSearch(const Name: RawByteString;
                  const DirList: RawByteString) : RawByteString
```

Visibility: default

Description: `ExeSearch` searches for an executable `Name` in the list of directories `DirList` (a list of directories, separator by `PathSeparator` (1194)). If the current OS also searches implicitly in the current working directory, the current directory is searched in the first place.

If the executable is found, then the full path of the executable is returned. If it is not found, an empty string is returned.

No check is performed whether the found file is actually executable.

See also: `FileSearch` (1525)

76.15.87 ExpandFileName

Synopsis: Expand a relative filename to an absolute filename.

Declaration: `function ExpandFileName(const FileName: UnicodeString) : UnicodeString`
`function ExpandFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExpandFileName` expands the filename to an absolute filename. It changes all directory separator characters to the one appropriate for the system first.

If an empty filename is passed, it is expanded to the current directory.

Errors: None.

See also: `ExpandFileNameCase` (1513), `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

Listing: ./sysutex/ex33.pp

Program Example33;

{ This program demonstrates the ExpandFileName function }

Uses sysutils;

Procedure Testit (F : **String**);

begin

WriteLn (F, ' expands to : ', **ExpandFileName**(F));
end;

Begin

 Testit('ex33.pp');
 Testit(**ParamStr**(0));
 Testit('/pp/bin/win32/ppc386');
 Testit('\pp\bin\win32\ppc386');
 Testit('.');

End.

76.15.88 ExpandFileNameCase

Synopsis: Expand a filename entered as case insensitive to the full path as stored on the disk.

Declaration: `function ExpandFileNameCase(const FileName: UnicodeString;`
`out MatchFound: TFilenameCaseMatch)`
`: UnicodeString`
`function ExpandFileNameCase(const FileName: RawByteString;`
`out MatchFound: TFilenameCaseMatch)`
`: RawByteString`

Visibility: default

Description: On case insensitive platforms, `ExpandFileNameCase` behaves similarly to `ExpandFileName` (1513) except for the fact that it returns the final part of the path with the same case of letters as found on the disk (if it exists - otherwise the case equals the one provided on input). On case sensitive platforms it also checks whether one or more full paths exist on disk which would correspond to the

76.15.90 ExtractFileDir

Synopsis: Extract the drive and directory part of a filename.

Declaration: `function ExtractFileDir(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileDir(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileDir` returns only the directory part of `FileName`, including a driveletter. The directory name has NO ending directory separator, in difference with `ExtractFilePath` (1516).

Errors: None.

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

Listing: `./sysutex/ex34.pp`

Program `Example34`;

{ This program demonstrates the ExtractFileName function }
{ \$H+ }

Uses `sysutils`;

Procedure `Testit(F : String)`;

begin

`Writeln ('FileName : ', F);`
`Writeln ('Has Name : ', ExtractFileName(F));`
`Writeln ('Has Path : ', ExtractFilePath(F));`
`Writeln ('Has Extension : ', ExtractFileExt(F));`
`Writeln ('Has Directory : ', ExtractFileDir(F));`
`Writeln ('Has Drive : ', ExtractFileDrive(F));`

end;

Begin

`Testit (Paramstr(0));`
`Testit ('/usr/local/bin/mysqld');`
`Testit ('c:\pp\bin\win32\ppc386.exe');`
`Testit ('/pp/bin/win32/ppc386.exe');`

End.

76.15.91 ExtractFileDrive

Synopsis: Extract the drive part from a filename.

Declaration: `function ExtractFileDrive(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileDrive(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `Extracts` the drive letter from a filename. Note that some operating systems do not support drive letters.

For an example, see `ExtractFileDir` (1515).

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

76.15.92 ExtractFileExt

Synopsis: Return the extension from a filename.

Declaration: `function ExtractFileExt(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileExt(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileExt` returns the extension (including the `.` (dot) character) of `FileName`.

For an example, see `ExtractFileDir` (1515).

Errors: None.

See also: `ChangeFileExt` (1492), `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

76.15.93 ExtractFileName

Synopsis: Extract the filename part from a full path filename.

Declaration: `function ExtractFileName(const FileName: UnicodeString) : UnicodeString`
`function ExtractFileName(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFileName` returns the filename part from `FileName`. The filename consists of all characters after the last directory separator character (`'/'` or `'\'`) or drive letter.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` (1516) and `ExtractFileName`.

For an example, see `ExtractFileDir` (1515).

Errors: None.

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

76.15.94 ExtractFilePath

Synopsis: Extract the path from a filename.

Declaration: `function ExtractFilePath(const FileName: UnicodeString) : UnicodeString`
`function ExtractFilePath(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `ExtractFilePath` returns the path part (including driveletter) from `FileName`. The path consists of all characters before the last directory separator character (`'/'` or `'\'`), including the directory separator itself. In case there is only a drive letter, that will be returned.

The full filename can always be reconstructed by concatenating the result of `ExtractFilePath` and `ExtractFileName` (1516).

For an example, see `ExtractFileDir` (1515).

Errors: None.

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516), `ExtractRelativePath` (1517)

76.15.95 ExtractRelativepath

Synopsis: Extract a relative path from a filename, given a base directory.

Declaration: `function ExtractRelativepath(const BaseName: UnicodeString;
const DestName: UnicodeString)
: UnicodeString
function ExtractRelativepath(const BaseName: RawByteString;
const DestName: RawByteString)
: RawByteString`

Visibility: default

Description: `ExtractRelativePath` constructs a relative path to go from `BaseName` to `DestName`. If `DestName` is on another drive (Not on Unix-like platforms) then the whole `Destname` is returned.

Note that directories must end on a path delimiter for this function to work correctly. If not, the last part is stripped and treated as a file name.

Errors: None.

See also: `ExtractFileName` (1516), `ExtractFilePath` (1516), `ExtractFileDir` (1515), `ExtractFileDrive` (1515), `ExtractFileExt` (1516)

Listing: `./sysutex/ex35.pp`

Program `Example35;`

{ This program demonstrates the ExtractRelativePath function }

Uses `sysutils;`

Procedure `Testit (FromDir, ToDir : String);`

begin

`Write ('From "', FromDir, '" to "', ToDir, '" via "');`

`WriteLn (ExtractRelativePath(FromDir, ToDir), '"');`

end;

Begin

`Testit ('/pp/src/compiler/', '/pp/bin/win32/ppc386/');`

`Testit ('/pp/bin/win32/ppc386/', '/pp/src/compiler/');`

`Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386/');`

`Testit ('/pp/bin/win32/', '/pp/src/compiler/ppcx386');`

`Testit ('e:/pp/bin/win32/ppc386/', 'd:/pp/src/compiler/');`

`Testit ('e:\pp\bin\win32\ppc386/', 'd:\pp\src\compiler/');`

`Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.2\');`

`Testit ('C:\FPC\3.0.2\ ', 'C:\FPC\3.0.4 rc1\');`

`Testit ('Q:\ ', 'Q:\FPC\3.0.4 rc1\');`

End.

76.15.96 ExtractShortPathName

Synopsis: Returns a 8.3 path name

Declaration: `function ExtractShortPathName(const FileName: UnicodeString)
: UnicodeString`

```
function ExtractShortPathName(const FileName: RawByteString)
    : RawByteString
```

Visibility: default

Description: `ExtractShortPathName` returns a 8.3 compliant filename that represents the same file as `FileName`. On platforms other than windows, this is `FileName` itself.

See also: `ExtractFilePath` (1516), `ExtractFileName` (1516)

76.15.97 FileAge

Synopsis: Return the timestamp of a file.

Declaration:

```
function FileAge(const FileName: UnicodeString) : LongInt
function FileAge(const FileName: UnicodeString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString;
    out FileDateTime: TDateTime; FollowLink: Boolean)
    : Boolean
function FileAge(const FileName: RawByteString) : LongInt
```

Visibility: default

Description: `FileAge` returns the last modification time of file `FileName`. The `FileDate` format can be transformed to `TDateTime` format with the `FileDateToDateTime` (1520) function.

Fileage cannot be used on directories, it will return -1 if `FileName` indicates a directory.

Errors: In case of errors, -1 is returned.

See also: `FileDateToDateTime` (1520), `FileExists` (1521), `FileGetAttr` (1521)

Listing: ./sysutex/ex36.pp

Program Example36;

{ This program demonstrates the FileAge function }

Uses sysutils;

Var S : TDateTime;
fa : Longint;

Begin

```
fa:=FileAge('ex36.pp');
If Fa<>-1 then
begin
S:=FileDateToDateTime(fa);
WriteLn('I'm from ',DateTimeToStr(S))
end;
```

End.

76.15.98 FileClose

Synopsis: Close a file handle.

Declaration: `procedure FileClose(Handle: THandle)`

Visibility: default

Description: `FileClose` closes the file handle `Handle`. After this call, attempting to read or write from the handle will result in an error.

For an example, see `FileCreate` (1519)

Errors: None.

See also: `FileCreate` (1519), `FileWrite` (1528), `FileOpen` (1523), `FileRead` (1524), `FileTruncate` (1528), `FileSeek` (1526)

76.15.99 FileCreate

Synopsis: Create a new file and return a handle to it.

Declaration:

```
function FileCreate(const FileName: UnicodeString) : THandle
function FileCreate(const FileName: UnicodeString; Rights: Integer)
    : THandle
function FileCreate(const FileName: UnicodeString; ShareMode: Integer;
    Rights: Integer) : THandle
function FileCreate(const FileName: RawByteString) : THandle
function FileCreate(const FileName: RawByteString; Rights: Integer)
    : THandle
function FileCreate(const FileName: RawByteString; ShareMode: Integer;
    Rights: Integer) : THandle
```

Visibility: default

Description: `FileCreate` creates a new file with name `FileName` on the disk and returns a file handle which can be used to read or write from the file with the `FileRead` (1524) and `FileWrite` (1528) functions.

If a file with name `FileName` already existed on the disk, it is overwritten.

The optional `Mode` parameter only has an effect under unix, where it can be used to set the mode (read, write, execute, sticky bit, setgid and setuid flags) of the created file to the specified custom value. On other platfors, the `Mode` parameter is ignored.

Errors: If an error occurs (e.g. disk full or non-existent path), the function returns `THandle(-1)`.

See also: `FileClose` (1518), `FileWrite` (1528), `FileOpen` (1523), `FileRead` (1524), `FileTruncate` (1528), `FileSeek` (1526)

Listing: `./sysutex/ex37.pp`

Program Example37;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses sysutils;

Var I,J,F : Longint;

Begin

```
F:= FileCreate ( 'test.dat' );
If F=-1 then
  Halt(1);
For I:=0 to 100 do
```

```

    FileWrite(F,I,SizeOf(i));
  FileClose(f);
  F:=FileOpen ('test.dat',fmOpenRead);
  For I:=0 to 100 do
    begin
      FileRead (F,J,SizeOf(J));
      If J<>I then
        Writeln ('Mismatch at file position ',I)
      end;
    FileSeek(F,0,fsFromBeginning);
    Randomize;
    Repeat
      FileSeek(F,Random(100)*4,fsFromBeginning);
      FileRead (F,J,SizeOf(J));
      Writeln ('Random read : ',j);
    Until J>80;
    FileClose(F);
    F:=FileOpen('test.dat',fmOpenWrite);
    I:=50*SizeOf(Longint);
    If FileTruncate(F,I) then
      Writeln('Successfully truncated file to ',I,' bytes.');
```

```

    FileClose(F);
  End.

```

76.15.100 FileDateToDateTime

Synopsis: Convert a `FileDate` value to a `TDateTime` value.

Declaration: `function FileDateToDateTime(Filedate: LongInt) : TDateTime`

Visibility: default

Description: `FileDateToDateTime` converts the date/time encoded in `filedate` to a `TDateTime` encoded form. It can be used to convert date/time values returned by the `FileAge` ([1518](#)) or `FindFirst` ([1529](#))/`FindNext` ([1530](#)) functions to `TDateTime` form.

Errors: None.

See also: `DateTimeToFileDate` ([1499](#))

Listing: `./sysutex/ex13.pp`

Program `Example13;`

```
{ This program demonstrates the FileDateToDateTime function }
```

Uses `sysutils;`

Var

```
  ThisAge : Longint;
```

Begin

```
  Write ('ex13.pp created on :');
```

```
  ThisAge:=FileAge('ex13.pp');
```

```
  Writeln (DateTimeToStr (FileDateToDateTime (ThisAge)));
```

```
End.
```

76.15.101 FileExists

Synopsis: Check whether a particular file exists in the filesystem.

Declaration: `function FileExists(const FileName: UnicodeString) : Boolean`
`function FileExists(const FileName: RawByteString) : Boolean`

Visibility: default

Description: `FileExists` returns `True` if a file with name `FileName` exists on the disk, `False` otherwise. On windows, this function will return `False` if a directory is passed as `FileName`. On unices, passing a directory name will result in `True`. The rationale is that on unix, a directory is a file as well.

Note that this function accepts a single filename as an argument, without wildcards. To check for the existence of multiple files, see the `FindFirst` (1529) function.

Errors: None.

See also: `FindFirst` (1529), `FileAge` (1518), `FileGetAttr` (1521), `FileSetAttr` (1527)

Listing: `./sysutex/ex38.pp`

Program `Example38;`

{ This program demonstrates the FileExists function }

Uses `sysutils;`

Begin

If `FileExists(ParamStr(0))` **Then**
 `Writeln('All is well, I seem to exist.');`

End.

76.15.102 FileFlush

Declaration: `function FileFlush(Handle: THandle) : Boolean`

Visibility: default

76.15.103 FileGetAttr

Synopsis: Return attributes of a file.

Declaration: `function FileGetAttr(const FileName: UnicodeString) : LongInt`
`function FileGetAttr(const FileName: RawByteString) : LongInt`

Visibility: default

Description: `FileGetAttr` returns the attribute settings of file `FileName`. The attribute is a OR-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On unix, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdVolume Label. Only for DOS/Windows on a plain FAT (not VFAT or Fat32) filesystem.

faDirectoryFile is a directory.

faArchivefile should be archived. Not possible on Unix

Errors: In case of error, -1 is returned.

See also: FileSetAttr ([1527](#)), FileAge ([1518](#)), FileGetDate ([1522](#))

Listing: ./sysutex/ex40.pp

Program Example40;

{ This program demonstrates the FileGetAttr function }

Uses sysutils;

Procedure Testit (**Name** : **String**);

Var F : Longint;

Begin

 F:= FileGetAttr(**Name**);

If F<>-1 **then**

begin

 WriteLn ('Testing : ',**Name**);

If (F **and** faReadOnly)<>0 **then**

 WriteLn ('File is ReadOnly');

If (F **and** faHidden)<>0 **then**

 WriteLn ('File is hidden');

If (F **and** faSysFile)<>0 **then**

 WriteLn ('File is a system file');

If (F **and** faVolumeID)<>0 **then**

 WriteLn ('File is a disk label');

If (F **and** faArchive)<>0 **then**

 WriteLn ('File is artchive file');

If (F **and** faDirectory)<>0 **then**

 WriteLn ('File is a directory');

end

else

 WriteLn ('Error reading attributes of ',**Name**);

end;

begin

 testit ('ex40.pp');

 testit (**ParamStr**(0));

 testit ('.');

 testit ('/');

End.

76.15.104 FileGetDate

Synopsis: Return the file time of an opened file.

Declaration: function FileGetDate(Handle: THandle) : LongInt

Visibility: default

fmOpenReadWrite Open file in read/write mode.

Under Windows and Unix, the above mode can be or-ed with one of the following sharing/locking flags:

fmShareCompat Open file in DOS share-compatibility mode

fmShareExclusive Lock file for exclusive use

fmShareDenyWrite Lock file so other processes can only read.

fmShareDenyRead Lock file so other processes cannot read.

fmShareDenyNone Do not lock file.

If the file has been successfully opened, it can be read from or written to (depending on the Mode parameter) with the `FileRead` (1524) and `FileWrite` functions.

Remark: Remark that you cannot open a file if it doesn't exist yet, i.e. it will not be created for you. If you want to create a new file, or overwrite an old one, use the `FileCreate` (1519) function.

There are some limitations to the sharing modes.

1. Sharing modes are only available on Unix and Windows platforms.
2. Unix only support sharing modes as of 2.4.0.
3. `fmShareDenyRead` only works under Windows at this time, and will always result in an error on Unix platforms because its file locking APIs do not support this concept.
4. File locking is advisory on Unix platforms. This means that the locks are only checked when a file is opened using a file locking mode. In other cases, existing locks are simply ignored. In particular, this means that `fmShareDenyNone` has no effect under Unix, because this can only be implemented as "use no locking" on those platforms. As a result, opening a file using this mode will always succeed under Unix as far as the locking is concerned, even if the file has already been opened using `fmShareExclusive`.
5. Under Solaris, closing a single file handle associated with a file will result in all locks on that file (even via other handles) being destroyed due to the behaviour of the underlying API (`fcntl`). Because of the same reason, on Solaris you cannot use `fmShareDenyWrite` in combination with `fmOpenWrite`, nor `fmShareExclusive` in combination with `fmOpenRead` although both work with `fmOpenReadWrite`.

For an example, see `FileCreate` (1519)

Errors: On Error, `THandle(-1)` is returned.

See also: `fmOpenRead` (1452), `fmOpenWrite` (1452), `fmOpenReadWrite` (1452), `fmShareDenyWrite` (1453), `fmShareExclusive` (1453), `fmShareDenyRead` (1453), `fmShareDenyNone` (1452), `fmShareCompat` (1452), `FileClose` (1518), `FileWrite` (1528), `FileCreate` (1519), `FileRead` (1524), `FileTruncate` (1528), `FileSeek` (1526)

76.15.107 FileRead

Synopsis: Read data from a filehandle in a buffer.

Declaration: `function FileRead(Handle: THandle; out Buffer; Count: LongInt) : LongInt`

Visibility: default

Description: `FileRead` reads `Count` bytes from file-handle `Handle` and stores them into `Buffer`. `Buffer` must be at least `Count` bytes long. No checking on this is performed, so be careful not to overwrite any memory. `Handle` must be the result of a `FileOpen` (1523) call.

The function returns the number of bytes actually read, or -1 on error.

For an example, see `FileCreate` (1519)

Errors: On error, -1 is returned.

See also: `FileClose` (1518), `FileWrite` (1528), `FileCreate` (1519), `FileOpen` (1523), `FileTruncate` (1528), `FileSeek` (1526)

76.15.108 FileSearch

Synopsis: Search for a file in a path.

Declaration:

```
function FileSearch(const Name: UnicodeString;
                   const DirList: UnicodeString;
                   Options: TFileSearchOptions) : UnicodeString
function FileSearch(const Name: UnicodeString;
                   const DirList: UnicodeString;
                   ImplicitCurrentDir: Boolean) : UnicodeString
function FileSearch(const Name: RawByteString;
                   const DirList: RawByteString;
                   Options: TFileSearchOptions) : RawByteString
function FileSearch(const Name: RawByteString;
                   const DirList: RawByteString;
                   ImplicitCurrentDir: Boolean) : RawByteString
```

Visibility: default

Description: `FileSearch` looks for the file `Name` in `DirList`, where `dirlist` is a list of directories, separated by semicolons or colons. It returns the full filename of the first match found. The optional `Options` parameter may be specified to influence the behaviour of the search algorithm. It is a set of the following options:

sfoImplicitCurrentDir Always search the current directory first, even if it is not specified.

sfoStripQuotes Strip quotes from the components in the search path.

A deprecated form of the function allowed to specify using the boolean `ImplicitCurrentDir` parameter whether the current directory was searched implicitly or not. By default, the current directory is searched.

Errors: On error, an empty string is returned.

See also: `ExpandFileName` (1513), `FindFirst` (1529)

Listing: `./sysutex/ex41.pp`

Program `Example41` ;

{ Program to demonstrate the FileSearch function. }

Uses `Sysutils` ;

Const
{ \$ifdef unix }

```

    FN = 'find';
    P = '.: / bin : / usr / bin';
  {$else}
    FN = 'find.exe';
    P = 'c:\dos;c:\windows;c:\windows\system;c:\windows\system32';
  {$endif}

begin
  WriteLn ('find is in : ', FileSearch (FN,P));
end.

```

76.15.109 FileSeek

Synopsis: Set the current file position on a file handle.

Declaration: `function FileSeek(Handle: THandle; FOffset: LongInt; Origin: LongInt) : LongInt`
`function FileSeek(Handle: THandle; FOffset: Int64; Origin: LongInt) : Int64`

Visibility: default

Description: `FileSeek` sets the file pointer on position `Offset`, starting from `Origin`. `Origin` can be one of the following values:

fsFromBeginning `Offset` is relative to the first byte of the file. This position is zero-based. i.e. the first byte is at offset 0.

fsFromCurrent `Offset` is relative to the current position.

fsFromEnd `Offset` is relative to the end of the file. This means that `Offset` can only be zero or negative in this case.

If successful, the function returns the new file position, relative to the beginning of the file.

Remark: The abovementioned constants do not exist in Delphi.

Errors: On error, -1 is returned.

See also: `FileClose` ([1518](#)), `FileWrite` ([1528](#)), `FileCreate` ([1519](#)), `FileOpen` ([1523](#)), `FileRead` ([1524](#)), `FileTruncate` ([1528](#))

Listing: `./sysutex/ex37.pp`

Program Example37;

{ This program demonstrates the FileCreate/FileSeek/FileReed/FileTruncate functions }

Uses sysutils;

Var I,J,F : Longint;

Begin

```

F:=FileCreate ('test.dat');
If F=-1 then
  Halt(1);
For I:=0 to 100 do
  FileWrite(F,I,SizeOf(i));
FileClose(f);

```

```

F:=FileOpen ('test.dat',fmOpenRead);
For I:=0 to 100 do
begin
  FileRead (F,J,SizeOf(J));
  If J<>I then
    Writeln ('Mismatch at file position ',I)
  end;
FileSeek (F,0,fsFromBeginning);
Randomize;
Repeat
  FileSeek (F,Random(100)*4,fsFromBeginning);
  FileRead (F,J,SizeOf(J));
  Writeln ('Random read : ',j);
Until J>80;
FileClose(F);
F:=FileOpen('test.dat',fmOpenWrite);
I:=50*SizeOf(LongInt);
If FileTruncate(F,I) then
  Writeln('Successfully truncated file to ',I,' bytes. ');
FileClose(F);
End.

```

76.15.110 FileSetAttr

Synopsis: Set the attributes of a file.

Declaration: `function FileSetAttr(const Filename: UnicodeString; Attr: LongInt) : LongInt`
`function FileSetAttr(const Filename: RawByteString; Attr: LongInt) : LongInt`

Visibility: default

Description: `FileSetAttr` sets the attributes of `FileName` to `Attr`. If the function was successful, 0 is returned, -1 otherwise. `Attr` can be set to an OR-ed combination of the pre-defined `faXXX` constants.

This function is not implemented on Unixes.

Errors: On error, -1 is returned (always on Unixes).

See also: `FileGetAttr` ([1521](#)), `FileGetDate` ([1522](#)), `FileSetDate` ([1527](#))

76.15.111 FileSetDate

Synopsis: Set the date of a file.

Declaration: `function FileSetDate(const FileName: UnicodeString; Age: LongInt) : LongInt`
`function FileSetDate(const FileName: RawByteString; Age: LongInt) : LongInt`
`function FileSetDate(Handle: THandle; Age: LongInt) : LongInt`

Visibility: default

Description: `FileSetDate` sets the file date of the open file with handle `Handle` or to `Age`, where `Age` is a DOS date-and-time stamp value.

Alternatively, the filename may be specified with the `FileName` argument. This variant of the call is mandatory on unices, since there is no OS support for setting a file timestamp based on a handle. (the handle may not be a real file at all).

The function returns zero if successful.

Errors: On Unix, the handle variant always returns -1, since this is impossible to implement. On Windows and DOS, a negative error code is returned.

76.15.112 FileTruncate

Synopsis: Truncate an open file to a given size.

Declaration: `function FileTruncate(Handle: THandle; Size: Int64) : Boolean`

Visibility: default

Description: `FileTruncate` truncates the file with handle `Handle` to `Size` bytes. The file must have been opened for writing prior to this call. The function returns `True` is successful, `False` otherwise.

For an example, see `FileCreate` (1519).

Errors: On error, the function returns `False`.

See also: `FileClose` (1518), `FileWrite` (1528), `FileCreate` (1519), `FileOpen` (1523), `FileRead` (1524), `FileSeek` (1526)

76.15.113 FileWrite

Synopsis: Write data from a buffer to a given filehandle.

Declaration: `function FileWrite(Handle: THandle; const Buffer; Count: LongInt)
: LongInt`

Visibility: default

Description: `FileWrite` writes `Count` bytes from `Buffer` to the file with handle `Handle`. Prior to this call, the file must have been opened for writing. `Buffer` must be at least `Count` bytes large, or a memory access error may occur.

The function returns the number of bytes written, or -1 in case of an error.

For an example, see `FileCreate` (1519).

Errors: In case of error, -1 is returned.

See also: `FileClose` (1518), `FileCreate` (1519), `FileOpen` (1523), `FileRead` (1524), `FileTruncate` (1528), `FileSeek` (1526)

76.15.114 FindClose

Synopsis: Close a find handle

Declaration: `procedure FindClose(var F: TUnicodeSearchRec)
procedure FindClose(var F: TRawbyteSearchRec)`

Visibility: default

Description: `FindClose` ends a series of `FindFirst` (1529)/`FindNext` (1530) calls, and frees any memory used by these calls. It is *absolutely* necessary to do this call, or huge memory losses may occur.

For an example, see `FindFirst` (1529).

Errors: None.

See also: `FindFirst` (1529), `FindNext` (1530)

76.15.115 FindCmdLineSwitch

Synopsis: Check whether a certain switch is present on the command-line.

Declaration:

```
function FindCmdLineSwitch(const Switch: string;
                           const Chars: TSysCharSet; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: string; IgnoreCase: Boolean)
                           : Boolean
function FindCmdLineSwitch(const Switch: string) : Boolean
```

Visibility: default

Description: `FindCmdLineSwitch` will check all command-line arguments for the presence of the option `Switch`. It will return `True` if it was found, `False` otherwise. Characters that appear in `Chars` (default is `SwitchChars` (1457)) are assumed to indicate an option (switch). If the parameter `IgnoreCase` is `True`, case will be ignored when looking for the switch. Default is to search case sensitive.

Errors: None.

See also: `SwitchChars` (1457)

76.15.116 FindFirst

Synopsis: Start a file search and return a findhandle

Declaration:

```
function FindFirst(const Path: UnicodeString; Attr: LongInt;
                  out Rslt: TUnicodeSearchRec) : LongInt
function FindFirst(const Path: RawByteString; Attr: LongInt;
                  out Rslt: TRawbyteSearchRec) : LongInt
```

Visibility: default

Description: `FindFirst` looks for files that match the name (possibly with wildcards) in `Path` and extra attributes `Attr`. It then fills up the `Rslt` record with data gathered about the file. It returns 0 if a file matching the specified criteria is found, a nonzero value (-1 on Unix-like platforms) otherwise.

`Attr` is an or-ed combination of the following constants:

faReadOnlyThe file is read-only.

faHiddenThe file is hidden. (On unix, this means that the filename starts with a dot)

faSysFileThe file is a system file (On unix, this means that the file is a character, block or FIFO file).

faVolumeIdDrive volume Label. Not possible under unix, and on Windows-like systems, this works only for plan FAT (not Fat32 or VFAT) filesystems.

faDirectoryFile is a directory.

faArchivefile needs to be archived. Not possible on Unix

It is a common misconception that `Attr` specifies a set of attributes which must be matched in order for a file to be included in the list. This is not so: The value of `Attr` specifies *additional* attributes, this means that the returned files are either normal files or have an attribute which is present in `Attr`.

Specifically: specifying `faDirectory` as a value for `Attr` does not mean that only directories will be returned. Normal files *and* directories will be returned.

The `Rslt` record can be fed to subsequent calls to `FindNext`, in order to find other files matching the specifications.

Remark: A successful `FindFirst` call must *always* be followed by a `FindClose` (1528) call with the same `Rslt` record. Failure to do so will result in memory leaks. If the `findfirst` call failed (i.e. returned a nonzero handle) there is no need to call `FindClose`.

Errors: On error the function returns -1 on Unix-like platforms, a nonzero error code on Windows.

See also: `FindClose` (1528), `FindNext` (1530)

Listing: ./sysutex/ex43.pp

Program Example43;

{ This program demonstrates the FindFirst function }

Uses SysUtils;

Var Info : TSearchRec;
Count : Longint;

Begin

```
Count:=0;
If FindFirst ( '*',faAnyFile and faDirectory ,Info)=0 then
  begin
    Repeat
      Inc(Count);
      With Info do
        begin
          If (Attr and faDirectory) = faDirectory then
            Write('Dir : ');
            Writeln (Name:40,Size:15);
          end;
        Until FindNext(info)<>0;
      end;
    FindClose(Info);
    Writeln ('Finished search. Found ',Count,' matches');
```

End.

76.15.117 FindNext

Synopsis: Find the next entry in a findhandle.

Declaration: function FindNext(var Rslt: TUnicodeSearchRec) : LongInt
function FindNext(var Rslt: TRawbyteSearchRec) : LongInt

Visibility: default

Description: `FindNext` finds a next occurrence of a search sequence initiated by `FindFirst`. If another record matching the criteria in `Rslt` is found, 0 is returned, a nonzero constant is returned otherwise.

Remark: The last `FindNext` call must *always* be followed by a `FindClose` call with the same `Rslt` record. Failure to do so will result in memory loss.

For an example, see `FindFirst` (1529)

Errors: On error (no more file is found), a nonzero constant is returned.

See also: `FindFirst` (1529), `FindClose` (1528)

76.15.118 FloattoCurr

Synopsis: Convert a float to a Currency value.

Declaration: `function FloattoCurr(const Value: Extended) : Currency`

Visibility: default

Description: `FloatToCurr` converts the `Value` floating point value to a Currency value. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` (1454) and `MaxCurrency` (1454)). If not, an `EConvertError` (1616) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1616) exception is raised.

See also: `EConvertError` (1616), `TryFloatToCurr` (1602), `MinCurrency` (1454), `MaxCurrency` (1454)

76.15.119 FloatToDateTime

Synopsis: Convert a float to a TDateTime value.

Declaration: `function FloatToDateTime(const Value: Extended) : TDateTime`

Visibility: default

Description: `FloatToDateTime` converts the `Value` floating point value to a TDateTime value. It checks whether `Value` is in the valid range of dates (determined by `MinDateTime` (1454) and `MaxDateTime` (1454)). If not, an `EConvertError` (1616) exception is raised.

Errors: If `Value` is out of range, an `EConvertError` (1616) exception is raised.

See also: `EConvertError` (1616), `MinDateTime` (1454), `MaxDateTime` (1454)

76.15.120 FloatToDecimal

Synopsis: Convert a float value to a TFloatRec value.

Declaration:

```
procedure FloatToDecimal(out Result: TFloatRec; const Value;
                        ValueType: TFloatValue; Precision: Integer;
                        Decimals: Integer)
procedure FloatToDecimal(out Result: TFloatRec; Value: Extended;
                        Precision: Integer; Decimals: Integer)
```

Visibility: default

Description: `FloatToDecimal` converts the float `Value` to a float description in the `Result.TFloatRec` (1463) format. It will store `Precision` digits in the `Digits` field, of which at most `Decimal` decimals.

Errors: None.

See also: `TFloatRec` (1463)

76.15.121 FloatToStr

Synopsis: Convert a float value to a string using a fixed format.

Declaration:

```
function FloatToStr(Value: Extended) : string
function FloatToStr(Value: Extended;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Double) : string
function FloatToStr(Value: Double;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Single) : string
function FloatToStr(Value: Single;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Currency) : string
function FloatToStr(Value: Currency;
                    const FormatSettings: TFormatSettings) : string
function FloatToStr(Value: Comp) : string
function FloatToStr(Value: Comp; const FormatSettings: TFormatSettings)
    : string
function FloatToStr(Value: Int64) : string
function FloatToStr(Value: Int64; const FormatSettings: TFormatSettings)
    : string
```

Visibility: default

Description: `FloatToStr` converts the floating point variable `Value` to a string representation. It will choose the shortest possible notation of the two following formats:

Fixed format will represent the string in fixed notation,

Decimal format will represent the string in scientific notation.

More information on these formats can be found in `FloatToStrF` ([1533](#)). `FloatToStr` is completely equivalent to the following call:

```
FloatToStrF(Value, ffGeneral, 15, 0);
```

Errors: None.

See also: `FloatToStrF` ([1533](#)), `FormatFloat` ([1546](#)), `StrToFloat` ([1589](#))

Listing: `./sysutex/ex67.pp`

Program Example67;

{ This program demonstrates the FloatToStr function }

Uses sysutils;

Procedure Testit (Value : Extended);

begin

WriteLn (Value, ' -> ', **FloatToStr**(Value));

WriteLn (-Value, ' -> ', **FloatToStr**(-Value));

end;

Begin

 Testit (0.0);

```

Testit (1.1);
Testit (1.1e-3);
Testit (1.1e-20);
Testit (1.1e-200);
Testit (1.1e+3);
Testit (1.1e+20);
Testit (1.1e+200);
End.

```

76.15.122 FloatToStrF

Synopsis: Convert a float value to a string using a given format.

Declaration:

```

function FloatToStrF(Value: Extended; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Extended; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Double; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Double; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Single; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Single; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Comp; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Comp; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Currency; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
    Precision: Integer; Digits: Integer) : string
function FloatToStrF(Value: Int64; format: TFloatFormat;
    Precision: Integer; Digits: Integer;
    const FormatSettings: TFormatSettings) : string

```

Visibility: default

Description: FloatToStrF converts the floating point number value to a string representation, according to the settings of the parameters Format, Precision and Digits.

The meaning of the Precision and Digits parameter depends on the Format parameter. The format is controlled mainly by the Format parameter. It can have one of the following values:

ffcurrencyMoney format. Value is converted to a string using the global variables CurrencyString, CurrencyFormat and NegCurrFormat. The Digits parameter specifies the number of digits following the decimal point and should be in the range -1 to 18. If Digits equals -1, CurrencyDecimals is assumed. The Precision parameter is ignored.

ffExponent Scientific format. Value is converted to a string using scientific notation: 1 digit before the decimal point, possibly preceded by a minus sign if Value is negative. The number of digits after the decimal point is controlled by Precision and must lie in the range 0 to 15.

ffFixed Fixed point format. Value is converted to a string using fixed point notation. The result is composed of all digits of the integer part of Value, preceded by a minus sign if Value is negative. Following the integer part is DecimalSeparator and then the fractional part of Value, rounded off to Digits numbers. If the number is too large then the result will be in scientific notation.

ffGeneral General number format. The argument is converted to a string using ffExponent or ffFixed format, depending on which one gives the shortest string. There will be no trailing zeroes. If Value is less than 0.00001 or if the number of decimals left of the decimal point is larger than Precision then scientific notation is used, and Digits is the minimum number of digits in the exponent. Otherwise Digits is ignored.

ffnumber Is the same as ffFixed, except that thousand separators are inserted in the resulting string.

Errors: None.

See also: FloatToStr ([1532](#)), FloatToText ([1535](#))

Listing: ./sysutex/ex68.pp

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
 ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');

Writeln (FloatToStrF(Value, FF, I, J));

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt : ', Fmt[ff], ') : ');

Writeln (FloatToStrF(-Value, FF, I, J));

end;

end;

Begin

 Testit (1.1);

 Testit (1.1E1);

 Testit (1.1E-1);

 Testit (1.1E5);

 Testit (1.1E-5);

 Testit (1.1E10);

 Testit (1.1E-10);

 Testit (1.1E15);

```

Testit (1.1E-15);
Testit (1.1E100);
Testit (1.1E-100);
End.

```

76.15.123 FloatToText

Synopsis: Return a string representation of a float, with a given format.

Declaration: `function FloatToText (Buffer: PChar; Value: Extended; format: TFloatFormat; Precision: Integer; Digits: Integer) : LongInt`
`function FloatToText (Buffer: PChar; Value: Extended; format: TFloatFormat; Precision: Integer; Digits: Integer; const FormatSettings: TFormatSettings) : LongInt`

Visibility: default

Description: `FloatToText` converts the floating point variable `Value` to a string representation and stores it in `Buffer`. The conversion is governed by `format`, `Precision` and `Digits`. more information on these parameters can be found in `FloatToStrF` ([1533](#)). `Buffer` should point to enough space to hold the result. No checking on this is performed.

The result is the number of characters that was copied in `Buffer`.

Errors: None.

See also: `FloatToStr` ([1532](#)), `FloatToStrF` ([1533](#))

Listing: `./sysutex/ex69.pp`

Program Example68;

{ This program demonstrates the FloatToStrF function }

Uses sysutils;

Const Fmt : **Array** [TFloatFormat] **of** **string**[10] =
 ('general', 'exponent', 'fixed', 'number', 'Currency');

Procedure Testit (Value : Extended);

Var I, J : longint;
 FF : TFloatFormat;
 S : ShortString;

begin

For I:=5 **to** 15 **do**

For J:=1 **to** 4 **do**

For FF:=ffgeneral **to** ffcurrency **do**

begin

Write (Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

 SetLength(S, **FloatToText** (@S[1], Value, FF, I, J));

Writeln (S);

Write (-Value, '(Prec: ', I:2, ', Dig: ', J, ', fmt: ', Fmt[ff], ') : ');

 SetLength(S, **FloatToText** (@S[1], -Value, FF, I, J));

Writeln (S);


```

        end;
end;

Begin
  Testit (1.1);
  Testit (1.1E1);
  Testit (1.1E-1);
  Testit (1.1E5);
  Testit (1.1E-5);
  Testit (1.1E10);
  Testit (1.1E-10);
  Testit (1.1E15);
  Testit (1.1E-15);
  Testit (1.1E100);
  Testit (1.1E-100);
End.

```

76.15.124 FloatToTextFmt

Synopsis: Convert a float value to a string using a given mask.

Declaration: `function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar; FormatSettings: TFormatSettings) : Integer`
`function FloatToTextFmt(Buffer: PChar; Value: Extended; format: PChar) : Integer`

Visibility: default

Description: `FloatToTextFmt` returns a textual representation of `Value` in the memory location pointed to by `Buffer`. it uses the formatting specification in `Format` to do this. The return value is the number of characters that were written in the buffer.

For a list of valid formatting characters, see `FormatFloat` ([1546](#))

Errors: No length checking is performed on the buffer. The buffer should point to enough memory to hold the complete string. If this is not the case, an access violation may occur.

See also: `FormatFloat` ([1546](#))

76.15.125 FmtStr

Synopsis: Format a string with given arguments.

Declaration: `procedure FmtStr(var Res: string; const Fmt: string; const args: Array of const)`
`procedure FmtStr(var Res: string; const Fmt: string; const args: Array of const; const FormatSettings: TFormatSettings)`

Visibility: default

Description: `FmtStr` calls `Format` ([1537](#)) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `Format` ([1537](#)).

Errors: In case of error, a `EConvertError` ([1616](#)) exception is raised.

See also: `Format` ([1537](#)), `FormatBuf` ([1544](#)), `EConvertError` ([1616](#))

Listing: ./sysutex/ex70.pp

Program Example70;

```
{ This program demonstrates the FmtStr function }
```

Uses sysutils;

Var S : AnsiString;

Begin

S:= '';

FmtStr (S, 'For some nice examples of fomattng see %s.', ['Format']);

WriteLn (S);

End.

76.15.126 ForceDirectories

Synopsis: Create a chain of directories

Declaration: function ForceDirectories(const Dir: RawByteString) : Boolean
function ForceDirectories(const Dir: UnicodeString) : Boolean

Visibility: default

Description: ForceDirectories tries to create any missing directories in Dir till the whole path in Dir exists. It returns True if Dir already existed or was created succesfully. If it failed to create any of the parts, False is returned.

76.15.127 Format

Synopsis: Format a string with given arguments.

Declaration: function Format(const Fmt: string; const Args: Array of const) : string
function Format(const Fmt: string; const Args: Array of const;
const FormatSettings: TFormatSettings) : string

Visibility: default

Description: Format replaces all placeholders in Fmt with the arguments passed in Args and returns the resulting string. A placeholder looks as follows:

```
'%' [[Index] ':' ] ['-'] [Width] ['.' Precision] ArgType
```

elements between single quotes must be typed as shown without the quotes, and elements between square brackets [] are optional. The meaning of the different elements are shown below:

'%' starts the placeholder. If you want to insert a literal % character, then you must insert two of them : %%.

Index ':' takes the Index-th element in the argument array as the element to insert. If index is omitted, then the zeroth argument is taken.

'-' tells Format to left-align the inserted text. The default behaviour is to right-align inserted text. This can only take effect if the Width element is also specified.

Widththe inserted string must have at least `Width` characters. If not, the inserted string will be padded with spaces. By default, the string is left-padded, resulting in a right-aligned string. This behaviour can be changed by the usage of the `'-'` character.

?' PrecisionIndicates the precision to be used when converting the argument. The exact meaning of this parameter depends on `ArgType`.

The `Index`, `Width` and `Precision` parameters can be replaced by `*`, in which case their value will be read from the next element in the `Args` array. This value must be an integer, or an `EConvert-Error` (1616) exception will be raised.

The argument type is determined from `ArgType`. It can have one of the following values (case insensitive):

DDecimal format. The next argument in the `Args` array should be an integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

EScientific format. The next argument in the `Args` array should be a Floating point value. The argument is converted to a decimal string using scientific notation, using `FloatToStrF` (1533), where the optional precision is used to specify the total number of decimals. (default a value of 15 is used). The exponent is formatted using maximally 3 digits.

In short, the `E` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffExponent, Precision, 3)
```

FFixed point format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string, using fixed notation (see `FloatToStrF` (1533)). `Precision` indicates the number of digits following the decimal point.

In short, the `F` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffFixed, fixed, 9999, Precision)
```

GGeneral number format. The next argument in the `Args` array should be a floating point value. The argument is converted to a decimal string using fixed point notation or scientific notation, depending on which gives the shortest result. `Precision` is used to determine the number of digits after the decimal point.

In short, the `G` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffGeneral, Precision, 3)
```

MCurrency format. the next argument in the `Args` array must be a floating point value. The argument is converted to a decimal string using currency notation. This means that fixed-point notation is used, but that the currency symbol is appended. If precision is specified, then then it overrides the `CurrencyDecimals` global variable used in the `FloatToStrF` (1533)

In short, the `M` specifier formats it's argument as follows:

```
FloatToStrF (Argument, ffCurrency, 9999, Precision)
```

NNumber format. This is the same as fixed point format, except that thousand separators are inserted in the resulting string.

PPointer format. The next argument in the `Args` array must be a pointer (typed or untyped). The pointer value is converted to a string of length 8, representing the hexadecimal value of the pointer.

SString format. The next argument in the `Args` array must be a string. The argument is simply copied to the result string. If `Precision` is specified, then only `Precision` characters are copied to the result string.

UUnsigned decimal format. The next argument in the `Args` array should be an unsigned integer. The argument is converted to a decimal string. If precision is specified, then the string will have at least `Precision` digits in it. If needed, the string is (left) padded with zeroes.

Xhexadecimal format. The next argument in the `Args` array must be an integer. The argument is converted to a hexadecimal string with just enough characters to contain the value of the integer. If `Precision` is specified then the resulting hexadecimal representation will have at least `Precision` characters in it (with a maximum value of 32).

Errors: In case of error, an `EConvertError` exception is raised. Possible errors are:

- 1.Errors in the format specifiers.
- 2.The next argument is not of the type needed by a specifier.
- 3.The number of arguments is not sufficient for all format specifiers.

See also: `FormatBuf` ([1544](#)), `EConvertError` ([1616](#))

Listing: `./sysutex/ex71.pp`

Program `example71`;

`{ $mode objfpc }`

`{ This program demonstrates the Format function }`

Uses `sysutils`;

Var `P` : `Pointer`;
 `fmt,S` : **string**;

`{ Expected output:`

```

    [%d] => [10]
    [%%] => [%]
    [%10d] => [          10]
    [%.4d] => [0010]
    [%10.4d] => [          0010]
    [%0:d] => [10]
    [%0:10d] => [          10]
    [%0:10.4d] => [          0010]
    [%0:-10d] => [10
    [%0:-10.4d] => [0010
    [%-*.d] => [00010]

```

`}`

Procedure `TestInteger`;

begin

Try

```

    Fmt:= '[%d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%%]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    fmt:= '[%.4d]'; S:= Format (fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10.4d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10.4d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10d]'; S:= Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10.4d]'; S:= Format (fmt,[10]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%-*.d]'; S:= Format (fmt,[4,5,10]); writeln (Fmt:12, ' => ',s);

```

except

```

    On E : Exception do
        begin
            WriteLn ( 'Exception caught : ', E.Message );
        end;
    end;
    writeLn ( 'Press enter' );
    readLn;
end;

{ Expected output:
    [%x] => [A]
    [%10x] => [          A]
    [%10.4x] => [          000A]
    [%0:x] => [A]
    [%0:10x] => [          A]
    [%0:10.4x] => [          000A]
    [%0:-10x] => [A          ]
    [%0:-10.4x] => [000A      ]
    [%-*.x] => [0000A]
}

Procedure TestHexadecimal;
begin
    try
        Fmt:= '%x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%10x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%10.4x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:10.4x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%0:-10.4x'; S:=Format (Fmt,[10]); writeln (Fmt:12, ' => ',s);
        Fmt:= '%-*.x'; S:=Format (Fmt,[4,5,10]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                WriteLn ( 'Exception caught : ', E.Message );
            end;
        end;
        writeLn ( 'Press enter' );
        readLn;
    end;

    { Expected output:
        [0x%p] => [0x0012D687]
        [0x%10p] => [0x  0012D687]
        [0x%10.4p] => [0x  0012D687]
        [0x%0:p] => [0x0012D687]
        [0x%0:10p] => [0x  0012D687]
        [0x%0:10.4p] => [0x  0012D687]
        [0x%0:-10p] => [0x0012D687 ]
        [0x%0:-10.4p] => [0x0012D687 ]
        [%-*.p] => [0012D687]
    }

Procedure TestPointer;
begin
    P:= Pointer(1234567);
    try
        Fmt:= '[0x%p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);

```

```

Fmt:= '[0x%10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:10.4p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10p]'; S:=Format (Fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[0x%0:-10.4p]'; S:=Format (fmt,[P]); writeln (Fmt:12, ' => ',s);
Fmt:= '[%-*.p]'; S:=Format (fmt,[4,5,P]); writeln (Fmt:12, ' => ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
end;
writeln ('Press enter');
readln;
end;

{ Expected output:
  [%s]=> [This is a string]
  [%0:s]=> [This is a string]
  [%0:18s]=> [ This is a string]
  [%0:-18s]=> [This is a string ]
  [%0:18.12s]=> [ This is a st]
  [%-*.s]=> [This is a st ]
}

Procedure TestString;
begin
  try
    Fmt:='[%s]'; S:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:s]'; s:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:18s]'; s:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:-18s]'; s:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%0:18.12s]'; s:=Format(fmt,['This is a string']); Writeln (fmt:12, '=> ',s);
    fmt:='[%-*.s]'; s:=Format(fmt,[18,12,'This is a string']); Writeln (fmt:12, '=> ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
  end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [1.2340000000000000E+000]
  [%10e] => [1.2340000000000000E+000]
  [%10.4e] => [1.234E+000]
  [%0:e] => [1.2340000000000000E+000]
  [%0:10e] => [1.2340000000000000E+000]
  [%0:10.4e] => [1.234E+000]
  [%0:-10e] => [1.2340000000000000E+000]
  [%0:-10.4e] => [1.234E+000]
  [%-*.e] => [1.2340E+000]
}

Procedure TestExponential;
begin

```

```

Try
  Fmt:= '[%e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%10e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%10.4e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%0:e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%0:10e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%0:-10e]'; S:=Format (Fmt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%0:-10.4e]'; S:=Format (fnt,[1.234]); writeln (Fmt:12, ' => ',s);
  Fmt:= '[%-*.e]'; S:=Format (fnt,[4,5,1.234]); writeln (Fmt:12, ' => ',s);
except
  On E : Exception do
    begin
      Writeln ('Exception caught : ',E.Message);
    end;
  end;
  writeln ('Press enter');
  readln;
end;

{ Expected output:
  [%e] => [-1.2340000000000000E+000]
  [%10e] => [-1.2340000000000000E+000]
  [%10.4e] => [-1.234E+000]
  [%0:e] => [-1.2340000000000000E+000]
  [%0:10e] => [-1.2340000000000000E+000]
  [%0:10.4e] => [-1.234E+000]
  [%0:-10e] => [-1.2340000000000000E+000]
  [%0:-10.4e] => [-1.234E+000]
  [%-*.e] => [-1.2340E+000]
}

Procedure TestNegativeExponential;
begin
  Try
    Fmt:= '[%e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%10.4e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10e]'; S:=Format (Fmt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%0:-10.4e]'; S:=Format (fnt,[-1.234]); writeln (Fmt:12, ' => ',s);
    Fmt:= '[%-*.e]'; S:=Format (fnt,[4,5,-1.234]); writeln (Fmt:12, ' => ',s);
  except
    On E : Exception do
      begin
        Writeln ('Exception caught : ',E.Message);
      end;
    end;
    writeln ('Press enter');
    readln;
  end;

{ Expected output:
  [%e] => [1.2340000000000000E-002]
  [%10e] => [1.2340000000000000E-002]
  [%10.4e] => [1.234E-002]
  [%0:e] => [1.2340000000000000E-002]

```

```

    [%0:10e] => [1.2340000000000000E-002]
    [%0:10.4e] => [1.234E-002]
    [%0:-10e] => [1.2300000000000000E-002]
    [%0:-10.4e] => [1.234E-002]
    [%-*.e] => [1.2340E-002]
}
Procedure TestSmallExponential;
begin
    Try
        Fmt:= '[%e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10e]'; S:=Format (Fmt,[0.0123]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10.4e]'; S:=Format (fmt,[0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.e]'; S:=Format (fmt,[4,5,0.01234]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                WriteLn ('Exception caught : ',E.Message);
            end;
    end;
    writeln ('Press enter');
    readln;
end;

{ Expected output:
    [%e] => [-1.2340000000000000E-002]
    [%10e] => [-1.2340000000000000E-002]
    [%10.4e] => [-1.234E-002]
    [%0:e] => [-1.2340000000000000E-002]
    [%0:10e] => [-1.2340000000000000E-002]
    [%0:10.4e] => [-1.234E-002]
    [%0:-10e] => [-1.2340000000000000E-002]
    [%0:-10.4e] => [-1.234E-002]
    [%-*.e] => [-1.2340E-002]
}
Procedure TestSmallNegExponential;
begin
    Try
        Fmt:= '[%e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%10.4e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:10.4e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10e]'; S:=Format (Fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%0:-10.4e]'; S:=Format (fmt,[-0.01234]); writeln (Fmt:12, ' => ',s);
        Fmt:= '[%-*.e]'; S:=Format (fmt,[4,5,-0.01234]); writeln (Fmt:12, ' => ',s);
    except
        On E : Exception do
            begin
                WriteLn ('Exception caught : ',E.Message);
            end;
    end;
    writeln ('Press enter');

```

```

    readln;
end;

begin
    TestInteger;
    TestHexadecimal;
    TestPointer;
    teststring;
    TestExponential;
    TestNegativeExponential;
    TestSmallExponential;
    TestSmallNegExponential;
end.

```

76.15.128 FormatBuf

Synopsis: Format a string with given arguments and store the result in a buffer.

Declaration: `function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt; fmtLen: Cardinal; const Args: Array of const) : Cardinal`

```

function FormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
    fmtLen: Cardinal; const Args: Array of const;
    const FormatSettings: TFormatSettings) : Cardinal

```

Visibility: default

Description: `FormatBuf` calls `Format` ([1537](#)) and stores the result in `Buf`.

See also: `Format` ([1537](#))

Listing: `./sysutex/ex72.pp`

Program Example72;

{ This program demonstrates the FormatBuf function }

Uses sysutils;

Var

S : ShortString;

Const

Fmt : ShortString = 'For some nice examples of fomatting see %s.';

Begin

S:= '';

SetLength(S, **FormatBuf** (S[1], 255, Fmt[1], **Length**(Fmt), ['Format']));

Writeln (S);

End.

76.15.129 FormatCurr

Synopsis: Format a currency

Declaration: `function FormatCurr(const Format: string; Value: Currency) : string`
`function FormatCurr(const Format: string; Value: Currency;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `FormatCurr` formats the currency `Value` according to the formatting rule in the `Format` parameter, and returns the resulting string.

For an explanation of the formatting characters usable in the `Format` parameter, see `FormatFloat` (1546).

See also: `FormatFloat` (1546), `FloatToText` (1535)

76.15.130 FormatDateTime

Synopsis: Return a string representation of a `TDateTime` value with a given format.

Declaration: `function FormatDateTime(const FormatStr: string; DateTime: TDateTime;`
`Options: TFormatDateTimeOptions) : string`
`function FormatDateTime(const FormatStr: string; DateTime: TDateTime;`
`const FormatSettings: TFormatSettings;`
`Options: TFormatDateTimeOptions) : string`

Visibility: default

Description: `FormatDateTime` formats the date and time encoded in `DateTime` according to the formatting given in `FormatStr`. The complete list of formatting characters can be found in `formatchars` (1448).

Errors: On error (such as an invalid character in the formatting string), and `EConvertError` (1616) exception is raised.

See also: `DateTimeToStr` (1500), `DateToStr` (1502), `TimeToStr` (1599), `StrToDateTime` (1587), `EConvertError` (1616)

Listing: `./sysutex/ex14.pp`

Program Example14;

{ This program demonstrates the FormatDateTime function }

Uses sysutils;

Var ThisMoment : TDateTime;

Begin

 ThisMoment:=Now;

WriteLn ('Now : ', **FormatDateTime**('hh:nn ', ThisMoment));

WriteLn ('Now : ', **FormatDateTime**('DD MM YYYY', ThisMoment));

WriteLn ('Now : ', **FormatDateTime**('c', ThisMoment));

End.

76.15.131 FormatFloat

Synopsis: Format a float according to a certain mask.

Declaration: `function FormatFloat(const Format: string; Value: Extended) : string`
`function FormatFloat(const Format: string; Value: Extended;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `FormatFloat` formats the floating-point value given by `Value` using the format specifications in `Format`. The format specifier can give format specifications for positive, negative or zero values (separated by a semicolon).

If the format specifier is empty or the value needs more than 18 digits to be correctly represented, the result is formatted with a call to `FloatToStrF` (1533) with the `ffGeneral` format option.

The following format specifiers are supported:

0 is a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the 0. If not, the 0 is left as-is.

is also a digit place holder. If there is a corresponding digit in the value being formatted, then it replaces the #. If not, it is removed. by a space.

. determines the location of the decimal point. Only the first '.' character is taken into account. If the value contains digits after the decimal point, then it is replaced by the value of the `DecimalSeparator` character.

, determines the use of the thousand separator character in the output string. If the format string contains one or more ',' characters, then thousand separators will be used. The `ThousandSeparator` character is used.

E+ determines the use of scientific notation. If 'E+' or 'E-' (or their lowercase counterparts) are present then scientific notation is used. The number of digits in the output string is determined by the number of 0 characters after the 'E+'.

; This character separates sections for positive, negative, and zero numbers in the format string.

Errors: If an error occurs, an exception is raised.

See also: `FloatToStr` (1532)

Listing: `./sysutex/ex89.pp`

Program `Example89`;

{ This program demonstrates the FormatFloat function }

Uses `sysutils`;

Const

```
NrFormat=9;
FormatStrings : Array[1..NrFormat] of string = (
    '',
    '0',
    '0.00',
    '#.##',
    '###0.00',
    '###0.00;(#,##0.00)',
    '###0.00;;Zero',
    '0.000E+00',
    '#####E-0');
```

```

NrValue = 5;
FormatValues : Array[1..NrValue] of Double =
  (1234, -1234, 0.5, 0, -0.5);

Width = 12;
FWidth = 20;

Var
  I, J : Integer;
  S : String;

begin
  Write( 'Format' : FWidth);
  For I:=1 to NrValue do
    Write(FormatValues[I] : Width : 2);
  WriteLn;
  For I:=1 to NrFormat do
    begin
      Write(FormatStrings[I] : FWidth);
      For J:=1 to NrValue do
        begin
          S:=FormatFloat(FormatStrings[I], FormatValues[J]);
          Write(S : Width);
        end;
      WriteLn;
    end;
End.

```

76.15.132 FreeAndNil

Synopsis: Free object if needed, and set object reference to Nil

Declaration: `procedure FreeAndNil(var obj)`

Visibility: default

Description: `FreeAndNil` will free the object in `Obj` and will set the reference in `Obj` to `Nil`. The reference is set to `Nil` first, so if an exception occurs in the destructor of the object, the reference will be `Nil` anyway.

Errors: Exceptions that occur during the destruction of `Obj` are not caught.

76.15.133 FreeMemAndNil

Synopsis: Free the heap memory pointed to by a pointer and set pointer to nil.

Declaration: `procedure FreeMemAndNil(var p)`

Visibility: default

Description: `FreeMemAndNil` will free the memory pointed to by `P` and will set `P` to `Nil`. Note that this function is not type safe; the programmer is responsible for ensuring that this function is called with a correct pointer parameter. Failure to do so may result in run-time errors.

See also: `FreeAndNil` ([1547](#))

76.15.134 GetAppConfigDir

Synopsis: Return the appropriate directory for the application's configuration files.

Declaration: `function GetAppConfigDir(Global: Boolean) : string`

Visibility: default

Description: `GetAppConfigDir` returns the name of a directory in which the application should store its configuration files on the current OS. If the parameter `Global` is `True` then the directory returned is a global directory, i.e. valid for all users on the system. If the parameter `Global` is false, then the directory is specific for the user who is executing the program. On systems that do not support multi-user environments, these two directories may be the same.

The directory which is returned is the name of the directory where the application is supposed to store files. This does not mean that the directory exists, or that the user can write in this directory (especially if `Global=True`). It just returns the name of the appropriate location. Also note that the returned name always contains an ending path delimiter.

On systems where the operating system provides a call to determine this location, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1489) call, but can be configured by means of the `OnGetApplicationName` (1471) callback.

If `VendorName` (1610) is not-empty, then `VendorName` will also be inserted before the application-specific directory.

Errors: None.

See also: `GetAppConfigFile` (1548), `ApplicationName` (1489), `OnGetApplicationName` (1471), `CreateDir` (1497), `SysConfigDir` (1457), `VendorName` (1610)

76.15.135 GetAppConfigFile

Synopsis: Return an appropriate name for an application configuration file.

Declaration: `function GetAppConfigFile(Global: Boolean) : string`

`function GetAppConfigFile(Global: Boolean; SubDir: Boolean) : string`

Visibility: default

Description: `GetAppConfigFile` returns the name of a file in which the application can store its configuration parameters. The exact name and location of the file depends on the customs of the operating system.

The `Global` parameter determines whether it is a global configuration file (value `True`) or a personal configuration file (value `False`).

The parameter `SubDir`, in case it is set to `True`, will insert the name of a directory before the filename. This can be used in case the application needs to store other data than configuration data in an application-specific directory. Default behaviour is to set this to `False`.

Note that on Windows, even when `Subdir` is `False`, a subdirectory is created for the application configuration files, as per the windows specifications. Specifying `true` will create a subdirectory of the application settings subdirectory.

The default file extension of the returned file is: `.cfg`

No assumptions should be made about the existence or writeability of this file, or the directory where the file should reside. It is best to call `ForceDirectories` (1537) prior to opening a file with the resulting filename.

On systems where the operating system provides a call to determine the location of configuration files, this call will be used. On systems where there is no such call, an algorithm is used which reflects common practice on that system.

The application name is deduced from the binary name via the `ApplicationName` (1489) call, but can be configured by means of the `OnGetApplicationName` (1471) callback.

If `VendorName` (1610) is not-empty, then `VendorName` will be inserted in the path for the config file directory.

Errors: None.

See also: `GetAppConfigDir` (1548), `OnGetApplicationName` (1471), `ApplicationName` (1489), `CreateDir` (1497), `ConfigExtension` (1450), `SysConfigDir` (1457), `VendorName` (1610)

76.15.136 GetCurrentDir

Synopsis: Return the current working directory of the application.

Declaration: `function GetCurrentDir : AnsiString`

Visibility: default

Description: `GetCurrentDir` returns the current working directory.

Errors: None.

See also: `SetCurrentDir` (1568), `DiskFree` (1506), `DiskSize` (1506)

Listing: `./sysutex/ex28.pp`

Program `Example28`;

{ This program demonstrates the GetCurrentDir function }

Uses `sysutils`;

Begin

`WriteLn ('Current Directory is : ',GetCurrentDir);`

End.

76.15.137 GetDirs

Synopsis: Return a list of directory names from a path.

Declaration: `function GetDirs(var DirName: UnicodeString;
 var Dirs: Array of PWideChar) : LongInt
function GetDirs(var DirName: RawByteString;
 var Dirs: Array of PAnsiChar) : LongInt`

Visibility: default

Description: `GetDirs` splits `DirName` in a null-byte separated list of directory names, `Dirs` is an array of `PChars`, pointing to these directory names. The function returns the number of directories found, or -1 if none were found. `DirName` must contain only `OSDirSeparator` as Directory separator chars.

Errors: None.

See also: `ExtractRelativePath` (1517)

Listing: ./sysutex/ex45.pp

Program Example45;

```
{ This program demonstrates the GetDirs function }
{$H+}
```

Uses sysutils;

```
Var Dirs : Array[0..127] of pchar;
    I,Count : longint;
    Dir,NewDir : String;
```

Begin

```
Dir:=GetCurrentDir;
WriteLn ('Dir : ',Dir);
NewDir:='';
count:=GetDirs(Dir,Dirs);
For I:=0 to Count-1 do
    begin
        NewDir:=NewDir+' / '+StrPas( Dirs[I]);
        WriteLn (NewDir);
    end;
```

End.

76.15.138 GetDriveIDFromLetter

Synopsis: Return the drive ID based on a drive letter

Declaration: function GetDriveIDFromLetter(const ADrive: RawByteString) : Byte
function GetDriveIDFromLetter(const ADrive: UnicodeString) : Byte

Visibility: default

Description: GetDriveIDFromLetter returns the drive ID based on a drive letter. The drive ID can then be used in the DiskSize (1506) and DiskFree (1506) calls.

See also: DiskSize (1506), DiskFree (1506)

76.15.139 GetEnvironmentString

Synopsis: Return an environment variable by index.

Declaration: function GetEnvironmentString(Index: Integer) : AnsiString

Visibility: default

Description: GetEnvironmentString returns the Index-th environment variable. The index is 1 based, and is bounded from above by the result of GetEnvironmentVariableCount (1551).

For an example, GetEnvironmentVariableCount (1551).

Remark: Note that on Windows, environment strings can start with an equal sign (=). This is a trick used to pass the current working directory to a newly created proces. In this case, extracting the variable name as the characters before the first equal sign will result in an empty name.

Errors: If there is no environment, an empty string is returned.

See also: GetEnvironmentVariable (1551), GetEnvironmentVariableCount (1551)

76.15.140 GetEnvironmentVariable

Synopsis: Return the value of an environment variable.

Declaration: `function GetEnvironmentVariable(const EnvVar: AnsiString) : AnsiString`
`function GetEnvironmentVariable(const EnvVar: UnicodeString)`
`: UnicodeString`

Visibility: default

Description: `GetEnvironmentVariable` returns the value of the `EnvVar` environment variable. If the specified variable does not exist or `EnvVar` is empty, an empty string is returned.

See also: `GetEnvironmentString` ([1550](#)), `GetEnvironmentVariableCount` ([1551](#))

76.15.141 GetEnvironmentVariableCount

Synopsis: Return the number of variables in the environment.

Declaration: `function GetEnvironmentVariableCount : Integer`

Visibility: default

Description: `GetEnvironmentVariableCount` returns the number of variables in the environment. The number is 1 based, but the result may be zero if there are no environment variables.

Errors: If there is no environment, -1 may be returned.

See also: `GetEnvironmentString` ([1550](#)), `GetEnvironmentVariable` ([1551](#))

Listing: `./sysutex/ex92.pp`

```
{ $h+ }
program example92;

{ This program demonstrates the
  GetEnvironmentVariableCount function }

uses sysutils;

Var
  I : Integer;

begin
  For I:=1 to GetEnvironmentVariableCount do
    Writeln(i:3, ' : ', GetEnvironmentString(i));
end.
```

76.15.142 GetFileHandle

Synopsis: Extract OS handle from an untyped file or text file.

Declaration: `function GetFileHandle(var f: File) : THandle`
`function GetFileHandle(var f: Text) : THandle`

Visibility: default

Description: `GetFileHandle` returns the operating system handle for the file descriptor `F`. It can be used in various file operations which are not directly supported by the pascal language.

76.15.143 GetLastError

Synopsis: Return the last code from the OS.

Declaration: `function GetLastError : Integer`

Visibility: default

Description: `GetLastError` returns the error code from the last operating system call. It does not reset this code. In general, it should be called when an operating system call reported an error condition. In that case, `GetLastError` gives extended information about the error.

No assumptions should be made about the resetting of the error code by subsequent OS calls. This may be platform dependent.

See also: `RaiseLastError` ([1565](#))

76.15.144 GetLocalTime

Synopsis: Get the local time.

Declaration: `procedure GetLocalTime(var SystemTime: TSystemTime)`

Visibility: default

Description: `GetLocalTime` returns the system time in a `TSystemTime` ([1467](#)) format.

Errors: None.

See also: `Now` ([1564](#)), `Date` ([1499](#)), `Time` ([1597](#)), `TSystemTime` ([1467](#))

76.15.145 GetLocalTimeOffset

Synopsis: Return local timezone offset

Declaration: `function GetLocalTimeOffset : Integer`

Visibility: default

Description: `GetLocalTimeOffset` returns the local timezone offset in minutes. This is the difference between UTC time and local time:

`UTC = LocalTime + GetLocalTimeOffset`

Note that on Linux/Unix, this information may be inaccurate around the DST time changes (for optimization). In that case, the `unix.ReReadLocalTime` ([1870](#)) unit must be used to re-initialize the timezone information.

See also: `unix.ReReadLocalTime` ([1870](#)), `Date` ([1499](#)), `Time` ([1597](#)), `Now` ([1564](#))

76.15.146 GetModuleName

Synopsis: Return the name of the current module

Declaration: `function GetModuleName(Module: HMODULE) : string`

Visibility: default

Description: `GetModuleName` returns the name of the current module. On windows, this is the name of the executable when executed in an executable, or the name of the library when executed in a library.

On all other platforms, the result is always empty, since they provide no such functionality.

76.15.147 GetTempDir

Synopsis: Return name of system's temporary directory

```
Declaration: function GetTempDir(Global: Boolean) : string
              function GetTempDir : string
```

Visibility: default

Description: `GetTempDir` returns the temporary directory of the system. If `Global` is `True` (the default value) it returns the system temporary directory, if it is `False` then a directory private to the user is returned. The returned name will end with a directory delimiter character.

These directories may be the same. No guarantee is made that this directory exists or is writeable by the user.

The `OnGetTempDir` (1472) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: [OnGetTempDir \(1472\)](#), [GetTempFileName \(1553\)](#)

76.15.148 GetTempFileName

Synopsis: Return the name of a temporary file.

```
Declaration: function GetTempFileName(const Dir: string; const Prefix: string)
           : string
function GetTempFileName : string
function GetTempFileName(Dir: PChar; Prefix: PChar; uUnique: DWord;
           TempFileName: PChar) : DWord
```

Visibility: default

Description: `GetTempFileName` returns the name of a temporary file in directory `Dir`. The name of the file starts with `Prefix`.

If `Dir` is empty, the value returned by `GetTempDir` is used, and if `Prefix` is empty, 'TMP' is used.

The OnGetTempFile (1472) handler may be set to provide custom handling of this routine: One could implement callbacks which take into consideration frameworks like KDE or GNOME, and return a different value from the default system implementation.

Errors: On error, an empty string is returned.

See also: [GetTempDir \(1553\)](#), [OnGetTempFile \(1472\)](#)

76.15.149 GetTickCount

Synopsis: Get tick count (32-bit, deprecated)

```
Declaration: function GetTickCount : LongWord
```

Visibility: default

Description: `GetTickCount` returns an increasing clock tick count. It is useful for time measurements, but no assumptions should be made as to the interval between the ticks. This function is provided for Delphi compatibility, use `GetTickCount64` (1554) instead.

See also: [GetTickCount64 \(1554\)](#), [Now \(1564\)](#), [Time \(1597\)](#), [Sleep \(1569\)](#)

76.15.150 GetTickCount64

Synopsis: Get tick count (64-bit)

Declaration: `function GetTickCount64 : QWord`

Visibility: default

Description: `GetTickCount64` returns an increasing clock tick count. It is useful for time measurements, but no assumptions should be made as to the interval between the ticks.

See also: [Now \(1564\)](#), [Time \(1597\)](#), [Sleep \(1569\)](#)

76.15.151 GetUserDir

Synopsis: Returns the current user's home directory.

Declaration: `function GetUserDir : string`

Visibility: default

Description: `GetUserDir` returns the home directory of the current user. On Unix-like systems (that includes Mac OS X), this is the value of the HOME environment variable. On Windows, this is the PROFILE special folder. On all other platforms, the application installation directory is returned.

If non-empty, it contains a trailing path delimiter.

See also: [GetAppConfigDir \(1548\)](#)

76.15.152 GuidCase

Synopsis: Return the index of a GUID in an array of GUID values

Declaration: `function GuidCase(const GUID: TGuid; const List: Array of TGuid)
: Integer`

Visibility: default

Description: `GuidCase` returns the index of GUID in the array `List`, where 0 denotes the first element in the list. If GUID is not present in the list, -1 is returned.

See also: [IsEqualGUID \(1559\)](#)

76.15.153 GUIDToString

Synopsis: Convert a TGUID to a string representation.

Declaration: `function GUIDToString(const GUID: TGuid) : string`

Visibility: default

Description: `GUIDToString` converts the GUID identifier in GUID to a string representation in the form

`{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}`

Where each X is a hexadecimal digit.

Errors: None.

See also: [Supports \(1594\)](#), [#rtl.system.TGUID \(1242\)](#), [StringToGUID \(1577\)](#), [IsEqualGuid \(1559\)](#)

76.15.154 HashName

Synopsis: Calculate a hash from a null-terminated string

Declaration: `function HashName(Name: PAnsiChar) : LongWord`

Visibility: default

Description: `HashName` calculates a hash value from a null terminated string. The hash value is calculated in such a way that it returns the same value for strings that only differ in case.

76.15.155 HookSignal

Synopsis: Hook a specified signal

Declaration: `procedure HookSignal(RtlSigNum: Integer)`

Visibility: default

Description: `HookSignal` installs the RTL default signal handler for signal `RtlSigNum`. It does not check whether the signal is already handled, and should therefor only be called if `InquireSignal` returns `ssNotHooked`.

76.15.156 IncAMonth

Synopsis: Increase a date with a certain amount of months

Declaration: `procedure IncAMonth(var Year: Word; var Month: Word; var Day: Word; NumberOfMonths: Integer)`

Visibility: default

Description: `IncAMonth` increases the date as specified by `Year`, `Month`, `Day` with `NumberOfMonths`. It takes care of the number of days in a month when calculating the result.

This function does the same as `IncMonth` ([1556](#)), but operates on an already decoded date.

See also: `IncMonth` ([1556](#))

76.15.157 IncludeLeadingPathDelimiter

Synopsis: Prepend a path delimiter if there is not already one.

Declaration: `function IncludeLeadingPathDelimiter(const Path: UnicodeString) : UnicodeString`
`function IncludeLeadingPathDelimiter(const Path: RawByteString) : RawByteString`

Visibility: default

Description: `IncludeLeadingPathDelimiter` will insert a path delimiter (`#rtl.system.DirectorySeparator` ([1194](#))) in the first position of `Path`, if there is not already a directory separator at that position. It will return the resulting string. If the path is empty, a `DirectorySeparator` character is returned.

See also: `IncludeTrailingPathDelimiter` ([1556](#)), `ExcludeLeadingPathDelimiter` ([1511](#)), `ExcludeTrailingPathDelimiter` ([1511](#)), `ConcatPaths` ([1496](#))

Listing: ./sysutex/ex94.pp

Program Example94;

{ This program demonstrates the IncludeLeadingPathDelimiter function }

Uses sysutils;

Begin

End.

76.15.158 IncludeTrailingBackslash

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration:

```
function IncludeTrailingBackslash(const Path: UnicodeString)
    : UnicodeString
function IncludeTrailingBackslash(const Path: RawByteString)
    : RawByteString
```

Visibility: default

Description: IncludeTrailingBackslash is provided for backwards compatibility with Delphi. Use IncludeTrailingPathDelimiter (1556) instead.

See also: IncludeTrailingPathDelimiter (1556), ExcludeTrailingPathDelimiter (1511), PathDelim (1455), IsPathDelimiter (1560)

76.15.159 IncludeTrailingPathDelimiter

Synopsis: Add trailing directory separator to a pathname, if needed.

Declaration:

```
function IncludeTrailingPathDelimiter(const Path: UnicodeString)
    : UnicodeString
function IncludeTrailingPathDelimiter(const Path: RawByteString)
    : RawByteString
```

Visibility: default

Description: IncludeTrailingPathDelimiter adds a trailing path delimiter character (PathDelim (1455)) to Path if none is present yet, and returns the result.

If Path is empty, a path delimiter is returned, for Delphi compatibility.

See also: IncludeTrailingBackslash (1556), ExcludeTrailingPathDelimiter (1511), PathDelim (1455), IsPathDelimiter (1560)

76.15.160 IncMonth

Synopsis: Increases the month in a TDateTime value with a given amount.

Declaration:

```
function IncMonth(const DateTime: TDateTime; NumberOfMonths: Integer)
    : TDateTime
```

Visibility: default

Description: `IncMonth` increases the month number in `DateTime` with `NumberOfMonths`. It wraps the result as to get a month between 1 and 12, and updates the year accordingly. `NumberOfMonths` can be negative, and can be larger than 12 (in absolute value).

Errors: None.

See also: `Date` ([1499](#)), `Time` ([1597](#)), `Now` ([1564](#))

Listing: `./sysutex/ex15.pp`

Program `Example15`;

{ This program demonstrates the IncMonth function }

Uses `sysutils`;

Var `ThisDay` : `TDateTime`;

Begin

```

ThisDay := Date;
Writeln ('ThisDay : ', DateToStr(ThisDay));
Writeln ('6 months ago : ', DateToStr(IncMonth(ThisDay, -6)));
Writeln ('6 months from now : ', DateToStr(IncMonth(ThisDay, 6)));
Writeln ('12 months ago : ', DateToStr(IncMonth(ThisDay, -12)));
Writeln ('12 months from now : ', DateToStr(IncMonth(ThisDay, 12)));
Writeln ('18 months ago : ', DateToStr(IncMonth(ThisDay, -18)));
Writeln ('18 months from now : ', DateToStr(IncMonth(ThisDay, 18)));
End.
```

76.15.161 InquireSignal

Synopsis: Check whether a signal handler is set (unix only)

Declaration: `function InquireSignal(RtlSigNum: Integer) : TSignalState`

Visibility: `default`

Description: `RtlSigNum` will check whether the signal `RtlSigNum` is being handled, and by whom. It returns a `TSignalState` result to report the state of the signal, which can be one of the following values:

ssNotHooked No signal handler is set for the signal.

ssHooked A signal handler is set by the RTL code for the signal.

ssOverridden A signal handler was set for the signal by third-party code.

This routine works by resetting the signal handlers, so it is risky to call.

76.15.162 IntToHex

Synopsis: Convert an integer value to a hexadecimal string.

Declaration: `function IntToHex(Value: LongInt; Digits: Integer) : string`
`function IntToHex(Value: Int64; Digits: Integer) : string`
`function IntToHex(Value: QWord; Digits: Integer) : string`

Visibility: `default`

Description: `IntToHex` converts `Value` to a hexadecimal string representation. The result will contain at least `Digits` characters. If `Digits` is less than the needed number of characters, the string will NOT be truncated. If `Digits` is larger than the needed number of characters, the result is padded with zeroes.

Errors: None.

See also: `IntToStr` ([1558](#))

Listing: `./sysutex/ex73.pp`

Program `Example73`;

{ This program demonstrates the IntToHex function }

Uses `sysutils`;

Var `I` : `longint`;

Begin

For `I:=0 to 31 do`

begin

WriteLn (`IntToHex(1 shl I,8)`);

WriteLn (`IntToHex(15 shl I,8)`)

end;

End.

76.15.163 IntToStr

Synopsis: Convert an integer value to a decimal string.

Declaration: `function IntToStr(Value: LongInt) : string`
 `function IntToStr(Value: Int64) : string`
 `function IntToStr(Value: QWord) : string`

Visibility: `default`

Description: `IntToStr` converts `Value` to its string representation. The resulting string has only as much characters as needed to represent the value. If the value is negative a minus sign is prepended to the string.

Errors: None.

See also: `IntToHex` ([1557](#)), `StrToInt` ([1590](#))

Listing: `./sysutex/ex74.pp`

Program `Example74`;

{ This program demonstrates the IntToStr function }

Uses `sysutils`;

Var `I` : `longint`;

Begin

For `I:=0 to 31 do`

begin

```

    Writeln (IntToStr(1 shl I));
    Writeln (IntToStr(15 shl I));
end;
End.

```

76.15.164 IsDelimiter

Synopsis: Check whether a given string is a delimiter character.

Declaration: `function IsDelimiter(const Delimiters: string; const S: string; Index: Integer) : Boolean`

Visibility: default

Description: `IsDelimiter` checks whether the `Index`-th character in the string `S` is a delimiter character as passed in `Delimiters`. If `Index` is out of range, `False` is returned.

Errors: None.

See also: `LastDelimiter` ([1561](#))

76.15.165 IsEqualGUID

Synopsis: Check whether two `TGUID` variables are equal.

Declaration: `function IsEqualGUID(const guid1: TGUID; const guid2: TGUID) : Boolean`

Visibility: default

Description: `IsEqualGUID` checks whether `guid1` and `guid2` are equal, and returns `True` if this is the case, or `False` otherwise.

See also: `Supports` ([1594](#)), `#rtl.system.TGUID` ([1242](#)), `StringToGUID` ([1577](#)), `GuidToString` ([1554](#))

76.15.166 IsLeapYear

Synopsis: Determine whether a year is a leap year.

Declaration: `function IsLeapYear(Year: Word) : Boolean`

Visibility: default

Description: `IsLeapYear` returns `True` if `Year` is a leap year, `False` otherwise.

Errors: None.

See also: `IncMonth` ([1556](#)), `Date` ([1499](#))

Listing: `./sysutex/ex16.pp`

Program `Example16;`

{ This program demonstrates the IsLeapYear function }

Uses `sysutils;`

Var `YY,MM,dd : Word;`

```

Procedure TestYear (Y : Word);

begin
  WriteLn (Y, ' is leap year : ', IsLeapYear(Y));
end;

Begin
  DeCodeDate (Date , YY, mm, dd);
  TestYear(yy);
  TestYear(2000);
  TestYear(1900);
  TestYear(1600);
  TestYear(1992);
  TestYear(1995);
End.

```

76.15.167 IsPathDelimiter

Synopsis: Is the character at the given position a pathdelimiter ?

Declaration: `function IsPathDelimiter(const Path: UnicodeString; Index: Integer) : Boolean`
`function IsPathDelimiter(const Path: RawByteString; Index: Integer) : Boolean`

Visibility: default

Description: `IsPathDelimiter` returns `True` if the character at position `Index` equals `PathDelim` ([1455](#)), i.e. if it is a path delimiter character for the current platform.

Errors: `IncludeTrailingPathDelimiter` ([1556](#)) `ExcludeTrailingPathDelimiter` ([1511](#)) `PathDelim` ([1455](#))

76.15.168 IsValidIdent

Synopsis: Check whether a string is a valid identifier name.

Declaration: `function IsValidIdent(const Ident: string; AllowDots: Boolean; StrictDots: Boolean) : Boolean`

Visibility: default

Description: `IsValidIdent` returns `True` if `Ident` can be used as a component name. It returns `False` otherwise. `Ident` must consist of a letter or underscore, followed by a combination of letters, numbers or underscores to be a valid identifier.

Errors: None.

Listing: `./sysutex/ex75.pp`

Program Example75;

{ This program demonstrates the IsValidIdent function }

Uses sysutils;

Procedure Testit (S : **String**);

```

begin
  Write ( '"', S, '" is ');
  If not IsValidIdent(S) then
    Write('NOT ');
  WriteLn ('a valid identifier');
end;

Begin
  Testit ('_MyObj');
  Testit ('My__Obj1');
  Testit ('My_1_Obj');
  Testit ('1MyObject');
  Testit ('My@Object');
  Testit ('M123');
End.

```

76.15.169 LastDelimiter

Synopsis: Return the last occurrence of a set of delimiters in a string.

Declaration: `function LastDelimiter(const Delimiters: string; const S: string)
: Integer`

Visibility: default

Description: `LastDelimiter` returns the *last* occurrence of any character in the set `Delimiters` in the string `S`.

Listing: ./sysutex/ex88.pp

Program example88;

{ This program demonstrates the LastDelimiter function }

uses SysUtils;

begin

 WriteLn (LastDelimiter ('\.: ', 'c:\filename.ext'));
end.

76.15.170 LeftStr

Synopsis: Return a number of characters starting at the left of a string.

Declaration: `function LeftStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `LeftStr` returns the `Count` leftmost characters of `S`. It is equivalent to a call to `Copy (S, 1, Count)`.

Errors: None.

See also: `RightStr` ([1567](#)), `TrimLeft` ([1600](#)), `TrimRight` ([1600](#)), `Trim` ([1599](#))

Listing: ./sysutex/ex76.pp

Program Example76;

{ This program demonstrates the LeftStr function }

Uses sysutils;

Begin

```

  WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',20));
  WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',15));
  WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',1));
  WriteLn ( LeftStr ( 'abcdefghijklmnopqrstuvwxyz ',200));

```

End.

76.15.171 LoadStr

Synopsis: Load a string from the resource tables.

Declaration: `function LoadStr(Ident: Integer) : string`

Visibility: default

Description: This function is not yet implemented. resources are not yet supported.

76.15.172 LowerCase

Synopsis: Return a lowercase version of a string.

Declaration: `function LowerCase(const s: string) : string; Overload`
`function LowerCase(const V: variant) : string; Overload`
`function LowerCase(const s: UnicodeString) : UnicodeString; Overload`

Visibility: default

Description: `LowerCase` returns the lowercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the lowercase function of the system unit, and is provided for compatibility only.

`LowerCase` does not change the number of characters (or bytes) in an ansistring or shortstring.

Errors: None.

See also: `AnsiLowerCase` ([1479](#)), `UpperCase` ([1609](#)), `AnsiUpperCase` ([1487](#))

Listing: ./sysutex/ex77.pp

Program Example77;

{ This program demonstrates the LowerCase function }

Uses sysutils;

Begin

```

  WriteLn ( LowerCase( 'THIS WILL COME out all LoWeRcAsE !' ));

```

End.

76.15.173 MSecsToTimeStamp

Synopsis: Convert a number of milliseconds to a TDateTime value.

Declaration: `function MSecsToTimeStamp(MSecs: Comp) : TTimeStamp`

Visibility: default

Description: `MSecsToTimeStamp` converts the given number of milliseconds to a `TTimeStamp` date/time notation.

Use `TTimeStamp` variables if you need to keep very precise track of time.

Errors: None.

See also: `TimeStampToMSecs` ([1598](#)), `DateTimeToTimeStamp` ([1502](#))

Listing: `./sysutex/ex17.pp`

Program `Example17;`

{ This program demonstrates the MSecsToTimeStamp function }

Uses `sysutils;`

Var `MS : Comp;`
 `TS : TTimeStamp;`
 `DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp(Now);`
 `WriteLn ('Now in days since 1/1/0001 : ',TS.Date);`
 `WriteLn ('Now in millisecs since midnight : ',TS.Time);`
 `MS:=TimeStampToMSecs(TS);`
 `WriteLn ('Now in millisecs since 1/1/0001 : ',MS);`
 `MS:=MS-1000*3600*2;`
 `TS:=MSecsToTimeStamp(MS);`
 `DT:=TimeStampToDateTime(TS);`
 `WriteLn ('Now minus 1 day : ',DateTimeToStr(DT));`

End.

76.15.174 NewStr

Synopsis: Allocate a new ansistring on the heap.

Declaration: `function NewStr(const S: string) : PString; Overload`

Visibility: default

Description: `NewStr` assigns a new dynamic string on the heap, copies `S` into it, and returns a pointer to the newly assigned string.

This function is obsolete, and shouldn't be used any more. The `AnsiString` mechanism also allocates ansistrings on the heap, and should be preferred over this mechanism.

For an example, see `AssignStr` ([1489](#)).

Errors: If not enough memory is present, an `EOutOfMemory` exception will be raised.

See also: `AssignStr` ([1489](#)), `DisposeStr` ([1507](#))

76.15.175 Now

Synopsis: Returns the current date and time.

Declaration: `function Now : TDateTime`

Visibility: default

Description: `Now` returns the current date and time. It is equivalent to `Date+Time`.

Errors: None.

See also: `Date` ([1499](#)), `Time` ([1597](#))

Listing: `./sysutex/ex18.pp`

Program `Example18;`

{ This program demonstrates the Now function }

Uses `sysutils;`

Begin

`WriteLn ('Now : ', DateTimeToStr (Now));`

End.

76.15.176 OutOfMemoryError

Synopsis: Raise an `EOutOfMemory` exception

Declaration: `procedure OutOfMemoryError`

Visibility: default

Description: `OutOfMemoryError` raises an `EOutOfMemory` ([1621](#)) exception, with an exception object that has been allocated on the heap at program startup. The program should never create an `EOutOfMemory` ([1621](#)) exception, but always call this routine.

See also: `EOutOfMemory` ([1621](#))

76.15.177 QuotedStr

Synopsis: Return a quotes version of a string.

Declaration: `function QuotedStr(const S: string) : string`

Visibility: default

Description: `QuotedStr` returns the string `S`, quoted with single quotes. This means that `S` is enclosed in single quotes, and every single quote in `S` is doubled. It is equivalent to a call to `AnsiQuotedStr(s, '"')`.

Errors: None.

See also: `AnsiQuotedStr` ([1480](#)), `AnsiExtractQuotedStr` ([1478](#))

Listing: `./sysutex/ex78.pp`

```

Program Example78;

{ This program demonstrates the QuotedStr function }

Uses sysutils;

Var S : AnsiString;

Begin
  S:= 'He said ''Hello'' and walked on';
  WriteLn (S);
  WriteLn ( ' becomes' );
  WriteLn (QuotedStr(S));
End.

```

76.15.178 RaiseLastError

Synopsis: Raise an exception with the last Operating System error code.

Declaration: `procedure RaiseLastError; Overload`
`procedure RaiseLastError(LastError: Integer); Overload`

Visibility: default

Description: `RaiseLastError` raises an `EOSError` ([1620](#)) exception with the error code returned by `GetLastError`. If the Error code is nonzero, then the corresponding error message will be returned. If the error code is zero, a standard message will be returned.

Errors: This procedure may not be implemented on all platforms. If it is not, then a normal Exception ([1623](#)) will be raised.

See also: `EOSError` ([1620](#)), `GetLastError` ([1552](#)), Exception ([1623](#))

76.15.179 RemoveDir

Synopsis: Remove a directory from the filesystem.

Declaration: `function RemoveDir(const Dir: RawByteString) : Boolean`
`function RemoveDir(const Dir: UnicodeString) : Boolean`

Visibility: default

Description: `RemoveDir` removes directory `Dir` from the disk. If the directory is not absolute, it is appended to the current working directory.

For an example, see `CreateDir` ([1497](#)).

Errors: In case of error (e.g. the directory isn't empty) the function returns `False`. If successful, `True` is returned.

76.15.180 RenameFile

Synopsis: Rename a file.

Declaration: `function RenameFile(const OldName: UnicodeString;
const NewName: UnicodeString) : Boolean
function RenameFile(const OldName: RawByteString;
const NewName: RawByteString) : Boolean`

Visibility: default

Description: `RenameFile` renames a file from `OldName` to `NewName`. The function returns `True` if successful, `False` otherwise. For safety, the new name must be a full path specification, including the directory, otherwise it will be assumed to be a filename relative to the current working directory. *Remark:* The implementation of `RenameFile` relies on the underlying OS's support for renaming/-moving a file. Whether or not a file can be renamed accros disks or partitions depends entirely on the OS. On unix-like OS-es, the rename function will fail when used accross partitions. On Windows, it will work.

Errors: On Error, `False` is returned.

See also: `DeleteFile` ([1505](#))

Listing: `./sysutex/ex44.pp`

Program `Example44;`

`{ This program demonstrates the RenameFile function }`

Uses `sysutils;`

Var `F : Longint;
S : String;`

Begin
`S:= 'Some short file.';
F:= FileCreate ('test.dap');
FileWrite(F,S[1],Length(S));
FileClose(F);
If RenameFile ('test.dap', 'test.dat') then
Writeln ('Successfully renamed files. ');
End.`

76.15.181 ReplaceDate

Synopsis: Replace the date part of a date/time stamp

Declaration: `procedure ReplaceDate(var DateTime: TDateTime; const NewDate: TDateTime)`

Visibility: default

Description: `ReplaceDate` replaces the date part of `DateTime` with `NewDate`. The time part is left unchanged.

See also: `ReplaceTime` ([1566](#))

76.15.182 ReplaceTime

Synopsis: Replace the time part

Declaration: `procedure ReplaceTime(var dati: TDateTime; NewTime: TDateTime)`

Visibility: default

Description: `ReplaceTime` replaces the time part in `dateTime` with `NewTime`. The date part remains untouched.

76.15.183 RightStr

Synopsis: Return a number of characters from a string, starting at the end.

Declaration: `function RightStr(const S: string; Count: Integer) : string`

Visibility: default

Description: `RightStr` returns the `Count` rightmost characters of `S`. It is equivalent to a call to `Copy (S, Length (S) + 1 - Count, Count)`.

If `Count` is larger than the actual length of `S` only the real length will be used.

Errors: None.

See also: `LeftStr` ([1561](#)), `Trim` ([1599](#)), `TrimLeft` ([1600](#)), `TrimRight` ([1600](#))

Listing: `./sysutex/ex79.pp`

Program `Example79;`

{ This program demonstrates the RightStr function }

Uses `sysutils;`

Begin

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz',20)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz',15)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz',1)`);

WriteLn (`RightStr('abcdefghijklmnopqrstuvwxyz',200)`);

End.

76.15.184 SafeLoadLibrary

Synopsis: Load a library safely

Declaration: `function SafeLoadLibrary(const FileName: AnsiString; ErrorMode: DWord)
: HMODULE`

Visibility: default

Description: `SafeLoadLibrary` saves and restores some registers before and after issuing a call to `LoadLibrary`.

Errors: None.

76.15.185 SameFileName

Synopsis: Are two filenames referring to the same file ?

Declaration: `function SameFileName(const S1: string; const S2: string) : Boolean`

Visibility: default

Description: `SameFileName` returns `True` if calling `AnsiCompareFileName` ([1475](#)) with arguments `S1` and `S2` returns 0, and returns `False` otherwise.

Errors: None.

See also: `AnsiCompareFileName` ([1475](#))

76.15.186 SameStr

Synopsis: Check whether 2 strings are the same, case insensitive

Declaration: `function SameStr(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameStr` checks whether `S1` and `S2` are the same. This is equivalent to checking that `CompareStr` (1494) returns 0.

Errors: None.

See also: `CompareStr` (1494)

76.15.187 SameText

Synopsis: Checks whether 2 strings are the same (case insensitive)

Declaration: `function SameText(const s1: string; const s2: string) : Boolean`

Visibility: default

Description: `SameText` calls `CompareText` (1495) with `S1` and `S2` as parameters and returns `True` if the result of that call is zero, or `False` otherwise.

Errors: None.

See also: `CompareText` (1495), `AnsiSameText` (1481), `AnsiSameStr` (1481)

76.15.188 SetCurrentDir

Synopsis: Set the current directory of the application.

Declaration: `function SetCurrentDir(const NewDir: RawByteString) : Boolean`
`function SetCurrentDir(const NewDir: UnicodeString) : Boolean`

Visibility: default

Description: `SetCurrentDir` sets the current working directory of your program to `NewDir`. It returns `True` if the function was successfull, `False` otherwise.

Errors: In case of error, `False` is returned.

See also: `GetCurrentDir` (1549)

76.15.189 SetDirSeparators

Synopsis: Set the directory separators to the known directory separators.

Declaration: `function SetDirSeparators(const FileName: UnicodeString) : UnicodeString`
`function SetDirSeparators(const FileName: RawByteString) : RawByteString`

Visibility: default

Description: `SetDirSeparators` returns `FileName` with all possible `DirSeparators` replaced by `OSDirSeparator`.

Errors: None.

See also: `ExpandFileName` (1513), `ExtractFilePath` (1516), `ExtractFileDir` (1515)

Listing: ./sysutex/ex47.pp

Program Example47;

{ This program demonstrates the SetDirSeparators function }

Uses sysutils;

Begin

WriteLn (SetDirSeparators('/pp\bin\win32\ppc386'));

End.

76.15.190 ShowException

Synopsis: Show the current exception to the user.

Declaration: procedure ShowException(ExceptObject: TObject; ExceptAddr: Pointer)

Visibility: default

Description: ShowException shows a message stating that a ExceptObject was raised at address ExceptAddr.

It uses ExceptionErrorMessage (1510) to create the message, and is aware of the fact whether the application is a console application or a GUI application. For a console application, the message is written to standard error output. For a GUI application, OnShowException (1472) is executed.

Errors: If, for a GUI application, OnShowException (1472) is not set, no message will be displayed to the user.

The exception message can be at most 255 characters long: It is possible that no memory can be allocated on the heap, so ansistrings are not available, so a shortstring is used to display the message.

See also: ExceptObject (1510), ExceptAddr (1509), ExceptionErrorMessage (1510)

76.15.191 Sleep

Synopsis: Suspend execution of a program for a certain time.

Declaration: procedure Sleep(milliseconds: Cardinal)

Visibility: default

Description: Sleep suspends the execution of the program for the specified number of milliseconds (milliseconds).

After the specified period has expired, program execution resumes.

Remark: The indicated time is not exact, i.e. it is a minimum time. No guarantees are made as to the exact duration of the suspension.

76.15.192 SScanf

Synopsis: Scan a string for substrings and return the substrings

Declaration: function SScanf(const s: string; const fmt: string;
const Pointers: Array of Pointer) : Integer

Visibility: default

Description: `SScanf` scans the string `S` for the elements specified in `Fmt`, and returns the elements in the pointers in `Pointers`. The `Fmt` can contain placeholders of the form `%X` where `X` can be one of the following characters:

dPlaceholder for a decimal number.

fPlaceholder for a floating point number (an extended)

sPlaceholder for a string of arbitrary length.

cPlaceholder for a single character

The `Pointers` array contains a list of pointers, each pointer should point to a memory location of a type that corresponds to the type of placeholder in that position:

dA pointer to an integer.

fA pointer to an extended.

sA pointer to an ansistring.

cA pointer to a single character.

Errors: No error checking is performed on the type of the memory location.

See also: `Format` ([1537](#))

76.15.193 StrAlloc

Synopsis: Allocate a null-terminated string on the heap.

Declaration: `function StrAlloc(Size: Cardinal) : PChar`

Visibility: default

Description: `StrAlloc` reserves memory on the heap for a string with length `Len`, terminating `#0` included, and returns a pointer to it.

Additionally, `StrAlloc` allocates 4 extra bytes to store the size of the allocated memory. Therefore this function is NOT compatible with the `StrAlloc` ([1147](#)) function of the `Strings` unit.

For an example, see `StrBufSize` ([1570](#)).

Errors: None.

See also: `StrBufSize` ([1570](#)), `StrDispose` ([1573](#)), `StrAlloc` ([1147](#))

76.15.194 StrBufSize

Synopsis: Return the size of a null-terminated string allocated on the heap.

Declaration: `function StrBufSize(Str: PChar) : Cardinal`
`function StrBufSize(str: PWideChar) : Cardinal`

Visibility: default

Description: `StrBufSize` returns the memory allocated for `Str`. This function ONLY gives the correct result if `Str` was allocated using `StrAlloc` ([1570](#)).

Errors: If no more memory is available, a runtime error occurs.

See also: `StrAlloc` ([1570](#)), `StrDispose` ([1573](#))

Listing: ./sysutex/ex46.pp

Program Example46;

```
{ This program demonstrates the StrBufSize function }
{$H+}
```

Uses sysutils;

Const S = 'Some nice string';

Var P : Pchar;

Begin

```
P:= StrAlloc (Length(S)+1);
```

```
StrPCopy(P,S);
```

```
Write (P, ' has length ',length(S));
```

```
Writeln (' and buffer size ',StrBufSize(P));
```

```
StrDispose(P);
```

End.

76.15.195 StrByteType

Synopsis: Return the type of byte in a null-terminated string for a multi-byte character set

Declaration: function StrByteType(Str: PChar; Index: Cardinal) : TmbcsByteType

Visibility: default

Description: StrByteType returns the type of byte in the null-terminated string Str at (0-based) position Index.

Errors: No checking on the index is performed.

See also: TmbcsByteType ([1465](#)), ByteType ([1492](#))

76.15.196 strcat

Synopsis: Concatenate 2 null-terminated strings.

Declaration: function strcat(dest: PChar; source: PChar) : PChar

```
function strcat(dest: PWideChar; source: PWideChar) : PWideChar
```

Visibility: default

Description: Attaches Source to Dest and returns Dest.

Errors: No length checking is performed.

See also: StrLCat ([1577](#))

Listing: ./stringex/ex11.pp

Program Example11;

Uses strings;

```
{ Program to demonstrate the StrCat function. }
```

```

Const P1 : PChar = 'This is a PChar String.';

Var P2 : PChar;

begin
  P2:= StrAlloc (StrLen(P1)*2+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2=P1 }
  StrCat (P2,P1);                { Append P2 once more }
  Writeln ('P2 : ',P2);
  StrDispose(P2);
end.

```

76.15.197 StrCharLength

Synopsis: Return the length of a null-terminated string in characters.

Declaration: `function StrCharLength(const Str: PChar) : Integer`

Visibility: default

Description: `StrCharLength` returns the length of the null-terminated string `Str` (a widestring) in characters (not in bytes). It uses the widestring manager to do this.

76.15.198 strcmp

Synopsis: Compare 2 null-terminated strings, case sensitive.

Declaration: `function strcmp(str1: PChar; str2: PChar) : SizeInt`
`function strcmp(str1: PWideChar; str2: PWideChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings `S1` and `S2`. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

For an example, see `StrLComp` ([1578](#)).

Errors: None.

See also: `StrLComp` ([1578](#)), `StrIComp` ([1575](#)), `StrLComp` ([1580](#))

76.15.199 StrCopy

Synopsis: Copy a null-terminated string

Declaration: `function strcpy(dest: PChar; source: PChar) : PChar; Overload`
`function StrCopy(Dest: PWideChar; Source: PWideChar) : PWideChar`
`; Overload`

Visibility: default

Description: Copy the null terminated string in *Source* to *Dest*, and returns a pointer to *Dest*. *Dest* needs enough room to contain *Source*, i.e. `StrLen (Source) + 1` bytes.

Errors: No length checking is performed.

See also: `StrPCopy` ([1583](#)), `StrLCopy` ([1578](#)), `StrECopy` ([1573](#))

Listing: `./stringex/ex4.pp`

Program `Example4`;

Uses `strings`;

{ Program to demonstrate the StrCopy function. }

Const `P : PChar = 'This is a PCHAR string.'`;

var `PP : PChar`;

begin

`PP := StrAlloc (StrLen (P) + 1);`

`STrCopy (PP, P);`

If `StrComp (PP, P) <> 0` **then**

`Writeln ('Oh-oh problems ...')`

else

`Writeln ('All is well : PP=', PP);`

`StrDispose (PP);`

end.

76.15.200 StrDispose

Synopsis: Dispose of a null-terminated string on the heap.

Declaration: `procedure StrDispose (Str: PChar)`
`procedure StrDispose (str: PWideChar)`

Visibility: `default`

Description: `StrDispose` frees any memory allocated for *Str*. This function will only function correctly if *Str* has been allocated on the heap, for example using `StrAlloc` ([1570](#)) or `StrNew` ([1582](#)) from the `SysUtils` unit.

For an example, see `StrBufSize` ([1570](#)).

Errors: If an invalid pointer is passed, or a pointer not allocated with `StrAlloc`, an error may occur.

See also: `StrBufSize` ([1570](#)), `StrAlloc` ([1570](#)), `StrNew` ([1582](#))

76.15.201 strecopy

Synopsis: Copy a null-terminated string, return a pointer to the end.

Declaration: `function strecopy (dest: PChar; source: PChar) : PChar`
`function strecopy (dest: PWideChar; source: PWideChar) : PWideChar`

Visibility: `default`

Description: Copies the Null-terminated string in *Source* to *Dest*, and returns a pointer to the end (i.e. the terminating Null-character) of the copied string.

Errors: No length checking is performed.

See also: [StrLCopy \(1578\)](#), [StrCopy \(1572\)](#)

Listing: ./stringex/ex6.pp

Program Example6;

Uses strings;

{ Program to demonstrate the StrECopy function. }

Const P : PChar = 'This is a PCHAR string.';

Var PP : PChar;

begin

PP:=StrAlloc (StrLen(P)+1);

If Longint(StrECopy(PP,P))–Longint(PP)<>StrLen(P) **then**

 Writeln('Something is wrong here !')

else

 Writeln ('PP= ',PP);

 StrDispose(PP);

end.

76.15.202 strend

Synopsis: Return a pointer to the end of a null-terminated string

Declaration: `function strend(p: PChar) : PChar`
`function strend(p: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the end of P. (i.e. to the terminating null-character.

Errors: None.

See also: [StrLen \(1579\)](#)

Listing: ./stringex/ex7.pp

Program Example6;

Uses strings;

{ Program to demonstrate the StrEnd function. }

Const P : PChar = 'This is a PCHAR string.';

begin

If Longint(StrEnd(P))–Longint(P)<>StrLen(P) **then**

 Writeln('Something is wrong here !')

else

 Writeln ('All is well..');

end.

76.15.203 StrFmt

Synopsis: Format a string with given arguments, store the result in a buffer.

Declaration: `function StrFmt(Buffer: PChar; Fmt: PChar; const args: Array of const) : PChar`
`function StrFmt(Buffer: PChar; Fmt: PChar; const Args: Array of const; const FormatSettings: TFormatSettings) : PChar`

Visibility: default

Description: `StrFmt` will format `fmt` with `Args`, as the `Format` (1537) function does, and it will store the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain the whole result.

Errors: for a list of errors, see `Format` (1537).

See also: `StrLFmt` (1579), `FmtStr` (1536), `Format` (1537), `FormatBuf` (1544)

Listing: `./sysutex/ex80.pp`

Program `Example80`;

{ This program demonstrates the StrFmt function }

Uses `sysutils`;

Var `S` : `AnsiString`;

Begin

`SetLength(S,80);`

`WriteLn (StrFmt (@S[1], 'For some nice examples of fomattting see %s.', ['Format']));`
End.

76.15.204 stricmp

Synopsis: Compare 2 null-terminated strings, case insensitive.

Declaration: `function stricmp(str1: PChar; str2: PChar) : SizeInt`
`function stricmp(str1: PWideChar; str2: PWideChar) : SizeInt`

Visibility: default

Description: Compares the null-terminated strings `S1` and `S2`, ignoring case. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

Errors: None.

See also: `StrLComp` (1578), `StrComp` (1572), `StrLComp` (1580)

Listing: `./stringex/ex8.pp`

```

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
        P2 : PChar = 'This is the second string.';

Var L : Longint;

begin
  Write ( 'P1 and P2 are ');
  If StrComp (P1,P2)<>0 then write ( 'NOT ');
  write ( 'equal. The first ');
  L:=1;
  While StrLComp(P1,P2,L)=0 do inc (L);
  dec(L);
  WriteLn (L, ' characters are the same. ');
end.

```

76.15.205 StringOf

Synopsis: Create a unicode string from an array of bytes

Declaration: `function StringOf(const Bytes: TBytes) : UnicodeString`

Visibility: default

Description: `StringOf` converts an array of bytes (`Bytes`) to a unicode string. It interprets the bytes as a single-byte string, using the default codepage.

To create a string where the bytes are interpreted as wide chars, use `WideStringOf` ([1613](#)) instead.

Errors: None.

See also: `WideBytesOf` ([1610](#)), `WideStringOf` ([1613](#))

76.15.206 StringReplace

Synopsis: Replace occurrences of one substring with another in a string.

Declaration: `function StringReplace(const S: string; const OldPattern: string;
const NewPattern: string; Flags: TReplaceFlags)
: string`

Visibility: default

Description: `StringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be runed with `Flags`, which is of type `TReplaceFlags` ([1465](#)). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` ([1465](#)), `WideStringReplace` ([1613](#))

76.15.207 StringToGUID

Synopsis: Convert a string to a native TGUID type.

Declaration: `function StringToGUID(const S: string) : TGUID`

Visibility: default

Description: `StringToGUID` converts the string `S` to a valid GUID. The string `S` should be of the form

```
{XXXXXXXX-XXXX-XXXX-XXXX-XXXXXXXXXXXX}
```

Where each `X` is a hexadecimal digit. The dashes and braces are required.

Errors: In case `S` contains an invalid GUID representation, a `EConvertError` (1616) exception is raised.

See also: Supports (1594), `#rtl.system.TGUID` (1242), `GUIDToString` (1554), `IsEqualGuid` (1559)

76.15.208 strlcat

Synopsis: Concatenate 2 null-terminated strings, with length boundary.

Declaration: `function strlcat(dest: PChar; source: PChar; l: SizeInt) : PChar`
`function strlcat(dest: PWideChar; source: PWideChar; l: SizeInt)`
`: PWideChar`

Visibility: default

Description: Adds `MaxLen` characters from `Source` to `Dest`, and adds a terminating null-character. Returns `Dest`.

Errors: None.

See also: `StrCat` (1571)

Listing: `./stringex/ex12.pp`

Program `Example12;`

Uses `strings;`

{ Program to demonstrate the StrLCat function. }

Const `P1 : PChar = '1234567890';`

Var `P2 : PChar;`

begin

`P2:= StrAlloc (StrLen(P1)*2+1);`

`P2^:=#0; { Zero length }`

`StrCat (P2,P1);`

`StrLCat (P2,P1,5);`

`Writeln ('P2 = ',P2);`

`StrDispose(P2)`

end.

76.15.209 strlcomp

Synopsis: Compare limited number of characters of 2 null-terminated strings

Declaration: `function strlcomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt`
`function strlcomp(str1: PWideChar; str2: PWideChar; l: SizeInt)`
`: SizeInt`

Visibility: default

Description: Compares maximum L characters of the null-terminated strings S1 and S2. The result is

- A negative Longint when S1<S2.
- 0 when S1=S2.
- A positive Longint when S1>S2.

Errors: None.

See also: StrComp ([1572](#)), StrIComp ([1575](#)), StrLComp ([1580](#))

Listing: ./stringex/ex8.pp

Program Example8;

Uses strings;

{ Program to demonstrate the StrLComp function. }

Const P1 : PChar = 'This is the first string.';
P2 : PChar = 'This is the second string.';

Var L : Longint;

begin

Write ('P1 and P2 are ');
If StrComp (P1,P2)<>0 **then write** ('NOT ');
write ('equal. The first ');
L:=1;
While StrLComp(P1,P2,L)=0 **do inc** (L);
dec(L);
WriteLn (L,' characters are the same.');

end.

76.15.210 StrLCopy

Synopsis: Copy a null-terminated string, limited in length.

Declaration: `function strlcopy(dest: PChar; source: PChar; maxlen: SizeInt) : PChar`
`; Overload`
`function StrLCopy(Dest: PWideChar; Source: PWideChar; MaxLen: SizeInt)`
`: PWideChar; Overload`

Visibility: default

Description: Copies MaxLen characters from Source to Dest, and makes Dest a null terminated string.

Errors: No length checking is performed.

See also: StrCopy ([1572](#)), StrECopy ([1573](#))

Listing: ./stringex/ex5.pp

Program Example5;

Uses strings;

{ Program to demonstrate the StrLCopy function. }

Const P : PChar = '123456789ABCDEF';

var PP : PChar;

begin

PP:= StrAlloc(11);

WriteLn ('First 10 characters of P : ',StrLCopy (PP,P,10));

StrDispose(PP);

end.

76.15.211 StrLen

Synopsis: Length of a null-terminated string.

Declaration: function strlen(p: PChar) : SizeInt; Overload
function StrLen(p: PWideChar) : SizeInt; Overload

Visibility: default

Description: Returns the length of the null-terminated string P. If P equals Nil then zero (0) is returned.

Errors: None.

See also: StrNew ([1582](#))

Listing: ./stringex/ex1.pp

Program Example1;

Uses strings;

{ Program to demonstrate the StrLen function. }

Const P : PChar = 'This is a constant pchar string';

begin

WriteLn ('P : ',p);

WriteLn ('length(P) : ',StrLen(P));

end.

76.15.212 StrLFmt

Synopsis: Format a string with given arguments, but with limited length.

Declaration: `function StrLFmt(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
const args: Array of const) : PChar
function StrLFmt(Buffer: PChar; Maxlen: Cardinal; Fmt: PChar;
const args: Array of const;
const FormatSettings: TFormatSettings) : PChar`

Visibility: default

Description: `StrLFmt` will format `fmt` with `Args`, as the `Format` (1537) function does, and it will store maximally `Maxlen` characters of the result in `Buffer`. The function returns `Buffer`. `Buffer` should point to enough space to contain `MaxLen` characters.

Errors: for a list of errors, see `Format` (1537).

See also: `StrFmt` (1575), `FmtStr` (1536), `Format` (1537), `FormatBuf` (1544)

Listing: `./sysutex/ex81.pp`

Program `Example80`;

{ This program demonstrates the StrFmt function }

Uses `sysutils`;

Var `S` : `AnsiString`;

Begin

`SetLength(S,80);`

WriteLn (`StrLFmt` (`@S[1]`,80,'For some nice examples of fomattting see %s.',['Format']));
End.

76.15.213 `strlicomp`

Synopsis: Compare limited number of characters in 2 null-terminated strings, ignoring case.

Declaration: `function strlicomp(str1: PChar; str2: PChar; l: SizeInt) : SizeInt
function strlicomp(str1: PWideChar; str2: PWideChar; l: SizeInt)
: SizeInt`

Visibility: default

Description: Compares maximum `L` characters of the null-terminated strings `S1` and `S2`, ignoring case. The result is

- A negative `Longint` when `S1<S2`.
- 0 when `S1=S2`.
- A positive `Longint` when `S1>S2`.

For an example, see `StrIComp` (1575)

Errors: None.

See also: `StrLComp` (1578), `StrComp` (1572), `StrIComp` (1575)

76.15.214 strlower

Synopsis: Convert null-terminated string to all-lowercase.

Declaration: `function strlower(p: PChar) : PChar`
`function strlower(p: PWideChar) : PWideChar`

Visibility: default

Description: Converts P to an all-lowercase string. Returns P.

Errors: None.

See also: [StrUpper \(1594\)](#)

Listing: ./stringex/ex14.pp

Program Example14;

Uses strings;

{ Program to demonstrate the StrLower and StrUpper functions. }

Const

P1 : PChar = 'THIS IS AN UPPERCASE PCHAR STRING';
P2 : PChar = 'this is a lowercase string';

begin

WriteLn ('Uppercase : ', StrUpper(P2));
StrLower (P1);
WriteLn ('Lowercase : ', P1);

end.

76.15.215 StrMove

Synopsis: Move a null-terminated string to new location.

Declaration: `function strmove(dest: PChar; source: PChar; l: SizeInt) : PChar`
`; Overload`
`function StrMove(dest: PWideChar; source: PWideChar; l: SizeInt)`
`: PWideChar; Overload`

Visibility: default

Description: Copies MaxLen characters from Source to Dest. No terminating null-character is copied. Returns Dest

Errors: None.

See also: [StrLCopy \(1578\)](#), [StrCopy \(1572\)](#)

Listing: ./stringex/ex10.pp

Program Example10;

Uses strings;

{ Program to demonstrate the StrMove function. }

```
Const P1 : PCHAR = 'This is a pchar string.';
```

```
Var P2 : Pchar;
```

```
begin
  P2:=StrAlloc(StrLen(P1)+1);
  StrMove (P2,P1,StrLen(P1)+1); { P2:=P1 }
  Writeln ('P2 = ',P2);
  StrDispose(P2);
end.
```

76.15.216 strnew

Synopsis: Allocate room for new null-terminated string.

Declaration: `function strnew(p: PChar) : PChar; Overload`
`function strnew(p: PWideChar) : PWideChar; Overload`

Visibility: default

Description: Copies P to the Heap, and returns a pointer to the copy.

Errors: Returns Nil if no memory was available for the copy.

See also: StrCopy ([1572](#)), StrDispose ([1573](#))

Listing: ./stringex/ex16.pp

Program Example16;

Uses strings;

{ Program to demonstrate the StrNew function. }

```
Const P1 : PChar = 'This is a PChar string';
```

```
var P2 : PChar;
```

```
begin
  P2:=StrNew (P1);
  If P1=P2 then
    writeln ('This can''t be happening...')
  else
    writeln ('P2 : ',P2);
    StrDispose(P2);
end.
```

76.15.217 StrNextChar

Synopsis: Returns a pointer to the location of the next empty character in a null-terminated string

Declaration: `function StrNextChar(const Str: PChar) : PChar`

Visibility: default

Description: StrNextChar returns a pointer to the null-character that terminates the string Str

Errors: if Str is not properly terminated, an access violation may occur.

76.15.218 StrPas

Synopsis: Convert a null-terminated string to an ansistring.

Declaration: `function StrPas(Str: PChar) : string; Overload`
`function StrPas(Str: PWideChar) : UnicodeString; Overload`

Visibility: default

Description: Converts a null terminated string in `Str` to an `Ansistring`, and returns this string. This string is NOT truncated at 255 characters as is the system unit's version.

Errors: None.

See also: `StrPCopy` ([1583](#)), `StrPLCopy` ([1583](#))

76.15.219 StrPCopy

Synopsis: Copy an ansistring to a null-terminated string.

Declaration: `function StrPCopy(Dest: PChar; const Source: string) : PChar; Overload`
`function StrPCopy(Dest: PWideChar; const Source: UnicodeString)`
`: PWideChar; Overload`

Visibility: default

Description: `StrPCopy` Converts the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the string `Source`, i.e. `Length(Source)+1` bytes.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `Source`.

See also: `StrPLCopy` ([1583](#)), `StrPas` ([1583](#))

76.15.220 StrPLCopy

Synopsis: Copy a limited number of characters from an ansistring to a null-terminated string.

Declaration: `function StrPLCopy(Dest: PChar; const Source: string; MaxLen: SizeUInt)`
`: PChar; Overload`
`function StrPLCopy(Dest: PWideChar; const Source: UnicodeString;`
`MaxLen: SizeUInt) : PWideChar; Overload`

Visibility: default

Description: `StrPLCopy` Converts maximally `MaxLen` characters of the `Ansistring` in `Source` to a Null-terminated string, and copies it to `Dest`. `Dest` needs enough room to contain the characters.

Errors: No checking is performed to see whether `Dest` points to enough memory to contain `L` characters of `Source`.

See also: `StrPCopy` ([1583](#))

76.15.221 strpos

Synopsis: Find position of one null-terminated substring in another.

Declaration: `function strpos(str1: PChar; str2: PChar) : PChar`
`function strpos(str1: PWideChar; str2: PWideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the first occurrence of S2 in S1. If S2 does not occur in S1, returns Nil.

Errors: None.

See also: StrScan ([1584](#)), StrRScan ([1584](#))

Listing: ./stringex/ex15.pp

Program Example15;

Uses strings;

{ Program to demonstrate the StrPos function. }

Const P : PChar = 'This is a PChar string.';
 S : PChar = 'is';

begin

WriteLn ('Position of ''is'' in P : ', sizeint(**StrPos**(P,S)) - sizeint(P));
end.

76.15.222 strrscan

Synopsis: Find last occurrence of a character in a null-terminated string.

Declaration: `function strrscan(p: PChar; c: Char) : PChar`
`function strrscan(p: PWideChar; c: WideChar) : PWideChar`

Visibility: default

Description: Returns a pointer to the last occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

For an example, see StrScan ([1584](#)).

Errors: None.

See also: StrScan ([1584](#)), StrPos ([1584](#))

76.15.223 StrScan

Synopsis: Find first occurrence of a character in a null-terminated string.

Declaration: `function strscan(p: PChar; c: Char) : PChar; Overload`
`function StrScan(P: PWideChar; C: WideChar) : PWideChar; Overload`

Visibility: default

Description: Returns a pointer to the first occurrence of the character C in the null-terminated string P. If C does not occur, returns Nil.

Errors: None.

See also: [StrRScan \(1584\)](#), [StrPos \(1584\)](#)

Listing: ./stringex/ex13.pp

Program Example13;

Uses strings;

{ Program to demonstrate the StrScan and StrRScan functions. }

Const P : PChar = 'This is a PCHAR string.';
 S : Char = 's' ;

begin

WriteLn ('P, starting from first ''s'' : ', **StrScan**(P,s));

WriteLn ('P, starting from last ''s'' : ', **StrRScan**(P,s));

end.

76.15.224 StrToBool

Synopsis: Convert a string to a boolean value

Declaration: `function StrToBool(const S: string) : Boolean`

Visibility: default

Description: `StrToBool` will convert the string `S` to a boolean value. The string `S` can contain one of 'True', 'False' (case is ignored) or a numerical value. If it contains a numerical value, 0 is converted to False, all other values result in True. If the string `S` contains no valid boolean, then an `EConvertError (1616)` exception is raised.

Errors: On error, an `EConvertError (1616)` exception is raised.

See also: [BoolToStr \(1490\)](#)

76.15.225 StrToBoolDef

Synopsis: Convert string to boolean value, returning default in case of error

Declaration: `function StrToBoolDef(const S: string; Default: Boolean) : Boolean`

Visibility: default

Description: `StrToBoolDef` tries to convert the string `S` to a boolean value, and returns the boolean value in case of success. In case `S` does not contain a valid boolean string, `Default` is returned.

See also: [StrToBool \(1585\)](#), [TryStrToBool \(1602\)](#)

76.15.226 StrToCurr

Synopsis: Convert a string to a currency value

Declaration: `function StrToCurr(const S: string) : Currency`

`function StrToCurr(const S: string;`

`const FormatSettings: TFormatSettings) : Currency`

Visibility: default

Description: `StrToCurr` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, an `EConvertError` (1616) exception is raised.

Errors: On error, an `EConvertError` (1616) exception is raised.

See also: `CurrToStr` (1498), `StrToCurrDef` (1586)

76.15.227 StrToCurrDef

Synopsis: Convert a string to a currency value, using a default value

Declaration:

```
function StrToCurrDef(const S: string; Default: Currency) : Currency
function StrToCurrDef(const S: string; Default: Currency;
                      const FormatSettings: TFormatSettings) : Currency
```

Visibility: default

Description: `StrToCurrDef` converts a string to a currency value and returns the value. The string should contain a valid currency amount, without currency symbol. If the conversion fails, the fallback `Default` value is returned.

Errors: On error, the `Default` value is returned.

See also: `CurrToStr` (1498), `StrToCurr` (1585)

76.15.228 StrToDate

Synopsis: Convert a date string to a `TDateTime` value.

Declaration:

```
function StrToDate(const S: ShortString) : TDateTime
function StrToDate(const S: AnsiString) : TDateTime
function StrToDate(const S: ShortString; separator: Char) : TDateTime
function StrToDate(const S: AnsiString; separator: Char) : TDateTime
function StrToDate(const S: string; FormatSettings: TFormatSettings)
    : TDateTime
function StrToDate(const S: ShortString; const useformat: string;
                  separator: Char) : TDateTime
function StrToDate(const S: AnsiString; const useformat: string;
                  separator: Char) : TDateTime
function StrToDate(const S: PChar; Len: Integer;
                  const useformat: string; separator: Char) : TDateTime
```

Visibility: default

Description: `StrToDate` converts the string `S` to a `TDateTime` date value. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1616) exception is raised.

See also: `StrToTime` (1593), `DateToStr` (1502), `TimeToStr` (1599), `EConvertError` (1616)

Listing: ./sysutex/ex19.pp

Program Example19;

```
{ This program demonstrates the StrToDate function }
```

Uses sysutils;

```
Procedure TestStr (S : String);
```

begin

```
WriteIn (S, ' : ', DateToStr (StrToDate (S)));  
end;
```

Begin

```

WriteIn ( 'ShortDateFormat ', ShortDateFormat );
TestStr ( DateTimeToStr ( Date ) );
TestStr ( '05'+DateSeparator+'05'+DateSeparator+'1999' );
TestStr ( '5'+DateSeparator+'5' );
TestStr ( '5' );
End.

```

76.15.229 StrToDateDef

Synopsis: Convert string to date, returning a default value

```

Declaration: function StrToDateDef(const S: ShortString; const Defvalue: TDateTime)
            : TDateTime
function StrToDateDef(const S: ShortString; const Defvalue: TDateTime;
            separator: Char) : TDateTime
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime)
            : TDateTime
function StrToDateDef(const S: AnsiString; const Defvalue: TDateTime;
            separator: Char) : TDateTime

```

Visibility: default

Description: `StrToDateDef` tries to convert the string `S` to a valid `TDateTime` date value, and returns `DefValue` if `S` does not contain a valid date indication.

Errors: None.

See also: [StrToDate \(1586\)](#), [TryStrToDate \(1603\)](#), [StrToTimeDef \(1594\)](#)

76.15.230 StrToDateTime

Synopsis: Convert a date/time string to a `TDateTime` value.

```

Declaration: function StrToDateTime(const S: AnsiString) : TDateTime
              function StrToDateTime(const s: ShortString;
                                      const FormatSettings: TFormatSettings) : TDateTime
              function StrToDateTime(const s: AnsiString;
                                      const FormatSettings: TFormatSettings) : TDateTime

```

Visibility: default

Description: `StrToDateTime` converts the string `S` to a `TDateTime` date and time value. The date and time parts must be separated by a space.

For the date part, the same restrictions apply as for the `StrToDate` (1586) function: The Date must consist of 1 to three numbers, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the 3 numbers (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1616) exception is raised.

See also: `StrToDate` (1586), `StrToTime` (1593), `DateTimeToStr` (1500), `EConvertError` (1616)

Listing: `./sysutex/ex20.pp`

Program `Example20`;

{ This program demonstrates the StrToDateTime function }

Uses `sysutils`;

Procedure `TestStr` (`S` : **String**);

begin

WriteLn (`S`, ' : ', `DateTimeToStr(StrToDateTime(S))`);

end;

Begin

WriteLn ('ShortDateFormat ', `ShortDateFormat`);

TestStr(`DateTimeToStr(Now)`);

TestStr('05-05-1999 15:50 ');

TestStr('5-5 13:30 ');

TestStr('5 1:30PM');

End.

76.15.231 StrToDateTimeDef

Synopsis: Convert string to date/time, returning a default value

Declaration:

```
function StrToDateTimeDef(const S: ShortString;
                          const Defvalue: TDateTime) : TDateTime
function StrToDateTimeDef(const S: AnsiString;
                          const Defvalue: TDateTime) : TDateTime
```

Visibility: default

Description: `StrToDateTimeDef` tries to convert the string `S` to a valid `TDateTime` date and time value, and returns `DefValue` if `S` does not contain a valid date-time indication.

Errors: None.

See also: `StrToTimeDef` (1594), `StrToDateDef` (1587), `TryStrToDateTime` (1603), `StrToDateTime` (1587)

76.15.232 StrToDWord

Synopsis: Convert string to DWord (cardinal)

Declaration: `function StrToDWord(const s: string) : DWord`

Visibility: default

Description: `StrToDWord` will convert the string `S` to a `DWord` value, and returns the value.

Errors: In case the string `S` is not a valid number, or is a value outside the `DWord` range, an `EConvertError` exception will be raised.

See also: `TryStrToDWord` (1604), `StrToDWordDef` (1589)

76.15.233 StrToDWordDef

Synopsis: Convert string to DWord (cardinal), using default

Declaration: `function StrToDWordDef(const S: string; Default: DWord) : DWord`

Visibility: default

Description: `StrToDWordDef` will try to convert the string `S` to a `DWord` value. If the conversion was succesful, it returns the value.

If the conversion failed, the fallback value in `Default` is returned.

See also: `TryStrToDWord` (1604), `StrToDWord` (1589)

76.15.234 StrToFloat

Synopsis: Convert a string to a floating-point value.

Declaration: `function StrToFloat(const S: string) : Extended`
`function StrToFloat(const S: string;`
`const FormatSettings: TFormatSettings) : Extended`

Visibility: default

Description: `StrToFloat` converts the string `S` to a floating point value. `S` should contain a valid string representation of a floating point value (either in decimal or scientific notation). The `thousandseparator` character may however not be used.

Up to and including version 2.2.2 of the compiler, if the string contains a decimal value, then the decimal separator character can either be a `'.'` or the value of the `DecimalSeparator` variable.

As of version 2.3.1, the string may contain only the `DecimalSeparator` character. The dot `('')` can no longer be used instead of the `DecimalSeparator`.

Errors: If the string `S` doesn't contain a valid floating point string, then an exception will be raised.

See also: `TextToFloat` (1596), `FloatToStr` (1532), `FormatFloat` (1546), `StrToInt` (1590)

Listing: `./sysutex/ex90.pp`

Program `Example90`;

```
{ This program demonstrates the StrToFloat function }
{$mode objfpc}
{$h+ }
```

```

Uses SysUtils;

Const
  NrValues = 5;
  TestStr : Array[1..NrValues] of string =
    ('1,1 ', '-0,2 ', '1,2E-4 ', '0 ', '1E4 ');

Procedure Testit;

Var
  I : Integer;
  E : Extended;

begin
  Writeln('Using DecimalSeparator : ', DecimalSeparator);
  For I:=1 to NrValues do
    begin
      Writeln('Converting : ', TestStr[I]);
      Try
        E:=StrToFloat(TestStr[I]);
        Writeln('Converted value : ', E);
      except
        On E : Exception do
          Writeln('Exception when converting : ', E.Message);
        end;
      end;
    end;

  Begin
    DecimalSeparator:= ',';
    Testit;
    DecimalSeparator:= '.';
    Testit;
  End.

```

76.15.235 StrToFloatDef

Synopsis: Convert a string to a float, with a default value.

Declaration: function StrToFloatDef(const S: string; const Default: Extended)
: Extended
function StrToFloatDef(const S: string; const Default: Extended;
const FormatSettings: TFormatSettings) : Extended

Visibility: default

Description: StrToFloatDef tries to convert the string S to a floating point value, and returns this value. If the conversion fails for some reason, the value Default is returned instead.

Errors: None. On error, the Default value is returned.

76.15.236 StrToInt

Synopsis: Convert a string to an integer value.

Declaration: function StrToInt(const s: string) : LongInt

Visibility: default

Description: `StrToInt` will convert the string `S` to an integer. If the string contains invalid characters or has an invalid format, then an `EConvertError` (1616) is raised.

To be successfully converted, a string can contain a combination of `numerical` characters, possibly preceded by a minus sign (-). Spaces are not allowed.

The string `S` can contain a number in decimal, hexadecimal, binary or octal format, as described in the language reference. For enumerated values, the string must be the name of the enumerated value. The name is searched case insensitively.

For hexadecimal values, the prefix '0x' or 'x' (case insensitive) may be used as well.

Errors: In case of error, an `EConvertError` is raised.

See also: `IntToStr` (1558), `StrToIntDef` (1592), `EConvertError` (1616)

Listing: ./sysutex/ex82.pp

Program Example82;

{\$mode objfpc}

{ This program demonstrates the StrToInt function }

Uses sysutils;

Begin

WriteLn (`StrToInt`('1234'));

WriteLn (`StrToInt`('-1234'));

WriteLn (`StrToInt`('0'));

Try

WriteLn (`StrToInt`('12345678901234567890'));

except

On E : `EConvertError` **do**

WriteLn ('Invalid number encountered');

end;

End.

76.15.237 StrToInt64

Synopsis: Convert a string to an `Int64` value.

Declaration: `function StrToInt64(const s: string) : Int64`

Visibility: default

Description: `StrToInt64` converts the string `S` to a `Int64` value, and returns this value. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the \$ character) are supported.

Errors: On error, a `EConvertError` (1616) exception is raised.

See also: `TryStrToInt64` (1605), `StrToInt64Def` (1592), `StrToInt` (1590), `TryStrToInt` (1605), `StrToIntDef` (1592)

76.15.238 StrToInt64Def

Synopsis: Convert a string to an Int64 value, with a default value

Declaration: `function StrToInt64Def(const S: string; Default: Int64) : Int64`

Visibility: default

Description: `StrToInt64Def` tries to convert the string `S` to a `Int64` value, and returns this value. If the conversion fails for some reason, the value `Default` is returned instead.

Errors: None. On error, the `Default` value is returned.

See also: `StrToInt64` ([1591](#)), `TryStrToInt64` ([1605](#)), `StrToInt` ([1590](#)), `TryStrToInt` ([1605](#)), `StrToIntDef` ([1592](#))

76.15.239 StrToIntDef

Synopsis: Convert a string to an integer value, with a default value.

Declaration: `function StrToIntDef(const S: string; Default: LongInt) : LongInt`

Visibility: default

Description: `StrToIntDef` will convert a string to an integer. If the string contains invalid characters or has an invalid format, then `Default` is returned.

To be successfully converted, a string can contain a combination of numerical characters, possibly preceded by a minus sign (-). Spaces are not allowed.

Errors: None.

See also: `IntToStr` ([1558](#)), `StrToInt` ([1590](#))

Listing: `./sysutex/ex83.pp`

Program `Example82`;

`{ $mode objfpc }`

`{ This program demonstrates the StrToInt function }`

Uses `sysutils`;

Begin

`WriteLn (StrToIntDef ('1234' , 0));`

`WriteLn (StrToIntDef ('-1234' , 0));`

`WriteLn (StrToIntDef ('0' , 0));`

`Try`

`WriteLn (StrToIntDef ('12345678901234567890' , 0));`

`except`

`On E : EConvertError do`

`WriteLn ('Invalid number encountered');`

`end;`

End.

76.15.240 StrToQWord

Synopsis: Convert a string to a QWord.

```
Declaration: function StrToQWord(const s: string) : QWord
```

Visibility: default

Description: TryStrToQWord converts the string S to a valid QWord (unsigned 64-bit) value, and returns the result.

Errors: If the string `S` does not contain a valid `QWord` value, a `EConvertError` ([1616](#)) exception is raised.

See also: [TryStrToQWord \(1605\)](#), [StrToQWordDef \(1593\)](#), [StrToInt64 \(1591\)](#), [StrToInt \(1590\)](#)

76.15.241 StrToQWordDef

Synopsis: Try to convert a string to a QWord, returning a default value in case of failure.

Declaration: `function StrToQWordDef(const S: string; Default: QWord) : QWord`

Visibility: default

Description: `StrToQWordDef` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and returns the result. If the conversion fails, the function returns the value passed in `Def`.

See also: [StrToQWord \(1593\)](#), [TryStrToQWord \(1605\)](#), [StrToInt64Def \(1592\)](#), [StrToIntDef \(1592\)](#)

76.15.242 StrToTime

Synopsis: Convert a time string to a `TDateTime` value.

```
Declaration: function StrToTime(const S: Shortstring) : TDateTime
              function StrToTime(const S: Ansistring) : TDateTime
              function StrToTime(const S: ShortString; separator: Char) : TDateTime
              function StrToTime(const S: AnsiString; separator: Char) : TDateTime
              function StrToTime(const S: string; FormatSettings: TFormatSettings)
                  : TDateTime
              function StrToTime(const S: PChar; Len: Integer; separator: Char)
                  : TDateTime
```

Visibility: default

Description: `StrToTime` converts the string `S` to a `TDateTime` time value. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

Errors: On error (e.g. an invalid date or invalid character), an `EConvertError` (1616) exception is raised.

See also: [StrToDate \(1586\)](#), [StrToDateTime \(1587\)](#), [TimeToStr \(1599\)](#), [EConvertError \(1616\)](#)

Listing: ./sysutex/ex21.pp

Program Example21 ;

```
{ This program demonstrates the StrToTime function }
```

Uses sysutils;

```

Procedure TestStr (S : String);

begin
    WriteLn (S, ' : ', TimeToStr(StrToTime(S)));
end;

Begin
    teststr (TimeToStr(Time));
    teststr ('12:00');
    teststr ('15:30');
    teststr ('3:30PM');
End.

```

76.15.243 StrToTimeDef

Synopsis: Convert string to time, returning a default value

```
Declaration: function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime)
           : TDateTime
function StrToTimeDef(const S: ShortString; const Defvalue: TDateTime;
           separator: Char) : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime)
           : TDateTime
function StrToTimeDef(const S: AnsiString; const Defvalue: TDateTime;
           separator: Char) : TDateTime
```

Visibility: default

Description: `StrToTimeDef` tries to convert the string `S` to a valid `TDateTime` time value, and returns `DefValue` if `S` does not contain a valid time indication.

Errors: None.

See also: [StrToTime \(1593\)](#), [TryStrToTime \(1605\)](#), [StrToDateDef \(1587\)](#)

76.15.244 strupper

Synopsis: Convert null-terminated string to all-uppercase

```
Declaration: function strupper(p: PChar) : PChar
             function strupper(p: PWideChar) : PWideChar
```

Visibility: default

Description: Converts `P` to an all-uppercase string. Returns `P`.

For an example, see [StrLower \(1581\)](#)

Errors: None.

See also: [StrLower \(1581\)](#)

76.15.245 Supports

Synopsis: Check whether a class or given interface supports an interface

Declaration:

```
function Supports(const Instance: IInterface; const AClass: TClass;
                  out Obj) : Boolean; Overload
function Supports(const Instance: IInterface; const IID: TGuid;
                  out Intf) : Boolean; Overload
function Supports(const Instance: TObject; const IID: TGuid; out Intf)
                  : Boolean; Overload
function Supports(const Instance: TObject; const IID: Shortstring;
                  out Intf) : Boolean; Overload
function Supports(const Instance: IInterface; const AClass: TClass)
                  : Boolean; Overload
function Supports(const Instance: IInterface; const IID: TGuid)
                  : Boolean; Overload
function Supports(const Instance: TObject; const IID: TGuid) : Boolean
                  ; Overload
function Supports(const Instance: TObject; const IID: Shortstring)
                  : Boolean; Overload
function Supports(const AClass: TClass; const IID: TGuid) : Boolean
                  ; Overload
function Supports(const AClass: TClass; const IID: Shortstring)
                  : Boolean; Overload
```

Visibility: default

Description: Supports checks whether Instance supports the interface identified by IID. It returns True if it is supported, False. Optionally, a pointer to the interface is returned to Intf.

Errors: None.

See also: StringToGUID ([1577](#))

76.15.246 SysErrorMessage

Synopsis: Format a system error message.

Declaration: function SysErrorMessage(ErrorCode: Integer) : string

Visibility: default

Description: SysErrorMessage returns a string that describes the operating system error code ErrorCode.

Errors: This routine may not be implemented on all platforms.

See also: EOSError ([1620](#))

76.15.247 SystemTimeToDateTime

Synopsis: Convert a system time to a TDateTime value.

Declaration: function SystemTimeToDateTime(const SystemTime: TSystemTime) : TDateTime

Visibility: default

Description: SystemTimeToDateTime converts a TSystemTime record to a TDateTime style date/time indication.

Errors: None.

See also: DateTimeToSystemTime ([1501](#))

Listing: ./sysutex/ex22.pp

Program Example22;

{ This program demonstrates the SystemTimeToDateTime function }

Uses sysutils;

Var ST : TSystemTime;

Begin

 DateTimeToSystemTime(**Now**,ST);

With St **do**

begin

Writeln ('Today is ',year,'/',month,'/',Day);

Writeln ('The time is ',Hour,':',minute,':',Second,'.',',MilliSecond);

end;

Writeln ('Converted : ',DateTimeToStr(SystemTimeToDateTime(ST)));

End.

76.15.248 TextToFloat

Synopsis: Convert a buffer to a float value.

Declaration: function TextToFloat(Buffer: PChar; out Value: Extended) : Boolean
 function TextToFloat(Buffer: PChar; out Value: Extended;
 const FormatSettings: TFormatSettings) : Boolean
 function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue)
 : Boolean
 function TextToFloat(Buffer: PChar; out Value; ValueType: TFloatValue;
 const FormatSettings: TFormatSettings) : Boolean

Visibility: default

Description: TextToFloat converts the string in Buffer to a floating point value. Buffer should contain a valid stroing representation of a floating point value (either in decimal or scientific notation). If the buffer contains a decimal value, then the decimal separator character can either be a '.' or the value of the DecimalSeparator variable.

The function returns True if the conversion was successful.

Errors: If there is an invalid character in the buffer, then the function returns False

See also: StrToFloat ([1589](#)), FloatToStr ([1532](#)), FormatFloat ([1546](#))

Listing: ./sysutex/ex91.pp

Program Example91;

{ This program demonstrates the TextToFloat function }

{ \$mode objfpc }

{ \$h+ }

Uses SysUtils;

Const

 NrValues = 5;

 TestStr : **Array**[1..NrValues] **of** pchar =

```
( '1,1 ', '-0,2 ', '1,2E-4 ', '0 ', '1E4 ' );
```

```
Procedure Testit;
```

```
Var
```

```
  I : Integer;  
  E : Extended;
```

```
begin
```

```
  WriteLn( 'Using DecimalSeparator : ', DecimalSeparator);
```

```
  For I:=1 to NrValues do
```

```
    begin
```

```
      WriteLn( 'Converting : ', TestStr[i]);
```

```
      If TextToFloat( TestStr[i],E) then
```

```
        WriteLn( 'Converted value : ',E)
```

```
      else
```

```
        WriteLn( 'Unable to convert value.');
```

```
      end;
```

```
end;
```

```
Begin
```

```
  DecimalSeparator:= ',';
```

```
  Testit;
```

```
  DecimalSeparator:= '.';
```

```
  Testit;
```

```
End.
```

76.15.249 Time

Synopsis: Returns the current time.

Declaration: `function Time : TDateTime`

Visibility: default

Description: Time returns the current time in TDateTime format. The date part of the TDateTimeValue is set to zero.

Errors: None.

See also: Now ([1564](#)), Date ([1499](#))

Listing: ./sysutex/ex23.pp

Program Example23;

```
{ This program demonstrates the Time function }
```

```
Uses sysutils;
```

```
Begin
```

```
  WriteLn ( 'The time is : ', TimeToStr(Time));
```

```
End.
```

76.15.250 TimeStampToDateTime

Synopsis: Convert a TimeStamp value to a TDateTime value.

Declaration: `function TimeStampToDateTime(const TimeStamp: TTimeStamp) : TDateTime`

Visibility: default

Description: `TimeStampToDateTime` converts `TimeStamp` to a `TDateTime` format variable. It is the inverse operation of `DateTimeToTimeStamp` (1502).

Errors: None.

See also: `DateTimeToTimeStamp` (1502), `TimeStampToMSecs` (1598)

Listing: `./sysutex/ex24.pp`

Program `Example24`;

{ This program demonstrates the TimeStampToDateTime function }

Uses `sysutils`;

Var `TS : TTimeStamp;`
 `DT : TDateTime;`

Begin

`TS:=DateTimeToTimeStamp (Now);`

With `TS do`

begin

`WriteLn ('Now is ',time,' millisecond past midnight');`

`WriteLn ('Today is ',Date,' days past 1/1/0001');`

end;

`DT:=TimeStampToDateTime(TS);`

`WriteLn ('Together this is : ',DateTimeToStr(DT));`

End.

76.15.251 TimeStampToMSecs

Synopsis: Converts a timestamp to a number of milliseconds.

Declaration: `function TimeStampToMSecs(const TimeStamp: TTimeStamp) : comp`

Visibility: default

Description: `TimeStampToMSecs` converts `TimeStamp` to the number of milliseconds since 1/1/0001.

Use `TTimeStamp` variables if you need to keep very precise track of time.

For an example, see `MSecsToTimeStamp` (1563).

Errors: None.

See also: `MSecsToTimeStamp` (1563), `TimeStampToDateTime` (1598)

76.15.252 TimeToStr

Synopsis: Convert a `TDateTime` time to a string using a predefined format.

Declaration: `function TimeToStr(Time: TDateTime) : string`
`function TimeToStr(Time: TDateTime;`
`const FormatSettings: TFormatSettings) : string`

Visibility: default

Description: `TimeToStr` converts the time in `Time` to a string. It uses the `LongTimeFormat` variable to see what formatting needs to be applied. It is therefor entirely equivalent to a `FormatDateTime('tt', Time)` call.

Errors: None.

Listing: `./sysutex/ex25.pp`

Program `Example25;`

{ This program demonstrates the TimeToStr function }

Uses `sysutils;`

Begin

`WriteLn ('The current time is : ', TimeToStr(Time));`

End.

76.15.253 Trim

Synopsis: Trim whitespace from the ends of a string.

Declaration: `function Trim(const S: string) : string`
`function Trim(const S: WideString) : WideString`
`function Trim(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the beginning and end of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `TrimLeft` ([1600](#)), `TrimRight` ([1600](#))

Listing: `./sysutex/ex84.pp`

Program `Example84;`

{ This program demonstrates the Trim function }

Uses `sysutils;`

`{ $H+ }`

Procedure `Testit (S : String);`

```

begin
  Writeln ( ' ', Trim(S), ' ');
end;

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

76.15.254 TrimLeft

Synopsis: Trim whitespace from the beginning of a string.

Declaration: `function TrimLeft(const S: string) : string`
`function TrimLeft(const S: WideString) : WideString`
`function TrimLeft(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the beginning of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1599](#)), `TrimRight` ([1600](#))

Listing: `./sysutex/ex85.pp`

Program Example85;

{ This program demonstrates the TrimLeft function }

Uses sysutils;
`{ $H+ }`

Procedure Testit (S : **String**);

```

begin
  Writeln ( ' ', TrimLeft(S), ' ');
end;

```

```

Begin
  Testit ( '  ha ha what gets lost ? ');
  Testit (#10#13'haha ');
  Testit ( '          ');
End.

```

76.15.255 TrimRight

Synopsis: Trim whitespace from the end of a string.

Declaration: `function TrimRight(const S: string) : string`
`function TrimRight(const S: WideString) : WideString`
`function TrimRight(const S: UnicodeString) : UnicodeString`

Visibility: default

Description: `Trim` strips blank characters (spaces and control characters) at the end of `S` and returns the resulting string. All characters with ordinal values less than or equal to 32 (a space) are stripped.

If the string contains only spaces, an empty string is returned.

Errors: None.

See also: `Trim` ([1599](#)), `TrimLeft` ([1600](#))

Listing: `./sysutex/ex86.pp`

Program `Example86`;

{ This program demonstrates the TrimRight function }

Uses `sysutils`;
`{ $H+ }`

Procedure `Testit (S : String)`;

begin
 WriteLn (' ', TrimRight(S), ' ');
end;

Begin
 Testit (' ha ha what gets lost ? ');
 Testit (#10#13'haha ');
 Testit (' ');
End.

76.15.256 TryEncodeDate

Synopsis: Try to encode a date, and indicate success.

Declaration: `function TryEncodeDate(Year: Word; Month: Word; Day: Word;
 out Date: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeDate` will check the validity of the `Year`, `Month` and `Day` arguments, and if they are all valid, then they will be encoded as a `TDateTime` value and returned in `Date`. The function will return `True` in this case. If an invalid argument is passed, then `False` will be returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeDate` ([1508](#)), `DecodeDateFully` ([1504](#)), `DecodeDate` ([1503](#)), `TryEncodeTime` ([1601](#))

76.15.257 TryEncodeTime

Synopsis: Try to encode a time, and indicate success.

Declaration: `function TryEncodeTime(Hour: Word; Min: Word; Sec: Word; MSec: Word;
 out Time: TDateTime) : Boolean`

Visibility: default

Description: `TryEncodeTime` will check the validity of the `Hour`, `Min`, `Sec` and `MSec` arguments, and will encode them in a `TDateTime` value which is returned in `Time`. If the arguments are valid, then `True` is returned, otherwise `False` is returned.

Errors: None. If an error occurs during the encoding, `False` is returned.

See also: `EncodeTime` ([1509](#)), `DecodeTime` ([1504](#)), `TryEncodeDate` ([1601](#))

76.15.258 TryFloatToCurr

Synopsis: Try to convert a float value to a currency value and report on success.

Declaration: `function TryFloatToCurr(const Value: Extended; var AResult: Currency) : Boolean`

Visibility: default

Description: `TryFloatToCurr` tries convert the `Value` floating point value to a `Currency` value. If successful, the function returns `True` and the resulting currency value is returned in `AResult`. It checks whether `Value` is in the valid range of currencies (determined by `MinCurrency` ([1454](#)) and `MaxCurrency` ([1454](#))). If not, `False` is returned.

Errors: If `Value` is out of range, `False` is returned.

See also: `FloatToCurr` ([1531](#)), `MinCurrency` ([1454](#)), `MaxCurrency` ([1454](#))

76.15.259 TryStringToGUID

Synopsis: Try to transform a string to a GUID

Declaration: `function TryStringToGUID(const S: string; out Guid: TGUID) : Boolean`

Visibility: default

Description: `TryStringToGUID` tries to convert the string `S` to a `TGUID` value, returned in `GUID`. It returns `True` if the conversion succeeds, and `False` if the string `S` does not contain a valid GUID notation. The string `S` must be 38 characters long, must start with `{` and end on `}`, and contain a valid GUID string (hex number grouped using 8-4-4-4-12 digits).

Errors: In case `S` does not contain a valid GUID number, `False` is returned.

See also: `StringToGUID` ([1577](#))

76.15.260 TryStrToBool

Synopsis: Try to convert a string to a boolean value

Declaration: `function TryStrToBool(const S: string; out Value: Boolean) : Boolean`

Visibility: default

Description: `TryStrToBool` tries to convert the string `S` to a boolean value, and returns this value in `Value`. In this case, the function returns `True`. If `S` does not contain a valid boolean string, the function returns `False`, and the contents of `Value` is indetermined.

Valid boolean string constants are in the `FalseBoolStrs` ([1470](#)) (for `False` values) and `TrueBoolStrs` ([1473](#)) (for `True` values) variables.

See also: `StrToBool` ([1585](#)), `StrToBoolDef` ([1585](#))

76.15.261 TryStrToCurr

Synopsis: Try to convert a string to a currency

Declaration: `function TryStrToCurr(const S: string; out Value: Currency) : Boolean`
`function TryStrToCurr(const S: string; out Value: Currency;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToCurr` converts the string `S` to a currency value and returns the value in `Value`. The function returns `True` if it was successful, `False` if not. This is contrary to `StrToCurr` (1585), which raises an exception when the conversion fails.

The function takes into account locale information.

See also: `StrToCurr` (1585), `TextToFloat` (1596)

76.15.262 TryStrToDate

Synopsis: Try to convert a string with a date indication to a `TDateTime` value

Declaration: `function TryStrToDate(const S: ShortString; out Value: TDateTime)`
`: Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime)`
`: Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime;`
`separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime;`
`separator: Char) : Boolean`
`function TryStrToDate(const S: ShortString; out Value: TDateTime;`
`const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: AnsiString; out Value: TDateTime;`
`const useformat: string; separator: Char) : Boolean`
`function TryStrToDate(const S: string; out Value: TDateTime;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToDate` tries to convert the string `S` to a `TDateTime` date value, and stores the date in `Value`. The Date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month. (This is *not* supported in Delphi)

The order of the digits (y/m/d, m/d/y, d/m/y) is determined from the `ShortDateFormat` variable.

The function returns `True` if the string contained a valid date indication, `False` otherwise.

See also: `StrToDate` (1586), `StrToTime` (1593), `TryStrToTime` (1605), `TryStrToDateTime` (1603), `DateToStr` (1502), `TimeToStr` (1599)

76.15.263 TryStrToDateTime

Synopsis: Try to convert a string with date/time indication to a `TDateTime` value

Declaration: `function TryStrToDateTime(const S: ShortString; out Value: TDateTime)`
`: Boolean`

```
function TryStrToDateTime(const S: AnsiString; out Value: TDateTime)
    : Boolean
function TryStrToDateTime(const S: string; out Value: TDateTime;
    const FormatSettings: TFormatSettings)
    : Boolean
```

Visibility: default

Description: `TryStrToDateTime` tries to convert the string `S` to a `TDateTime` date and time value, and stores the result in `Value`. The date must consist of 1 to three digits, separated by the `DateSeparator` character. If two numbers are given, they are supposed to form the day and month of the current year. If only one number is given, it is supposed to represent the day of the current month (This is *not* supported in Delphi). The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid date and time indication, `False` otherwise.

See also: `TryStrToDate` ([1603](#)), `TryStrToTime` ([1605](#)), `StrToDateTime` ([1587](#)), `StrToTime` ([1593](#)), `DateToStr` ([1502](#)), `TimeToStr` ([1599](#))

76.15.264 TryStrToDWord

Synopsis: Try to convert a string to DWord (cardinal)

Declaration: `function TryStrToDWord(const s: string; out D: DWord) : Boolean`

Visibility: default

Description: `TryStrToDWord` will try to convert the string `S` to a `DWord` value. It returns `True` if the conversion was successful, and in that case returns the value in `D`.

If the conversion failed or the value was outside of the valid range for `DWord` values, `False` is returned.

See also: `StrToDWord` ([1589](#)), `StrToDWordDef` ([1589](#))

76.15.265 TryStrToFloat

Synopsis: Try to convert a string to a float.

Declaration: `function TryStrToFloat(const S: string; out Value: Single) : Boolean`
`function TryStrToFloat(const S: string; out Value: Single;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double) : Boolean`
`function TryStrToFloat(const S: string; out Value: Double;`
`const FormatSettings: TFormatSettings) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended) : Boolean`
`function TryStrToFloat(const S: string; out Value: Extended;`
`const FormatSettings: TFormatSettings) : Boolean`

Visibility: default

Description: `TryStrToFloat` tries to convert the string `S` to a floating point value, and stores the result in `Value`. It returns `True` if the operation was successful, and `False` if it failed. This operation takes into account the system settings for floating point representations.

Errors: On error, `False` is returned.

See also: `StrToFloat` ([1589](#))

76.15.266 TryStrToInt

Synopsis: Try to convert a string to an integer, and report on success.

Declaration: `function TryStrToInt(const s: string; out i: LongInt) : Boolean`

Visibility: default

Description: `TryStrToInt` tries to convert the string `S` to an integer, and returns `True` if this was successful. In that case the converted integer is returned in `I`. If the conversion failed, (an invalid string, or the value is out of range) then `False` is returned.

Errors: None. On error, `False` is returned.

See also: `StrToInt` ([1590](#)), `TryStrToInt64` ([1605](#)), `StrToIntDef` ([1592](#)), `StrToInt64` ([1591](#)), `StrToInt64Def` ([1592](#))

76.15.267 TryStrToInt64

Synopsis: Try to convert a string to an int64 value, and report on success.

Declaration: `function TryStrToInt64(const s: string; out i: Int64) : Boolean`

Visibility: default

Description: `TryStrToInt64` tries to convert the string `S` to a `Int64` value, and returns this value in `I` if successful. If the conversion was successful, the function result is `True`, or `False` otherwise. The string can only contain numerical characters, and optionally a minus sign as the first character. Whitespace is not allowed.

Hexadecimal values (starting with the `$` character) are supported.

Errors: None. On error, `False` is returned.

See also: `StrToInt64` ([1591](#)), `StrToInt64Def` ([1592](#)), `StrToInt` ([1590](#)), `TryStrToInt` ([1605](#)), `StrToIntDef` ([1592](#))

76.15.268 TryStrToQWord

Synopsis: Try to convert a string to a QWord value, and report on success

Declaration: `function TryStrToQWord(const s: string; out Q: QWord) : Boolean`

Visibility: default

Description: `TryStrToQWord` tries to convert the string `S` to a valid `QWord` (unsigned 64-bit) value, and stores the result in `I`. If the conversion fails, the function returns `False`, else it returns `True`.

See also: `StrToQWord` ([1593](#)), `StrToQWordDef` ([1593](#)), `TryStrToInt64` ([1605](#)), `TryStrToInt` ([1605](#))

76.15.269 TryStrToTime

Synopsis: Try to convert a string with a time indication to a `TDateTime` value

```
Declaration: function TryStrToTime(const S: ShortString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime)
              : Boolean
function TryStrToTime(const S: ShortString; out Value: TDateTime;
              separator: Char) : Boolean
function TryStrToTime(const S: AnsiString; out Value: TDateTime;
```

```

        separator: Char) : Boolean
function TryStrToTime(const S: string; out Value: TDateTime;
        const FormatSettings: TFormatSettings) : Boolean

```

Visibility: default

Description: `TryStrToTime` tries to convert the string `S` to a `TDateTime` time value, and stores the result in `Value`. The time must consist of 1 to 4 digits, separated by the `TimeSeparator` character. If two numbers are given, they are supposed to form the hour and minutes.

The function returns `True` if the string contained a valid time indication, `False` otherwise.

See also: `TryStrToDate` ([1603](#)), `TryStrToDateTime` ([1603](#)), `StrToDate` ([1586](#)), `StrToTime` ([1593](#)), `DateToStr` ([1502](#)), `TimeToStr` ([1599](#))

76.15.270 UnhookSignal

Synopsis: `UnHook` a specified signal

Declaration: `procedure UnhookSignal(RtlSigNum: Integer; OnlyIfHooked: Boolean)`

Visibility: default

Description: `UnHookSignal` de-installs the RTL default signal handler for signal `RtlSigNum`. If `OnlyIfHooked` is `True` then `UnhookSignal` will first check if the signal was hooked by the RTL routines, and has not been overridden since.

76.15.271 UnicodeCompareStr

Synopsis: Compare 2 unicode strings

Declaration: `function UnicodeCompareStr(const s1: UnicodeString;
 const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareStr` compares 2 unicode strings `S1` and `S2` in a case sensitive manner. The result of the function is

< 0 If `S1`<`S2`

0 If `S1`=`S2`

> 0 If `S1`>`S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1606](#)), `CompareStr` ([1494](#)), `CompareText` ([1495](#)), `UnicodeSameStr` ([1608](#))

76.15.272 UnicodeCompareText

Synopsis: Compare 2 strings case insensitively

Declaration: `function UnicodeCompareText(const s1: UnicodeString;
 const s2: UnicodeString) : PtrInt`

Visibility: default

Description: `UnicodeCompareText` compares 2 unicode strings `S1` and `S2`, ignoring case. The result of the function is

< 0 If `S1 < S2`

0 If `S1 = S2`

> 0 If `S1 > S2`

This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` (1606), `CompareStr` (1494), `CompareText` (1495), `UnicodeSameStr` (1608)

76.15.273 UnicodeFmtStr

Synopsis: Format a string with given arguments, procedural version.

Declaration:

```
procedure UnicodeFmtStr(var Res: UnicodeString;
                        const Fmt: UnicodeString;
                        const args: Array of const)
procedure UnicodeFmtStr(var Res: UnicodeString;
                        const Fmt: UnicodeString;
                        const args: Array of const;
                        const FormatSettings: TFormatSettings)
```

Visibility: default

Description: `UnicodeFmtStr` calls `UnicodeFormat` (1607) with `Fmt` and `Args` as arguments, and stores the result in `Res`. For more information on how the resulting string is composed, see `UnicodeFormat` (1607).

Errors: In case of error, an `EConvertError` (1616) exception is raised.

See also: `UnicodeFormat` (1607), `UnicodeFormatBuf` (1608)

76.15.274 UnicodeFormat

Synopsis: Format unicode string

Declaration:

```
function UnicodeFormat(const Fmt: UnicodeString;
                       const Args: Array of const) : UnicodeString
function UnicodeFormat(const Fmt: UnicodeString;
                       const Args: Array of const;
                       const FormatSettings: TFormatSettings)
                       : UnicodeString
```

Visibility: default

Description: `UnicodeFormat` is the unicode equivalent of `Format` (1537). It follows the same rules and uses the same formatting strings.

Errors: In case of error, an `EConvertError` (1616) exception is raised.

See also: `Format` (1537), `UnicodeFormatBuf` (1608)

76.15.275 UnicodeFormatBuf

Synopsis: Format a unicode string with given arguments and store the result in a unicodebuffer.

Declaration:

```
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                           fmtLen: Cardinal; const Args: Array of const)
                           : Cardinal
function UnicodeFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                           fmtLen: Cardinal; const Args: Array of const;
                           const FormatSettings: TFormatSettings)
                           : Cardinal
```

Visibility: default

Description: `UnicodeFormatBuf` is the unicode equivalent of `FormatBuf` ([1544](#)). It follows the same rules and uses the same formatting st

Errors: In case of error, an `EConvertError` ([1616](#)) exception is raised.

See also: `FormatBuf` ([1544](#)), `UnicodeFormat` ([1607](#))

76.15.276 UnicodeLowerCase

Synopsis: Return lowercase version of a string

Declaration:

```
function UnicodeLowerCase(const s: UnicodeString) : UnicodeString
```

Visibility: default

Description: `UnicodeLowerCase` returns an all-lowercase version of the unicodestring `S`. It relies on the unicode manager to do so.

See also: `UnicodeUpperCase` ([1609](#)), `UpperCase` ([1609](#)), `LowerCase` ([1562](#))

76.15.277 UnicodeSameStr

Synopsis: Check whether 2 strings are equal

Declaration:

```
function UnicodeSameStr(const s1: UnicodeString;
                        const s2: UnicodeString) : Boolean
```

Visibility: default

Description: `UnicodeSameStr` checks whether the unicode strings `S1` and `S2` are equal, case sensitively. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` ([1606](#)), `CompareStr` ([1494](#)), `CompareText` ([1495](#)), `UnicodeSameText` ([1608](#)), `SameStr` ([1568](#))

76.15.278 UnicodeSameText

Synopsis: Check whether 2 strings are the same, ignoring case

Declaration:

```
function UnicodeSameText(const s1: UnicodeString;
                        const s2: UnicodeString) : Boolean
```

Visibility: default

Description: `UnicodeSameText` checks whether the unicode strings `S1` and `S2` are equal, ignoring case. The function returns `True` if the strings are equal, `False` if they are not. This function relies on a widestring manager to perform the actual comparison, as it will take into account various equivalent code points: it is not a simple byte-by-byte comparison.

See also: `UnicodeCompareText` (1606), `CompareStr` (1494), `CompareText` (1495), `UnicodeSameStr` (1608), `SameText` (1568)

76.15.279 UnicodeStringReplace

Synopsis: Replace one occurrence of a string with another

Declaration: `function UnicodeStringReplace(const S: UnicodeString;
const OldPattern: UnicodeString;
const NewPattern: UnicodeString;
Flags: TReplaceFlags) : UnicodeString`

Visibility: default

Description: `UnicodeStringReplace` is the unicode version of `StringReplace` (1576); it follows the same rules and has the same behaviour, but operates on unicode strings instead of ansistrings.

See also: `StringReplace` (1576)

76.15.280 UnicodeUpperCase

Synopsis: Return uppercase version of a string

Declaration: `function UnicodeUpperCase(const s: UnicodeString) : UnicodeString`

Visibility: default

Description: `UnicodeUpperCase` returns an all-uppercase version of the unicodestring `S`. It relies on the unicode manager to do so.

See also: `UnicodeLowerCase` (1608), `LowerCase` (1562), `UpperCase` (1609)

76.15.281 UpperCase

Synopsis: Return an uppercase version of a string.

Declaration: `function UpperCase(const s: string) : string; Overload
function UpperCase(const s: UnicodeString) : UnicodeString; Overload`

Visibility: default

Description: `UpperCase` returns the uppercase equivalent of `S`. Ansi characters are not taken into account, only ASCII codes below 127 are converted. It is completely equivalent to the `UpCase` function of the system unit, and is provided for compatibility only.

Errors: None.

See also: `AnsiLowerCase` (1479), `LowerCase` (1562), `AnsiUpperCase` (1487)

Listing: `./sysutex/ex87.pp`

The comparison takes into account wide characters, i.e. it takes care of strange accented characters.
Contrary to `WideCompareText` (1611), the comparison is case sensitive.

Errors: None.

See also: `WideCompareText` (1611), `WideSameStr` (1612), `WideSameText` (1613)

76.15.285 `WideCompareText`

Synopsis: Compare two widestrings (ignoring case).

Declaration: `function WideCompareText(const s1: WideString; const s2: WideString)
: PtrInt`

Visibility: default

Description: `WideCompareStr` compares two widestrings and returns the following result:

`< 0` if `S1 < S2`.
`0` if `S1 = S2`.
`> 0` if `S1 > S2`.

The comparison takes into account wide characters, i.e. it takes care of strange accented characters.
Contrary to `WideCompareStr` (1610), the comparison is case insensitive.

Errors: None.

See also: `WideCompareStr` (1610), `WideSameStr` (1612), `WideSameText` (1613)

76.15.286 `WideFmtStr`

Synopsis: Widestring format

Declaration: `procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
const args: Array of const)
procedure WideFmtStr(var Res: WideString; const Fmt: WideString;
const args: Array of const;
const FormatSettings: TFormatSettings)`

Visibility: default

Description: `WideFmtStr` formats `Args` according to the format string in `Fmt` and returns the resulting string
in `Res`.

See also: `WideFormat` (1611), `WideFormatBuf` (1612), `Format` (1537)

76.15.287 `WideFormat`

Synopsis: Format a wide string.

Declaration: `function WideFormat(const Fmt: WideString; const Args: Array of const)
: WideString
function WideFormat(const Fmt: WideString; const Args: Array of const;
const FormatSettings: TFormatSettings) : WideString`

Visibility: default

Description: `WideFormat` does the same as `Format` ([1537](#)) but accepts as a formatting string a `WideString`. The resulting string is also a `WideString`.

For more information about the used formatting characters, see the `Format` ([1537](#)) string.

See also: `Format` ([1537](#))

76.15.288 WideFormatBuf

Synopsis: Format widestring in a buffer.

Declaration:

```
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                      fmtLen: Cardinal; const Args: Array of const)
                      : Cardinal
function WideFormatBuf(var Buffer; BufLen: Cardinal; const Fmt;
                      fmtLen: Cardinal; const Args: Array of const;
                      const FormatSettings: TFormatSettings) : Cardinal
```

Visibility: default

Description: `WideFormatBuf` calls simply `WideFormat` ([1611](#)) with `Fmt` (with length `FmtLen` bytes) and stores maximum `BufLen` bytes in the buffer `buf`. It returns the number of copied bytes.

See also: `WideFmtStr` ([1611](#)), `WideFormat` ([1611](#)), `Format` ([1537](#)), `FormatBuf` ([1544](#))

76.15.289 WideLowerCase

Synopsis: Change a widestring to all-lowercase.

Declaration: `function WideLowerCase(const s: WideString) : WideString`

Visibility: default

Description: `WideLowerCase` converts the string `S` to lowercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideUpperCase` ([1614](#))

76.15.290 WideSameStr

Synopsis: Check whether two widestrings are the same (case sensitive)

Declaration: `function WideSameStr(const s1: WideString; const s2: WideString) : Boolean`

Visibility: default

Description: `WideSameStr` returns `True` if `WideCompareStr` ([1610](#)) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameText` ([1613](#)), `WideCompareStr` ([1610](#)), `WideCompareText` ([1611](#)), `AnsiSameStr` ([1481](#))

76.15.291 WideStringText

Synopsis: Check whether two wstrings are the same (ignoring case)

Declaration: `function WideStringText(const s1: WideString; const s2: WideString)
: Boolean`

Visibility: default

Description: `WideStringText` returns `True` if `WideCompareText` (1611) returns 0 (zero), i.e. when `S1` and `S2` are the same string (taking into account case).

See also: `WideSameStr` (1612), `WideCompareStr` (1610), `WideCompareText` (1611), `AnsiSameText` (1481)

76.15.292 WideStrAlloc

Synopsis: Allocate a null-terminated wstring on the heap.

Declaration: `function WideStrAlloc(size: Cardinal) : PWideChar`

Visibility: default

Description: `WideStrAlloc` reserves memory on the heap for a wstring with length `Len`, (terminating `#0#0` included), and returns a pointer to it.

Additionally, `WideStrAlloc` allocates 4 extra bytes to store the size of the allocated memory.

Errors: None.

See also: `StrBufSize` (1570), `StrDispose` (1573), `StrAlloc` (1147)

76.15.293 WideStringOf

Synopsis: Create unicode string from array of bytes

Declaration: `function WideStringOf(const Value: TBytes) : UnicodeString`

Visibility: default

Description: `WideStringOf` converts an array of bytes (`Bytes`) to a unicode string. It considers each pair of bytes in the array as a single wide char. The array should have an even length. If the length is uneven, the last byte will be ignored.

This function performs the opposite operation of `BytesOf` (1491).

To create a string where the bytes are interpreted as ansichars, use `StringOf` (1576) instead.

See also: `StringOf` (1576), `WideBytesOf` (1610), `BytesOf` (1491)

76.15.294 WideStringReplace

Synopsis: Replace occurrences of one substring with another in a wstring.

Declaration: `function WideStringReplace(const S: WideString;
const OldPattern: WideString;
const NewPattern: WideString;
Flags: TReplaceFlags) : WideString`

Visibility: default

Description: `WideStringReplace` searches the string `S` for occurrences of the string `OldPattern` and, if it is found, replaces it with `NewPattern`. It returns the resulting string. The behaviour of `StringReplace` can be runed with `Flags`, which is of type `TReplaceFlags` (1465). Standard behaviour is to replace only the first occurrence of `OldPattern`, and to search case sensitively.

Errors: None.

See also: `TReplaceFlags` (1465), `StringReplace` (1576)

76.15.295 WideStringUpperCase

Synopsis: Change a widestring to all-uppercase.

Declaration: `function WideStringUpperCase(const s: WideString) : WideString`

Visibility: default

Description: `WideUpperCase` converts the string `S` to uppercase characters and returns the resulting string. It takes into account the operating system language settings when doing this, so special characters are converted correctly as well.

Remark: On Unix-like platforms, a widestring manager must be installed for this function to work correctly.

Errors: None.

See also: `WideLowerCase` (1612)

76.15.296 WrapText

Synopsis: Word-wrap a text.

Declaration: `function WrapText(const Line: string; const BreakStr: string;
const BreakChars: TSysCharSet; MaxCol: Integer)
: string
function WrapText(const Line: string; MaxCol: Integer) : string`

Visibility: default

Description: `WrapText` does a wordwrap at column `MaxCol` of the string in `Line`. It breaks the string only at characters which are in `BreakChars` (default whitespace and hyphen) and inserts then the string `BreakStr` (default the lineending character for the current OS).

Portions of text that are between single or double quotes will be considered single words and the text will not be broken between the quotes.

See also: `StringReplace` (1576)

76.16 EAbort

76.16.1 Description

`Abort` is raised by the `Abort` (1474) procedure. It is not displayed in GUI applications, and serves only to immediately abort the current procedure, and return control to the main program loop.

See also: `Abort` (1474)

76.17 EAbstractError

76.17.1 Description

`EAbstractError` is raised when an abstract error occurs, i.e. when an unimplemented abstract method is called.

76.18 EAccessViolation

76.18.1 Description

`EAccessViolation` is raised when the OS reports an Access Violation, i.e. when invalid memory is accessed.

See also: `EObjectCheck` ([1620](#))

76.19 EArgumentException

76.19.1 Description

`EArgumentException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (usually indicating an invalid codepoint in a unicode string).

See also: `EArgumentOutOfRangeException` ([1615](#))

76.20 EArgumentNilException

76.20.1 Description

`EArgumentNilException` is an exception raised when an argument is `Nil` when it should not be `Nil`.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1623](#))

76.21 EArgumentOutOfRangeException

76.21.1 Description

`EArgumentOutOfRangeException` is raised by many character conversion/handling routines to indicate an erroneous argument was passed to the function (indicating an invalid character index in a unicode string).

See also: `EArgumentException` ([1615](#))

76.22 EAssertionFailed

76.22.1 Description

`EAssertionFailed` is raised when an application that is compiled with assertions, encounters an invalid assertion.

76.23 EBusError

76.23.1 Description

`EBusError` is raised in case of a bus error.

76.24 EControlC

76.24.1 Description

`EControlC` is raised when the user has pressed CTRL-C in a console application.

76.25 EConvertError

76.25.1 Description

`EConvertError` is raised by the various conversion routines in the `SysUtils` unit. The message will contain more specific error information.

76.26 EDirectoryNotFoundException

76.26.1 Description

`EDirectoryNotFoundException` is an exception raised when a directory is referenced that does not exist.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1623](#)), `EFileNotFoundException` ([1617](#)), `EPathNotFoundException` ([1621](#)), `EPathTooLongException` ([1621](#))

76.27 EDivByZero

76.27.1 Description

`EDivByZero` is used when the operating system or CPU signals a division by zero error.

76.28 EEncodingError

76.28.1 Description

`EEncodingError` is the exception classed used by the `TEncoding` class to indicate errors.

See also: TEncoding ([1644](#))

76.29 EExternal

76.29.1 Description

EExternal is the base exception for all external exceptions, as reported by the CPU or operating system, as opposed to internal exceptions, which are raised by the program itself. The SysUtils unit converts all operating system errors to descendents of EExternal.

See also: EInterror ([1618](#)), EExternal ([1617](#)), EMathError ([1619](#)), EExternalException ([1617](#)), EAccessViolation ([1615](#)), EPrivilege ([1622](#)), EStackOverflow ([1622](#)), EControlC ([1616](#))

76.30 EExternalException

76.30.1 Description

EExternalException is raised when an external routine raises an exception.

See also: EExternal ([1617](#))

76.31 EFileNotFoundException

76.31.1 Description

EFileNotFoundException is an exception raised when a file is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: Exception ([1623](#)), EPathNotFoundException ([1621](#)), EDirectoryNotFoundException ([1616](#)), EPathTooLongException ([1621](#))

76.32 EFormatError

76.32.1 Description

EFormatError is raised in case of an error in one of the various Format ([1537](#)) functions.

See also: Format ([1537](#))

76.33 EHeapMemoryError

76.33.1 Description

EHeapMemoryError is raised when an error occurs in heap (dynamically allocated) memory.

See also: EHeapException ([1457](#)), EOutOfMemory ([1621](#)), EInvalidPointer ([1619](#))

76.33.2 Method overview

Page	Method	Description
1618	FreeInstance	Free the exception instance

76.33.3 EHeapMemoryError.FreeInstance

Synopsis: Free the exception instance

Declaration: `procedure FreeInstance; Override`

Visibility: `public`

Description: `FreeInstance` checks whether the exception instance may be freed prior to calling the inherited `FreeInstance`. The exception is only freed in case of normal program shutdown, if a heap error occurred, the exception instance is not freed.

76.34 EInOutError**76.34.1 Description**

`EInOutError` is raised when a IO routine of Free Pascal returns an error. The error is converted to an `EInOutError` only if the input/output checking feature of FPC is turned on. The error code of the input/output operation is returned in `ErrorCode` (??).

See also: `EInOutError.ErrorCode` (??)

76.35 EInterror**76.35.1 Description**

`EInterror` is used when the operating system or CPU signals an integer operation error, e.g., an overflow.

76.36 EIntfCastError**76.36.1 Description**

`EIntfCastError` is raised when an invalid interface cast is encountered.

See also: `EInvalidCast` ([1619](#))

76.37 EIntOverflow**76.37.1 Description**

`EIntOverflow` is used when the operating system or CPU signals a integer overflow error.

See also: `EIntError` ([1618](#)), `EDivByZero` ([1616](#)), `ERangeError` ([1622](#))

76.38 EInvalidCast

76.38.1 Description

EInvalidCast is raised when an invalid typecast error (using the `as` operator) is encountered.

See also: EIntfCastError ([1618](#))

76.39 EInvalidContainer

76.39.1 Description

EInvalidContainer is not yet used by Free Pascal, and is provided for Delphi compatibility only.

76.40 EInvalidInsert

76.40.1 Description

EInvalidInsert is not yet used by Free Pascal, and is provided for Delphi compatibility only.

76.41 EInvalidOp

76.41.1 Description

EInvalidOp is raised when an invalid operation is encountered.

76.42 EInvalidPointer

76.42.1 Description

EInvalidPointer is raised when an invalid heap pointer is used.

See also: EHeapException ([1457](#)), EHeapMemoryError ([1617](#)), EOutOfMemory ([1621](#))

76.43 EMathError

76.43.1 Description

EMathError is used when the operating system or CPU signals a floating point overflow error.

See also: EIntError ([1618](#)), EIntOverflow ([1618](#)), EDivByZero ([1616](#)), ERangeError ([1622](#))

76.44 ENoConstructException

76.44.1 Description

ENoConstructException is the exception raised when an instance of type TCharacter is being created. The TCharacter class only contains static methods, no instances of this class should

be instantiated.

76.45 ENoThreadSupport

76.45.1 Description

`ENoThreadSupport` is raised when some thread routines are invoked, and thread support was not enabled when the program was compiled.

76.46 ENotImplemented

76.46.1 Description

`ENotImplemented` can be used to raise an exception when a particular call had been defined, but was not implemented.

76.47 ENotSupportedException

76.47.1 Description

`ENotSupportedException` is an exception raised when a function or procedure is not supported for a certain platform.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: [Exception \(1623\)](#)

76.48 ENoWideStringSupport

76.48.1 Description

`ENoWideStringSupport` is the exception raised when a run-time 233 occurs, i.e. when widestring routines are called and the application does not contain widestring support.

76.49 EObjectCheck

76.49.1 Description

`EObjectCheck` is raised when the `-CR` (check object references) command-line option or `{ $OBJECTCHECKS ON }` directive is in effect and a `Nil` reference to an object or class was encountered.

See also: [EAccessViolation \(1615\)](#)

76.50 EOSError

76.50.1 Description

`EOSError` is raised when some Operating System call fails. The `ErrorCode` (??) property contains the operating system error code.

See also: `EOSError.ErrorCode` (??)

76.51 EOutOfMemory

76.51.1 Description

`EOutOfMemory` occurs when memory can no longer be allocated on the heap. An instance of `EOutOfMemory` is allocated on the heap at program startup, so it is available when needed.

See also: `EHeapException` ([1457](#)), `EHeapMemoryError` ([1617](#)), `EInvalidPointer` ([1619](#))

76.52 EOverflow

76.52.1 Description

`EOverflow` occurs when a float operation overflows. (i.e. result is too big to represent).

See also: `EIntError` ([1618](#)), `EIntOverflow` ([1618](#)), `EDivByZero` ([1616](#)), `ERangeError` ([1622](#)), `EUnderFlow` ([1622](#))

76.53 EPackageError

76.53.1 Description

`EPackageError` is not yet used by Free Pascal, and is provided for Delphi compatibility only.

76.54 EPathNotFoundException

76.54.1 Description

`EPathNotFoundException` is an exception raised when a path is referenced that does not exist. This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1623](#)), `EFileNotFoundException` ([1617](#)), `EDirectoryNotFoundException` ([1616](#)), `EPathTooLongException` ([1621](#))

76.55 EPathTooLongException

76.55.1 Description

`EPathTooLongException` is an exception raised when a pathname argument is longer than the allowed pathname length for files.

This exception class is provided for Delphi compatibility, but is not actually used in FPC.

See also: `Exception` ([1623](#)), `EFileNotFoundException` ([1617](#)), `EDirectoryNotFoundException` ([1616](#)), `EPathNotFoundException` ([1621](#))

76.56 EPrivilege

76.56.1 Description

EPrivilege is raised when the OS reports that an invalid instruction was executed.

76.57 EPropReadOnly

76.57.1 Description

EPropReadOnly is raised when an attempt is made to write to a read-only property.

76.58 EPropWriteOnly

76.58.1 Description

EPropWriteOnly is raised when an attempt is made to read from a write-only property.

See also: EPropReadOnly ([1622](#))

76.59 ERangeError

76.59.1 Description

ERangeError is raised by the Free Pascal runtime library if range checking is on, and a range check error occurs.

See also: EIntError ([1618](#)), EDivByZero ([1616](#)), EIntOverflow ([1618](#))

76.60 ESafecallException

76.60.1 Description

ESafecallException is not yet used by Free Pascal, and is provided for Delphi compatibility only.

76.61 EStackOverflow

76.61.1 Description

EStackOverflow occurs when the stack has grown too big (e.g. by infinite recursion).

76.62 EUnderflow

76.62.1 Description

EOverflow occurs when a float operation underflows (i.e. result is too small to represent).

See also: EIntError ([1618](#)), EIntOverflow ([1618](#)), EDivByZero ([1616](#)), ERangeError ([1622](#)), EOverflow ([1621](#))

76.63 EVariantError

76.63.1 Description

EVariantError is raised by the internal variant routines.

76.63.2 Method overview

Page	Method	Description
1623	CreateCode	Create an instance of EVariantError with a particular error code.

76.63.3 EVariantError.CreateCode

Synopsis: Create an instance of EVariantError with a particular error code.

Declaration: constructor CreateCode(Code: LongInt)

Visibility: default

Description: CreateCode calls the inherited constructor, and sets the ErrCode (??) property to Code.

See also: ErrCode (??)

76.64 Exception

76.64.1 Description

Exception is the base class for all exception handling routines in the RTL and FCL. While it is possible to raise an exception with any class descending from TObject, it is recommended to use Exception as the basis of exception class objects: the Exception class introduces properties to associate a message and a help context with the exception being raised. What is more, the SysUtils unit sets the necessary hooks to catch and display unhandled exceptions: in such cases, the message displayed to the end user, will be the message stored in the exception class.

See also: ExceptObject ([1510](#)), ExceptAddr ([1509](#)), ExceptionErrorMessage ([1510](#)), ShowException ([1569](#)), Abort ([1474](#))

76.64.2 Method overview

Page	Method	Description
1624	Create	Constructs a new exception object with a given message.
1624	CreateFmt	Constructs a new exception object and formats a new message.
1625	CreateFmtHelp	Constructs a new exception object and sets the help context and formats the message
1625	CreateHelp	Constructs a new exception object and sets the help context.
1624	CreateRes	Constructs a new exception object and gets the message from a resource.
1624	CreateResFmt	Constructs a new exception object and formats the message from a resource.
1625	CreateResFmtHelp	Constructs a new exception object and sets the help context and formats the message from a resource
1625	CreateResHelp	Constructs a new exception object and sets the help context and gets the message from a resource
1626	ToString	Nicely formatted version of the exception message

76.64.3 Property overview

Page	Properties	Access	Description
1626	HelpContext	rw	Help context associated with the exception.
1626	Message	rw	Message associated with the exception.

76.64.4 Exception.Create

Synopsis: Constructs a new exception object with a given message.

Declaration: `constructor Create(const msg: string)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.CreateFmt` ([1624](#)), `Exception.Message` ([1626](#))

76.64.5 Exception.CreateFmt

Synopsis: Constructs a new exception object and formats a new message.

Declaration: `constructor CreateFmt(const msg: string; const args: Array of const)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1624](#)), `Exception.Message` ([1626](#)), `Format` ([1537](#))

76.64.6 Exception.CreateRes

Synopsis: Constructs a new exception object and gets the message from a resource.

Declaration: `constructor CreateRes(ResString: PString)`

Visibility: `public`

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1624](#)), `Exception.CreateFmt` ([1624](#)), `Exception.CreateResFmt` ([1624](#)), `Exception.Message` ([1626](#))

76.64.7 Exception.CreateResFmt

Synopsis: Constructs a new exception object and formats the message from a resource.

Declaration: `constructor CreateResFmt(ResString: PString; const Args: Array of const)`

Visibility: `public`

Description: `CreateResFmt` does the same as `CreateFmt` ([1624](#)), but fetches the message from the resource `string ResString`.

Errors: Construction may fail if there is not enough memory on the heap.

See also: `Exception.Create` ([1624](#)), `Exception.CreateFmt` ([1624](#)), `Exception.CreateRes` ([1624](#)), `Exception.Message` ([1626](#))

76.64.8 Exception.CreateHelp

Synopsis: Constructs a new exception object and sets the help context.

Declaration: `constructor CreateHelp(const Msg: string; AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateHelp` does the same as the `Create` (1624) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1626) property.

See also: `Exception.Create` (1624)

76.64.9 Exception.CreateFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message

Declaration: `constructor CreateFmtHelp(const Msg: string;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateFmtHelp` does the same as the `CreateFmt` (1624) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1626) property.

See also: `Exception.CreateFmt` (1624)

76.64.10 Exception.CreateResHelp

Synopsis: Constructs a new exception object and sets the help context and gets the message from a resource

Declaration: `constructor CreateResHelp(ResString: PString; AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateResHelp` does the same as the `CreateRes` (1624) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1626) property.

See also: `Exception.CreateRes` (1624)

76.64.11 Exception.CreateResFmtHelp

Synopsis: Constructs a new exception object and sets the help context and formats the message from a resource

Declaration: `constructor CreateResFmtHelp(ResString: PString;
const Args: Array of const;
AHelpContext: LongInt)`

Visibility: `public`

Description: `CreateResFmtHelp` does the same as the `CreateResFmt` (1624) constructor, but additionally stores `AHelpContext` in the `HelpContext` (1626) property.

See also: `Exception.CreateResFmt` (1624)

76.64.12 Exception.ToString

Synopsis: Nicely formatted version of the exception message

Declaration: `function ToString : string; Override`

Visibility: public

Description: `ToString` overrides the `ToString` method to return a concatenation of classname and `Exception.Message` (1626).

See also: `Exception.Message` (1626)

76.64.13 Exception.HelpContext

Synopsis: Help context associated with the exception.

Declaration: `Property HelpContext : LongInt`

Visibility: public

Access: Read,Write

Description: `HelpContext` is the help context associated with the exception, and can be used to provide context-sensitive help when the exception error message is displayed. It should be set in the exception constructor.

See also: `Exception.CreateHelp` (1625), `Exception.Message` (1626)

76.64.14 Exception.Message

Synopsis: Message associated with the exception.

Declaration: `Property Message : string`

Visibility: public

Access: Read,Write

Description: `Message` provides additional information about the exception. It is shown to the user in e.g. the `ShowException` (1569) routine, and should be set in the constructor when the exception is raised.

See also: `Exception.Create` (1624), `Exception.HelpContext` (1626)

76.65 EZeroDivide

76.65.1 Description

`EZeroDivide` occurs when a float division by zero occurs.

See also: `EIntError` (1618), `EIntOverflow` (1618), `EDivByZero` (1616), `ERangeError` (1622)

76.66 IReadWriteSync

76.66.1 Description

`IReadWriteSync` is an interface for synchronizing read/write operations. Writers are always guaranteed to have exclusive access: readers may or may not have simultaneous access, depending on the implementation.

76.66.2 Method overview

Page	Method	Description
1627	<code>BeginRead</code>	Start a read operation.
1627	<code>BeginWrite</code>	Start a write operation.
1627	<code>EndRead</code>	End a read operation
1628	<code>EndWrite</code>	End a write operation.

76.66.3 `IReadWriteSync.BeginRead`

Synopsis: Start a read operation.

Declaration: `procedure BeginRead`

Visibility: `default`

Description: `BeginRead` indicates that a read operation is about to be started. If a write operation is in progress, then the call will block until the write operation finished. Depending on the implementation the call may also block if another read operation is in progress.

After `BeginRead`, any write operation started with `BeginWrite` ([1627](#)) will block until `EndRead` ([1627](#)) is called.

See also: `IReadWriteSync.EndRead` ([1627](#)), `IReadWriteSync.BeginWrite` ([1627](#)), `IReadWriteSync.EndWrite` ([1628](#))

76.66.4 `IReadWriteSync.EndRead`

Synopsis: End a read operation

Declaration: `procedure EndRead`

Visibility: `default`

Description: `EndRead` signals the end of a read operation. If there was any blocked write operation, that will be unblocked by a call to `EndRead`.

See also: `IReadWriteSync.BeginRead` ([1627](#)), `IReadWriteSync.BeginWrite` ([1627](#)), `IReadWriteSync.EndWrite` ([1628](#))

76.66.5 `IReadWriteSync.BeginWrite`

Synopsis: Start a write operation.

Declaration: `function BeginWrite : Boolean`

Visibility: `default`

Description: `BeginWrite` signals the begin of a write operation. This call will block if any other read or write operation is currently in progress. It will resume only after all other read or write operations have finished.

See also: `IReadWriteSync.EndRead` ([1627](#)), `IReadWriteSync.EndWrite` ([1628](#)), `IReadWriteSync.BeginRead` ([1627](#))

76.66.6 IReadWriteSync.EndWrite

Synopsis: End a write operation.

Declaration: `procedure EndWrite`

Visibility: `default`

Description: `EndWrite` signals the end of a write operation. After the call to `EndWrite` any other read or write operations can start.

See also: `IReadWriteSync.EndRead` ([1627](#)), `IReadWriteSync.EndWrite` ([1628](#)), `IReadWriteSync.BeginRead` ([1627](#))

76.67 TBigEndianUnicodeEncoding

76.67.1 Description

`TBigEndianUnicodeEncoding` is the encoding class used to represent the UTF-16 big-endian encoding.

See also: `TBigEndianUnicodeEncoding` ([1628](#)), `TUTF7Encoding` ([1714](#)), `TMBCSEncoding` ([1665](#)), `TBigEndianUnicodeEncoding` ([1628](#))

76.67.2 Method overview

Page	Method	Description
1628	<code>Clone</code>	Clone a <code>TBigEndianUnicodeEncoding</code> instance
1628	<code>GetPreamble</code>	Return BOM marker bytes

76.67.3 TBigEndianUnicodeEncoding.Clone

Synopsis: Clone a `TBigEndianUnicodeEncoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: `Clone` overrides `TEncoding.Clone` ([1645](#)) to provide a clone of the `TBigEndianUnicodeEncoding` instance.

See also: `TEncoding.Clone` ([1645](#))

76.67.4 TBigEndianUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: `public`

Description: `GetPreamble` overrides `TEncoding.GetPreamble` ([1647](#)) to return the 2 UTF-16 BOM Marker bytes (`FFFE`).

See also: `TEncoding.GetPreamble` ([1647](#))

76.68 TBooleanHelper

76.68.1 Description

TBooleanHelper is a helper type for the Boolean type. It contains mostly conversion routines to and from other types.

See also: TStringHelper (1691), TShortIntHelper (1677), TSmallIntHelper (1689), TWordHelper (1718), TCardinalHelper (1635), TIntegerHelper (1660), TInt64Helper (1658), TQWordHelper (1674), TNativeIntHelper (1668), TByteHelper (1632), TByteBoolHelper (1630), TWordBoolHelper (1717), TLongBoolHelper (1663)

76.68.2 Method overview

Page	Method	Description
1629	Parse	Convert string value to boolean value.
1629	Size	Return the size (in bytes) of the
1630	ToInteger	Convert to an integer value
1629	ToString	Convert a boolean value to string.
1630	TryToParse	Try to convert a string to a boolean value

76.68.3 TBooleanHelper.Parse

Synopsis: Convert string value to boolean value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: Parse attempts to convert the string S to a boolean value. It uses the StrToBool (1585) function to perform the conversion.

Errors: If S does not contain a valid string representation, then an EConvertError (1616) exception is raised.

See also: TBooleanHelper.TryToParse (1630), TBooleanHelper.ToString (1629), TBooleanHelper.ToInteger (1630)

76.68.4 TBooleanHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in bytes) of the boolean value. This is equivalent to SizeOf (Boolean).

See also: SizeOf (1392)

76.68.5 TBooleanHelper.ToString

Synopsis: Convert a boolean value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue` boolean to a string representation. In the function method version the boolean value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the boolean strings `BoolStrs` (1442). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1490) function.

See also: `BoolStrs` (1442), `BoolToStr` (1490)

76.68.6 TBooleanHelper.TryToParse

Synopsis: Try to convert a string to a boolean value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a boolean value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TBooleanHelper.Parse` (1629), `TBooleanHelper.ToString` (1629)

76.68.7 TBooleanHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the boolean value, typecasted to `Integer`.

See also: `TBooleanHelper.ToString` (1629)

76.69 TByteBoolHelper

76.69.1 Description

`TByteBoolHelper` is a helper type for the `ByteBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TWordHelper` (1718), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TByteHelper` (1632), `TByteBoolHelper` (1630), `TWordBoolHelper` (1717), `TLongBoolHelper` (1663)

76.69.2 Method overview

Page	Method	Description
1631	<code>Parse</code>	Convert string value to ByteBool value.
1631	<code>Size</code>	Return the size (in bytes) of the
1632	<code>ToInteger</code>	Convert to an integer value
1631	<code>ToString</code>	Convert a ByteBool value to string.
1632	<code>TryToParse</code>	Try to convert a string to a ByteBool value

76.69.3 TByteBoolHelper.Parse

Synopsis: Convert string value to ByteBool value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: `public`

Description: `Parse` attempts to convert the string `S` to a ByteBool value. It uses the `StrToBool` ([1585](#)) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` ([1616](#)) exception is raised.

See also: `TByteBoolHelper.TryToParse` ([1632](#)), `TByteBoolHelper.ToString` ([1631](#)), `TByteBoolHelper.ToInteger` ([1632](#))

76.69.4 TByteBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in bytes) of the ByteBool value. This is equivalent to `SizeOf(ByteBool)`.

See also: `SizeOf` ([1392](#))

76.69.5 TByteBoolHelper.ToString

Synopsis: Convert a ByteBool value to string.

Declaration: `class function ToString(const AValue: Boolean;
UseBoolStrs: TUseBoolStrs) : string; Overload
; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class method version, convert the `AValue` ByteBool to a string representation. In the function method version the ByteBool value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the ByteBool strings `BoolStrs` ([1442](#)). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` ([1490](#)) function.

See also: `BoolStrs` ([1442](#)), `BoolToStr` ([1490](#))

76.69.6 TByteBoolHelper.TryParse

Synopsis: Try to convert a string to a ByteBool value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a `ByteBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TByteBoolHelper.Parse` ([1631](#)), `TByteBoolHelper.ToString` ([1631](#))

76.69.7 TByteBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `ByteBool` value, typecasted to `Integer`.

See also: `TByteBoolHelper.ToString` ([1631](#))

76.70 TByteHelper

76.70.1 Description

`TByteHelper` contains some auxiliary routines for a byte-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1691](#)), `TShortIntHelper` ([1677](#)), `TSmallIntHelper` ([1689](#)), `TWordHelper` ([1718](#)), `TCardinalHelper` ([1635](#)), `TIntegerHelper` ([1660](#)), `TInt64Helper` ([1658](#)), `TQWordHelper` ([1674](#)), `TNativeIntHelper` ([1668](#)), `TNativeUIntHelper` ([1671](#))

76.70.2 Method overview

Page	Method	Description
1633	<code>Parse</code>	Convert from a string
1633	<code>Size</code>	Size, in bytes, of the byte value
1634	<code>ToBoolean</code>	Convert to a boolean value
1634	<code>ToDouble</code>	Convert to a double-sized floating point value
1634	<code>ToExtended</code>	Convert to an extended-sized floating point value
1634	<code>ToHexString</code>	Convert to a hexadecimal string representation
1635	<code>ToSingle</code>	Convert to a single-sized floating point value
1633	<code>ToString</code>	Convert the value to string
1633	<code>TryParse</code>	Try to convert a string to a byte, report success or failure

76.70.3 TByteHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Byte; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a byte value. It uses the `StrToInt` (1590) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid byte value, an `EConvertError` (1616) exception is raised.

See also: `TByteHelper.ToString` (1633), `TByteHelper.TryParse` (1633), `StrToInt` (1590)

76.70.4 TByteHelper.Size

Synopsis: Size, in bytes, of the byte value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in bytes) of the byte value. This is equivalent to `SizeOf(Byte)`.

Errors: None.

See also: `SizeOf` (1392)

76.70.5 TByteHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Byte) : string; Overload; Static`
`function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the byte value itself is used. The `IntToStr` (1558) function is used to do the conversion.

See also: `TByteHelper.Parse` (1633), `IntToStr` (1558)

76.70.6 TByteHelper.TryParse

Synopsis: Try to convert a string to a byte, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Byte)`
`: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a byte, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the byte is returned in `AValue`.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: `TByteHelper.Parse` (1633), `Val` (1413)

76.70.7 TByteHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the byte value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TByteHelper.ToSingle` (1635), `TByteHelper.ToDouble` (1634), `TByteHelper.ToExtended` (1634), `TByteHelper.ToString` (1633), `TByteHelper.ToHexString` (1634)

76.70.8 TByteHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the byte value to a double-sized floating point value.

See also: `TByteHelper.ToBoolean` (1634), `TByteHelper.ToExtended` (1634), `TByteHelper.ToSingle` (1635), `TByteHelper.ToString` (1633), `TByteHelper.ToHexString` (1634)

76.70.9 TByteHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the byte value to an extended-sized floating point value

See also: `TByteHelper.ToBoolean` (1634), `TByteHelper.ToSingle` (1635), `TByteHelper.ToDouble` (1634), `TByteHelper.ToString` (1633), `TByteHelper.ToHexString` (1634)

76.70.10 TByteHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the byte value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TByteHelper.ToBoolean` (1634), `TByteHelper.ToSingle` (1635), `TByteHelper.ToDouble` (1634), `TByteHelper.ToString` (1633), `TByteHelper.ToExtended` (1634)

76.70.11 TByteHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: `public`

Description: `ToSingle` converts the byte value to a single-sized floating point value.

See also: `TByteHelper.ToBoolean` ([1634](#)), `TByteHelper.ToDouble` ([1634](#)), `TByteHelper.ToExtended` ([1634](#)), `TByteHelper.ToString` ([1633](#)), `TByteHelper.ToHexString` ([1634](#))

76.71 TCardinalHelper

76.71.1 Description

`TCardinalHelper` contains some auxiliary routines for a Cardinal-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1691](#)), `TShortIntHelper` ([1677](#)), `TSmallIntHelper` ([1689](#)), `TWordHelper` ([1718](#)), `TByteHelper` ([1632](#)), `TIntegerHelper` ([1660](#)), `TInt64Helper` ([1658](#)), `TQWordHelper` ([1674](#)), `TNativeIntHelper` ([1668](#)), `TNativeUIntHelper` ([1671](#))

76.71.2 Method overview

Page	Method	Description
1635	<code>Parse</code>	Convert from a string
1636	<code>Size</code>	Size, in bytes, of the Cardinal value
1636	<code>ToBoolean</code>	Convert to a boolean value
1637	<code>ToDouble</code>	Convert to a double-sized floating point value
1637	<code>ToExtended</code>	Convert to an extended-sized floating point value
1637	<code>ToHexString</code>	Convert to a hexadecimal string representation
1637	<code>ToSingle</code>	Convert to an single-sized floating point value
1636	<code>ToString</code>	Convert the value to string
1636	<code>TryParse</code>	Try to convert a string to a Cardinal, report success or failure

76.71.3 TCardinalHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Cardinal; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a Cardinal value. It uses the `StrToInt` ([1590](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid Cardinal value, an `EConvertError` ([1616](#)) exception is raised.

See also: `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.TryParse` ([1636](#)), `StrToInt` ([1590](#))

76.71.4 TCardinalHelper.Size

Synopsis: Size, in bytes, of the Cardinal value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in Cardinals) of the Cardinal value. This is equivalent to `SizeOf (Cardinal)`.

Errors: None.

See also: `SizeOf` ([1392](#))

76.71.5 TCardinalHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Cardinal) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the Cardinal value itself is used. The `IntToStr` ([1558](#)) function is used to do the conversion.

See also: `TCardinalHelper.Parse` ([1635](#)), `IntToStr` ([1558](#))

76.71.6 TCardinalHelper.TryParse

Synopsis: Try to convert a string to a Cardinal, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Cardinal)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Cardinal, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the Cardinal is returned in `AValue`.

It uses the `val` ([1442](#)) function to perform the conversion, so no localization is taken into account.

See also: `TCardinalHelper.Parse` ([1635](#)), `Val` ([1413](#))

76.71.7 TCardinalHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the Cardinal value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TCardinalHelper.ToSingle` ([1637](#)), `TCardinalHelper.ToDouble` ([1637](#)), `TCardinalHelper.ToExtended` ([1637](#)), `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.ToHexString` ([1637](#))

76.71.8 TCardinalHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the Cardinal value to a double-sized floating point value.

See also: `TCardinalHelper.ToBoolean` ([1636](#)), `TCardinalHelper.ToExtended` ([1637](#)), `TCardinalHelper.ToSingle` ([1637](#)), `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.ToHexString` ([1637](#))

76.71.9 TCardinalHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the Cardinal value to an extended-sized floating point value.

See also: `TCardinalHelper.ToBoolean` ([1636](#)), `TCardinalHelper.ToSingle` ([1637](#)), `TCardinalHelper.ToDouble` ([1637](#)), `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.ToHexString` ([1637](#))

76.71.10 TCardinalHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the Cardinal value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TCardinalHelper.ToBoolean` ([1636](#)), `TCardinalHelper.ToSingle` ([1637](#)), `TCardinalHelper.ToDouble` ([1637](#)), `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.ToExtended` ([1637](#))

76.71.11 TCardinalHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the Cardinal value to a single-sized floating point value.

See also: `TCardinalHelper.ToBoolean` ([1636](#)), `TCardinalHelper.ToDouble` ([1637](#)), `TCardinalHelper.ToExtended` ([1637](#)), `TCardinalHelper.ToString` ([1636](#)), `TCardinalHelper.ToHexString` ([1637](#))

76.72 TDoubleHelper

76.72.1 Description

`TDoubleHelper` is the helper type for the Double-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a `Double`.

: TDoubleHelper (1638), TExtendedHelper (1650)

76.72.2 Method overview

Page	Method	Description
1641	BuildUp	Build a Double-sized floating point from its composing parts
1641	Exponent	Exponent of the floating-point value
1642	Fraction	Fraction of the floating-point value
1638	IsInfinity	Check whether a value is positive or negative infinity.
1639	IsNan	Check whether a value equals NaN.
1639	IsNegativeInfinity	Check whether a value is negative infinity.
1639	IsPositiveInfinity	Check whether a value is positive infinity.
1642	Mantissa	Mantissa of the floating-point
1639	Parse	Convert a string to a floating point value
1640	Size	Size (in bytes) of a Double-sized floating point value.
1642	SpecialType	Return the type of the Double-sized floating point value
1640	ToString	Convert a Double-sized floating point value to a string
1641	TryParse	Try to convert a string to a Double-sized floating point value.

76.72.3 Property overview

Page	Properties	Access	Description
1642	Bytes	rw	Indexed access to the individual bytes of the floating point value
1643	Exp	rw	The bit pattern of the exponent as stored in memory.
1643	Frac	rw	Bitpattern that makes up the fractional part.
1643	Sign	rw	Sign of the floating point value
1643	Words	rw	Indexed access to the words that make up the floating point value

76.72.4 TDoubleHelper.IsInfinity

: Check whether a value is positive or negative infinity.

```

class function IsInfinity(const AValue: Double) : Boolean; Overload
                                ; Static
function IsInfinity : Boolean; Overload

```

: public

IsInfinity checks whether a Double-sized floating point value represents a positive or negative infinity. If so, it returns **True**. When the class function version is used, the value can be specified using **AValue**. In the method version, the used value is (**Self**).

: TDoubleHelper.IsNan (1639), TDoubleHelper.IsPositiveInfinity (1639), TDoubleHelper.IsNegativeInfinity (1639)

76.72.5 TDoubleHelper.IsNan

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNan(const AValue: Double) : Boolean; Overload; Static
function IsNan : Boolean; Overload`

Visibility: public

Description: `IsNan` checks whether a Double-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsInfinity` (1638), `TDoubleHelper.IsPositiveInfinity` (1639), `TDoubleHelper.IsNegativeInfinity` (1639)

76.72.6 TDoubleHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

Declaration: `class function IsNegativeInfinity(const AValue: Double) : Boolean
; Overload; Static
function IsNegativeInfinity : Boolean; Overload`

Visibility: public

Description: `IsNegativeInfinity` checks whether a Double-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` (1639), `TDoubleHelper.IsPositiveInfinity` (1639), `TDoubleHelper.IsInfinity` (1638)

76.72.7 TDoubleHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

Declaration: `class function IsPositiveInfinity(const AValue: Double) : Boolean
; Overload; Static
function IsPositiveInfinity : Boolean; Overload`

Visibility: public

Description: `IsPositiveInfinity` checks whether a Double-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TDoubleHelper.IsNan` (1639), `TDoubleHelper.IsNegativeInfinity` (1639), `TDoubleHelper.IsInfinity` (1638)

76.72.8 TDoubleHelper.Parse

Synopsis: Convert a string to a floating point value

Declaration: `class function Parse(const AString: string) : Double; Overload; Static
class function Parse(const AString: string;
const AFormatSettings: TFormatSettings) : Double
; Overload; Static`

Visibility: public

Description: `Parse` will try to convert `AString` to a Double-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` (1616) exception is raised.

See also: `FloatToStr` (1532), `TDoubleHelper.ToString` (1640), `TDoubleHelper.TryParse` (1641)

76.72.9 TDoubleHelper.Size

Synopsis: Size (in bytes) of a Double-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` is the size (in bytes) of a Double-sized floating point value. It is equivalent to calling `SizeOf(Double)`.

See also: `SizeOf` (1392)

76.72.10 TDoubleHelper.ToString

Synopsis: Convert a Double-sized floating point value to a string

```
Declaration: class function ToString(const AValue: Double) : string; Overload
              ; Static
class function ToString(const AValue: Double;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Double;
                        const AFormat: TFloatFormat;
                        const APrecision: Integer;
                        const ADigits: Integer;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Double;
                        const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer)
                  : string; Overload
function ToString(const AFormat: TFloatFormat;
                  const APrecision: Integer; const ADigits: Integer;
                  const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString : string; Overload
```

Visibility: public

Description: `ToString` will convert `AValue` (or `Self` in the plain method version) to a string. Optionally `FormatSettings` can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` (1462) for an explanation of the various values). In this case, `FloatToStrF` (1533) is used to format the value. In the absence of these parameters, `FloatToStr` (1532) is called.

See also: `FloatToStr` (1532), `FloatToStrF` (1533), `TFloatFormat` (1462)

76.72.11 `TDoubleHelper.TryParse`

Synopsis: Try to convert a string to a Double-sized floating point value.

Declaration:

```
class function TryParse(const AString: string; out AValue: Double)
                        : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Double;
                        const AFormatSettings: TFormatSettings) : Boolean
                        ; Overload; Static
```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Double-sized floating point value and reports `True` if the conversion was successful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TDoubleHelper.Parse` (1639), `TDoubleHelper.ToString` (1640)

76.72.12 `TDoubleHelper.BuildUp`

Synopsis: Build a Double-sized floating point from its composing parts

Declaration:

```
procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
                  const AExponent: Integer)
```

Visibility: public

Description: `BuildUp` will compose a Double-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1643), `Exp` (1643) and `Frac` (1643) properties in 1 call.

See also: `TDoubleHelper.Sign` (1643), `TDoubleHelper.Exp` (1643), `TDoubleHelper.Frac` (1643)

76.72.13 `TDoubleHelper.Exponent`

Synopsis: Exponent of the floating-point value

Declaration:

```
function Exponent : Integer
```

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \times 2^X$, i.e. the exponent.

See also: `TDoubleHelper.Sign` (1643), `TDoubleHelper.Exp` (1643), `TDoubleHelper.Frac` (1643), `TDoubleHelper.Fraction` (1642), `TDoubleHelper.Mantissa` (1642)

76.72.14 TDoubleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TDoubleHelper.Sign` (1643), `TDoubleHelper.Exp` (1643), `TDoubleHelper.Exponent` (1641), `TDoubleHelper.Frac` (1643), `TDoubleHelper.Mantissa` (1642)

76.72.15 TDoubleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TDoubleHelper.Sign` (1643), `TDoubleHelper.Exp` (1643), `TDoubleHelper.Exponent` (1641), `TDoubleHelper.Frac` (1643), `TDoubleHelper.Fraction` (1642)

76.72.16 TDoubleHelper.SpecialType

Synopsis: Return the type of the Double-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the Double-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` (1442) for an explanation of the possible values.

See also: `TFloatSpecial` (1442)

76.72.17 TDoubleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TDoubleHelper.Words` (1643), `TDoubleHelper.Size` (1640)

76.72.18 TDoubleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the Double-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TDoubleHelper.Bytes` ([1642](#)), `TDoubleHelper.Size` ([1640](#))

76.72.19 TDoubleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TDoubleHelper.Bytes` ([1642](#)), `TDoubleHelper.Exp` ([1643](#)), `TDoubleHelper.Frac` ([1643](#)), `TDoubleHelper.Mantissa` ([1642](#)), `TDoubleHelper.Fraction` ([1642](#)), `TDoubleHelper.Exponent` ([1641](#))

76.72.20 TDoubleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent ([1641](#)).

See also: `TDoubleHelper.Bytes` ([1642](#)), `TDoubleHelper.Sign` ([1643](#)), `TDoubleHelper.Frac` ([1643](#)), `TDoubleHelper.Mantissa` ([1642](#)), `TDoubleHelper.Fraction` ([1642](#)), `TDoubleHelper.Exponent` ([1641](#))

76.72.21 TDoubleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TDoubleHelper.Bytes` ([1642](#)), `TDoubleHelper.Sign` ([1643](#)), `TDoubleHelper.Exp` ([1643](#)), `TDoubleHelper.Mantissa` ([1642](#)), `TDoubleHelper.Fraction` ([1642](#)), `TDoubleHelper.Exponent` ([1641](#))

76.73 TEncoding

76.73.1 Description

`TEncoding` is a mostly abstract class that contains various methods to deal with different encodings in single- and double-byte strings. In practice, one instance of a descendent of this class for each needed encoding can be instantiated and used. The class contains several class methods and properties to create such instances, and has several often-used instances available as class properties, in particular the default encoding.

See also: `TEncoding.ANSI` (1648), `TEncoding.ASCII` (1648), `TEncoding.Default` (1649), `TEncoding.BigEndianUnicode` (1649), `TEncoding.Unicode` (1649), `TEncoding.UTF7` (1649), `TEncoding.UTF8` (1650)

76.73.2 Method overview

Page	Method	Description
1645	<code>Clone</code>	Clone a <code>TEncoding</code> instance
1645	<code>Convert</code>	Convert an array of bytes from one encoding to another
1644	<code>FreeEncodings</code>	Free all standard encodings
1646	<code>GetBufferEncoding</code>	Attempt to guess the encoding of a buffer
1646	<code>GetEncoding</code>	Get an encoding instance for a given codepage.
1646	<code>GetMaxByteCount</code>	Returns the maximum number of bytes needed to represent a string
1647	<code>GetMaxCharCount</code>	Return the maximum number of characters that can be represented in a number of bytes
1647	<code>GetPreamble</code>	Return the BOM Marker used by the encoding
1647	<code>GetString</code>	Return a string based on an array of bytes
1645	<code>IsStandardEncoding</code>	Check if the encoding is one of the standard encodings

76.73.3 Property overview

Page	Properties	Access	Description
1648	<code>ANSI</code>	r	Ansi encoding instance
1648	<code>ASCII</code>	r	ASCII encoding instance
1649	<code>BigEndianUnicode</code>	r	Big-endian Unicode (UTF16BE) encoding instance
1647	<code>CodePage</code>	r	Codepage for this encoding
1649	<code>Default</code>	r	Default codepage
1648	<code>EncodingName</code>	r	Name of this encoding
1648	<code>IsSingleByte</code>	r	Is the encoding a single-byte encoding or not ?
1649	<code>Unicode</code>	r	UTF16 encoding instance
1649	<code>UTF7</code>	r	UTF7 encoding instance
1650	<code>UTF8</code>	r	UTF8 encoding instance

76.73.4 TEncoding.FreeEncodings

Synopsis: Free all standard encodings

Declaration: `class procedure FreeEncodings`

Visibility: `public`

Description: `FreeEncodings` frees all the standard encodings `TEncoding.ANSI` (1648), `TEncoding.ASCII` (1648), `TEncoding.Default` (1649), `TEncoding.BigEndianUnicode` (1649), `TEncoding.Unicode` (1649), `TEncoding.UTF7` (1649) and `TEncoding.UTF8` (1650). There should be no need to call this function directly, it is called automatically when the program exits.

See also: [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.Default \(1649\)](#), [TEncoding.BigEndianUnicode \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF7 \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.5 TEncoding.Clone

Synopsis: Clone a TEncoding instance

Declaration: `function Clone : TEncoding; Virtual`

Visibility: public

Description: Clone creates a copy of a TEncoding instance. This method returns Nil in TEncoding and must be implemented in descendent classes.

See also: [TEncoding.Create \(1644\)](#)

76.73.6 TEncoding.Convert

Synopsis: Convert an array of bytes from one encoding to another

Declaration: `class function Convert(Source: TEncoding; Destination: TEncoding;
const Bytes: TBytes) : TBytes; Overload
class function Convert(Source: TEncoding; Destination: TEncoding;
const Bytes: TBytes; StartIndex: Integer;
Count: Integer) : TBytes; Overload`

Visibility: public

Description: Convert will convert the bytes in Bytes from encoding Source to encoding Destination and returns the converted bytes as an array. If StartIndex and Count are specified, the conversion starts at (zero-based) index StartIndex, and only Count bytes will be converted.

See also: [TEncoding.GetBytes \(1644\)](#), [TEncoding.GetChars \(1644\)](#)

76.73.7 TEncoding.IsStandardEncoding

Synopsis: Check if the encoding is one of the standard encodings

Declaration: `class function IsStandardEncoding(AEncoding: TEncoding) : Boolean
; Static`

Visibility: public

Description: IsStandardEncoding will return True is one of the standard encoding instances TEncoding.ANSI (1648), TEncoding.ASCII (1648), TEncoding.Default (1649), TEncoding.BigEndianUnicode (1649), TEncoding.Unicode (1649), TEncoding.UTF7 (1649) or TEncoding.UTF8 (1650). Otherwise it returns False.

See also: [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.Default \(1649\)](#), [TEncoding.BigEndianUnicode \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF7 \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.8 TEncoding.GetBufferEncoding

Synopsis: Attempt to guess the encoding of a buffer

Declaration:

```

class function GetBufferEncoding(const Buffer: TBytes;
                                var AEncoding: TEncoding) : Integer
                                ; Overload; Static
class function GetBufferEncoding(const Buffer: TBytes;
                                var AEncoding: TEncoding;
                                ADefaultEncoding: TEncoding) : Integer
                                ; Overload; Static

```

Visibility: public

Description: `GetBufferEncoding` checks the BOM marker of an array of bytes `Buffer`, and returns the found encoding in `AEncoding`. Only the `TEncoding.BigEndianUnicode` (1649) `TEncoding.Unicode` (1649) and `TEncoding.UTF8` (1650) encodings will be tried.

If `AEncoding` is non-`Nil` on entry, it will be used to check the BOM marker with. No other encoding will be tried in that case.

If `ADefaultEncoding` is specified, it will be returned in case no match was found.

The function returns the number of bytes in the BOM Marker.

See also: `TEncoding.BigEndianUnicode` (1649), `TEncoding.Unicode` (1649), `TEncoding.UTF8` (1650), `TEncoding.GetPreamble` (1647)

76.73.9 TEncoding.GetEncoding

Synopsis: Get an encoding instance for a given codepage.

Declaration:

```

class function GetEncoding(CodePage: Integer) : TEncoding; Overload
                                ; Static
class function GetEncoding(const EncodingName: UnicodeString)
                                : TEncoding; Overload; Static

```

Visibility: public

Description: `GetEncoding` will return an instance of `TEncoding` for the given codepage `CodePage`. The codepage can also be specified by name `EncodingName`. The returned instance is an appropriate descendent of `TEncoding` and needs to be freed by the caller.

See also: `TUnicodeEncoding` (1712), `TBigEndianUnicodeEncoding` (1628), `TUTF8Encoding` (1715), `TUTF7Encoding` (1714), `TMBCSEncoding` (1665)

76.73.10 TEncoding.GetMaxByteCount

Synopsis: Returns the maximum number of bytes needed to represent a string

Declaration:

```

function GetMaxByteCount(CharCount: Integer) : Integer; Virtual
                                ; Abstract

```

Visibility: public

Description: `GetMaxByteCount` returns the maximum number of bytes needed to represent a string of `CharCount` characters in the given encoding.

This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxCharCount` (1647)

76.73.11 TEncoding.GetMaxCharCount

Synopsis: Return the maximum number of characters that can be represented in a number of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Virtual
; Abstract`

Visibility: public

Description: `GetMaxCharCount` returns the theoretical maximum number of characters that can be represented in a buffer of length `ByteCount` in the given encoding. Note that the actual number of characters that can be represented may well be much less and depends on the encoding and the actual characters. This is an abstract method, implemented by descendents of `TEncoding`.

See also: `TEncoding.GetMaxByteCount` ([1646](#))

76.73.12 TEncoding.GetPreamble

Synopsis: Return the BOM Marker used by the encoding

Declaration: `function GetPreamble : TBytes; Virtual; Abstract`

Visibility: public

Description: `GetPreamble` returns the BOM marker bytes used by the encoding. This is only meaningful for the UTF8 and Unicode encodings, for all other encodings there is no BOM Marker.

See also: `TUnicodeEncoding` ([1712](#)), `TBigEndianUnicodeEncoding` ([1628](#)), `TUTF8Encoding` ([1715](#))

76.73.13 TEncoding.GetString

Synopsis: Return a string based on an array of bytes

Declaration: `function GetString(const Bytes: TBytes) : UnicodeString; Overload
function GetString(const Bytes: TBytes; ByteIndex: Integer;
ByteCount: Integer) : UnicodeString; Overload`

Visibility: public

Description: `GetString` will return a unicode string, created from the bytes in the `Bytes` array. The bytes array will be interpreted according to the encoding which the `TEncoding` represents.

If `ByteIndex` and `ByteCount` are specified, only the `ByteCount` bytes starting at position `ByteIndex` will be converted.

Errors: In case of invalid bytes, an `EEncodingError` exception may be raised.

76.73.14 TEncoding.CodePage

Synopsis: Codepage for this encoding

Declaration: `Property CodePage : Cardinal`

Visibility: public

Access: Read

Description: `CodePage` is the numerical codepage for this encoding. It is a number as used in the Windows codepage registry.

See also: `TEncoding.EncodingName` ([1648](#))

76.73.15 TEncoding.EncodingName

Synopsis: Name of this encoding

Declaration: `Property EncodingName : UnicodeString`

Visibility: public

Access: Read

Description: `EncodingName` is the name for this encoding. It's based on the windows name for the encoding and is calculated from the codepage.

See also: `TEncoding.CodePage` ([1647](#))

76.73.16 TEncoding.IsSingleByte

Synopsis: Is the encoding a single-byte encoding or not ?

Declaration: `Property IsSingleByte : Boolean`

Visibility: public

Access: Read

Description: `IsSingleByte` determines whether an encoding is single-byte or not. It is `false` for all standard encodings.

76.73.17 TEncoding.ANSI

Synopsis: Ansi encoding instance

Declaration: `Property ANSI : TEncoding`

Visibility: public

Access: Read

Description: `ANSI` is the ANSI codepage encoding instance, it is the default single-byte string codepage on windows (as returned by `DefaultSystemCodePage` ([1442](#))). This instance is created and maintained by the system, it should not be freed.

See also: `(??)`, `TEncoding.ASCII` ([1648](#)), `TEncoding.Default` ([1649](#)), `TEncoding.BigEndianUnicode` ([1649](#)), `TEncoding.Unicode` ([1649](#)), `TEncoding.UTF7` ([1649](#)), `TEncoding.UTF8` ([1650](#))

76.73.18 TEncoding.ASCII

Synopsis: ASCII encoding instance

Declaration: `Property ASCII : TEncoding`

Visibility: public

Access: Read

Description: `ASCII` is the ASCII codepage (`CP_ASCII`) encoding instance. This instance is created and maintained by the system, it should not be freed.

See also: `TEncoding.ANSI` ([1648](#)), `TEncoding.ASCII` ([1648](#)), `TEncoding.Default` ([1649](#)), `TEncoding.BigEndianUnicode` ([1649](#)), `TEncoding.Unicode` ([1649](#)), `TEncoding.UTF7` ([1649](#)), `TEncoding.UTF8` ([1650](#))

76.73.19 TEncoding.BigEndianUnicode

Synopsis: Big-endian Unicode (UTF16BE) encoding instance

Declaration: `Property BigEndianUnicode : TEncoding`

Visibility: public

Access: Read

Description: `BigEndianUnicode` is the Big-endian Unicode encoding instance (CP_UTF16BE) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.Default \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF7 \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.20 TEncoding.Default

Synopsis: Default codepage

Declaration: `Property Default : TEncoding`

Visibility: public

Access: Read

Description: `Default` is the default encoding instance (it equals the ANSI codepage). This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.BigEndianUnicode \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF7 \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.21 TEncoding.Unicode

Synopsis: UTF16 encoding instance

Declaration: `Property Unicode : TEncoding`

Visibility: public

Access: Read

Description: `Unicode` is the Big-endian Unicode encoding instance (CP_UTF16) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.Default \(1649\)](#), [TEncoding.BigEndianUnicode \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF7 \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.22 TEncoding.UTF7

Synopsis: UTF7 encoding instance

Declaration: `Property UTF7 : TEncoding`

Visibility: public

Access: Read

Description: `UTF7` is the UTF7 encoding instance (CP_UTF7) This instance is created and maintained by the system, it should not be freed.

See also: [\(??\)](#), [TEncoding.ANSI \(1648\)](#), [TEncoding.ASCII \(1648\)](#), [TEncoding.Default \(1649\)](#), [TEncoding.BigEndianUnicode \(1649\)](#), [TEncoding.Unicode \(1649\)](#), [TEncoding.UTF8 \(1650\)](#)

76.73.23 TEncoding.UTF8

Synopsis: UTF8 encoding instance

Declaration: `Property UTF8 : TEncoding`

Visibility: public

Access: Read

Description: UTF8 is the UTF7 encoding instance (CP_UTF7) This instance is created and maintained by the system, it should not be freed.

See also: (??), TEncoding.ANSI (1648), TEncoding.ASCII (1648), TEncoding.Default (1649), TEncoding.BigEndianUnicode (1649), TEncoding.Unicode (1649), TEncoding.UTF7 (1649)

76.74 TExtendedHelper

76.74.1 Description

TExtendedHelper is the helper type for the Extended-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a Extended.

See also: TDoubleHelper (1638), TExtendedHelper (1650)

76.74.2 Method overview

Page	Method	Description
1653	BuildUp	Build a Extended-sized floating point from its composing parts
1654	Exponent	Exponent of the floating-point value
1654	Fraction	Fraction of the floating-point value
1652	IsInfinity	Check whether a value is positive or negative infinity.
1652	IsNan	Check whether a value equals NaN.
1653	IsNegativeInfinity	Check whether a value is negative infinity.
1653	IsPositiveInfinity	Check whether a value is positive infinity.
1654	Mantissa	Mantissa of the floating-point
1651	Parse	Convert a string to a floating point value
1653	Size	Size (in bytes) of a Extended-sized floating point value.
1654	SpecialType	Return the type of the Extended-sized floating point value
1651	ToString	Convert a Extended-sized floating point value to a string
1652	TryParse	Try to convert a string to a Extended-sized floating point value.

76.74.3 Property overview

Page	Properties	Access	Description
1655	Bytes	rw	Indexed access to the individual bytes of the floating point value
1655	Exp	rw	The bit pattern of the exponent as stored in memory.
1656	Frac	rw	Bitpattern that makes up the fractional part.
1655	Sign	rw	Sign of the floating point value
1655	Words	rw	Indexed access to the words that make up the floating point value

76.74.4 TExtendedHelper.ToString

Synopsis: Convert a Extended-sized floating point value to a string

```

Declaration: class function ToString(const AValue: Extended) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
              const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
class function ToString(const AValue: Extended;
              const AFormat: TFloatFormat;
              const APrecision: Integer;
              const ADigits: Integer) : string; Overload
              ; Static
class function ToString(const AValue: Extended;
              const AFormat: TFloatFormat;
              const APrecision: Integer;
              const ADigits: Integer;
              const AFormatSettings: TFormatSettings) : string
              ; Overload; Static
function ToString(const AFormat: TFloatFormat;
              const APrecision: Integer; const ADigits: Integer)
              : string; Overload
function ToString(const AFormat: TFloatFormat;
              const APrecision: Integer; const ADigits: Integer;
              const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString(const AFormatSettings: TFormatSettings) : string
              ; Overload
function ToString : string; Overload

```

Visibility: public

Description: ToString will convert AValue (or Self in the plain method version) to a string. Optionally FormatSettings can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` (1462) for an explanation of the various values). In this case, `FloatToStrF` (1533) is used to format the value. In the absence of these parameters, `FloatToStr` (1532) is called.

See also: [FloatToStr \(1532\)](#), [FloatToStrF \(1533\)](#), [TFloatFormat \(1462\)](#)

76.74.5 TExtendedHelper.Parse

Synopsis: Convert a string to a floating point value

```
Declaration: class function Parse(const AString: string) : Extended; Overload
            ; Static
            class function Parse(const AString: string;
                                const AFormatSettings: TFormatSettings) : Extended
            ; Overload; Static
```

Visibility: public

Description: `Parse` will try to convert `AString` to a Extended-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` (1616) exception is raised.

See also: `FloatToStr` (1532), `TExtendedHelper.ToString` (1651), `TExtendedHelper.TryParse` (1652)

76.74.6 TExtendedHelper.TryParse

Synopsis: Try to convert a string to a Extended-sized floating point value.

Declaration:

```
class function TryParse(const AString: string; out AValue: Extended)
                        : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Extended;
                        const AFormatSettings: TFormatSettings) : Boolean
                        ; Overload; Static
```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a Extended-sized floating point value and reports `True` if the conversion was succesful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TExtendedHelper.Parse` (1651), `TExtendedHelper.ToString` (1651)

76.74.7 TExtendedHelper.IsNaN

Synopsis: Check whether a value equals NaN.

Declaration:

```
class function IsNaN(const AValue: Extended) : Boolean; Overload
                        ; Static
function IsNaN : Boolean; Overload
```

Visibility: public

Description: `IsNaN` checks whether a Extended-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: `TExtendedHelper.IsInfinity` (1652), `TExtendedHelper.IsPositiveInfinity` (1653), `TExtendedHelper.IsNegativeInfinity` (1653)

76.74.8 TExtendedHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

Declaration:

```
class function IsInfinity(const AValue: Extended) : Boolean; Overload
                        ; Static
function IsInfinity : Boolean; Overload
```

Visibility: public

Description: `IsInfinity` checks whether a Extended-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: `TExtendedHelper.IsNaN` (1652), `TExtendedHelper.IsPositiveInfinity` (1653), `TExtendedHelper.IsNegativeInfinity` (1653)

76.74.9 TExtendedHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

Declaration: `class function IsNegativeInfinity(const AValue: Extended) : Boolean
; Overload; Static
function IsNegativeInfinity : Boolean; Overload`

Visibility: public

Description: `IsNegativeInfinity` checks whether a Extended-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TExtendedHelper.IsNan` ([1652](#)), `TExtendedHelper.IsPositiveInfinity` ([1653](#)), `TExtendedHelper.IsInfinity` ([1652](#))

76.74.10 TExtendedHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

Declaration: `class function IsPositiveInfinity(const AValue: Extended) : Boolean
; Overload; Static
function IsPositiveInfinity : Boolean; Overload`

Visibility: public

Description: `IsPositiveInfinity` checks whether a Extended-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: `TExtendedHelper.IsNan` ([1652](#)), `TExtendedHelper.IsNegativeInfinity` ([1653](#)), `TExtendedHelper.IsInfinity` ([1652](#))

76.74.11 TExtendedHelper.Size

Synopsis: Size (in bytes) of a Extended-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` is the size (in bytes) of a Extended-sized floating point value. It is equivalent to calling `SizeOf(Extended)`.

See also: `SizeOf` ([1392](#))

76.74.12 TExtendedHelper.BuildUp

Synopsis: Build a Extended-sized floating point from its composing parts

Declaration: `procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
const AExponent: Integer)`

Visibility: public

Description: `BuildUp` will compose a Extended-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` ([1655](#)), `Exp` ([1655](#)) and `Frac` ([1656](#)) properties in 1 call.

See also: `TExtendedHelper.Sign` ([1655](#)), `TExtendedHelper.Exp` ([1655](#)), `TExtendedHelper.Frac` ([1656](#))

76.74.13 TExtendedHelper.Exponent

Synopsis: Exponent of the floating-point value

Declaration: `function Exponent : Integer`

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \cdot 2^X$, i.e. the exponent.

See also: `TExtendedHelper.Sign` ([1655](#)), `TExtendedHelper.Exp` ([1655](#)), `TExtendedHelper.Frac` ([1656](#)), `TExtendedHelper.Fraction` ([1654](#)), `TExtendedHelper.Mantissa` ([1654](#))

76.74.14 TExtendedHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TExtendedHelper.Sign` ([1655](#)), `TExtendedHelper.Exp` ([1655](#)), `TExtendedHelper.Exponent` ([1654](#)), `TExtendedHelper.Frac` ([1656](#)), `TExtendedHelper.Mantissa` ([1654](#))

76.74.15 TExtendedHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TExtendedHelper.Sign` ([1655](#)), `TExtendedHelper.Exp` ([1655](#)), `TExtendedHelper.Exponent` ([1654](#)), `TExtendedHelper.Frac` ([1656](#)), `TExtendedHelper.Fraction` ([1654](#))

76.74.16 TExtendedHelper.SpecialType

Synopsis: Return the type of the Extended-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the Extended-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` ([1442](#)) for an explanation of the possible values.

See also: `TFloatSpecial` ([1442](#))

76.74.17 TExtendedHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TExtendedHelper.Words` ([1655](#)), `TExtendedHelper.Size` ([1653](#))

76.74.18 TExtendedHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the Extended-sized floating point value. The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TExtendedHelper.Bytes` ([1655](#)), `TExtendedHelper.Size` ([1653](#))

76.74.19 TExtendedHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TExtendedHelper.Bytes` ([1655](#)), `TExtendedHelper.Exp` ([1655](#)), `TExtendedHelper.Frac` ([1656](#)), `TExtendedHelper.Mantissa` ([1654](#)), `TExtendedHelper.Fraction` ([1654](#)), `TExtendedHelper.Exponent` ([1654](#))

76.74.20 TExtendedHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent ([1654](#)).

See also: `TExtendedHelper.Bytes` ([1655](#)), `TExtendedHelper.Sign` ([1655](#)), `TExtendedHelper.Frac` ([1656](#)), `TExtendedHelper.Mantissa` ([1654](#)), `TExtendedHelper.Fraction` ([1654](#)), `TExtendedHelper.Exponent` ([1654](#))

76.74.21 TExtendedHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: `public`

Access: `Read, Write`

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TExtendedHelper.Bytes` (1655), `TExtendedHelper.Sign` (1655), `TExtendedHelper.Exp` (1655), `TExtendedHelper.Mantissa` (1654), `TExtendedHelper.Fraction` (1654), `TExtendedHelper.Exponent` (1654)

76.75 TGuidHelper

76.75.1 Description

`TGuidHelper` provides various methods for a `TGUID` (1442) type.

See also: `TGUID` (1442)

76.75.2 Method overview

Page	Method	Description
1656	<code>Create</code>	Initialize a <code>TGUID</code> instance from data.
1657	<code>NewGuid</code>	Create a new <code>GUID</code>
1657	<code>ToByteArray</code>	Convert to array of bytes
1657	<code>ToString</code>	Convert to string

76.75.3 TGuidHelper.Create

Synopsis: Initialize a `TGUID` instance from data.

```

Declaration: class function Create(const Data; BigEndian: Boolean) : TGuid; Overload
              ; Static
class function Create(const Data: Array of Byte; AStartIndex: Cardinal;
                    BigEndian: Boolean) : TGuid; Overload; Static
class function Create(const Data; DataEndian: TEndian) : TGuid
              ; Overload; Static
class function Create(const B: TBytes; DataEndian: TEndian) : TGuid
              ; Overload; Static
class function Create(const B: TBytes; AStartIndex: Cardinal;
                    DataEndian: TEndian) : TGuid; Overload; Static
class function Create(const S: string) : TGuid; Overload; Static
class function Create(A: Integer; B: SmallInt; C: SmallInt;
                    const D: TBytes) : TGuid; Overload; Static
class function Create(A: Integer; B: SmallInt; C: SmallInt; D: Byte;
                    E: Byte; F: Byte; G: Byte; H: Byte; I: Byte;
                    J: Byte; K: Byte) : TGuid; Overload; Static
class function Create(A: Cardinal; B: Word; C: Word; D: Byte; E: Byte;
                    F: Byte; G: Byte; H: Byte; I: Byte; J: Byte;
                    K: Byte) : TGuid; Overload; Static

```

Visibility: default

Description: `Create` will initialize a `TGUID` (1442) from byte data. The byte-data can come in different forms

Data can be a plain buffer. The GUID Data will be read from the buffer (`SizeOf(TGUID)` bytes), according to the `BigEndian` argument.

Data can be an array of bytes. `SizeOf(TGUID)` bytes will be read from the array, starting at index `StartIndex` (default 0). The GUID Data will be read according to the `BigEndian` argument.

Scan can be a string containing a string representation of the GUID, which is converted using `StringToGUID` (1577).

A,B,C,D (optionally E,F,G,H,I,J,K) where the arguments are simply the various components of the GUID.

See also: `TGUID` (1442), `StringToGUID` (1577)

76.75.4 TGuidHelper.NewGuid

Synopsis: Create a new GUID

Declaration: `class function NewGuid : TGuid; Static`

Visibility: default

Description: `NewGUID` creates and returns a new (??) using `CreateGUID` (1497)

See also: `CreateGUID` (1497)

76.75.5 TGuidHelper.ToByteArray

Synopsis: Convert to array of bytes

Declaration: `function ToByteArray(DataEndian: TEndian) : TBytes`

Visibility: default

Description: `ToByteArray` converts the `TGUID` to an array of bytes (of length `SizeOf(TGUID)`). The bytes will be ordered according to `DataEndian`.

See also: `TGUIDHelper.ToString` (1657), `TGUIDHelper.Create` (1656)

76.75.6 TGuidHelper.ToString

Synopsis: Convert to string

Declaration: `function ToString(SkipBrackets: Boolean) : string`

Visibility: default

Description: `ToString` will convert the `TGUID` to a string representation, using `GUIDToString` (1554)

See also: `GUIDToString` (1554)

76.76 TInt64Helper

76.76.1 Description

`TInt64Helper` contains some auxiliary routines for a `Int64`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1691](#)), `TShortIntHelper` ([1677](#)), `TSmallIntHelper` ([1689](#)), `TWordHelper` ([1718](#)), `TCardinalHelper` ([1635](#)), `TIntegerHelper` ([1660](#)), `TByteHelper` ([1632](#)), `TQWordHelper` ([1674](#)), `TNativeIntHelper` ([1668](#)), `TNativeUIntHelper` ([1671](#))

76.76.2 Method overview

Page	Method	Description
1658	<code>Parse</code>	Convert from a string
1658	<code>Size</code>	Size, in bytes, of the <code>Int64</code> value
1659	<code>ToBoolean</code>	Convert to a boolean value
1659	<code>ToDouble</code>	Convert to a double-sized floating point value
1660	<code>ToExtended</code>	Convert to an extended-sized floating point value
1660	<code>ToHexString</code>	Convert to a hexadecimal string representation
1660	<code>ToSingle</code>	Convert to a single-sized floating point value
1659	<code>ToString</code>	Convert the value to string
1659	<code>TryParse</code>	Try to convert a string to a <code>Int64</code> , report success or failure

76.76.3 TInt64Helper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Int64; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `Int64` value. It uses the `StrToInt64` ([1591](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Int64` value, an `EConvertError` ([1616](#)) exception is raised.

See also: `TInt64Helper.ToString` ([1659](#)), `TInt64Helper.TryParse` ([1659](#)), `StrToInt64` ([1591](#))

76.76.4 TInt64Helper.Size

Synopsis: Size, in bytes, of the `Int64` value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in `Int64`s) of the `Int64` value. This is equivalent to `SizeOf(Int64)`.

Errors: None.

See also: `SizeOf` ([1392](#))

76.76.5 TInt64Helper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Int64) : string; Overload
; Static
function ToString : string; Overload`

Visibility: public

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Int64` value itself is used. The `IntToStr` ([1558](#)) function is used to do the conversion.

See also: `TInt64Helper.Parse` ([1658](#)), `IntToStr` ([1558](#))

76.76.6 TInt64Helper.TryParse

Synopsis: Try to convert a string to a `Int64`, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Int64)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Int64`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Int64` is returned in `AValue`.

It uses the `val` ([1442](#)) function to perform the conversion, so no localization is taken into account.

See also: `TInt64Helper.Parse` ([1658](#)), `Val` ([1413](#))

76.76.7 TInt64Helper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Int64` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TInt64Helper.ToSingle` ([1660](#)), `TInt64Helper.ToDouble` ([1659](#)), `TInt64Helper.ToExtended` ([1660](#)), `TInt64Helper.ToString` ([1659](#)), `TInt64Helper.ToHexString` ([1660](#))

76.76.8 TInt64Helper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Int64` value to a double-sized floating point value.

See also: `TInt64Helper.ToBoolean` ([1659](#)), `TInt64Helper.ToExtended` ([1660](#)), `TInt64Helper.ToSingle` ([1660](#)), `TInt64Helper.ToString` ([1659](#)), `TInt64Helper.ToHexString` ([1660](#))

76.76.9 TInt64Helper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Int64` value to an extended-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1659), `TInt64Helper.ToSingle` (1660), `TInt64Helper.ToDouble` (1659), `TInt64Helper.ToString` (1659), `TInt64Helper.HexString` (1660)

76.76.10 TInt64Helper.HexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Int64` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TInt64Helper.ToBoolean` (1659), `TInt64Helper.ToSingle` (1660), `TInt64Helper.ToDouble` (1659), `TInt64Helper.ToString` (1659), `TInt64Helper.ToExtended` (1660)

76.76.11 TInt64Helper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Int64` value to a single-sized floating point value.

See also: `TInt64Helper.ToBoolean` (1659), `TInt64Helper.ToDouble` (1659), `TInt64Helper.ToExtended` (1660), `TInt64Helper.ToString` (1659), `TInt64Helper.HexString` (1660)

76.77 TIntegerHelper

76.77.1 Description

`TIntegerHelper` contains some auxiliary routines for a `Integer`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TWordHelper` (1718), `TCardinalHelper` (1635), `TByteHelper` (1632), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TNativeUIntHelper` (1671)

76.77.2 Method overview

Page	Method	Description
1661	<code>Parse</code>	Convert from a string
1661	<code>Size</code>	Size, in bytes, of the Integer value
1662	<code>ToBoolean</code>	Convert to a boolean value
1662	<code>ToDouble</code>	Convert to a double-sized floating point value
1662	<code>ToExtended</code>	Convert to an extended-sized floating point value
1663	<code>ToHexString</code>	Convert to a hexadecimal string representation
1663	<code>ToSingle</code>	Convert to a single-sized floating point value
1661	<code>ToString</code>	Convert the value to string
1662	<code>TryParse</code>	Try to convert a string to a Integer, report success or failure

76.77.3 TIntegerHelper.Size

Synopsis: Size, in bytes, of the Integer value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in Integers) of the Integer value. This is equivalent to `SizeOf(Integer)`.

Errors: None.

See also: `SizeOf` ([1392](#))

76.77.4 TIntegerHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Integer) : string; Overload
; Static
function ToString : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the Integer value itself is used. The `IntToStr` ([1558](#)) function is used to do the conversion.

See also: `TIntegerHelper.Parse` ([1661](#)), `IntToStr` ([1558](#))

76.77.5 TIntegerHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Integer; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a Integer value. It uses the `StrToInt` ([1590](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid Integer value, an `EConvertError` ([1616](#)) exception is raised.

See also: `TIntegerHelper.ToString` ([1661](#)), `TIntegerHelper.TryParse` ([1662](#)), `StrToInt` ([1590](#))

76.77.6 TIntegerHelper.TryParse

Synopsis: Try to convert a string to a Integer, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Integer)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Integer`, and reports the success of the attempt. If the attempt is succesful, then `True` is returned, and the actual value of the `Integer` is returned in `AValue`.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: `TIntegerHelper.Parse` (1661), `Val` (1413)

76.77.7 TIntegerHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Integer` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TIntegerHelper.ToSingle` (1663), `TIntegerHelper.ToDouble` (1662), `TIntegerHelper.ToExtended` (1662), `TIntegerHelper.ToString` (1661), `TIntegerHelper.ToHexString` (1663)

76.77.8 TIntegerHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Integer` value to a double-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1662), `TIntegerHelper.ToExtended` (1662), `TIntegerHelper.ToSingle` (1663), `TIntegerHelper.ToString` (1661), `TIntegerHelper.ToHexString` (1663)

76.77.9 TIntegerHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Integer` value to an extended-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1662), `TIntegerHelper.ToSingle` (1663), `TIntegerHelper.ToDouble` (1662), `TIntegerHelper.ToString` (1661), `TIntegerHelper.ToHexString` (1663)

76.77.10 TIntegerHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Integer` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TIntegerHelper.ToBoolean` (1662), `TIntegerHelper.ToSingle` (1663), `TIntegerHelper.ToDouble` (1662), `TIntegerHelper.ToString` (1661), `TIntegerHelper.ToExtended` (1662)

76.77.11 TIntegerHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Integer` value to a single-sized floating point value.

See also: `TIntegerHelper.ToBoolean` (1662), `TIntegerHelper.ToDouble` (1662), `TIntegerHelper.ToExtended` (1662), `TIntegerHelper.ToString` (1661), `TIntegerHelper.ToHexString` (1663)

76.78 TLongBoolHelper

76.78.1 Description

`TLongBoolHelper` is a helper type for the `LongBool` type. It contains mostly conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TWordHelper` (1718), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TByteHelper` (1632), `TByteBoolHelper` (1630), `TWordBoolHelper` (1717), `TLongBoolHelper` (1663)

76.78.2 Method overview

Page	Method	Description
1663	<code>Parse</code>	Convert string value to <code>LongBool</code> value.
1664	<code>Size</code>	Return the size (in bytes) of the
1665	<code>ToInteger</code>	Convert to an integer value
1664	<code>ToString</code>	Convert a <code>LongBool</code> value to string.
1664	<code>TryToParse</code>	Try to convert a string to a <code>LongBool</code> value

76.78.3 TLongBoolHelper.Parse

Synopsis: Convert string value to `LongBool` value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: `Parse` attempts to convert the string `S` to a `LongBool` value. It uses the `StrToBool` (1585) function to perform the conversion.

Errors: If `S` does not contain a valid string representation, then an `EConvertError` (1616) exception is raised.

See also: `TLongBoolHelper.TryToParse` (1664), `TLongBoolHelper.ToString` (1664), `TLongBoolHelper.ToInteger` (1665)

76.78.4 TLongBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` returns the size (in bytes) of the `LongBool` value. This is equivalent to `SizeOf(LongBool)`.

See also: `SizeOf` (1392)

76.78.5 TLongBoolHelper.ToString

Synopsis: Convert a `LongBool` value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
 function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue` `LongBool` to a string representation. In the function method version the `LongBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `LongBool` strings `BoolStrs` (1442). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1490) function.

See also: `BoolStrs` (1442), `BoolToStr` (1490)

76.78.6 TLongBoolHelper.TryToParse

Synopsis: Try to convert a string to a `LongBool` value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)
 : Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a `LongBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TLongBoolHelper.Parse` (1663), `TLongBoolHelper.ToString` (1664)

76.78.7 TLongBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `LongBool` value, typecasted to `Integer`.

See also: `TLongBoolHelper.ToString` ([1664](#))

76.79 TMBCSEncoding

76.79.1 Description

`TMBCSEncoding` is the encoding class used for most of the encodings, except the actual Unicode encodings. The codepage is specified during creation, and is by default the system codepage.

The name is somewhat misleading, since the MBCS is also used for single-byte encodings.

See also: `TUnicodeEncoding` ([1712](#)), `TUTF8Encoding` ([1715](#)), `TUTF7Encoding` ([1714](#)), `TBigendianUnicodeEncoding` ([1628](#))

76.79.2 Method overview

Page	Method	Description
1665	<code>Clone</code>	Clone a <code>TMBCSEncoding</code> instance
1665	<code>Create</code>	Create a new instance of a multi-byte character set encoding
1666	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1666	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes
1666	<code>GetPreamble</code>	Return BOM marker bytes

76.79.3 TMBCSEncoding.Create

Synopsis: Create a new instance of a multi-byte character set encoding

Declaration: `constructor Create; Virtual; Overload`
`constructor Create(ACodePage: Integer); Virtual; Overload`
`constructor Create(ACodePage: Integer; MBToWCharFlags: Integer; WCharToMBFlags: Integer); Virtual; Overload`

Visibility: public

Description: `Create` instantiates a new instance of the multi-byte character set encoding. The `ACodePage` parameter is optional, and defaults to `DefaultSystemCodePage` ([1442](#)).

The `MBToWCharFlags` and `WCharToMBFlags` parameters are stored but are otherwise unused in the Free Pascal implementation of `TMBCSEncoding`

76.79.4 TMBCSEncoding.Clone

Synopsis: Clone a `TMBCSEncoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: public

Description: `CLone` overrides `TEncoding.Clone` (1645) to provide a clone of the `TMBCSEncoding` instance.

See also: `TEncoding.Clone` (1645)

76.79.5 `TMBCSEncoding.GetMaxByteCount`

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount(CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1646) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1646)

76.79.6 `TMBCSEncoding.GetMaxCharCount`

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount(ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1647) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1647)

76.79.7 `TMBCSEncoding.GetPreamble`

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1647) to return the BOM Marker bytes (none, for this implementation).

See also: `TEncoding.GetPreamble` (1647)

76.80 `TMultiReadExclusiveWriteSynchronizer`

76.80.1 Description

`TMultiReadExclusiveWriteSynchronizer` is a default implementation of the `IReadWriteSync` (1626) interface. It uses a single mutex to protect access to the read/write resource, resulting in a single thread having access to the resource.

See also: `IReadWriteSync` (1626)

76.80.2 Interfaces overview

Page	Interfaces	Description
1626	IReadWriteSync	Read/Write synchronizer

76.80.3 Method overview

Page	Method	Description
1668	Beginread	Request read access to the resource
1667	Beginwrite	Request write access to the resource.
1667	Create	Create a new instance of the TMultiReadExclusiveWriteSynchronizer class
1667	Destroy	Destroys the TMultiReadExclusiveWriteSynchronizer instance
1668	Endread	Release read access to the resource
1668	Endwrite	Release write access to the resource

76.80.4 TMultiReadExclusiveWriteSynchronizer.Create

Synopsis: Create a new instance of the TMultiReadExclusiveWriteSynchronizer class

Declaration: constructor Create; Virtual

Visibility: public

Description: Create creates a new instance of TMultiReadExclusiveWriteSynchronizer. It initializes a TRTLCriticalSection.

Errors: None.

See also: TRTLCriticalSection ([1246](#))

76.80.5 TMultiReadExclusiveWriteSynchronizer.Destroy

Synopsis: Destroys the TMultiReadExclusiveWriteSynchronizer instance

Declaration: destructor Destroy; Override

Visibility: public

Description: Create destroys the instance of TMultiReadExclusiveWriteSynchronizer. It frees the TRTLCriticalSection it initialized, and calls the inherited destructor.

Errors: None.

See also: TRTLCriticalSection ([1246](#))

76.80.6 TMultiReadExclusiveWriteSynchronizer.Beginwrite

Synopsis: Request write access to the resource.

Declaration: function Beginwrite : Boolean

Visibility: public

Description: Beginwrite is the implementation of IReadWriteSync.BeginWrite. It simply enters the critical section, and returns True.

Errors: None.

See also: `IReadWriteSync.BeginWrite` ([1627](#)), `EndWrite` ([1668](#))

76.80.7 `TMultiReadExclusiveWriteSynchronizer.Endwrite`

Synopsis: Release write access to the resource

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `Beginwrite` is the implementation of `IReadWriteSync.EndWrite`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndWrite` ([1628](#)), `BeginWrite` ([1667](#))

76.80.8 `TMultiReadExclusiveWriteSynchronizer.Beginread`

Synopsis: Request read access to the resource

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` is the implementation of `IReadWriteSync.BeginRead`. It simply attempts to enter the critical section.

Errors: None.

See also: `IReadWriteSync.BeginRead` ([1627](#)), `EndRead` ([1668](#))

76.80.9 `TMultiReadExclusiveWriteSynchronizer.Endread`

Synopsis: Release read access to the resource

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` is the implementation of `IReadWriteSync.EndRead`. It simply leaves the critical section.

Errors: None.

See also: `IReadWriteSync.EndRead` ([1627](#)), `BeginRead` ([1668](#))

76.81 `TNativeIntHelper`

76.81.1 Description

`TNativeIntHelper` contains some auxiliary routines for a `NativeInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` ([1691](#)), `TShortIntHelper` ([1677](#)), `TSmallIntHelper` ([1689](#)), `TWordHelper` ([1718](#)), `TCardinalHelper` ([1635](#)), `TIntegerHelper` ([1660](#)), `TInt64Helper` ([1658](#)), `TQWordHelper` ([1674](#)), `TNativeIntHelper` ([1668](#)), `TByteHelper` ([1632](#))

76.81.2 Method overview

Page	Method	Description
1669	<code>Parse</code>	Convert from a string
1669	<code>Size</code>	Size, in bytes, of the <code>NativeInt</code> value
1670	<code>ToBoolean</code>	Convert to a boolean value
1670	<code>ToDouble</code>	Convert to a double-sized floating point value
1670	<code>ToExtended</code>	Convert to an extended-sized floating point value
1671	<code>ToHexString</code>	Convert to a hexadecimal string representation
1671	<code>ToSingle</code>	Convert to an single-sized floating point value
1669	<code>ToString</code>	Convert the value to string
1670	<code>TryParse</code>	Try to convert a string to a <code>NativeInt</code> , report success or failure

76.81.3 TNativeIntHelper.Parse

Synopsis: Convert from a string

```
Declaration: class function Parse(const AString: string) : NativeInt; Static
```

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `NativeInt` value. It uses the `StrToInt` (1590) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `NativeInt` value, an `EConvertError` (1616) exception is raised.

See also: [TNativeIntHelper.ToString \(1669\)](#), [TNativeIntHelper.TryParse \(1670\)](#), [StrToInt \(1590\)](#)

76.81.4 TNativeIntHelper.Size

Synopsis: Size, in bytes, of the NativeInt value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in `NativeInts`) of the `NativeInt` value. This is equivalent to `SizeOf(NativeInt)`.

Errors: None.

See also: [SizeOf \(1392\)](#)

76.81.5 TNativeIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: NativeInt) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the NativeInt value itself is used. The IntToStr (1558) function is used to do the conversion.

See also: [TNativeIntHelper.Parse \(1669\)](#), [IntToStr \(1558\)](#)

76.81.6 TNativeIntHelper.TryParse

Synopsis: Try to convert a string to a NativeInt, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: NativeInt)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `NativeInt`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `NativeInt` is returned in `AValue`.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: `TNativeIntHelper.Parse` (1669), `Val` (1413)

76.81.7 TNativeIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `NativeInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TNativeIntHelper.ToSingle` (1671), `TNativeIntHelper.ToDouble` (1670), `TNativeIntHelper.ToExtended` (1670), `TNativeIntHelper.ToString` (1669), `TNativeIntHelper.ToHexString` (1671)

76.81.8 TNativeIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to a double-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1670), `TNativeIntHelper.ToExtended` (1670), `TNativeIntHelper.ToSingle` (1671), `TNativeIntHelper.ToString` (1669), `TNativeIntHelper.ToHexString` (1671)

76.81.9 TNativeIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeInt` value to an extended-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1670), `TNativeIntHelper.ToSingle` (1671), `TNativeIntHelper.ToDouble` (1670), `TNativeIntHelper.ToString` (1669), `TNativeIntHelper.ToHexString` (1671)

76.81.10 TNativeIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TNativeIntHelper.ToBoolean` (1670), `TNativeIntHelper.ToSingle` (1671), `TNativeIntHelper.ToDouble` (1670), `TNativeIntHelper.ToString` (1669), `TNativeIntHelper.ToExtended` (1670)

76.81.11 TNativeIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `NativeInt` value to a single-sized floating point value.

See also: `TNativeIntHelper.ToBoolean` (1670), `TNativeIntHelper.ToDouble` (1670), `TNativeIntHelper.ToExtended` (1670), `TNativeIntHelper.ToString` (1669), `TNativeIntHelper.ToHexString` (1671)

76.82 TNativeUIntHelper

76.82.1 Description

`NativeUInt` contains some auxiliary routines for a `NativeUInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TWordHelper` (1718), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TByteHelper` (1632)

76.82.2 Method overview

Page	Method	Description
1672	<code>Parse</code>	Convert from a string
1672	<code>Size</code>	Size, in bytes, of the <code>NativeUInt</code> value
1673	<code>ToBoolean</code>	Convert to a boolean value
1673	<code>ToDouble</code>	Convert to a double-sized floating point value
1673	<code>ToExtended</code>	Convert to an extended-sized floating point value
1673	<code>ToHexString</code>	Convert to a hexadecimal string representation
1674	<code>ToSingle</code>	Convert to an single-sized floating point value
1672	<code>ToString</code>	Convert the value to string
1672	<code>TryParse</code>	Try to convert a string to a <code>NativeUInt</code> , report success or failure

76.82.3 TNativeUIntHelper.Parse

Synopsis: Convert from a string

```
Declaration: class function Parse(const AString: string) : NativeUInt; Static
```

Visibility: public

Description: Parse will attempt to convert the string `AString` to a `NativeUInt` value. It uses the `StrToInt` (1590) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid NativeUInt value, an EConvertError (1616) exception is raised.

See also: [NativeUInt.ToString \(1442\)](#), [NativeUInt.TryParse \(1442\)](#), [StrToInt \(1590\)](#)

76.82.4 TNativeUIntHelper.Size

Synopsis: Size, in bytes, of the NativeUInt value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in `NativeUInts`) of the `NativeUInt` value. This is equivalent to `SizeOf(NativeUInt)`.

Errors: None.

See also: [SizeOf \(1392\)](#)

76.82.5 TNativeUIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: NativeUInt) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the NativeUInt value itself is used. The IntToStr (1558) function is used to do the conversion.

See also: [NativeUInt.Parse \(1442\)](#), [IntToStr \(1558\)](#)

76.82.6 TNativeUIntHelper.TryParse

Synopsis: Try to convert a string to a NativeUInt, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: NativeUInt)
                                         : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a NativeUInt, and reports the success of the attempt. If the attempt is succesful, then True is returned, and the actual value of the NativeUInt is returned in AValue.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: [NativeUInt.Parse \(1442\)](#), [Val \(1413\)](#)

76.82.7 TNativeUIntHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `NativeUInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `NativeUInt.ToSingle` (1442), `NativeUInt.ToDouble` (1442), `NativeUInt.ToExtended` (1442), `NativeUInt.ToString` (1442), `NativeUInt.ToHexString` (1442)

76.82.8 TNativeUIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to a double-sized floating point value.

See also: `NativeUInt.ToBoolean` (1442), `NativeUInt.ToExtended` (1442), `NativeUInt.ToSingle` (1442), `NativeUInt.ToString` (1442), `NativeUInt.ToHexString` (1442)

76.82.9 TNativeUIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `NativeUInt` value to an extended-sized floating point value.

See also: `NativeUInt.ToBoolean` (1442), `NativeUInt.ToSingle` (1442), `NativeUInt.ToDouble` (1442), `NativeUInt.ToString` (1442), `NativeUInt.ToHexString` (1442)

76.82.10 TNativeUIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `NativeUInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `NativeUInt.ToBoolean` (1442), `NativeUInt.ToSingle` (1442), `NativeUInt.ToDouble` (1442), `NativeUInt.ToString` (1442), `NativeUInt.ToExtended` (1442)

76.82.11 TNativeUIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `NativeUInt` value to a single-sized floating point value.

See also: `NativeUInt.ToBoolean` (1442), `NativeUInt.ToDouble` (1442), `NativeUInt.ToExtended` (1442), `NativeUInt.ToString` (1442), `NativeUInt.ToHexString` (1442)

76.83 TQWordHelper

76.83.1 Description

`TQWordHelper` contains some auxiliary routines for a `QWord`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TWordHelper` (1718), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TByteHelper` (1632), `TNativeIntHelper` (1668), `TNativeUIntHelper` (1671)

76.83.2 Method overview

Page	Method	Description
1674	<code>Parse</code>	Convert from a string
1675	<code>Size</code>	Size, in bytes, of the <code>QWord</code> value
1675	<code>ToBoolean</code>	Convert to a boolean value
1676	<code>ToDouble</code>	Convert to a double-sized floating point value
1676	<code>ToExtended</code>	Convert to an extended-sized floating point value
1676	<code>ToHexString</code>	Convert to a hexadecimal string representation
1676	<code>ToSingle</code>	Convert to an single-sized floating point value
1675	<code>ToString</code>	Convert the value to string
1675	<code>TryParse</code>	Try to convert a string to a <code>QWord</code> , report success or failure

76.83.3 TQWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : QWord; Static`

Visibility: public

Description: `Parse` will attempt to convert the string `AString` to a `QWord` value. It uses the `StrToQWord` (1593) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `QWord` value, an `EConvertError` (1616) exception is raised.

See also: `TQWordHelper.ToString` (1675), `TQWordHelper.TryParse` (1675), `StrToQWord` (1593)

76.83.4 TQWordHelper.Size

Synopsis: Size, in bytes, of the QWord value

```
Declaration: class function Size : Integer; Static
```

Visibility: public

Description: `Size` returns the size (in QWords) of the QWord value. This is equivalent to `SizeOf (QWord)`.

Errors: None.

See also: [SizeOf \(1392\)](#)

76.83.5 TQWordHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: QWord) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the QWord value itself is used. The IntToStr (1558) function is used to do the conversion.

See also: [TQWordHelper.Parse \(1674\)](#), [IntToStr \(1558\)](#)

76.83.6 TQWordHelper.TryParse

Synopsis: Try to convert a string to a QWord, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: QWord)
                                         : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a QWord, and reports the success of the attempt. If the attempt is succesful, then True is returned, and the actual value of the QWord is returned in AValue.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: [TQWordHelper.Parse \(1674\)](#), [Val \(1413\)](#)

76.83.7 TQWordHelper.ToBoolean

Synopsis: Convert to a boolean value

```
Declaration: function ToBoolean : Boolean
```

Visibility: public

Description: ToBoolean converts the QWord value to a boolean: it returns True if the value is nonzero, False if it is zero.

See also: [TQWordHelper.ToSingle \(1676\)](#), [TQWordHelper.ToDouble \(1676\)](#), [TQWordHelper.ToExtended \(1676\)](#), [TQWordHelper.ToString \(1675\)](#), [TQWordHelper.ToHexString \(1676\)](#)

76.83.8 TQWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: `public`

Description: `ToDouble` converts the `QWord` value to a double-sized floating point value.

See also: `TQWordHelper.ToBoolean` (1675), `TQWordHelper.ToExtended` (1676), `TQWordHelper.ToSingle` (1676), `TQWordHelper.ToString` (1675), `TQWordHelper.HexString` (1676)

76.83.9 TQWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: `public`

Description: `ToDouble` converts the `QWord` value to an extended-sized floating point value.

See also: `TQWordHelper.ToBoolean` (1675), `TQWordHelper.ToSingle` (1676), `TQWordHelper.ToDouble` (1676), `TQWordHelper.ToString` (1675), `TQWordHelper.HexString` (1676)

76.83.10 TQWordHelper.HexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: `public`

Description: `ToHexString` converts the `QWord` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TQWordHelper.ToBoolean` (1675), `TQWordHelper.ToSingle` (1676), `TQWordHelper.ToDouble` (1676), `TQWordHelper.ToString` (1675), `TQWordHelper.ToExtended` (1676)

76.83.11 TQWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: `public`

Description: `ToSingle` converts the `QWord` value to a single-sized floating point value.

See also: `TQWordHelper.ToBoolean` (1675), `TQWordHelper.ToDouble` (1676), `TQWordHelper.ToExtended` (1676), `TQWordHelper.ToString` (1675), `TQWordHelper.HexString` (1676)

76.84 TShortIntHelper

76.84.1 Description

TShortIntHelper contains some auxiliary routines for a ShortInt-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: TStringHelper (1691), TByteHelper (1632), TSmallIntHelper (1689), TWordHelper (1718), TCardinalHelper (1635), TIntegerHelper (1660), TInt64Helper (1658), TQWordHelper (1674), TNativeIntHelper (1668), TNativeUIntHelper (1671)

76.84.2 Method overview

Page	Method	Description
1677	Parse	Convert from a string
1677	Size	Size, in bytes, of the ShortInt value
1678	ToBoolean	Convert to a boolean value
1678	ToDouble	Convert to a double-sized floating point value
1679	ToExtended	Convert to an extended-sized floating point value
1679	ToHexString	Convert to a hexadecimal string representation
1679	ToSingle	Convert to a single-sized floating point value
1678	ToString	Convert the value to string
1678	TryParse	Try to convert a string to a ShortInt, report success or failure

76.84.3 TShortIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : ShortInt; Static`

Visibility: public

Description: Parse will attempt to convert the string AString to a ShortInt value. It uses the StrToInt (1590) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid ShortInt value, an EConvertError (1616) exception is raised.

See also: TShortIntHelper.ToString (1678), TShortIntHelper.TryParse (1678), StrToInt (1590)

76.84.4 TShortIntHelper.Size

Synopsis: Size, in bytes, of the ShortInt value

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in ShortInts) of the ShortInt value. This is equivalent to SizeOf(Byte).

Errors: None.

See also: SizeOf (1392)

76.84.5 TShortIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: ShortInt) : string; Overload
                ; Static
                function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the ShortInt value itself is used. The IntToStr (1558) function is used to do the conversion.

See also: [TShortIntHelper.Parse \(1677\)](#), [IntToStr \(1558\)](#)

76.84.6 TShortIntHelper.TryParse

Synopsis: Try to convert a string to a ShortInt, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: ShortInt)
                                         : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a ShortInt, and reports the success of the attempt. If the attempt is succesful, then True is returned, and the actual value of the ShortInt is returned in AValue.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: [TShortIntHelper.Parse \(1677\)](#), [Val \(1413\)](#)

76.84.7 TShortIntHelper.ToBoolean

Synopsis: Convert to a boolean value

```
Declaration: function ToBoolean : Boolean
```

Visibility: public

Description: `ToBoolean` converts the `ShortInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: [TShortIntHelper.ToSingle \(1679\)](#), [TShortIntHelper.ToDouble \(1678\)](#), [TShortIntHelper.ToExtended \(1679\)](#), [TShortIntHelper.ToString \(1678\)](#), [TShortIntHelper.ToHexString \(1679\)](#)

76.84.8 TShortIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

```
Declaration: function ToDouble : Double
```

Visibility: public

Description: ToDouble converts the ShortInt value to a double-sized floating point value.

See also: [TShortIntHelper.ToBoolean \(1678\)](#), [TShortIntHelper.ToExtended \(1679\)](#), [TShortIntHelper.ToSingle \(1679\)](#), [TShortIntHelper.ToString \(1678\)](#), [TShortIntHelper.ToHexString \(1679\)](#)

76.84.9 TShortIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `ShortInt` value to an extended-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1678), `TShortIntHelper.ToSingle` (1679), `TShortIntHelper.ToDouble` (1678), `TShortIntHelper.ToString` (1678), `TShortIntHelper.ToHexString` (1679)

76.84.10 TShortIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `ShortInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TShortIntHelper.ToBoolean` (1678), `TShortIntHelper.ToSingle` (1679), `TShortIntHelper.ToDouble` (1678), `TShortIntHelper.ToString` (1678), `TShortIntHelper.ToExtended` (1679)

76.84.11 TShortIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `ShortInt` value to a single-sized floating point value.

See also: `TShortIntHelper.ToBoolean` (1678), `TShortIntHelper.ToDouble` (1678), `TShortIntHelper.ToExtended` (1679), `TShortIntHelper.ToString` (1678), `TShortIntHelper.ToHexString` (1679)

76.85 TSimpleRWSync

76.85.1 Description

`TSimpleRWSync` implements a simple read/write locking mechanism. It controls access to an object: only a single thread is allowed access to an object for either read or write operations.

Access is controlled through a single critical section.

See also: `TMultiReadExclusiveWriteSynchronizer` (1666)

76.85.2 Interfaces overview

Page	Interfaces	Description
1626	<code>IRReadWriteSync</code>	Read/Write synchronizer

76.85.3 Method overview

Page	Method	Description
1681	Beginread	Acquire a read lock
1680	Beginwrite	Acquire a write lock
1680	Create	Create a new instance of <code>TSimpleRWSync</code>
1680	Destroy	Removes the <code>TSimpleRWSync</code> instance from memory
1681	Endread	Release the read lock
1680	Endwrite	Release the write lock

76.85.4 TSimpleRWSync.Create

Synopsis: Create a new instance of `TSimpleRWSync`

Declaration: `constructor Create; Virtual`

Visibility: `public`

Description: `Create` allocates a new instance of `TSimpleRWSync` and initializes the critical section for use in the various methods.

See also: `TSimpleRWSync.Destroy` ([1680](#))

76.85.5 TSimpleRWSync.Destroy

Synopsis: Removes the `TSimpleRWSync` instance from memory

Declaration: `destructor Destroy; Override`

Visibility: `public`

Description: `Destroy` releases the critical section and removes the `TSimpleRWSync` instance from memory.

See also: `TSimpleRWSync.Create` ([1680](#))

76.85.6 TSimpleRWSync.Beginwrite

Synopsis: Acquire a write lock

Declaration: `function Beginwrite : Boolean`

Visibility: `public`

Description: `Beginwrite` waits till all other threads have released their read or write locks on the object, and then acquires a write lock on the object.

See also: `TSimpleRWSync.BeginRead` ([1681](#)), `TSimpleRWSync.EndWrite` ([1680](#))

76.85.7 TSimpleRWSync.Endwrite

Synopsis: Release the write lock

Declaration: `procedure Endwrite`

Visibility: `public`

Description: `EndWrite` releases the current threads lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: `TSimpleRWSync.BeginWrite` ([1680](#)), `TSimpleRWSync.EndRead` ([1681](#))

76.85.8 TSimpleRWSync.Beginread

Synopsis: Acquire a read lock

Declaration: `procedure Beginread`

Visibility: `public`

Description: `BeginRead` waits till all other threads have released their read or write locks on the object, and then acquires a read lock on the object.

See also: `TSimpleRWSync.BeginWrite` ([1680](#)), `TSimpleRWSync.EndRead` ([1681](#))

76.85.9 TSimpleRWSync.Endread

Synopsis: Release the read lock

Declaration: `procedure Endread`

Visibility: `public`

Description: `EndRead` releases the current threads read lock on the object, allowing other threads to acquire a read or write lock on the object.

See also: `TSimpleRWSync.BeginRead` ([1681](#)), `TSimpleRWSync.EndWrite` ([1680](#))

76.86 TSingleHelper

76.86.1 Description

`TSingleHelper` is the helper type for the single-sized floating point type. It contains some conversion methods, as well as access to the low-level structure of the floating-point representation of a single.

See also: `TDoubleHelper` ([1638](#)), `TExtendedHelper` ([1650](#))

76.86.2 Method overview

Page	Method	Description
1686	BuildUp	Build a single-sized floating point from its composing parts
1686	Exponent	Exponent of the floating-point value
1687	Fraction	Fraction of the floating-point value
1682	GetB	
1682	GetE	
1683	GetF	
1683	GetS	
1682	GetW	
1684	IsInfinity	Check whether a value is positive or negative infinity.
1683	IsNan	Check whether a value equals NaN.
1684	IsNegativeInfinity	Check whether a value is negative infinity.
1684	IsPositiveInfinity	Check whether a value is positive infinity.
1687	Mantissa	Mantissa of the floating-point
1685	Parse	Convert a string to a floating point value
1683	SetB	
1683	SetE	
1683	SetF	
1683	SetS	
1683	SetW	
1685	Size	Size (in bytes) of a single-sized floating point value.
1687	SpecialType	Return the type of the single-sized floating point value
1685	ToString	Convert a single-sized floating point value to a string
1686	TryParse	Try to convert a string to a single-sized floating point value.

76.86.3 Property overview

Page	Properties	Access	Description
1687	Bytes	rw	Indexed access to the individual bytes of the floating point value
1688	Exp	rw	The bit pattern of the exponent as stored in memory.
1688	Frac	rw	Bitpattern that makes up the fractional part.
1688	Sign	rw	Sign of the floating point value
1688	Words	rw	Indexed access to the words that make up the floating point value

76.86.4 TSingleHelper.GetB

Declaration: `function GetB(AIndex: Cardinal) : Byte`

Visibility: default

76.86.5 TSingleHelper.GetW

Declaration: `function GetW(AIndex: Cardinal) : Word`

Visibility: default

76.86.6 TSingleHelper.GetE

Declaration: `function GetE : QWord`

Visibility: default

76.86.7 TSingleHelper.GetF

Declaration: `function GetF : QWord`

Visibility: `default`

76.86.8 TSingleHelper.GetS

Declaration: `function GetS : Boolean`

Visibility: `default`

76.86.9 TSingleHelper.SetB

Declaration: `procedure SetB(AIndex: Cardinal; const AValue: Byte)`

Visibility: `default`

76.86.10 TSingleHelper.SetW

Declaration: `procedure SetW(AIndex: Cardinal; const AValue: Word)`

Visibility: `default`

76.86.11 TSingleHelper.SetE

Declaration: `procedure SetE(AValue: QWord)`

Visibility: `default`

76.86.12 TSingleHelper.SetF

Declaration: `procedure SetF(AValue: QWord)`

Visibility: `default`

76.86.13 TSingleHelper.SetS

Declaration: `procedure SetS(AValue: Boolean)`

Visibility: `default`

76.86.14 TSingleHelper.IsNan

Synopsis: Check whether a value equals NaN.

Declaration: `class function IsNan(const AValue: Single) : Boolean; Overload; Static`
`function IsNan : Boolean; Overload`

Visibility: `public`

Description: `IsNan` checks whether a single-sized floating point value is NaN (Not a Number). If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: [TSingleHelper.IsInfinity \(1684\)](#), [TSingleHelper.IsPositiveInfinity \(1684\)](#), [TSingleHelper.IsNegativeInfinity \(1684\)](#)

76.86.15 TSingleHelper.IsInfinity

Synopsis: Check whether a value is positive or negative infinity.

```
Declaration: class function IsInfinity(const AValue: Single) : Boolean; Overload
                ; Static
                function IsInfinity : Boolean; Overload
```

Visibility: public

Description: `IsInfinity` checks whether a single-sized floating point value represents a positive or negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: [TSingleHelper.IsNaN \(1683\)](#), [TSingleHelper.IsPositiveInfinity \(1684\)](#), [TSingleHelper.IsNegativeInfinity \(1684\)](#)

76.86.16 TSingleHelper.IsNegativeInfinity

Synopsis: Check whether a value is negative infinity.

```
Declaration: class function IsNegativeInfinity(const AValue: Single) : Boolean
                                                    ; Overload; Static
function IsNegativeInfinity : Boolean; Overload
```

Visibility: public

Description: `IsNegativeInfinity` checks whether a single-sized floating point value represents a negative infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is (`Self`).

See also: [TSingleHelper.IsNan \(1683\)](#), [TSingleHelper.IsPositiveInfinity \(1684\)](#), [TSingleHelper.IsInfinity \(1684\)](#)

76.86.17 TSingleHelper.IsPositiveInfinity

Synopsis: Check whether a value is positive infinity.

```
Declaration: class function IsPositiveInfinity(const AValue: Single) : Boolean
                                                    ; Overload; Static
function IsPositiveInfinity : Boolean; Overload
```

Visibility: public

Description: `IsPositiveInfinity` checks whether a single-sized floating point value represents a positive infinity. If so, it returns `True`. When the class function version is used, the value can be specified using `AValue`. In the method version, the used value is `(Self)`.

See also: [TSingleHelper.IsNan \(1683\)](#), [TSingleHelper.IsNegativeInfinity \(1684\)](#), [TSingleHelper.IsInfinity \(1684\)](#)

76.86.18 TSingleHelper.Parse

Synopsis: Convert a string to a floating point value

Declaration: `class function Parse(const AString: string) : Single; Overload; Static`
`class function Parse(const AString: string;`
`const AFormatSettings: TFormatSettings) : Single`
`; Overload; Static`

Visibility: public

Description: `Parse` will try to convert `AString` to a single-sized floating point value. It will take into account internationalization settings. (it uses `FloatToStr`).

Errors: If the string `AString` is not a valid floating-point value, a `EConvertError` ([1616](#)) exception is raised.

See also: `FloatToStr` ([1532](#)), `TSingleHelper.ToString` ([1685](#)), `TSingleHelper.TryParse` ([1686](#))

76.86.19 TSingleHelper.Size

Synopsis: Size (in bytes) of a single-sized floating point value.

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: `Size` is the size (in bytes) of a single-sized floating point value. It is equivalent to calling `SizeOf(Single)`.

See also: `SizeOf` ([1392](#))

76.86.20 TSingleHelper.ToString

Synopsis: Convert a single-sized floating point value to a string

Declaration: `class function ToString(const AValue: Single) : string; Overload`
`; Static`
`class function ToString(const AValue: Single;`
`const AFormatSettings: TFormatSettings) : string`
`; Overload; Static`
`class function ToString(const AValue: Single;`
`const AFormat: TFloatFormat;`
`const APrecision: Integer;`
`const ADigits: Integer) : string; Overload`
`; Static`
`class function ToString(const AValue: Single;`
`const AFormat: TFloatFormat;`
`const APrecision: Integer;`
`const ADigits: Integer;`
`const AFormatSettings: TFormatSettings) : string`
`; Overload; Static`
`function ToString(const AFormat: TFloatFormat;`
`const APrecision: Integer; const ADigits: Integer)`
`: string; Overload`
`function ToString(const AFormat: TFloatFormat;`
`const APrecision: Integer; const ADigits: Integer;`
`const AFormatSettings: TFormatSettings) : string`
`; Overload`

```
function ToString(const AFormatSettings: TFormatSettings) : string
    ; Overload
function ToString : string; Overload
```

Visibility: public

Description: `ToString` will convert `AValue` (or `Self` in the plain method version) to a string. Optionally `FormatSettings` can be specified, to be able to specify the decimal separator character to use.

Additionally, a precision `APrecision` and number of digits `ADigits` can be specified, in conjunction with a `AFormat` parameter to specify the form in which the floating-point value must be represented. (see `TFloatFormat` (1462) for an explanation of the various values). In this case, `FloatToStrF` (1533) is used to format the value. In the absence of these parameters, `FloatToStr` (1532) is called.

See also: `FloatToStr` (1532), `FloatToStrF` (1533), `TFloatFormat` (1462)

76.86.21 TSingleHelper.TryParse

Synopsis: Try to convert a string to a single-sized floating point value.

```
Declaration: class function TryParse(const AString: string; out AValue: Single)
    : Boolean; Overload; Static
class function TryParse(const AString: string; out AValue: Single;
    const AFormatSettings: TFormatSettings) : Boolean
    ; Overload; Static
```

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a single-sized floating point value and reports `True` if the conversion was successful. In that case the parsed value is returned in `AValue`.

If the conversion failed, `False` is returned.

See also: `TSingleHelper.Parse` (1685), `TSingleHelper.ToString` (1685)

76.86.22 TSingleHelper.BuildUp

Synopsis: Build a single-sized floating point from its composing parts

```
Declaration: procedure BuildUp(const ASignFlag: Boolean; const AMantissa: QWord;
    const AExponent: Integer)
```

Visibility: public

Description: `BuildUp` will compose a single-sized floating point value from the sign `ASignFlag`, mantissa `AMantissa` and exponent `AExponent`. It simply sets the `Sign` (1688), `Exp` (1688) and `Frac` (1688) properties in 1 call.

See also: `TSingleHelper.Sign` (1688), `TSingleHelper.Exp` (1688), `TSingleHelper.Frac` (1688)

76.86.23 TSingleHelper.Exponent

Synopsis: Exponent of the floating-point value

```
Declaration: function Exponent : Integer
```

Visibility: public

Description: `Exponent` is the value X in the representation of the floating-point value in $m \times 2^X$, i.e. the exponent.

See also: `TSingleHelper.Sign` (1688), `TSingleHelper.Exp` (1688), `TSingleHelper.Frac` (1688), `TSingleHelper.Fraction` (1687), `TSingleHelper.Mantissa` (1687)

76.86.24 TSingleHelper.Fraction

Synopsis: Fraction of the floating-point value

Declaration: `function Fraction : Extended`

Visibility: public

Description: `Fraction` is the decimal part of the floating-point value.

See also: `TSingleHelper.Sign` (1688), `TSingleHelper.Exp` (1688), `TSingleHelper.Exponent` (1686), `TSingleHelper.Frac` (1688), `TSingleHelper.Mantissa` (1687)

76.86.25 TSingleHelper.Mantissa

Synopsis: Mantissa of the floating-point

Declaration: `function Mantissa : QWord`

Visibility: public

Description: `Mantissa` is the value of the significand without the hidden bit. This means it the plain bit pattern as it is stored in memory.

See also: `TSingleHelper.Sign` (1688), `TSingleHelper.Exp` (1688), `TSingleHelper.Exponent` (1686), `TSingleHelper.Frac` (1688), `TSingleHelper.Fraction` (1687)

76.86.26 TSingleHelper.SpecialType

Synopsis: Return the type of the single-sized floating point value

Declaration: `function SpecialType : TFloatSpecial`

Visibility: public

Description: `SpecialType` checks whether the single-sized floating point value equals one of several special values, and returns an enumerated value describing which value this is. See `TFloatSpecial` (1442) for an explanation of the possible values.

See also: `TFloatSpecial` (1442)

76.86.27 TSingleHelper.Bytes

Synopsis: Indexed access to the individual bytes of the floating point value

Declaration: `Property Bytes[AIndex: Cardinal]: Byte`

Visibility: public

Access: Read,Write

Description: `Bytes` can be used to get or set the various bytes that make up the single-sized floating point value. The index runs from 0 to `Size-1`.

See also: `TSingleHelper.Words` (1688), `TSingleHelper.Size` (1685)

76.86.28 TSingleHelper.Words

Synopsis: Indexed access to the words that make up the floating point value

Declaration: `Property Words[AIndex: Cardinal]: Word`

Visibility: public

Access: Read,Write

Description: `Words` can be used to get or set the various bytes that make up the single-sized floating point value.
The index runs from 0 to $(\text{Size}-1) \div 2$.

See also: `TSingleHelper.Bytes` (1687), `TSingleHelper.Size` (1685)

76.86.29 TSingleHelper.Sign

Synopsis: Sign of the floating point value

Declaration: `Property Sign : Boolean`

Visibility: public

Access: Read,Write

Description: `Sign` returns `True` if the sign bit of the value is set (i.e. it is a negative value) or `False` if it is not set (i.e. it is a positive value).

See also: `TSingleHelper.Bytes` (1687), `TSingleHelper.Exp` (1688), `TSingleHelper.Frac` (1688), `TSingleHelper.Mantissa` (1687), `TSingleHelper.Fraction` (1687), `TSingleHelper.Exponent` (1686)

76.86.30 TSingleHelper.Exp

Synopsis: The bit pattern of the exponent as stored in memory.

Declaration: `Property Exp : QWord`

Visibility: public

Access: Read,Write

Description: `Exp` is the internal representation of the Exponent (1686).

See also: `TSingleHelper.Bytes` (1687), `TSingleHelper.Sign` (1688), `TSingleHelper.Frac` (1688), `TSingleHelper.Mantissa` (1687), `TSingleHelper.Fraction` (1687), `TSingleHelper.Exponent` (1686)

76.86.31 TSingleHelper.Frac

Synopsis: Bitpattern that makes up the fractional part.

Declaration: `Property Frac : QWord`

Visibility: public

Access: Read,Write

Description: `Frac` is the bit pattern representing the fractional part (significand) including the preceding 1 (the hidden bit).

See also: `TSingleHelper.Bytes` (1687), `TSingleHelper.Sign` (1688), `TSingleHelper.Exp` (1688), `TSingleHelper.Mantissa` (1687), `TSingleHelper.Fraction` (1687), `TSingleHelper.Exponent` (1686)

76.87 TSmallIntHelper

76.87.1 Description

`TSmallIntHelper` contains some auxiliary routines for a `SmallInt`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TByteHelper` (1632), `TWordHelper` (1718), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TNativeUIntHelper` (1671)

76.87.2 Method overview

Page	Method	Description
1689	<code>Parse</code>	Convert from a string
1689	<code>Size</code>	Size, in bytes, of the <code>SmallInt</code> value
1690	<code>ToBoolean</code>	Convert to a boolean value
1691	<code>ToDouble</code>	Convert to a double-sized floating point value
1691	<code>ToExtended</code>	Convert to an extended-sized floating point value
1690	<code>ToHexString</code>	Convert to a hexadecimal string representation
1691	<code>ToSingle</code>	Convert to a single-sized floating point value
1690	<code>ToString</code>	Convert the value to string
1690	<code>TryParse</code>	Try to convert a string to a <code>SmallInt</code> , report success or failure

76.87.3 TSmallIntHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : SmallInt; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `SmallInt` value. It uses the `StrToInt` (1590) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `SmallInt` value, an `EConvertError` (1616) exception is raised.

See also: `TSmallIntHelper.ToString` (1690), `TSmallIntHelper.TryParse` (1690), `StrToInt` (1590)

76.87.4 TSmallIntHelper.Size

Synopsis: Size, in bytes, of the `SmallInt` value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in `SmallInt`s) of the `SmallInt` value. This is equivalent to `SizeOf(SmallInt)`.

Errors: None.

See also: `SizeOf` (1392)

76.87.5 TSmallIntHelper.ToString

Synopsis: Convert the value to string

```
Declaration: class function ToString(const AValue: SmallInt) : string; Overload
              ; Static
              function ToString : string; Overload
```

Visibility: public

Description: ToString will, in the class function variant of this method, convert AValue to a string representation. In the regular method overloaded version of ToString, the SmallInt value itself is used. The IntToStr (1558) function is used to do the conversion.

See also: `TSmallIntHelper.Parse` ([1689](#)), `IntToStr` ([1558](#))

76.87.6 TSmallIntHelper.TryParse

Synopsis: Try to convert a string to a SmallInt, report success or failure

```
Declaration: class function TryParse(const AString: string; out AValue: SmallInt)
                                     : Boolean; Static
```

Visibility: public

Description: TryParse attempts to convert the string AString to a SmallInt, and reports the success of the attempt. If the attempt is succesful, then True is returned, and the actual value of the SmallInt is returned in AValue.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: [TSmallIntHelper.Parse \(1689\)](#), [Val \(1413\)](#)

76.87.7 TSmallIntHelper.ToBoolean

Synopsis: Convert to a boolean value

```
Declaration: function ToBoolean : Boolean
```

Visibility: public

Description: `ToBoolean` converts the `SmallInt` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: [TSmallIntHelper.ToSingle \(1691\)](#), [TSmallIntHelper.ToDouble \(1691\)](#), [TSmallIntHelper.ToExtended \(1691\)](#), [TSmallIntHelper.ToString \(1690\)](#), [TSmallIntHelper.ToHexString \(1690\)](#)

76.87.8 TSmallIntHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

```
Declaration: function ToHexString : string; Overload
            function ToHexString(const AMinDigits: Integer) : string; Overload
```

Visibility: public

Description: `ToHexString` converts the `SmallInt` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TSmallIntHelper.ToBoolean` ([1690](#)), `TSmallIntHelper.ToSingle` ([1691](#)), `TSmallIntHelper.ToDouble` ([1691](#)), `TSmallIntHelper.ToString` ([1690](#)), `TSmallIntHelper.ToExtended` ([1691](#))

76.87.9 TSmallIntHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `SmallInt` value to a single-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` ([1690](#)), `TSmallIntHelper.ToDouble` ([1691](#)), `TSmallIntHelper.ToExtended` ([1691](#)), `TSmallIntHelper.ToString` ([1690](#)), `TSmallIntHelper.ToHexString` ([1690](#))

76.87.10 TSmallIntHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `SmallInt` value to a double-sized floating point value

See also: `TSmallIntHelper.ToBoolean` ([1690](#)), `TSmallIntHelper.ToExtended` ([1691](#)), `TSmallIntHelper.ToSingle` ([1691](#)), `TSmallIntHelper.ToString` ([1690](#)), `TSmallIntHelper.ToHexString` ([1690](#))

76.87.11 TSmallIntHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `SmallInt` value to an extended-sized floating point value.

See also: `TSmallIntHelper.ToBoolean` ([1690](#)), `TSmallIntHelper.ToSingle` ([1691](#)), `TSmallIntHelper.ToDouble` ([1691](#)), `TSmallIntHelper.ToString` ([1690](#)), `TSmallIntHelper.ToHexString` ([1690](#))

76.88 TStringHelper

76.88.1 Description

`TStringHelper` adds various helper routines to the string type. These are mostly conversion routines, and some formatting routines.

For similarity to C-like languages, all the indexes in these helper routines are zero based.

See also: `TGUIDHelper` ([1656](#))

76.88.2 Method overview

Page	Method	Description
1694	Compare	Compare 2 strings
1695	CompareOrdinal	Compare 2 strings byte for byte
1695	CompareText	Compare 2 strings case insensitively.
1701	CompareTo	Compare string to another
1701	Contains	Check if the string contains another
1695	Copy	Return a unique copy of a string
1701	CopyTo	Copy part of the string to an array of characters
1701	CountChar	Count the occurrences of a character
1696	Create	Create a new string
1702	DeQuotedString	Return a dequoted version of the string
1696	EndsText	Check if one string is the ending of another.
1702	EndsWith	Check if the string is ended by another.
1696	Equals	Check if 2 strings are equal
1697	Format	Format a string using provided arguments.
1702	GetHashCode	Get a hash code for the string
1702	IndexOf	Find the position (index) of a string or character
1703	IndexOfAny	Find the position (index) of any string or character in a list.
1704	IndexOfAnyUnquoted	Find the position (index) of any string or character in a list.
1703	IndexOfUnQuoted	Index of string, skipping quoted parts.
1704	Insert	Insert a string at a given position
1705	IsDelimiter	Check whether a character at a given position is a delimiter
1705	IsEmpty	Check whether the string is empty.
1697	IsNullOrEmpty	Check if a string is empty
1697	IsNullOrEmptySpace	Check if a string is empty or contains only whitespace characters.
1697	Join	Join a series of strings, separated using a given separator
1705	LastDelimiter	Return the last position of one of a series of delimiters
1705	LastIndexOf	Find the last position (index) of a string or character
1706	LastIndexOfAny	Find the last position (index) of any string or character in a list.
1698	LowerCase	Return the lowercase version of a string.
1706	PadLeft	Pad the string on the left with an indicated character
1707	PadRight	Pad the string on the right with an indicated character
1698	Parse	Return a string representation of the argument
1707	QuotedString	Return a quoted version of the string
1707	Remove	Remove a number of characters from the string
1708	Replace	Replace occurrences of one string with another.
1708	Split	Split a string in a number of parts
1709	StartsWith	Check if one string starts with another
1709	Substring	Return a part of the string
1698	ToBoolean	Convert string to boolean
1710	ToCharArray	Return the string as an array of characters.
1699	ToDouble	Convert string to double-sized floating point value
1699	ToExtended	Convert string to extended-sized floating point value
1699	ToInt64	Convert string to 64-bit signed integer
1700	ToInteger	Convert string to 32-bit signed integer
1710	ToLower	Convert to lowercase
1710	ToLowerInvariant	Convert to lowercase
1700	ToSingle	Convert string to single-sized floating point value
1710	ToUpper	Convert to uppercase.
1711	ToUpperInvariant	Convert to uppercase
1711	Trim	Strips a set of trim characters from the beginning and end of the string.
1712	TrimEnd	Alias for TrimRight
1711	TrimLeft	Strips a set of trim characters from the beginning of the string.
1711	TrimRight	Strips a set of trim characters from the end of the string.
1712	TrimStart	Alias for TrimLeft
1700	UpperCase	Return uppercase version of a string

76.88.3 Property overview

Page	Properties	Access	Description
1712	Chars	r	Zero-based Indexed access to the characters in the string.
1712	Length	r	Return the length of the string

76.88.4 TStringHelper.Compare

Synopsis: Compare 2 strings

Declaration: `class function Compare(const A: string; const B: string) : Integer; Overload; Static`
`class function Compare(const A: string; const B: string; IgnoreCase: Boolean) : Integer; Overload; Static`
`class function Compare(const A: string; const B: string; Options: TCompareOptions) : Integer; Overload; Static`
`class function Compare(const A: string; IndexA: Integer; const B: string; IndexB: Integer; ALen: Integer) : Integer; Overload; Static`
`class function Compare(const A: string; IndexA: Integer; const B: string; IndexB: Integer; ALen: Integer; IgnoreCase: Boolean) : Integer; Overload; Static`
`class function Compare(const A: string; IndexA: Integer; const B: string; IndexB: Integer; ALen: Integer; Options: TCompareOptions) : Integer; Overload; Static`

Visibility: public

Description: Compare compares strings A and B. It returns the following result:

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

The comparison can be influenced by using the appropriate overloaded version of the function.

- If the `IndexA` and `IndexB` parameters are present, the comparison starts at character index `IndexA` and `IndexB`. The indexes are zero-based.
- If the `ALen` parameters is present, then only the first `ALen` characters are compared. If not enough characters are present in either A or B, the comparison will include only as much characters as are present.
- If `IgnoreCase` is present and used, it determines whether the comparison is done case-sensitively. This form is deprecated, it is recommended to use the `AOptions` parameter and to include `coIgnoreCase`.
- The `AOptions` argument can be used to specify additional options. See `TCompareOption` ([1236](#)) for a list of possible values in this set.

Errors: None.

See also: `TStringHelper.CompareOrdinal` ([1695](#)), `TCompareOption` ([1236](#)), `TStringHelper.CompareTo` ([1701](#))

76.88.5 TStringHelper.CompareOrdinal

Synopsis: Compare 2 strings byte for byte

Declaration: `class function CompareOrdinal(const A: string; const B: string) : Integer; Overload; Static`
`class function CompareOrdinal(const A: string; IndexA: Integer; const B: string; IndexB: Integer; ALen: Integer) : Integer; Overload ; Static`

Visibility: public

Description: `CompareOrdinal` compares 2 strings A and B bitwise. It is faster than a regular compare, but offers less options.

- 0 if the strings are equal
- a negative number if $A < B$
- a positive number if $A > B$

Optionally, a zero-based starting index for the compare can be given for each of the strings: `IndexA` and `IndexB`. In this case a maximum amount of characters (`ALen`) to be compared must also be specified.

Errors: None.

See also: `TStringHelper.Compare` ([1694](#)), `TStringHelper.CompareTo` ([1701](#))

76.88.6 TStringHelper.CompareText

Synopsis: Compare 2 strings case insensitively.

Declaration: `class function CompareText(const A: string; const B: string) : Integer ; Static`

Visibility: public

Description: `CompareText` simply calls `SysUtils` ([1495](#)) with the 2 passed arguments.

Errors: None.

See also: `SysUtils` ([1495](#)), `TStringHelper.CompareTo` ([1701](#))

76.88.7 TStringHelper.Copy

Synopsis: Return a unique copy of a string

Declaration: `class function Copy(const Str: string) : string; Static`

Visibility: public

Description: `Copy` will copy the string on which it operates, and makes sure the result has reference count 1.

See also: `UniqueString` ([1442](#))

76.88.8 TStringHelper.Create

Synopsis: Create a new string

```
Declaration: class function Create(AChar: Char; ACount: Integer) : string; Overload
              ; Static
class function Create(const AValue: Array of Char) : string; Overload
              ; Static
class function Create(const AValue: Array of Char; StartIndex: Integer;
              ALen: Integer) : string; Overload; Static
```

Visibility: public

Description: `Create` returns a new string with an initial value based on the passed arguments:

- A character (AChar) and a count (ACount, in which case a string is returned of the specified length, filled with AChar).
- An array of characters AValue. The returned string will have the same length as the array, and the characters will be copied from the elements in the array. Optionally, a starting index StartIndex (zero based) and length ALen can be specified, in which case the string will contain at most ALen characters, which will have been copied starting at index StartIndex.

Errors: None.

See also: [StringOfChar \(1442\)](#)

76.88.9 TStringHelper.EndsText

Synopsis: Check if one string is the ending of another.

```
Declaration: class function EndsText(const ASubText: string; const AText: string)
              : Boolean; Static
```

Visibility: public

Description: `EndsText` returns `True` if `AText` ends on `SubText`, i.e. whether the last characters in `AText` are the ones found in `SubText`. The comparison is done case insensitively.

See also: [CompareText \(1495\)](#), [TStringHelper.EndsWith \(1702\)](#)

76.88.10 TStringHelper.Equals

Synopsis: Check if 2 strings are equal

```
Declaration: class function Equals(const a: string; const b: string) : Boolean
                ; Overload; Static
                function Equals(const AValue: string) : Boolean; Overload
```

Visibility: public

Description: Equals returns True if A=B, false otherwise.

See also: [CompareText \(1495\)](#), [TStringHelper.Compare \(1694\)](#)

76.88.11 TStringHelper.Format

Synopsis: Format a string using provided arguments.

Declaration: `class function Format(const AFormat: string; const args: Array of const) : string; Overload; Static`
`function Format(const args: Array of const) : string; Overload`

Visibility: public

Description: `Format` just calls `Sysutils.Format` ([1537](#)), passing on `AFormat` and `Args`. If `AFormat` is omitted, the string itself is used as the formatting string.

See also: `Sysutils.Format` ([1537](#))

76.88.12 TStringHelper.IsNullOrEmpty

Synopsis: Check if a string is empty

Declaration: `class function IsNullOrEmpty(const AValue: string) : Boolean; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0.

See also: `System.Length` ([1442](#)), `TStringHelper.IsNullOrEmptyWhiteSpace` ([1697](#))

76.88.13 TStringHelper.IsNullOrEmptyWhiteSpace

Synopsis: Check if a string is empty or contains only whitespace characters.

Declaration: `class function IsNullOrEmptyWhiteSpace(const AValue: string) : Boolean`
`; Static`

Visibility: public

Description: `IsNullOrEmpty` returns `True` if string `A` has length 0 or contains only whitespace characters (characters with ASCII code 32 or less).

See also: `TStringHelper.IsNullOrEmpty` ([1697](#)), `Trim` ([1599](#))

76.88.14 TStringHelper.Join

Synopsis: Join a series of strings, separated using a given separator

Declaration: `class function Join(const Separator: string;`
`const Values: Array of const) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string) : string; Overload`
`; Static`
`class function Join(const Separator: string;`
`const Values: Array of string; StartIndex: Integer;`
`ACount: Integer) : string; Overload; Static`

Visibility: public

Description: `ToBoolean` returns the contents of the string `S` as a boolean (if possible). It uses `StrToBool` (1585) to convert the value to a boolean.

Errors: If the string contains a value that cannot be translated to a boolean, an `EConvertError` (1616) exception may be raised.

See also: `StrToBool` (1585), `EConvertError` (1616), `TStringHelper.ToDouble` (1699), `TStringHelper.ToExtended` (1699), `TStringHelper.ToInt64` (1699), `TStringHelper.ToInteger` (1700), `TStringHelper.ToSingle` (1700)

76.88.18 TStringHelper.ToDouble

Synopsis: Convert string to double-sized floating point value

Declaration: `class function ToDouble(const S: string) : Double; Overload; Static
function ToDouble : Double; Overload`

Visibility: public

Description: `ToDouble` returns the contents of the string `S` as a Double-sized floating point value (if possible). It uses `StrToFloat` (1589) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1616) exception may be raised.

See also: `StrToFloat` (1589), `EConvertError` (1616), `TStringHelper.ToBoolean` (1698), `TStringHelper.ToExtended` (1699), `TStringHelper.ToInt64` (1699), `TStringHelper.ToInteger` (1700), `TStringHelper.ToSingle` (1700)

76.88.19 TStringHelper.ToExtended

Synopsis: Convert string to extended-sized floating point value

Declaration: `class function ToExtended(const S: string) : Extended; Overload
; Static
function ToExtended : Extended; Overload`

Visibility: public

Description: `ToExtended` returns the contents of the string `S` as a Extended-sized floating point value (if possible). It uses `StrToFloat` (1589) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1616) exception may be raised.

See also: `StrToFloat` (1589), `EConvertError` (1616), `TStringHelper.ToBoolean` (1698), `TStringHelper.ToDouble` (1699), `TStringHelper.ToInt64` (1699), `TStringHelper.ToInteger` (1700), `TStringHelper.ToSingle` (1700)

76.88.20 TStringHelper.ToInt64

Synopsis: Convert string to 64-bit signed integer

Declaration: `class function ToInt64(const S: string) : Int64; Overload; Static
function ToInt64 : Int64; Overload`

Visibility: public

Description: `ToInt64` returns the contents of the string `S` as a 64-bit signed integer value (if possible). It uses `StrToInt64` (1591) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1616) exception may be raised.

See also: `StrToInt64` (1591), `EConvertError` (1616), `TStringHelper.ToBoolean` (1698), `TStringHelper.ToDouble` (1699), `TStringHelper.ToExtended` (1699), `TStringHelper.ToInteger` (1700), `TStringHelper.ToSingle` (1700)

76.88.21 `TStringHelper.ToInteger`

Synopsis: Convert string to 32-bit signed integer

Declaration: `class function ToInteger(const S: string) : Integer; Overload; Static
function ToInteger : Integer; Overload`

Visibility: public

Description: `ToInteger` returns the contents of the string `S` as a 32-bit signed integer value (if possible). It uses `StrToInt64` (1591) to convert the value to an 64-bit sized integer value.

Errors: If the string contains a value that cannot be translated to an integer value, an `EConvertError` (1616) exception may be raised.

See also: `StrToInt64` (1591), `EConvertError` (1616), `TStringHelper.ToBoolean` (1698), `TStringHelper.ToDouble` (1699), `TStringHelper.ToExtended` (1699), `TStringHelper.ToInt64` (1699), `TStringHelper.ToSingle` (1700)

76.88.22 `TStringHelper.ToSingle`

Synopsis: Convert string to single-sized floating point value

Declaration: `class function ToSingle(const S: string) : Single; Overload; Static
function ToSingle : Single; Overload`

Visibility: public

Description: `ToSingle` returns the contents of the string `S` as a single-sized floating point value (if possible). It uses `StrToFloat` (1589) to convert the value to a floating point value.

Errors: If the string contains a value that cannot be translated to a floating point value, an `EConvertError` (1616) exception may be raised.

See also: `StrToFloat` (1589), `EConvertError` (1616), `TStringHelper.ToBoolean` (1698), `TStringHelper.ToDouble` (1699), `TStringHelper.ToInt64` (1699), `TStringHelper.ToInteger` (1700), `TStringHelper.ToExtended` (1699)

76.88.23 `TStringHelper.UpperCase`

Synopsis: Return uppercase version of a string

Declaration: `class function UpperCase(const S: string) : string; Overload; Static`

Visibility: public

Description: `UpperCase` returns an uppercase version of the string `S`.

See also: `#rtl.sysutils.UpperCase` (1609)

76.88.24 TStringHelper.CompareTo

Synopsis: Compare string to another

Declaration: `function CompareTo(const B: string) : Integer`

Visibility: public

Description: `CompareTo` will compare the string value to the string B. It returns the following result:

- 0 if the strings are equal
- a negative number if `Self < B`
- a positive number if `Self > B`

The `StrComp` ([1572](#)) function is used for this.

See also: `TStringHelper.Compare` ([1694](#)), `TStringHelper.CompareOrdinal` ([1695](#)), `StrComp` ([1572](#))

76.88.25 TStringHelper.Contains

Synopsis: Check is the string contains another

Declaration: `function Contains(const AValue: string) : Boolean`

Visibility: public

Description: `Contains` returns `True` if the string value contains `AValue`, i.e. it returns `Pos(Self, AValue) > 0`.

See also: `Pos` ([1365](#))

76.88.26 TStringHelper.CopyTo

Synopsis: Copy part of the string to an array of characters

Declaration: `procedure CopyTo(SourceIndex: Integer; var destination: Array of Char;
DestinationIndex: Integer; ACount: Integer)`

Visibility: public

Description: `CopyTo` copies at most `ACount` characters from the source string (`Self`) to the array `Destination`, starting at (zero based) index `SourceIndex`. The characters are copied to the array starting at position `DestinationIndex` (zero based).

See also: `Copy` ([1194](#))

76.88.27 TStringHelper.CountChar

Synopsis: Count the occurrences of a character

Declaration: `function CountChar(const C: Char) : Integer`

Visibility: public

Description: `CountChar` returns the number of occurrences of `C` in the string (`Self`).

See also: `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.IndexOfAny` ([1703](#))

76.88.28 TStringHelper.DeQuotedString

Synopsis: Return a dequoted version of the string

Declaration: `function DeQuotedString : string; Overload`
`function DeQuotedString(const AQuoteChar: Char) : string; Overload`

Visibility: public

Description: `DeQuotedString` will return a dequoted version of the string (`Self`), where the quote character is `AQuoteChar` (default: a single quote `'`). The string must start and end with the quote character, or it is returned as-is. Any double occurrences of the quote character `AQuoteChar` will be returned as a single quote.

See also: `AnsiQuotedString` ([1442](#)), `AnsiExtractQuotedString` ([1442](#))

76.88.29 TStringHelper.EndsWith

Synopsis: Check if the string is ended by another.

Declaration: `function EndsWith(const AValue: string) : Boolean; Overload`
`function EndsWith(const AValue: string; IgnoreCase: Boolean) : Boolean`
`; Overload`

Visibility: public

Description: `EndsWith` returns `True` if the string (`Self`) ends on `AValue`, i.e. whether the last characters in `Self` are the ones found in `AValue`. The comparison is done case insensitively depending on the `IgnoreCase` argument (which is false by default).

See also: `CompareText` ([1495](#)), `TStringHelper.EndsWithText` ([1696](#))

76.88.30 TStringHelper.GetHashCode

Synopsis: Get a hash code for the string

Declaration: `function GetHashCode : Integer`

Visibility: public

Description: `GetHashCode` returns a hash value for the string (`Self`).

76.88.31 TStringHelper.IndexOf

Synopsis: Find the position (index) of a string or character

Declaration: `function IndexOf(AValue: Char) : Integer; Overload`
`function IndexOf(const AValue: string) : Integer; Overload`
`function IndexOf(AValue: Char; StartIndex: Integer) : Integer; Overload`
`function IndexOf(const AValue: string; StartIndex: Integer) : Integer`
`; Overload`
`function IndexOf(AValue: Char; StartIndex: Integer; ACount: Integer)`
`: Integer; Overload`
`function IndexOf(const AValue: string; StartIndex: Integer;`
`ACount: Integer) : Integer; Overload`

Visibility: public

Description: `IndexOf` returns the zero-based index of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOfUnQuoted` ([1703](#)), `TStringHelper.IndexOfAny` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#)), `TStringHelper.LastIndexOf` ([1705](#)), `TStringHelper.LastIndexOfAny` ([1706](#))

76.88.32 TStringHelper.IndexOfUnQuoted

Synopsis: Index of string, skipping quoted parts.

Declaration:

```
function IndexOfUnQuoted(const AValue: string; StartQuote: Char;
                        EndQuote: Char; StartIndex: Integer) : Integer
; Overload
```

Visibility: public

Description: `IndexOfUnQuoted` will return the zero-based index of `AValue` in the string (`Self`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`. The search starts at (zero-based) position `StartIndex`, which is by default 0.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.IndexOfAny` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#)), `TStringHelper.LastIndexOf` ([1705](#)), `TStringHelper.LastIndexOfAny` ([1706](#))

76.88.33 TStringHelper.IndexOfAny

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAny(const AnyOf: Array of Char) : Integer; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: Integer)
: Integer; Overload
function IndexOfAny(const AnyOf: Array of Char; StartIndex: Integer;
                    ACount: Integer) : Integer; Overload
function IndexOfAny(const AnyOf: Array of string) : Integer; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: Integer)
: Integer; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: Integer;
                    ACount: Integer) : Integer; Overload
function IndexOfAny(const AnyOf: Array of string; StartIndex: Integer;
                    ACount: Integer; out AMatch: Integer) : Integer
; Overload
```

Visibility: public

Description: `IndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on succesful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.IndexOfUnquoted` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#)), `TStringHelper.LastIndexOf` ([1705](#)), `TStringHelper.LastIndexOfAny` ([1706](#))

76.88.34 TStringHelper.IndexOfAnyUnquoted

Synopsis: Find the position (index) of any string or character in a list.

Declaration:

```
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char) : Integer
    ; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: Integer) : Integer; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of Char;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: Integer; ACount: Integer)
    : Integer; Overload
function IndexOfAnyUnquoted(const AnyOf: Array of string;
                           StartQuote: Char; EndQuote: Char;
                           StartIndex: Integer; out Matched: Integer)
    : Integer; Overload
```

Visibility: public

Description: `IndexOfAnyUnquoted` returns the zero-based index of the first matching element in an array of charaters or strings (`AnyOf`), but disregards any quoted parts in the string. A quoted part is determined by a starting `StartQuote` and end-quote character `EndQuote`.

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character. Not specifying this option is equivalent to specifying zero.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying the amount of remaining characters.

If `AMatch` is specified, on succesful return it will contain the index of the element in the array that contains the found match.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.IndexOfUnquoted` ([1703](#)), `TStringHelper.IndexOfAny` ([1703](#)), `TStringHelper.LastIndexOf` ([1705](#)), `TStringHelper.LastIndexOfAny` ([1706](#))

76.88.35 TStringHelper.Insert

Synopsis: Insert a string at a given position

Declaration:

```
function Insert(StartIndex: Integer; const AValue: string) : string
```

Visibility: public

Description: Insert inserts the string AValue in a string (Self) at the (zero-based) position StartIndex. It returns the resulting string (Self). If StartIndex is less than zero, it is set to zero. If StartIndex is higher than the length, AValue is appended to the string.

See also: Insert ([1345](#))

76.88.36 TStringHelper.IsDelimiter

Synopsis: Check whether a character at a given position is a delimiter

Declaration: `function IsDelimiter(const Delimiters: string; Index: Integer) : Boolean`

Visibility: public

Description: IsDelimiter returns True if the character at (zero-based) position Index is one of the delimiter characters in Delimiters. If Index is out of range, False is returned.

See also: IsDelimiter ([1559](#))

76.88.37 TStringHelper.IsEmpty

Synopsis: Check whether the string is empty.

Declaration: `function IsEmpty : Boolean`

Visibility: public

Description: IsEmpty returns True if the string has length zero.

See also: TStringHelper.IsNullOrEmpty ([1697](#)), TStringHelper.Length ([1712](#)), Length ([1194](#))

76.88.38 TStringHelper.LastDelimiter

Synopsis: Return the last position of one of a series of delimiters

Declaration: `function LastDelimiter(const Delims: string) : Integer`

Visibility: public

Description: LastDelimiter searches the string backwards for an occurrence of one of the characters in Delims, and returns the corresponding (zero-based) index in the string. If no occurrence is found, -1 is returned.

See also: TStringHelper.isDelimiter ([1705](#)), TStringHelper.IndexOf ([1702](#)), TStringHelper.IndexOfAny ([1703](#)), TStringHelper.LastIndexOf ([1705](#)), TStringHelper.LastIndexOfAny ([1706](#))

76.88.39 TStringHelper.LastIndexOf

Synopsis: Find the last position (index) of a string or character

Declaration: `function LastIndexOf(AValue: Char) : Integer; Overload
function LastIndexOf(const AValue: string) : Integer; Overload
function LastIndexOf(AValue: Char; AStartIndex: Integer) : Integer
; Overload
function LastIndexOf(const AValue: string; AStartIndex: Integer)`

```

        : Integer; Overload
function LastIndexOf(AValue: Char; AStartIndex: Integer;
        ACount: Integer) : Integer; Overload
function LastIndexOf(const AValue: string; AStartIndex: Integer;
        ACount: Integer) : Integer; Overload

```

Visibility: public

Description: `LastIndexOf` returns the zero-based index of the last occurrence of `AValue` in the string (`Self`). The value to search for can be a character or string (`AValue`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero based) index `StartIndex`. When specified, the search will start at the given character and proceeds towards the beginning of the string. Not specifying this option is equivalent to specifying `length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOfUnquoted` ([1703](#)), `TStringHelper.IndexOfAny` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#)), `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.LastIndexOfAny` ([1706](#))

76.88.40 TStringHelper.LastIndexOfAny

Synopsis: Find the last position (index) of any string or character in a list.

```

Declaration: function LastIndexOfAny(const AnyOf: Array of Char) : Integer; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: Integer) : Integer; Overload
function LastIndexOfAny(const AnyOf: Array of Char;
        AStartIndex: Integer; ACount: Integer) : Integer
; Overload

```

Visibility: public

Description: `LastIndexOfAny` returns the zero-based index of the first matching element in an array of characters or strings (`AnyOf`).

if no match is found, -1 is returned.

The search can be refined by specifying a (zero-based) index `StartIndex`. When specified, the search will start at the given character and proceeds to the start of the string. Not specifying this option is equivalent to specifying `Length-1`.

If `ACount` is given, at most `ACount` characters in the source string will be considered for the search. This count includes the starting character. Not specifying this argument is equivalent to specifying `StartIndex+1`.

See also: `Pos` ([1365](#)), `TStringHelper.IndexOf` ([1702](#)), `TStringHelper.IndexOfUnquoted` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#)), `TStringHelper.LastIndexOf` ([1705](#)), `TStringHelper.IndexOfAny` ([1703](#))

76.88.41 TStringHelper.PadLeft

Synopsis: Pad the string on the left with an indicated character

```

Declaration: function PadLeft(ATotalWidth: Integer) : string; Overload
function PadLeft(ATotalWidth: Integer; PaddingChar: Char) : string
; Overload

```

Visibility: public

Description: `PadLeft` pads the string (`Self`) on the left (i.e. at the beginning) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadRight` ([1707](#))

76.88.42 `TStringHelper.PadRight`

Synopsis: Pad the string on the right with an indicated character

Declaration: `function PadRight(ATotalWidth: Integer) : string; Overload`
`function PadRight(ATotalWidth: Integer; PaddingChar: Char) : string`
`; Overload`

Visibility: public

Description: `PadLeft` pads the string (`Self`) on the right (i.e. at the end) till it reaches length `ATotalWidth` with character `PaddingChar`. If `PaddingChar` is omitted, a space is used.

See also: `TStringHelper.PadLeft` ([1706](#))

76.88.43 `TStringHelper.QuotedString`

Synopsis: Return a quoted version of the string

Declaration: `function QuotedString : string; Overload`
`function QuotedString(const AQuoteChar: Char) : string; Overload`

Visibility: public

Description: `QuotedString` returns a quoted version of the string (`Self`). The quote character is specified in `AQuoteChar`, which by default is the double quote (`"`). Any existing quote characters occurrences will be doubled.

See also: `QuotedStr` ([1564](#)), `AnsiQuotedStr` ([1480](#))

76.88.44 `TStringHelper.Remove`

Synopsis: Remove a number of characters from the string

Declaration: `function Remove(StartIndex: Integer) : string; Overload`
`function Remove(StartIndex: Integer; ACount: Integer) : string`
`; Overload`

Visibility: public

Description: `Remove` removes `ACount` characters from the string, starting at (zero-based) index `StartIndex`. If `ACount` is omitted, all remaining characters are removed.

See also: `Delete` ([1308](#)), `TStringHelper.Replace` ([1708](#)), `TStringHelper.Insert` ([1704](#))

76.88.45 TStringHelper.Replace

Synopsis: Replace occurrences of one string with another.

Declaration: function Replace(OldChar: Char; NewChar: Char) : string; Overload
 function Replace(OldChar: Char; NewChar: Char;
 ReplaceFlags: TReplaceFlags) : string; Overload
 function Replace(const OldValue: string; const NewValue: string)
 : string; Overload
 function Replace(const OldValue: string; const NewValue: string;
 ReplaceFlags: TReplaceFlags) : string; Overload

Visibility: public

Description: Replace will replace occurrences of OldChar with NewChar or OldValue with NewValue.

If rfReplaceAll is in the ReplaceFlags, then all occurrences will be replaced, otherwise only the first occurrence is replaced.

If rfCaseInsensitive is in the ReplaceFlags, then the search for OldChar or OldValue is performed ignoring case.

See also: StringReplace ([1576](#)), TReplaceFlags ([1465](#))

76.88.46 TStringHelper.Split

Synopsis: Split a string in a number of parts

Declaration: function Split(const Separators: Array of Char) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; ACount: Integer)
 : TStringArray; Overload
 function Split(const Separators: Array of Char;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; ACount: Integer;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string) : TStringArray
 ; Overload
 function Split(const Separators: Array of string; ACount: Integer)
 : TStringArray; Overload
 function Split(const Separators: Array of string;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of string; ACount: Integer;
 Options: TStringSplitOptions) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuote: Char)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char) : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; Options: TStringSplitOptions)
 : TStringArray; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: Integer) : TStringArray
 ; Overload
 function Split(const Separators: Array of Char; AQuoteStart: Char;
 AQuoteEnd: Char; ACount: Integer;
 Options: TStringSplitOptions) : TStringArray; Overload

```

function Split(const Separators: Array of string; AQuote: Char)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char) : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; Options: TStringSplitOptions)
    : TStringArray; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: Integer) : TStringArray
    ; Overload
function Split(const Separators: Array of string; AQuoteStart: Char;
    AQuoteEnd: Char; ACount: Integer;
    Options: TStringSplitOptions) : TStringArray; Overload

```

Visibility: public

Description: `Split` will split the string (`Self`) using `Separators` as separator characters.

If `ACount` is supplied, then at most `ACount` strings will be included in the result. The default behaviour is to supply all strings.

if `Options` contains `ExcludeEmpty` then no empty strings will be included in the result. Empty strings may be included if multiple successive separator characters are found in the source string.

If `AQuoteStart` and `AQuoteEnd` are supplied, then no splitting will be performed between `AQuoteStart` and `AQuoteEnd` characters.

See also: `TStringHelper.Join` ([1697](#)), `TStringHelper.IndexOfAny` ([1703](#)), `TStringHelper.IndexOfAnyUnquoted` ([1704](#))

76.88.47 TStringHelper.StartsWith

Synopsis: Check if one string starts with another

```

Declaration: function StartsWith(const AValue: string) : Boolean; Overload
function StartsWith(const AValue: string; IgnoreCase: Boolean) : Boolean
    ; Overload

```

Visibility: public

Description: `StartsWith` will return `True` if the first characters of the string (`Self`) equal the string `AValue`.

If `IgnoreCase` is `True`, then the comparison is done case insensitive. The default is to compare strings case sensitively.

See also: `TStringHelper.EndsWith` ([1702](#))

76.88.48 TStringHelper.Substring

Synopsis: Return a part of the string

```

Declaration: function Substring(AStartIndex: Integer) : string; Overload
function Substring(AStartIndex: Integer; ALen: Integer) : string
    ; Overload

```

Visibility: public

Description: `SubString` returns the portion of the string starting at (zero-based) index `AStartIndex` with length `ALen`. If `ALen` is omitted, then all remaining characters are returned.

See also: `TStringHelper.Insert` ([1704](#)), `Copy` ([1194](#)), `TStringHelper.ToCharArray` ([1710](#))

76.88.49 TStringHelper.ToCharArray

Synopsis: Return the string as an array of characters.

Declaration: `function ToCharArray : TCharArray; Overload`
`function ToCharArray(AStartIndex: Integer; ALen: Integer) : TCharArray`
`; Overload`

Visibility: public

Description: `ToCharArray` returns part of the string (`Self`) as an array of characters. The characters are copied starting at (zero-based) index `AStartIndex` and at most `ALen` characters are copied. If `AStartIndex` and `ALen` are omitted, all the characters are returned.

Errors: If `AStartIndex` is less than zero, an `EAccessViolation` (1615) exception may be raised.

See also: `TStringHelper.Substring` (1709), `TStringHelper.Insert` (1704), `Copy` (1194)

76.88.50 TStringHelper.ToLower

Synopsis: Convert to lowercase

Declaration: `function ToLower : string; Overload`

Visibility: public

Description: `ToLower` returns a lowercase version of the string.

See also: `TStringHelper.LowerCase` (1698), `TStringHelper.ToUpper` (1710), `TStringHelper.ToUpperInvariant` (1711)

76.88.51 TStringHelper.ToLowerInvariant

Synopsis: Convert to lowercase

Declaration: `function ToLowerInvariant : string`

Visibility: public

Description: `ToLowerInvariant` is equal to `TStringHelper.ToLower` (1710)

See also: `TStringHelper.ToLower` (1710), `TStringHelper.ToUpper` (1710), `TStringHelper.ToUpperInvariant` (1711)

76.88.52 TStringHelper.ToUpper

Synopsis: Convert to uppercase.

Declaration: `function ToUpper : string; Overload`

Visibility: public

Description: `>ToUpper` returns an uppercase version of the string.

See also: `TStringHelper.ToLower` (1710), `TStringHelper.ToLowerInvariant` (1710), `TStringHelper.ToUpperInvariant` (1711)

76.88.53 TStringHelper.ToUpperInvariant

Synopsis: Convert to uppercase

Declaration: `function ToUpperInvariant : string`

Visibility: public

Description: `ToUpperInvariant` is equal to `TStringHelper.ToUpper` (1710)

See also: `TStringHelper.ToLower` (1710), `TStringHelper.ToLowerInvariant` (1710), `TStringHelper.ToUpper` (1710)

76.88.54 TStringHelper.Trim

Synopsis: Strips a set of trim characters from the beginning and end of the string.

Declaration: `function Trim : string; Overload`
`function Trim(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start and end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1599), `TStringHelper.TrimLeft` (1711), `TStringHelper.TrimRight` (1711)

76.88.55 TStringHelper.TrimLeft

Synopsis: Strips a set of trim characters from the beginning of the string.

Declaration: `function TrimLeft : string; Overload`
`function TrimLeft(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the start of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `TrimLeft` (1599), `TStringHelper.Trim` (1711), `TStringHelper.TrimRight` (1711)

76.88.56 TStringHelper.TrimRight

Synopsis: Strips a set of trim characters from the end of the string.

Declaration: `function TrimRight : string; Overload`
`function TrimRight(const ATrimChars: Array of Char) : string; Overload`

Visibility: public

Description: `Trim` returns the string (`Self`), removing all characters occurring in `ATrimChars` from the end of the string. If `ATrimChars` is not specified, all characters with ASCII code 32 or lower are assumed.

See also: `Trim` (1599), `TStringHelper.Trim` (1711), `TStringHelper.TrimLeft` (1711)

76.88.57 TStringHelper.TrimEnd

Synopsis: Alias for TrimRight

Declaration: `function TrimEnd(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimEnd is an alias for TStringHelper.TrimRight ([1711](#))

See also: TStringHelper.TrimRight ([1711](#)), TStringHelper.TrimStart ([1712](#))

76.88.58 TStringHelper.TrimStart

Synopsis: Alias for TrimLeft

Declaration: `function TrimStart(const ATrimChars: Array of Char) : string`

Visibility: public

Description: TrimStart is an alias for TStringHelper.TrimLeft ([1711](#))

See also: TStringHelper.TrimEnd ([1712](#)), TStringHelper.TrimLeft ([1711](#))

76.88.59 TStringHelper.Chars

Synopsis: Zero-based Indexed access to the characters in the string.

Declaration: `Property Chars[AIndex: Integer]: Char`

Visibility: public

Access: Read

Description: Chars provides zero-based indexed access to the characters in the string. The first character is at index 0, the last at Length-1.

See also: TStringHelper.Length ([1712](#))

76.88.60 TStringHelper.Length

Synopsis: Return the length of the string

Declaration: `Property Length : Integer`

Visibility: public

Access: Read

Description: Length returns the length (in bytes for single-byte strings) of the string.

See also: Length ([1194](#))

76.89 TUnicodeEncoding

76.89.1 Description

TUnicodeEncoding is the encoding class used to represent the UTF-16 encoding.

See also: TUnicodeEncoding ([1712](#)), TUTF7Encoding ([1714](#)), TMBCSEncoding ([1665](#)), TBigendianUnicodeEncoding ([1628](#))

76.89.2 Method overview

Page	Method	Description
1713	Clone	Clone a TUnicodeEncoding instance
1713	Create	Create a new instance of the TUnicodeEncoding class
1713	GetMaxByteCount	Return max number of bytes needed to represent a string
1713	GetMaxCharCount	Return max number of characters that can be represented by an array of bytes
1714	GetPreamble	Return BOM marker bytes

76.89.3 TUnicodeEncoding.Create

Synopsis: Create a new instance of the TUnicodeEncoding class

Declaration: constructor Create; Virtual

Visibility: public

Description: Create creates a new instance of the TUnicodeEncoding class and sets the codepage to CP_UTF16.

See also: TEncoding.CodePage ([1647](#)), TEncoding ([1644](#))

76.89.4 TUnicodeEncoding.Clone

Synopsis: Clone a TUnicodeEncoding instance

Declaration: function Clone : TEncoding; Override

Visibility: public

Description: Clone overrides TEncoding.Clone ([1645](#)) to provide a clone of the TUnicodeEncoding instance.

See also: TEncoding.Clone ([1645](#))

76.89.5 TUnicodeEncoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: function GetMaxByteCount(CharCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxByteCount overrides TEncoding.GetMaxByteCount ([1646](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxByteCount ([1646](#))

76.89.6 TUnicodeEncoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: function GetMaxCharCount(ByteCount: Integer) : Integer; Override

Visibility: public

Description: GetMaxCharCount overrides TEncoding.GetMaxCharCount ([1647](#)) to return the maximum number of bytes needed to represent a string.

See also: TEncoding.GetMaxCharCount ([1647](#))

76.89.7 TUnicodeEncoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: `public`

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1647) to return the 2 UTF-16 BOM Marker bytes (\$FF,\$FE).

See also: `TEncoding.GetPreamble` (1647)

76.90 TUTF7Encoding

76.90.1 Description

`TUTF7Encoding` is the encoding class used to represent the UTF7 encoding. This encoding is not so often used, and the class is provided mostly for completeness.

See also: `TUnicodeEncoding` (1712), `TUTF8Encoding` (1715), `TMBCSEncoding` (1665), `TBigendianUnicodeEncoding` (1628)

76.90.2 Method overview

Page	Method	Description
1714	<code>Clone</code>	Clone a <code>TUTF7Encoding</code> instance
1714	<code>Create</code>	Create a new instance of the <code>TUTF7Encoding</code> class
1715	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1715	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes

76.90.3 TUTF7Encoding.Create

Synopsis: Create a new instance of the `TUTF7Encoding` class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TUTF7Encoding` class and sets the codepage to `CP_UTF7`.

See also: `TEncoding.CodePage` (1647), `TEncoding` (1644)

76.90.4 TUTF7Encoding.Clone

Synopsis: Clone a `TUTF7Encoding` instance

Declaration: `function Clone : TEncoding; Override`

Visibility: `public`

Description: `Clone` overrides `TEncoding.Clone` (1645) to provide a clone of the `TUTF7Encoding` instance.

See also: `TEncoding.Clone` (1645)

76.90.5 TUTF7Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount (CharCount: Integer) : Integer; Override`

Visibility: `public`

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1646) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1646)

76.90.6 TUTF7Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount (ByteCount: Integer) : Integer; Override`

Visibility: `public`

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1647) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1647)

76.91 TUTF8Encoding

76.91.1 Description

`TUTF8Encoding` is the encoding class used to represent the UTF-8 encoding.

See also: `TUnicodeEncoding` (1712), `TUTF7Encoding` (1714), `TMBCSEncoding` (1665), `TBigendianUnicodeEncoding` (1628)

76.91.2 Method overview

Page	Method	Description
1716	<code>Clone</code>	Clone a <code>TUTF8Encoding</code> instance
1715	<code>Create</code>	Create a new instance of the <code>TUTF8Encoding</code> class
1716	<code>GetMaxByteCount</code>	Return max number of bytes needed to represent a string
1716	<code>GetMaxCharCount</code>	Return max number of characters that can be represented by an array of bytes
1716	<code>GetPreamble</code>	Return BOM marker bytes

76.91.3 TUTF8Encoding.Create

Synopsis: Create a new instance of the `TUTF8Encoding` class

Declaration: `constructor Create; Override`

Visibility: `public`

Description: `Create` creates a new instance of the `TUTF8Encoding` class and sets the codepage to `CP_UTF8`.

See also: `TEncoding.CodePage` (1647), `TEncoding` (1644)

76.91.4 TUTF8Encoding.Clone

Synopsis: Clone a TUTF8Encoding instance

Declaration: `function Clone : TEncoding; Override`

Visibility: public

Description: `Clone` overrides `TEncoding.Clone` (1645) to provide a clone of the `TUTF8Encoding` instance.

See also: `TEncoding.Clone` (1645)

76.91.5 TUTF8Encoding.GetMaxByteCount

Synopsis: Return max number of bytes needed to represent a string

Declaration: `function GetMaxByteCount(CharCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxByteCount` overrides `TEncoding.GetMaxByteCount` (1646) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxByteCount` (1646)

76.91.6 TUTF8Encoding.GetMaxCharCount

Synopsis: Return max number of characters that can be represented by an array of bytes

Declaration: `function GetMaxCharCount(ByteCount: Integer) : Integer; Override`

Visibility: public

Description: `GetMaxCharCount` overrides `TEncoding.GetMaxCharCount` (1647) to return the maximum number of bytes needed to represent a string.

See also: `TEncoding.GetMaxCharCount` (1647)

76.91.7 TUTF8Encoding.GetPreamble

Synopsis: Return BOM marker bytes

Declaration: `function GetPreamble : TBytes; Override`

Visibility: public

Description: `GetPreamble` overrides `TEncoding.GetPreamble` (1647) to return the 3 UTF8 BOM Marker bytes (\$EF,\$BB,\$BF).

See also: `TEncoding.GetPreamble` (1647)

76.92 TWordBoolHelper

76.92.1 Description

TWordBoolHelper is a helper type for the WordBool type. It contains mostly conversion routines to and from other types.

See also: TStringHelper ([1691](#)), TShortIntHelper ([1677](#)), TSmallIntHelper ([1689](#)), TWordHelper ([1718](#)), TCardinalHelper ([1635](#)), TIntegerHelper ([1660](#)), TInt64Helper ([1658](#)), TQWordHelper ([1674](#)), TNativeIntHelper ([1668](#)), TByteHelper ([1632](#)), TByteBoolHelper ([1630](#)), TWordBoolHelper ([1717](#)), TLongBoolHelper ([1663](#))

76.92.2 Method overview

Page	Method	Description
1717	Parse	Convert string value to WordBool value.
1717	Size	Return the size (in bytes) of the
1718	ToInteger	Convert to an integer value
1717	ToString	Convert a WordBool value to string.
1718	TryToParse	Try to convert a string to a WordBool value

76.92.3 TWordBoolHelper.Parse

Synopsis: Convert string value to WordBool value.

Declaration: `class function Parse(const S: string) : Boolean; Static`

Visibility: public

Description: Parse attempts to convert the string S to a WordBool value. It uses the StrToBool ([1585](#)) function to perform the conversion.

Errors: If S does not contain a valid string representation, then an EConvertError ([1616](#)) exception is raised.

See also: TWordBoolHelper.TryToParse ([1718](#)), TWordBoolHelper.ToString ([1717](#)), TWordBoolHelper.ToInteger ([1718](#))

76.92.4 TWordBoolHelper.Size

Synopsis: Return the size (in bytes) of the

Declaration: `class function Size : Integer; Static`

Visibility: public

Description: Size returns the size (in bytes) of the WordBool value. This is equivalent to `SizeOf(WordBool)`.

See also: SizeOf ([1392](#))

76.92.5 TWordBoolHelper.ToString

Synopsis: Convert a WordBool value to string.

Declaration: `class function ToString(const AValue: Boolean;
 UseBoolStrs: TUseBoolStrs) : string; Overload
 ; Static
function ToString(UseBoolStrs: TUseBoolStrs) : string; Overload`

Visibility: public

Description: `ToString` will, in the class method version, convert the `AValue WordBool` to a string representation. In the function method version the `WordBool` value itself (`Self`) will be converted.

If the `UseBoolStrs` parameter equals `TUseBoolStrs.True`, then the string representation will use the `WordBool` strings `BoolStrs` (1442). The default value for `UseBoolStrs` is `TUseBoolStrs.False`.

The conversion is done using the `BoolToStr` (1490) function.

See also: `BoolStrs` (1442), `BoolToStr` (1490)

76.92.6 TWordBoolHelper.TryToParse

Synopsis: Try to convert a string to a `WordBool` value

Declaration: `class function TryToParse(const S: string; out AValue: Boolean)`
`: Boolean; Static`

Visibility: public

Description: `TryToParse` will attempt to convert the string `S` to a `WordBool` value. If the attempt is successful, `True` is returned, and the actual value is returned in `AValue`. If the attempt failed, `False` is returned.

See also: `TWordBoolHelper.Parse` (1717), `TWordBoolHelper.ToString` (1717)

76.92.7 TWordBoolHelper.ToInteger

Synopsis: Convert to an integer value

Declaration: `function ToInteger : Integer`

Visibility: public

Description: `ToInteger` will return the `WordBool` value, typecasted to `Integer`.

See also: `TWordBoolHelper.ToString` (1717)

76.93 TWordHelper

76.93.1 Description

`TWordHelper` contains some auxiliary routines for a `Word`-typed ordinal value. It consists mainly of conversion routines to and from other types.

See also: `TStringHelper` (1691), `TShortIntHelper` (1677), `TSmallIntHelper` (1689), `TByteHelper` (1632), `TCardinalHelper` (1635), `TIntegerHelper` (1660), `TInt64Helper` (1658), `TQWordHelper` (1674), `TNativeIntHelper` (1668), `TNativeUIntHelper` (1671)

76.93.2 Method overview

Page	Method	Description
1719	<code>Parse</code>	Convert from a string
1719	<code>Size</code>	Size, in bytes, of the <code>Word</code> value
1720	<code>ToBoolean</code>	Convert to a boolean value
1720	<code>ToDouble</code>	Convert to a double-sized floating point value
1720	<code>ToExtended</code>	Convert to an extended-sized floating point value
1721	<code>ToHexString</code>	Convert to a hexadecimal string representation
1721	<code>ToSingle</code>	Convert to a single-sized floating point value
1719	<code>ToString</code>	Convert the value to string
1720	<code>TryParse</code>	Try to convert a string to a <code>Word</code> , report success or failure

76.93.3 TWordHelper.Parse

Synopsis: Convert from a string

Declaration: `class function Parse(const AString: string) : Word; Static`

Visibility: `public`

Description: `Parse` will attempt to convert the string `AString` to a `Word` value. It uses the `StrToInt` ([1590](#)) function to perform the conversion, so no localization is taken into account.

Errors: If the string does not contain a valid `Word` value, an `EConvertError` ([1616](#)) exception is raised.

See also: `TWordHelper.ToString` ([1719](#)), `TWordHelper.TryParse` ([1720](#)), `StrToInt` ([1590](#))

76.93.4 TWordHelper.Size

Synopsis: Size, in bytes, of the `Word` value

Declaration: `class function Size : Integer; Static`

Visibility: `public`

Description: `Size` returns the size (in Words) of the `Word` value. This is equivalent to `SizeOf(Word)`.

Errors: None.

See also: `SizeOf` ([1392](#))

76.93.5 TWordHelper.ToString

Synopsis: Convert the value to string

Declaration: `class function ToString(const AValue: Word) : string; Overload; Static`
`function ToString : string; Overload`

Visibility: `public`

Description: `ToString` will, in the class function variant of this method, convert `AValue` to a string representation. In the regular method overloaded version of `ToString`, the `Word` value itself is used. The `IntToStr` ([1558](#)) function is used to do the conversion.

See also: `TWordHelper.Parse` ([1719](#)), `IntToStr` ([1558](#))

76.93.6 TWordHelper.TryParse

Synopsis: Try to convert a string to a Word, report success or failure

Declaration: `class function TryParse(const AString: string; out AValue: Word)
: Boolean; Static`

Visibility: public

Description: `TryParse` attempts to convert the string `AString` to a `Word`, and reports the success of the attempt. If the attempt is successful, then `True` is returned, and the actual value of the `Word` is returned in `AValue`.

It uses the `val` (1442) function to perform the conversion, so no localization is taken into account.

See also: `TWordHelper.Parse` (1719), `Val` (1413)

76.93.7 TWordHelper.ToBoolean

Synopsis: Convert to a boolean value

Declaration: `function ToBoolean : Boolean`

Visibility: public

Description: `ToBoolean` converts the `Word` value to a boolean: it returns `True` if the value is nonzero, `False` if it is zero.

See also: `TWordHelper.ToSingle` (1721), `TWordHelper.ToDouble` (1720), `TWordHelper.ToExtended` (1720), `TWordHelper.ToString` (1719), `TWordHelper.ToHexString` (1721)

76.93.8 TWordHelper.ToDouble

Synopsis: Convert to a double-sized floating point value

Declaration: `function ToDouble : Double`

Visibility: public

Description: `ToDouble` converts the `Word` value to a double-sized floating point value.

See also: `TWordHelper.ToBoolean` (1720), `TWordHelper.ToExtended` (1720), `TWordHelper.ToSingle` (1721), `TWordHelper.ToString` (1719), `TWordHelper.ToHexString` (1721)

76.93.9 TWordHelper.ToExtended

Synopsis: Convert to an extended-sized floating point value

Declaration: `function ToExtended : Extended`

Visibility: public

Description: `ToDouble` converts the `Word` value to an extended-sized floating point value.

See also: `TWordHelper.ToBoolean` (1720), `TWordHelper.ToSingle` (1721), `TWordHelper.ToDouble` (1720), `TWordHelper.ToString` (1719), `TWordHelper.ToHexString` (1721)

76.93.10 TWordHelper.ToHexString

Synopsis: Convert to a hexadecimal string representation

Declaration: `function ToHexString(const AMinDigits: Integer) : string; Overload`
`function ToHexString : string; Overload`

Visibility: public

Description: `ToHexString` converts the `Word` value to a hexadecimal string representation. The `AMinDigits` argument specifies the minimal number of characters in the resulting string. The string will be left-padded with zeroes if the representation contains less than `AMinDigits` characters.

See also: `TWordHelper.ToBoolean` ([1720](#)), `TWordHelper.ToSingle` ([1721](#)), `TWordHelper.ToDouble` ([1720](#)), `TWordHelper.ToString` ([1719](#)), `TWordHelper.ToExtended` ([1720](#))

76.93.11 TWordHelper.ToSingle

Synopsis: Convert to an single-sized floating point value

Declaration: `function ToSingle : Single`

Visibility: public

Description: `ToSingle` converts the `Word` value to a single-sized floating point value.

See also: `TWordHelper.ToBoolean` ([1720](#)), `TWordHelper.ToDouble` ([1720](#)), `TWordHelper.ToExtended` ([1720](#)), `TWordHelper.ToString` ([1719](#)), `TWordHelper.ToHexString` ([1721](#))

Chapter 77

Reference for unit 'Types'

77.1 Used units

Table 77.1: Used units by unit 'Types'

Name	Page
System	1194

77.2 Overview

Starting with D6, types from Windows specific units that were needed in Kylix were extracted to this unit. So it mostly contains type of Windows origin that are needed in the VCL framework.

77.3 Constants, types and variables

77.3.1 Constants

`E_FAIL = ($80004005)`

Defined for Delphi compatibility, this should not be used.

`E_INVALIDARG = ($80070057)`

Defined for Delphi compatibility, this should not be used.

`GUID_NULL : TGuid = '{00000000-0000-0000-0000-000000000000}'`

`GUID_NULL` is the definition of the NULL (empty) GUID.

`LOCK_EXCLUSIVE = 2`

Defined for Delphi compatibility, this should not be used.

`LOCK_ONLYONCE = 4`

Defined for Delphi compatibility, this should not be used.

LOCK_WRITE = 1

Defined for Delphi compatibility, this should not be used.

STATFLAG_DEFAULT = 0

Defined for Delphi compatibility, this should not be used.

STATFLAG_NONAME = 1

Defined for Delphi compatibility, this should not be used.

STATFLAG_NOOPEN = 2

Defined for Delphi compatibility, this should not be used.

STGTY_LOCKBYTES = 3

Defined for Delphi compatibility, this should not be used.

STGTY_PROPERTY = 4

Defined for Delphi compatibility, this should not be used.

STGTY_STORAGE = 1

Defined for Delphi compatibility, this should not be used.

STGTY_STREAM = 2

Defined for Delphi compatibility, this should not be used.

STG_E_ABNORMALAPIEXIT = (\$800300FA)

Defined for Delphi compatibility, this should not be used.

STG_E_ACCESSDENIED = (\$80030005)

Defined for Delphi compatibility, this should not be used.

STG_E_BADBASEADDRESS = (\$80030110)

Defined for Delphi compatibility, this should not be used.

STG_E_CANTSAVE = (\$80030103)

Defined for Delphi compatibility, this should not be used.

STG_E_DISKISWRITEPROTECTED = (\$80030013)

Defined for Delphi compatibility, this should not be used.

STG_E_DOCFILECORRUPT = (\$80030109)

Defined for Delphi compatibility, this should not be used.

STG_E_EXTANTMARSHALLINGS = (\$80030108)

Defined for Delphi compatibility, this should not be used.

STG_E_FILEALREADYEXISTS = (\$80030050)

Defined for Delphi compatibility, this should not be used.

STG_E_FILENOTFOUND = (\$80030002)

Defined for Delphi compatibility, this should not be used.

STG_E_INCOMPLETE = (\$80030201)

Defined for Delphi compatibility, this should not be used.

STG_E_INSUFFICIENTMEMORY = (\$80030008)

Defined for Delphi compatibility, this should not be used.

STG_E_INUSE = (\$80030100)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFLAG = (\$800300FF)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDFUNCTION = (\$80030001)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHANDLE = (\$80030006)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDHEADER = (\$800300FB)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDNAME = (\$800300FC)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPARAMETER = (\$80030057)

Defined for Delphi compatibility, this should not be used.

STG_E_INVALIDPOINTER = (\$80030009)

Defined for Delphi compatibility, this should not be used.

STG_E_LOCKVIOLATION = (\$80030021)

Defined for Delphi compatibility, this should not be used.

STG_E_MEDIUMFULL = (\$80030070)

Defined for Delphi compatibility, this should not be used.

STG_E_NOMOREFILES = (\$80030012)

Defined for Delphi compatibility, this should not be used.

STG_E_NOTCURRENT = (\$80030101)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDDLL = (\$80030105)

Defined for Delphi compatibility, this should not be used.

STG_E_OLDFORMAT = (\$80030104)

Defined for Delphi compatibility, this should not be used.

STG_E_PATHNOTFOUND = (\$80030003)

Defined for Delphi compatibility, this should not be used.

STG_E_PROPSSETMISMATCHED = (\$800300F0)

Defined for Delphi compatibility, this should not be used.

STG_E_READFAULT = (\$8003001E)

Defined for Delphi compatibility, this should not be used.

STG_E_REVERTED = (\$80030102)

Defined for Delphi compatibility, this should not be used.

STG_E_SEEKERROR = (\$80030019)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREREQUIRED = (\$80030106)

Defined for Delphi compatibility, this should not be used.

STG_E_SHAREVIOLATION = (\$80030020)

Defined for Delphi compatibility, this should not be used.

STG_E_TERMINATED = (\$80030202)

Defined for Delphi compatibility, this should not be used.

STG_E_TOOMANYOPENFILES = (\$80030004)

Defined for Delphi compatibility, this should not be used.

STG_E_UNIMPLEMENTEDFUNCTION = (\$800300FE)

Defined for Delphi compatibility, this should not be used.

STG_E_UNKNOWN = (\$800300FD)

Defined for Delphi compatibility, this should not be used.

STG_E_WRITEFAULT = (\$8003001D)

Defined for Delphi compatibility, this should not be used.

STG_S_BLOCK = \$00030201

Defined for Delphi compatibility, this should not be used.

STG_S_CONVERTED = \$00030200

Defined for Delphi compatibility, this should not be used.

STG_S_MONITORING = \$00030203

Defined for Delphi compatibility, this should not be used.

STG_S_RETRYNOW = \$00030202

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_CUR = 1

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_END = 2

Defined for Delphi compatibility, this should not be used.

STREAM_SEEK_SET = 0

Defined for Delphi compatibility, this should not be used.

77.3.2 Types

`ArgList = Pointer`

`ArgList` is defined for Delphi/Kylix compatibility and should not be used.

`DWORD = LongWord`

Alias for cardinal type

`FILETIME = _FILETIME`

Alias for the `_FILETIME` type

`Largeint = Int64`

`Largeint` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LargeUint = QWord`

`LargeUint` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_INT = Largeint`

`LARGE_INT` is an alias for the `Int64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`LARGE_UINT = LargeUint`

`LARGE_UINT` is an alias for the `QWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PByte = System.PByte`

`PByte` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PCLSID = PGuid`

`PCLSID` is a pointer to a `TCLSID` type.

`PDisplay = Pointer`

`PDisplay` is defined for Delphi/Kylix compatibility and should not be used.

`PDouble = System.PDouble`

`PDouble` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PDWord = ^DWORD`

`PDWord` is equivalent to the `PCardinal` type.

`PEvent` = `Pointer`

`PEvent` is defined for Delphi/Kylix compatibility and should not be used.

`PFileTime` = `^TFileTime`

Pointer to `TFileTime` type

`PLargeInt` = `^Largeint`

`PLargeInt` is an alias for the `PInt64` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLargeuInt` = `^LargeUInt`

`PLargeUInt` is an alias for the `PQWord` type defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PLongint` = `System.PLongint`

`PLongint` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PoleStr` = `PWideChar`

`PoleStr` is a pointer to a (double) null-terminated array of `TChar` characters.

`PPoint` = `^TPoint`

`PPoint` is a typed pointer to the `TPoint` (1737) type.

`PPoleStr` = `^PoleStr`

`PPoleStr` is a typed pointer to a `PoleStr` variable.

`PRect` = `^TRect`

`PRect` is a typed pointer to the `TRect` (1746) type.

`PSize` = `^TSize`

`PSize` is a typed pointer to the `TSize` (1753) type.

`PSmallInt` = `System.PSmallInt`

`PSmallInt` is defined in the system unit. This is an alias for Delphi/Kylix compatibility.

`PSmallPoint` = `^TSmallPoint`

`PSmallPoint` is a typed pointer to the `TSmallPoint` (1732) record.

PStatStg = ^TStatStg

Pointer to TStatStg record.

PXrmOptionDescRec = ^TXrmOptionDescRec

PXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

Region = Pointer

Region is defined for Delphi/Kylix compatibility and should not be used.

STATSTG = TStatStg

Alias for the TStatStg type.

TagPoint = TPoint deprecated

tagPOINT is a simple alias for TPoint ([1737](#))

TagSize = TSize deprecated

tagSize is an alias for the TSize ([1753](#)) type.

```
tagSTATSTG = record
  pwcsName : POleStr;
  dwType : DWORD;
  cbSize
  : LARGE_UINT;
  mtime : TFileTime;
  ctime : TFileTime;
  atime
  : TFileTime;
  grfMode : DWORD;
  grfLocksSupported : DWORD;
  clsid
  : TCLSID;
  grfStateBits : DWORD;
  reserved : DWORD;
end
```

tagSTATSTG is used in the IStream.Stat ([1758](#)) call. It describes a storage medium (typically a file).

TArray4IntegerType = Array[0..3] of LongInt

TBooleanDynArray = Array of Boolean

TBooleanDynArray is a standard definition of a dynamical array of booleans.

TByteDynArray = Array of Byte

TByteDynArray is a standard definition of a dynamical array of (8-bit, unsigned) bytes.

TCardinalDynArray = Array of Cardinal

TCardinalDynArray is a standard definition of a dynamical array of (32-bit, unsigned) cardinals.

TCLSID = TGuid

TCLSID is an alias for the #rtl.system.TGUID (1242) type.

TCompDynArray = Array of Comp

TCurrencyArray = Array of currency

TDirection = (FromBeginning, FromEnd)

Table 77.2: Enumeration values for type TDirection

Value	Explanation
FromBeginning	
FromEnd	

TDoubleDynArray = Array of Double

TSoubleDynArray is a standard definition of a dynamical array of doubles. (regular floating point type)

TDuplicates = (dupIgnore, dupAccept, dupError)

Table 77.3: Enumeration values for type TDuplicates

Value	Explanation
dupAccept	Accept duplicates, adding them to the list.
dupError	Raise an error when an attempt is made to add a duplicate.
dupIgnore	Ignore the new item, do not add it to the list.

TDuplicates can be used to indicate how a list structure acts on the addition of a duplicate item to the list.

dupIgnore Ignore the new item, do not add it to the list.

dupAccept Accept duplicates, adding them to the list.

dupError Raise an error when an attempt is made to add a duplicate.

TEndian = (Big, Little)

Table 77.4: Enumeration values for type TEndian

Value	Explanation
Big	
Little	

TExtendedDynArray = Array of Extended

TFileTime = _FILETIME

Alias for the _FILETIME type

TInt64DynArray = Array of Int64

TInt64DynArray is a standard definition of a dynamical array of (64-bit, signed) int64s.

TIntegerDynArray = Array of Integer

TIntegerDynArray is a standard definition of a dynamical array of (32-bit, signed) integers.

TListCallback = procedure(data: pointer; arg: pointer) of object

TListCallback is the prototype for a Foreach operation on a list. It will be called with as Data the pointer in the list, and Arg will contain the extra user data added to the Foreach call. It can be used in methods of objects; for a version that can be used as a global procedure, see TListStaticCallback (1731)

TListStaticCallback = procedure(data: pointer; arg: pointer)

TListStaticCallback is the prototype for a Foreach operation on a list. It will be called with as Data the pointer in the list, and Arg will contain the extra user data added to the Foreach call. It can be used in plain procedures; for a version that can be used as a method, see TListCallback (1731)

TLongWordDynArray = Array of LongWord

TLongWordDynArray is a standard definition of a dynamical array of (32-bit, unsigned) LongWords.

TOLEChar = WideChar

TOLEChar is an alias for the WideChar type, defined in the system unit.

TPointerDynArray = Array of Pointer

Dynamic array of untyped pointers

TQWordDynArray = Array of QWord

TQWordDynArray is a standard definition of a dynamical array of (64-bit, unsigned) QWords.

TShortIntDynArray = Array of ShortInt

TShortintDynArray is a standard definition of a dynamical array of (8-bit, signed) shortints.

TSingleDynArray = Array of Single

TSingleDynArray is a standard definition of a dynamical array of singles. (smallest floating point type)

TSmallIntDynArray = Array of SmallInt

TSmallintDynArray is a standard definition of a dynamical array of (16-bit, unsigned) integers.

```
TSmallPoint = packed record
  X : SmallInt;
  Y : SmallInt;
end
```

TSmallPoint defines a point in a 2-dimensional plane, just like TPoint (1737), but the coordinates have a smaller range: The coordinates are smallints (16-bit, signed) and they run from -MaxSmallInt to maxSmallint.

TSplitRectType = (srLeft, srRight, srTop, srBottom)

Table 77.5: Enumeration values for type TSplitRectType

Value	Explanation
srBottom	
srLeft	
srRight	
srTop	

TStatStg = tagSTATSTG

TStatStg is a record type describing a storage medium. It is uses in the IStream.Stat (1758) function.

TStringDynArray = Array of AnsiString

TStringDynArray is a standard definition of a dynamical array of Ansistrings.

TValueRelationship = -1..1

TWideStringDynArray = Array of WideString

TWideStringDynArray is a standard definition of a dynamical array of WideStrings.

```
TWordDynArray = Array of Word
```

TWordDynArray is a standard definition of a dynamical array of (16-bit, unsigned) words.

```
TXrmOptionDescRec = record
end
```

TXrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
Widget = Pointer
```

Widget is defined for Delphi/Kylix compatibility and should not be used.

```
WidgetClass = Pointer
```

WidgetClass is defined for Delphi/Kylix compatibility and should not be used.

```
XrmOptionDescRec = TXrmOptionDescRec
```

XrmOptionDescRec is defined for Delphi/Kylix compatibility and should not be used.

```
_FILETIME = packed record
  dwLowDateTime : DWORD;
  dwHighDateTime
    : DWORD;
end
```

_FILETIME describes a file time stamp. It is defined for Delphi/Kylix compatibility and should not be used except when implementing or accessing the IStream interface. The TDateTime type should be used instead.

77.4 Procedures and functions

77.4.1 Bounds

Synopsis: Create a rectangle, given a position and size

Declaration: `function Bounds(ALeft: Integer; ATop: Integer; AWidth: Integer; AHeight: Integer) : TRect`

Visibility: default

Description: Bounds returns a TRect structure with the indicated position (Left=ALeft and Top=ATop) and size (Right=ALeft+AWidth and Bottom=ATop+AHeight)

See also: Rect ([1736](#)), PtInRect ([1735](#)), IntersectRect ([1734](#)), UnionRect ([1736](#))

77.4.2 CenterPoint

Synopsis: Return the center point of a rectangle

Declaration: `function CenterPoint(const Rect: TRect) : TPoint`

Visibility: default

Description: `CenterPoint` returns the center point of the rectangle `Rect`.

See also: `PtinRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736), `IsRectEmpty` (1735)

77.4.3 EqualRect

Synopsis: Check if two rectangles are equal.

Declaration: `function EqualRect(const r1: TRect; const r2: TRect) : Boolean`

Visibility: default

Description: `EqualRect` returns `True` if the rectangles `R1` and `R2` are equal (i.e. have the position and size). If the rectangles differ, the function returns `False`

See also: `Rect` (1736), `Bounds` (1733), `PtinRect` (1735), `IntersectRect` (1734), `UnionRect` (1736), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.4.4 InflateRect

Synopsis: Increase the rectangle in size, keeping it centered

Declaration: `function InflateRect(var Rect: TRect; dx: Integer; dy: Integer)
: Boolean`

Visibility: default

Description: `InflateRect` inflates the rectangle horizontally with `dx` pixels on each side, and vertically with `dy` pixels, thus keeping its center point on the same location. It returns `true` if the operation was successfully, `False` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `CenterPoint` (1734), `Size` (1736), `IsRectEmpty` (1735)

77.4.5 IntersectRect

Synopsis: Return the intersection of 2 rectangles

Declaration: `function IntersectRect(var Rect: TRect; const R1: TRect;
const R2: TRect) : Boolean`

Visibility: default

Description: `IntersectRect` returns the intersection of the 2 rectangles `R1` and `R2` in `Rect`. It returns `True` if the 2 rectangles have an intersection, otherwise `False` is returned, and `Rect` is filled with zero.

See also: `PtinRect` (1735), `UnionRect` (1736), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.4.6 IsRectEmpty

Synopsis: Check whether a rectangle is empty

Declaration: `function IsRectEmpty(const Rect: TRect) : Boolean`

Visibility: default

Description: `IsRectEmpty` returns true if the rectangle is empty, i.e. has a zero or negative width or height.

See also: `PtinRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.4.7 OffsetRect

Synopsis: Offset the rectangle

Declaration: `function OffsetRect(var Rect: TRect; DX: Integer; DY: Integer) : Boolean`

Visibility: default

Description: `OffsetRect` offsets the rectangle `Rect` by a horizontal distance `DX` and a vertical distance `DY`. The operation returns `True` if the operation was successful, `false` if it was not (only possible if the address of `Rect` is `Nil`).

See also: `PtinRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736), `IsRectEmpty` (1735)

77.4.8 Point

Synopsis: Create a point

Declaration: `function Point(x: Integer; y: Integer) : TPoint`

Visibility: default

Description: `Point` returns a `TPoint` structure with the given position (`X`, `Y`).

See also: `Rect` (1736), `PtinRect` (1735)

77.4.9 PtinRect

Synopsis: Check whether a point is inside a rectangle.

Declaration: `function PtinRect(const Rect: TRect; const p: TPoint) : Boolean`

Visibility: default

Description: `PtinRect` returns `True` if `p` is located inside `Rect`, and `False` if it is located outside the rectangle.

Remark: Note that the bottom, right edges are not considered part of the rectangle, therefore a point located on one of these edges will not be considered part of the rectangle, meaning that for a record (10,10,100,100) the point (90,100) will not be considered part of the record, but 90, 10 will be.

See also: `IntersectRect` (1734), `UnionRect` (1736), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.4.10 Rect

Synopsis: Create a rectangle record

Declaration: `function Rect (Left: Integer; Top: Integer; Right: Integer;
Bottom: Integer) : TRect`

Visibility: default

Description: `Rect` returns a rectangle structure with the 4 members `Left`, `Top`, `Right` and `Bottom` as passed in the arguments.

See also: `Bounds` (1733), `PtInRect` (1735), `IntersectRect` (1734), `UnionRect` (1736), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.4.11 Size

Synopsis: Return the size of the rectangle

Declaration: `function Size (AWidth: Integer; AHeight: Integer) : TSize`
`function Size (const ARect: TRect) : TSize`

Visibility: default

Description: `Size` returns a `TSize` record with the indicated `AWidth`, `AHeight`. In the case `ARect` is passed, the width and height are calculated (taking into account that the right, bottom are not considered part of the rectangle).

See also: `PtInRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `CenterPoint` (1734), `IsRectEmpty` (1735)

77.4.12 UnionRect

Synopsis: Return the union of 2 rectangles.

Declaration: `function UnionRect (var Rect: TRect; const R1: TRect; const R2: TRect)
: Boolean`

Visibility: default

Description: `UnionRect` returns the rectangle that encompasses both `R1` and `R2` in `Rect`. It returns `True` if the resulting rectangle is not empty, `False` if the result is an empty rectangle (in which case the result is filled with zeroes)

See also: `PtInRect` (1735), `IntersectRect` (1734), `IsRectEmpty` (1735), `OffsetRect` (1735), `InflateRect` (1734), `Size` (1736)

77.5 TPoint

```
TPoint = packed record
  x : LongInt;
  y : LongInt;
public
  class
    function Zero : TPoint; Static;
    function Add(const apt: TPoint
```

```

) : TPoint;
function Distance(const apt: TPoint) : ValReal;
function
IsZero : Boolean;
function Subtract(const apt: TPoint) : TPoint
;
procedure SetLocation(const apt: TPoint);
procedure SetLocation
(ax: LongInt; ay: LongInt);
procedure Offset(const apt: TPoint)
;
procedure Offset(dx: LongInt; dy: LongInt);
class function PointInCircle
(const apt: TPoint; const acenter: TPoint;
const aradius: Integer) : Boolean; Static;
TPoint.class
operator =(const apt1: TPoint; const apt2: TPoint)
: Boolean;
TPoint.class operator <>(const apt1: TPoint
; const apt2: TPoint)
: Boolean;

TPoint
.class operator +(const apt1: TPoint; const apt2: TPoint) : TPoint
;
TPoint.class operator -(const apt1: TPoint; const apt2: TPoint
) : TPoint;
TPoint.class operator :=(const aspt: TSmallPoint) :
TPoint;
TPoint.class operator explicit(const apt: TPoint) : TSmallPoint
;
end

```

TPoint is a generic definition of a point in a 2-dimensional discrete plane, where X indicates the horizontal position, and Y the vertical position (positions usually measured in pixels), and 0, 0 is the origin of the plane.

Usually, the origin is the upper-left corner of the screen, with Y increasing as one moves further down the screen - this is opposite to the mathematical view where Y increases as one moves upwards.

The coordinates are integers, (32-bit, signed) so the coordinate system runs from -MaxInt to MaxInt.

77.5.1 Method overview

Page	Method	Description
1738	Add	
1739	add(TPoint,TPoint):TPoint	
1740	assign(TSmallPoint):TPoint	
1738	Distance	
1739	equal(TPoint,TPoint):Boolean	
1740	explicit(TPoint):TSmallPoint	
1738	IsZero	
1739	notequal(TPoint,TPoint):Boolean	
1739	Offset	
1739	PointInCircle	
1739	SetLocation	
1738	Subtract	
1739	subtract(TPoint,TPoint):TPoint	
1738	Zero	

77.5.2 TPoint.Zero

Declaration: `class function Zero : TPoint; Static`

Visibility: public

77.5.3 TPoint.Add

Declaration: `function Add(const apt: TPoint) : TPoint`

Visibility: public

77.5.4 TPoint.Distance

Declaration: `function Distance(const apt: TPoint) : ValReal`

Visibility: public

77.5.5 TPoint.IsZero

Declaration: `function IsZero : Boolean`

Visibility: public

77.5.6 TPoint.Subtract

Declaration: `function Subtract(const apt: TPoint) : TPoint`

Visibility: public

77.5.7 TPoint.SetLocation

Declaration: `procedure SetLocation(const apt: TPoint)`

Visibility: public

77.5.8 TPoint.SetLocation

Declaration: `procedure SetLocation(ax: LongInt; ay: LongInt)`

Visibility: public

77.5.9 TPoint.Offset

Declaration: `procedure Offset(const apt: TPoint)`

Visibility: public

77.5.10 TPoint.Offset

Declaration: `procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: public

77.5.11 TPoint.PointInCircle

Declaration: `class function PointInCircle(const apt: TPoint; const acenter: TPoint;
const aradius: Integer) : Boolean; Static`

Visibility: public

77.5.12 TPoint.equal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator =(const apt1: TPoint; const apt2: TPoint)
: Boolean`

Visibility: public

77.5.13 TPoint.notequal(TPoint,TPoint):Boolean

Declaration: `TPoint.class operator <>(const apt1: TPoint; const apt2: TPoint)
: Boolean`

Visibility: public

77.5.14 TPoint.add(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator +(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

77.5.15 TPoint.subtract(TPoint,TPoint):TPoint

Declaration: `TPoint.class operator -(const apt1: TPoint; const apt2: TPoint) : TPoint`

Visibility: public

77.5.16 TPoint.assign(TSmallPoint):TPoint

Declaration: TPoint.class operator :=(const aspt: TSmallPoint) : TPoint

Visibility: public

77.5.17 TPoint.explicit(TPoint):TSmallPoint

Declaration: TPoint.class operator explicit(const apt: TPoint) : TSmallPoint

Visibility: public

77.6 TPointF

```
TPointF = packed record
  x : Single;
  y : Single;
public
  function
    Add(const apt: TPoint) : TPointF;
    function Add(const apt: TPointF
    ) : TPointF;
    function Distance(const apt: TPointF) : Single;
    function
      DotProduct(const apt: TPointF) : Single;
    function IsZero : Boolean
    ;
    function Subtract(const apt: TPointF) : TPointF;
    function Subtract
      (const apt: TPoint) : TPointF;
    procedure SetLocation(const apt:
      TPointF);
    procedure SetLocation(const apt: TPoint);
    procedure
      SetLocation(ax: LongInt; ay: LongInt);
    procedure Offset(const apt
      : TPointF);
    procedure Offset(const apt: TPoint);
    procedure Offset
      (dx: LongInt; dy: LongInt);
    function Scale(afactor: Single) : TPointF
    ;
    function Ceiling : TPoint;
    function Truncate : TPoint;
    function
      Floor : TPoint;
    function Round : TPoint;
    function Length : Single
    ;
    TPointF.class operator =(const apt1: TPointF; const apt2: TPointF
    )
      : Boolean;
    TPointF.class operator
```

```

<>(const apt1: TPointF; const apt2: TPointF)
: Boolean;
TPointF.class operator +(const apt1: TPointF
; const apt2: TPointF)
        : TPointF;
TPointF
.class operator -(const apt1: TPointF; const apt2: TPointF)
: TPointF;
TPointF.class operator -(const
apt1: TPointF) : TPointF;
TPointF.class operator *(const apt1:
TPointF; const apt2: TPointF)
        : Single
;
TPointF.class operator *(const apt1: TPointF; afactor: single
) : TPointF;
TPointF.class operator *(afactor: single; const apt1
: TPointF) : TPointF;
end

```

77.6.1 Method overview

Page	Method	Description
1742	Add	
1744	add(TPointF,TPointF):TPointF	
1743	Ceiling	
1742	Distance	
1742	DotProduct	
1744	equal(TPointF,TPointF):Boolean	
1743	Floor	
1742	IsZero	
1743	Length	
1744	multiply(single,TPointF):TPointF	
1744	multiply(TPointF,single):TPointF	
1744	multiply(TPointF,TPointF):Single	
1744	negative(TPointF):TPointF	
1744	notequal(TPointF,TPointF):Boolean	
1743	Offset	
1743	Round	
1743	Scale	
1742	SetLocation	
1742	Subtract	
1744	subtract(TPointF,TPointF):TPointF	
1743	Truncate	

77.6.2 TPointF.Add

Declaration: function Add(const apt: TPoint) : TPointF

Visibility: public

77.6.3 TPointF.Add

Declaration: function Add(const apt: TPointF) : TPointF

Visibility: public

77.6.4 TPointF.Distance

Declaration: function Distance(const apt: TPointF) : Single

Visibility: public

77.6.5 TPointF.DotProduct

Declaration: function DotProduct(const apt: TPointF) : Single

Visibility: public

77.6.6 TPointF.IsZero

Declaration: function IsZero : Boolean

Visibility: public

77.6.7 TPointF.Subtract

Declaration: function Subtract(const apt: TPointF) : TPointF

Visibility: public

77.6.8 TPointF.Subtract

Declaration: function Subtract(const apt: TPoint) : TPointF

Visibility: public

77.6.9 TPointF.SetLocation

Declaration: procedure SetLocation(const apt: TPointF)

Visibility: public

77.6.10 TPointF.SetLocation

Declaration: procedure SetLocation(const apt: TPoint)

Visibility: public

77.6.11 TPointF.SetLocation

Declaration: procedure SetLocation(ax: LongInt; ay: LongInt)

Visibility: public

77.6.12 TPointF.Offset

Declaration: `procedure Offset(const apt: TPointF)`

Visibility: `public`

77.6.13 TPointF.Offset

Declaration: `procedure Offset(const apt: TPoint)`

Visibility: `public`

77.6.14 TPointF.Offset

Declaration: `procedure Offset(dx: LongInt; dy: LongInt)`

Visibility: `public`

77.6.15 TPointF.Scale

Declaration: `function Scale(afactor: Single) : TPointF`

Visibility: `public`

77.6.16 TPointF.Ceiling

Declaration: `function Ceiling : TPoint`

Visibility: `public`

77.6.17 TPointF.Truncate

Declaration: `function Truncate : TPoint`

Visibility: `public`

77.6.18 TPointF.Floor

Declaration: `function Floor : TPoint`

Visibility: `public`

77.6.19 TPointF.Round

Declaration: `function Round : TPoint`

Visibility: `public`

77.6.20 TPointF.Length

Declaration: `function Length : Single`

Visibility: `public`

77.6.21 TPointF.equal(TPointF,TPointF):Boolean

Declaration: TPointF.class operator =(const apt1: TPointF; const apt2: TPointF)
: Boolean

Visibility: public

77.6.22 TPointF.notequal(TPointF,TPointF):Boolean

Declaration: TPointF.class operator <>(const apt1: TPointF; const apt2: TPointF)
: Boolean

Visibility: public

77.6.23 TPointF.add(TPointF,TPointF):TPointF

Declaration: TPointF.class operator +(const apt1: TPointF; const apt2: TPointF)
: TPointF

Visibility: public

77.6.24 TPointF.subtract(TPointF,TPointF):TPointF

Declaration: TPointF.class operator -(const apt1: TPointF; const apt2: TPointF)
: TPointF

Visibility: public

77.6.25 TPointF.negative(TPointF):TPointF

Declaration: TPointF.class operator -(const apt1: TPointF) : TPointF

Visibility: public

77.6.26 TPointF.multiply(TPointF,TPointF):Single

Declaration: TPointF.class operator *(const apt1: TPointF; const apt2: TPointF)
: Single

Visibility: public

77.6.27 TPointF.multiply(TPointF,single):TPointF

Declaration: TPointF.class operator *(const apt1: TPointF; afactor: single) : TPointF

Visibility: public

77.6.28 TPointF.multiply(single,TPointF):TPointF

Declaration: TPointF.class operator *(afactor: single; const apt1: TPointF) : TPointF

Visibility: public

77.7 TRect

```

TRect = packed record
private
    function getHeight : LongInt;
    function
    getLocation : TPoint;
    function getSize : TSize;
    function getWidth
    : LongInt;
    procedure setHeight (AValue: LongInt);
    procedure setSize
    (AValue: TSize);
    procedure setWidth(AValue: LongInt);
public
    constructor
    Create(Origin: TPoint);
    constructor Create(Origin: TPoint; AWidth
    : LongInt; AHeight: LongInt);
    constructor Create(ALeft: LongInt
    ; ATop: LongInt; ARight: LongInt;
    ABottom: LongInt
    );
    constructor Create(P1: TPoint; P2: TPoint; Normalize: Boolean
    );
    constructor Create(R: TRect; Normalize: Boolean);
    TRect.class
    operator =(L: TRect; R: TRect) : Boolean;
    TRect.class operator
    <>(L: TRect; R: TRect) : Boolean;
    TRect.class operator +(L: TRect
    ; R: TRect) : TRect;
    TRect.class operator *(L: TRect; R: TRect)
    : TRect;
    class function Empty : TRect; Static;
    procedure NormalizeRect
    ;
    function IsEmpty : Boolean;
    function Contains(Pt: TPoint) :
    Boolean;
    function Contains(R: TRect) : Boolean;
    function IntersectsWith
    (R: TRect) : Boolean;
    class function Intersect(R1: TRect; R2: TRect
    ) : TRect; Static;
    procedure Intersect(R: TRect);
    class function
    Union(R1: TRect; R2: TRect) : TRect; Static;
    procedure Union(R
    : TRect);
    class function Union(const Points: Array of TPoint) :
    TRect; Static;
    procedure Offset(DX: LongInt; DY: LongInt);

```

```

procedure
Offset(DP: TPoint);
procedure SetLocation(X: LongInt; Y: LongInt
);
procedure SetLocation(P: TPoint);
procedure Inflate(DX: LongInt
; DY: LongInt);
procedure Inflate(DL: LongInt; DT: LongInt; DR:
LongInt; DB: LongInt);
function CenterPoint : TPoint;
function
SplitRect(SplitType: TSplitRectType; ASize: LongInt) : TRect;
function
SplitRect(SplitType: TSplitRectType; Percent: Double) : TRect;
property Height : LongInt;
property Width : LongInt;
property
Size : TSize;
property Location : TPoint;
case LongInt of
0: (
Left : LongInt;
Top : LongInt;
Right : LongInt;
Bottom :
LongInt;
);
1: (
TopLeft : TPoint;
BottomRight : TPoint;
);
2
: (
Vector : TArray4IntegerType;
);
end

```

TRect defines a rectangle in a discrete plane. It is described by the horizontal (left, right) or vertical (top, Bottom) positions (in pixels) of the edges, or, alternatively, by the coordinates of the top left (TopLeft) and bottom right (BottomRight) corners.

77.7.1 Method overview

Page	Method	Description
1748	<code>add(TRect,TRect):TRect</code>	
1750	<code>CenterPoint</code>	
1749	<code>Contains</code>	
1748	<code>Create</code>	
1748	<code>Empty</code>	
1748	<code>equal(TRect,TRect):Boolean</code>	
1750	<code>Inflate</code>	
1749	<code>Intersect</code>	
1749	<code>IntersectsWith</code>	
1748	<code>IsEmpty</code>	
1748	<code>multiply(TRect,TRect):TRect</code>	
1748	<code>NormalizeRect</code>	
1748	<code>notequal(TRect,TRect):Boolean</code>	
1749	<code>Offset</code>	
1750	<code>SetLocation</code>	
1750	<code>SplitRect</code>	
1749	<code>Union</code>	

77.7.2 Property overview

Page	Properties	Access	Description
1750	<code>Height</code>	rw	
1751	<code>Location</code>	rw	
1751	<code>Size</code>	rw	
1751	<code>Width</code>	rw	

77.7.3 TRect.Create

Declaration: `constructor Create(Origin: TPoint)`

Visibility: `public`

77.7.4 TRect.Create

Declaration: `constructor Create(Origin: TPoint; AWidth: LongInt; AHeight: LongInt)`

Visibility: `public`

77.7.5 TRect.Create

Declaration: `constructor Create(ALeft: LongInt; ATop: LongInt; ARight: LongInt;
ABottom: LongInt)`

Visibility: `public`

77.7.6 TRect.Create

Declaration: `constructor Create(P1: TPoint; P2: TPoint; Normalize: Boolean)`

Visibility: `public`

77.7.7 TRect.Create

Declaration: constructor Create(R: TRect; Normalize: Boolean)

Visibility: public

77.7.8 TRect.equal(TRect,TRect):Boolean

Declaration: TRect.class operator =(L: TRect; R: TRect) : Boolean

Visibility: public

77.7.9 TRect.notequal(TRect,TRect):Boolean

Declaration: TRect.class operator <>(L: TRect; R: TRect) : Boolean

Visibility: public

77.7.10 TRect.add(TRect,TRect):TRect

Declaration: TRect.class operator +(L: TRect; R: TRect) : TRect

Visibility: public

77.7.11 TRect.multiply(TRect,TRect):TRect

Declaration: TRect.class operator *(L: TRect; R: TRect) : TRect

Visibility: public

77.7.12 TRect.Empty

Declaration: class function Empty : TRect; Static

Visibility: public

77.7.13 TRect.NormalizeRect

Declaration: procedure NormalizeRect

Visibility: public

77.7.14 TRect.IsEmpty

Declaration: function IsEmpty : Boolean

Visibility: public

77.7.15 TRect.Contains

Declaration: function Contains(Pt: TPoint) : Boolean

Visibility: public

77.7.16 TRect.Contains

Declaration: function Contains(R: TRect) : Boolean

Visibility: public

77.7.17 TRect.IntersectsWith

Declaration: function IntersectsWith(R: TRect) : Boolean

Visibility: public

77.7.18 TRect.Intersect

Declaration: class function Intersect(R1: TRect; R2: TRect) : TRect; Static

Visibility: public

77.7.19 TRect.Intersect

Declaration: procedure Intersect(R: TRect)

Visibility: public

77.7.20 TRect.Union

Declaration: class function Union(R1: TRect; R2: TRect) : TRect; Static

Visibility: public

77.7.21 TRect.Union

Declaration: procedure Union(R: TRect)

Visibility: public

77.7.22 TRect.Union

Declaration: class function Union(const Points: Array of TPoint) : TRect; Static

Visibility: public

77.7.23 TRect.Offset

Declaration: procedure Offset(DX: LongInt; DY: LongInt)

Visibility: public

77.7.24 TRect.Offset

Declaration: procedure Offset(DP: TPoint)

Visibility: public

77.7.25 TRect.SetLocation

Declaration: procedure SetLocation(X: LongInt; Y: LongInt)

Visibility: public

77.7.26 TRect.SetLocation

Declaration: procedure SetLocation(P: TPoint)

Visibility: public

77.7.27 TRect.Inflate

Declaration: procedure Inflate(DX: LongInt; DY: LongInt)

Visibility: public

77.7.28 TRect.Inflate

Declaration: procedure Inflate(DL: LongInt; DT: LongInt; DR: LongInt; DB: LongInt)

Visibility: public

77.7.29 TRect.CenterPoint

Declaration: function CenterPoint : TPoint

Visibility: public

77.7.30 TRect.SplitRect

Declaration: function SplitRect(SplitType: TSplitRectType; ASize: LongInt) : TRect

Visibility: public

77.7.31 TRect.SplitRect

Declaration: function SplitRect(SplitType: TSplitRectType; Percent: Double) : TRect

Visibility: public

77.7.32 TRect.Height

Declaration: Property Height : LongInt

Visibility: public

Access: Read,Write

77.7.33 TRect.Width

Declaration: Property Width : LongInt

Visibility: public

Access: Read,Write

77.7.34 TRect.Size

Declaration: Property Size : TSize

Visibility: public

Access: Read,Write

77.7.35 TRect.Location

Declaration: Property Location : TPoint

Visibility: public

Access: Read,Write

77.8 TRectF

```

TRectF = packed record
private
    function GetHeight : Single;
    function
        GetWidth : Single;
    procedure SetHeight (AValue: Single);
    procedure
        SetWidth(AValue: Single);
public
    function Union(const r: TRectF
        ) : TRectF;
    procedure Offset(const dx: Single; const dy: Single
        );
    property Width : Single;
    property Height : Single;
case Integer
    of
0: (
    Left : Single;
    Top : Single;
    Right : Single;
    Bottom
        : Single;
    );
1: (
    TopLeft : TPointF;
    BottomRight : TPointF;
    );
end

```


77.8.1 Method overview

Page	Method	Description
1752	Offset	
1752	Union	

77.8.2 Property overview

Page	Properties	Access	Description
1752	Height	rw	
1752	Width	rw	

77.8.3 TRectF.Union

Declaration: `function Union(const r: TRectF) : TRectF`

Visibility: `public`

77.8.4 TRectF.Offset

Declaration: `procedure Offset(const dx: Single; const dy: Single)`

Visibility: `public`

77.8.5 TRectF.Width

Declaration: `Property Width : Single`

Visibility: `public`

Access: `Read,Write`

77.8.6 TRectF.Height

Declaration: `Property Height : Single`

Visibility: `public`

Access: `Read,Write`

77.9 TSize

```

TSize = packed record
    cx : LongInt;
    cy : LongInt;
public
    function
    Add(const asz: TSize) : TSize;
    function Distance(const asz: TSize
    ) : Double;
    function IsZero : Boolean;
    function Subtract(const

```

```

asz: TSize) : TSize;
TSize.class operator =(const asz1: TSize;
const asz2: TSize) : Boolean;
TSize.class operator <>(const asz1
: TSize; const asz2: TSize) : Boolean;
TSize.class operator +(const
asz1: TSize; const asz2: TSize) : TSize;
TSize.class operator
-(const asz1: TSize; const asz2: TSize) : TSize;
property Width
: LongInt;
property Height : LongInt;
end

```

TSize is a type to describe the size of a rectangular area, where *cx* is the width, *cy* is the height (in pixels) of the rectangle.

77.9.1 Method overview

Page	Method	Description
1753	Add	
1754	add(TSize,TSize):TSize	
1753	Distance	
1754	equal(TSize,TSize):Boolean	
1753	IsZero	
1754	notequal(TSize,TSize):Boolean	
1754	Subtract	
1754	subtract(TSize,TSize):TSize	

77.9.2 Property overview

Page	Properties	Access	Description
1754	Height	rw	
1754	Width	rw	

77.9.3 TSize.Add

Declaration: function Add(const asz: TSize) : TSize

Visibility: public

77.9.4 TSize.Distance

Declaration: function Distance(const asz: TSize) : Double

Visibility: public

77.9.5 TSize.IsZero

Declaration: function IsZero : Boolean

Visibility: public

77.9.6 TSize.Subtract

Declaration: `function Subtract(const asz: TSize) : TSize`

Visibility: public

77.9.7 TSize.equal(TSize,TSize):Boolean

Declaration: `TSize.class operator =(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

77.9.8 TSize.notequal(TSize,TSize):Boolean

Declaration: `TSize.class operator <>(const asz1: TSize; const asz2: TSize) : Boolean`

Visibility: public

77.9.9 TSize.add(TSize,TSize):TSize

Declaration: `TSize.class operator +(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

77.9.10 TSize.subtract(TSize,TSize):TSize

Declaration: `TSize.class operator -(const asz1: TSize; const asz2: TSize) : TSize`

Visibility: public

77.9.11 TSize.Width

Declaration: `Property Width : LongInt`

Visibility: public

Access: Read,Write

77.9.12 TSize.Height

Declaration: `Property Height : LongInt`

Visibility: public

Access: Read,Write

77.10 IClassFactory

77.10.1 Description

`IClassFactory` is defined for Delphi/Kylix compatibility and should not be used.

77.10.2 Method overview

Page	Method	Description
1755	CreateInstance	Create a new instance of an interface.
1755	LockServer	Lock ActiveX server object.

77.10.3 IClassFactory.CreateInstance

Synopsis: Create a new instance of an interface.

Declaration: `function CreateInstance(const unkOuter: IUnknown; const riid: TGuid; out vObject) : HRESULT`

Visibility: default

Description: `IClassFactory.CreateInstance` is defined for Delphi/Kylix compatibility and should not be used.

77.10.4 IClassFactory.LockServer

Synopsis: Lock ActiveX server object.

Declaration: `function LockServer(fLock: LongBool) : HRESULT`

Visibility: default

Description: `IClassFactory.LockServer` is defined for Delphi/Kylix compatibility and should not be used.

77.11 ISequentialStream

77.11.1 Description

`ISequentialStream` is the interface for streams which only support sequential reading of chunks of data. It is defined for Delphi/Kylix compatibility and should not be used.

See also: `IStream` ([1756](#))

77.11.2 Method overview

Page	Method	Description
1755	Read	Read data from the stream
1756	Write	Write data to the stream

77.11.3 ISequentialStream.Read

Synopsis: Read data from the stream

Declaration: `function Read(pv: Pointer; cb: DWORD; pcbRead: PDWord) : HRESULT`

Visibility: default

Description: `Read` reads `cbCount` bytes from the stream into the memory pointed to by `pv` and returns the number of bytes read in `pcbread`. The result is zero for success or an error code.

See also: `ISequentialStream.Write` ([1756](#))

77.11.4 ISequentialStream.Write

Synopsis: Write data to the stream

Declaration: `function Write(pv: Pointer; cb: DWORD; pcbWritten: PDWord) : HRESULT`

Visibility: default

Description: `Write` writes `cbCount` bytes from the memory pointed to by `pv` to the stream and returns the number of bytes written in `pcbwritten`. The result is zero for success or an error code.

See also: `ISequentialStream.Read` ([1755](#))

77.12 IStream

77.12.1 Description

An abstract interface for an external (non pascal) stream, as defined in Microsoft COM interfaces

77.12.2 Method overview

Page	Method	Description
1758	Clone	Clone the stream instance
1757	Commit	Commit data to the stream
1757	CopyTo	Copy data from one stream to another
1757	LockRegion	Lock a region of bytes in the stream
1757	Revert	Revert changes
1756	Seek	Set the stream position
1756	SetSize	Set the stream size
1758	Stat	return information about the stream.
1758	UnlockRegion	Unlocks a previously locked region of bytes in the stream

77.12.3 IStream.Seek

Synopsis: Set the stream position

Declaration: `function Seek(dlibMove: LargeUint; dwOrigin: LongInt; out libNewPosition: LargeUint) : HRESULT`

Visibility: default

Description: `Seek` sets the stream position at `dlibMove` bytes from `dwOrigin` (one of the `SEEK_*` constants) and returns the new absolute position in `libNewPosition`. The function returns zero on success, or an error code.

Errors: On error, a nonzero exit code is returned.

77.12.4 IStream.SetSize

Synopsis: Set the stream size

Declaration: `function SetSize(libNewSize: LargeUint) : HRESULT`

Visibility: default

Description: `SetSize` sets the size of the stream to `libNewSize` bytes, if the stream allows it. On success, zero is returned.

Errors: On error, a nonzero exit code is returned.

77.12.5 IStream.CopyTo

Synopsis: Copy data from one stream to another

Declaration: `function CopyTo(stm: IStream; cb: LargeUInt; out cbRead: LargeUInt; out cbWritten: LargeUInt) : HRESULT`

Visibility: default

Description: `CopyTo` copies `cb` bytes from the stream to target stream `stm`. `cbRead` returns how many bytes were read from the stream, `cbWritten` returns how many bytes were actually written to the destination stream. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

77.12.6 IStream.Commit

Synopsis: Commit data to the stream

Declaration: `function Commit(grfCommitFlags: LongInt) : HRESULT`

Visibility: default

Description: `Commit` commits the data in the stream to the underlying medium. `Flags` is a set of options to control the commit operation (see MSDN for the possible flags).

Errors: On error, a nonzero exit code is returned.

77.12.7 IStream.Revert

Synopsis: Revert changes

Declaration: `function Revert : HRESULT`

Visibility: default

Description: `Revert` reverts all changes that were done to a transacted stream, i.e. all changes since the last commit. The function returns zero on success.

Errors: On error, a nonzero exit code is returned.

77.12.8 IStream.LockRegion

Synopsis: Lock a region of bytes in the stream

Declaration: `function LockRegion(libOffset: LargeUInt; cb: LargeUInt; dwLockType: LongInt) : HRESULT`

Visibility: default

Description: `LockRegion` locks a region of the storage, starting at `libOffset`, for `cbCount` bytes. The applied lock is of type `dwLockType`. The function returns zero if the lock was successfully applied.

Errors: On error, a nonzero exit code is returned.

77.12.9 IStream.UnlockRegion

Synopsis: Unlocks a previously locked region of bytes in the stream

Declaration: `function UnlockRegion(libOffset: LargeUInt; cb: LargeUInt;
dwLockType: LongInt) : HRESULT`

Visibility: default

Description: `UnlockRegion` removes the lock on a region of the storage, starting at `libOffset`, for `cbCount` bytes. The lock must be of type `dwLockType`. The function returns zero if the lock was successfully removed.

Errors: On error, a nonzero exit code is returned.

77.12.10 IStream.Stat

Synopsis: return information about the stream.

Declaration: `function Stat(out statstg: TStatStg; grfStatFlag: LongInt) : HRESULT`

Visibility: default

Description: `Stat` returns information about the stream in `statstg`, taking into account the flags in `grfStatFlag` (one of the `STATFLAG_` constants). The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

77.12.11 IStream.Clone

Synopsis: Clone the stream instance

Declaration: `function Clone(out stm: IStream) : HRESULT`

Visibility: default

Description: `Clone` returns an independent but initially equal copy of the stream in `stm`. The function returns zero if the call was successful.

Errors: On error, a nonzero exit code is returned.

Chapter 78

Reference for unit 'typinfo'

78.1 Used units

Table 78.1: Used units by unit 'typinfo'

Name	Page
System	1194
sysutils	1442

78.2 Overview

The `TypeInfo` unit contains many routines which can be used for the querying of the Run-Time Type Information (RTTI) which is generated by the compiler for classes that are compiled under the `{ $M+ }` switch. This information can be used to retrieve or set property values for published properties for totally unknown classes. In particular, it can be used to stream classes. The `TPersistent` class in the `Classes` unit is compiled in the `{ $M+ }` state and serves as the base class for all classes that need to be streamed.

The unit should be compatible to the Delphi 5 unit with the same name. The only calls that are still missing are the Variant calls, since Free Pascal does not support the variant type yet.

The examples in this chapter use a `rttiobj` auxiliary unit, which contains an object that has a published property for all supported types. It also contains some auxiliary routines and definitions. This unit is included in the documentation sources, in the directory `typinfex`.

78.3 Auxiliary functions

Other `typinfo` related functions.

Table 78.2:

Name	Description
GetEnumName (1779)	Get an enumerated type element name
GetEnumValue (1781)	Get ordinal number of an enumerated type, based on the name.
GetEnumNameCount (1780)	Get number of elements in an enumerated type.
GetTypeData (1793)	Skip type name and return a pointer to the type data
SetToString (1803)	Convert a set to its string representation
StringToSet (1805)	Convert a string representation of a set to a set

78.4 Getting or setting property values

Functions to set or set a property's value.

Table 78.3:

Name	Description
GetEnumProp (1780)	Return the value of an enumerated type property
GetFloatProp (1781)	Return the value of a float property
GetInt64Prop (1782)	Return the value of an Int64 property
GetMethodProp (1783)	Return the value of a procedural type property
GetObjectProp (1785)	Return the value of an object property
GetOrdProp (1787)	Return the value of an ordinal type property
GetPropValue (1790)	Return the value of a property as a variant
GetSetProp (1791)	Return the value of a set property
GetStrProp (1792)	Return the value of a string property
GetWideStrProp (1794)	Return the value of a widestring property
GetVariantProp (1794)	Return the value of a variant property
SetEnumProp (1798)	Set the value of an enumerated type property
SetFloatProp (1798)	Set the value of a float property
SetInt64Prop (1799)	Set the value of an Int64 property
SetMethodProp (1800)	Set the value of a procedural type property
SetObjectProp (1800)	Set the value of an object property
SetOrdProp (1801)	Set the value of an ordinal type property
SetPropValue (1801)	Set the value of a property through a variant
SetSetProp (1802)	Set the value of a set property
SetStrProp (1802)	Set the value of a string property
SetWideStrProp (1804)	Set the value of a widestring property
SetVariantProp (1804)	Set the value of a variant property

78.5 Examining published property information

Functions for retrieving or examining property information

Table 78.4:

Name	Description
FindPropInfo (1778)	Getting property type information, With error checking.
GetPropInfo (1788)	Getting property type information, No error checking.
GetPropInfos (1788)	Find property information of a certain kind
GetObjectPropClass (1786)	Return the declared class of an object property
GetPropList (1789)	Get a list of all published properties
IsPublishedProp (1795)	Is a property published
IsStoredProp (1795)	Is a property stored
PropIsType (1796)	Is a property of a certain kind
PropType (1797)	Return the type of a property

78.6 Constants, types and variables

78.6.1 Constants

`BooleanIdents : Array[Boolean] of string = ('False', 'True')`

Names for boolean values

`DotSep : string = '.'`

Name separator character

`OnGetPropValue : TGetPropValue = Nil`

This callback is set by the variants unit to enable reading of properties as a variant. If set, it is called by the `GetPropValue` (1790) function.

`OnGetVariantprop : TGetVariantProp = Nil`

This callback is set by the variants unit to enable reading of variant properties. If set, it is called by the `GetVariantProp` (1794) function.

`OnSetPropValue : TSetPropValue = Nil`

This callback is set by the variants unit to enable writing of properties as a variant. If set, it is called by the `SetPropValue` (1801) function.

`OnSetVariantprop : TSetVariantProp = Nil`

This callback is set by the variants unit to enable writing of variant properties. If set, it is called by the `GetVariantProp` (1794) function.

`ptConst = 3`

Constant used in access method

`ptField = 0`

Property acces directly from field

```
ptStatic = 1
```

Property acces via static method

```
ptVirtual = 2
```

Property acces via virtual method

```
tkAny = [ (TTypeKind) .. (TTypeKind) ]
```

Any property type

```
tkMethods = [tkMethod]
```

Only method properties. (event handlers)

```
tkProcedure = tkProcVar
```

Procedure kind

```
tkProperties = tkAny - tkMethods - [tkUnknown]
```

Real properties. (not methods)

```
tkString = tkSSString
```

Alias for the `tsSSString` enumeration value

78.6.2 Types

```
PManagedField = ^TManagedField
```

`PManagedField` is a pointer to `TManagedField` (1765). It is used to describe automatically managed fields in records when the type kind is `tkRecord`.

```
PProcedureParam = ^TProcedureParam
```

`PProcedureParam` is a pointer to `TProcedureParam`. It is used in `TProcedureSignature` (1805).

```
PPropInfo = ^TPropInfo
```

Pointer to `TPropInfo` (1767) record

```
PPropList = ^TPropList
```

Pointer to `TPropList` (1767)

```
PTypeInfo = ^PTypeInfo
```

Pointer to PTypeInfo (1763) pointer

```
PTypeData = ^TTypeData
```

Pointer to TTypeData (1775) record.

```
PTypeInfo = ^TTypeInfo
```

Pointer to TTypeInfo (1776) record

```
PVmtFieldEntry = ^TVmtFieldEntry
```

Pointer to #rtl.typinfo.TVmtFieldEntry (1777) type.

```
PVmtFieldTable = ^TVmtFieldTable
```

Pointer to #rtl.typinfo.TVmtFieldTable (1778) type.

```
ShortStringBase = string
```

ShortStringBase is the base definition of a short string.

```
TArrayTypeData = packed record
  Size : SizeInt;
  ElCount : SizeInt
;
  ElType : PTypeInfo;
  DimCount : Byte;
  Dims : Array[0..255]
    of PTypeInfo;
end
```

TArrayTypeData is used to describe arrays in RTTI. It can be encountered when the type kind is `tkArray`, and is used for both static and dynamic arrays and single or multi-dimensional arrays. The type of the array elements is described in `elType`, and the ranges for each of the dimensions (specified in `DimCount` in `Dims`).

```
TCallConv = (ccReg, ccCdecl, ccPascal, ccStdCall, ccSafeCall, ccCppdecl
,
              ccFar16, ccOldFPCCall, ccInternProc, ccSysCall, ccSoftFloat
,
              ccMWPascal)
```

Table 78.5: Enumeration values for type TCallConv

Value	Explanation
ccCdecl	Cdecl calling convention.
ccCppdecl	Cppdecl calling convention
ccFar16	Far16 calling convention (Delphi compatibility)
ccInternProc	InternProc calling convention (compiler internal)
ccMWPPascal	MWPPascal (MetroWerks Pascal) calling convention.
ccOldFPCCall	OldFPCCall calling convention (deprecated)
ccPascal	Pascal calling convention.
ccReg	Register calling convention
ccSafeCall	SafeCall calling convention.
ccSoftFloat	Softfloat calling convention.
ccStdCall	stdcall calling convention.
ccSysCall	SysCall calling convention.

TCallConv is a type describing the calling convention used by a method. It contains an element for all supported calling conventions.

```
TFloatType = (ftSingle, ftDouble, ftExtended, ftComp, ftCurr)
```

Table 78.6: Enumeration values for type TFloatType

Value	Explanation
ftComp	Comp-type float
ftCurr	Currency-type float
ftDouble	Double-sized float
ftExtended	Extended-size float
ftSingle	Single-sized float

The size of a float type.

```
TGetPropValue = function(Instance: TObject; PropInfo: PPropInfo;
    PreferStrings: Boolean) : Variant
```

The callback function must return the property with name PropName of instance Instance. If PreferStrings is true, it should favour converting the property to a string value. The function needs to return the variant with the property value.

```
TGetVariantProp = function(Instance: TObject; PropInfo: PPropInfo
    )
    : Variant
```

The callback function must return the variant property with name PropName of instance Instance.

```
TIntfFlag = (ifHasGuid, ifDispInterface, ifDispatch, ifHasStrGUID)
```

Table 78.7: Enumeration values for type TIntfFlag

Value	Explanation
ifDispatch	Interface is a dispatch interface
ifDispInterface	Interface is a dual dispatch interface
ifHasGuid	Interface has GUID identifier
ifHasStrGUID	Interface has a string GUID identifier

Type of interface.

```
TIntfFlags = Set of TIntfFlag
```

Set of TIntfFlag (1764).

```
TIntfFlagsBase = Set of TIntfFlag
```

Set of TIntfFlag (1764).

```
TManagedField = packed record
  TypeRef : PTypeInfo;
  FldOffset
    : SizeInt;
end
```

TManagedField describes 1 managed field in a record. It consists of type information (TypeRef) and an offset in the record's memory layout (FldOffset). Size can be determined from the type information.

```
TMethodKind = (mkProcedure, mkFunction, mkConstructor, mkDestructor,
  mkClassProcedure, mkClassFunction, mkClassConstructor
  ,
  mkClassDestructor, mkOperatorOverload)
```

Table 78.8: Enumeration values for type TMethodKind

Value	Explanation
mkClassConstructor	Class constructor method.
mkClassDestructor	Class destructor method.
mkClassFunction	Class function
mkClassProcedure	Class procedure
mkConstructor	Class constructor
mkDestructor	Class Desctructor
mkFunction	Function method
mkOperatorOverload	Operator overloader
mkProcedure	Procedure method.

Method type description

```
TOrdType = (otSByte, otUByte, otSWord, otUWord, otSLong, otULong)
```

Table 78.9: Enumeration values for type TOrdType

Value	Explanation
otSByte	Signed byte
otSLong	Signed longint
otSWord	Signed word
otUByte	Unsigned byte
otULong	Unsigned longint (Cardinal)
otUWord	Unsigned word

If the property is an ordinal type, then TOrdType determines the size and sign of the ordinal type:

TParamFlag = (pfVar, pfConst, pfArray, pfAddress, pfReference, pfOut)

Table 78.10: Enumeration values for type TParamFlag

Value	Explanation
pfAddress	Parameter is passed by address
pfArray	Parameter is an array parameter
pfConst	Parameter is a const parameter (i.e. cannot be modified)
pfOut	Parameter is a string parameter
pfReference	Parameter is passed by reference
pfVar	Parameter is a var parameter (passed by reference)

TParamFlag describes a parameter.

TParamFlags = Set of TParamFlag

The kind of parameter for a method

```
TProcedureParam = packed record
  Flags : Byte;
  ParamType : PTypeInfo;
  ;
  Name : ShortString;
end
```

TProcedureParam describes a single parameter to a procedure (or function).

TProcInfoProc = procedure(PropInfo: PPropInfo) of object

Property info callback method

```
TPropData = packed record
  PropCount : Word;
  PropList : record
    _alignmentdummy : PtrInt;
  end;
end
```

The TPropData record is not used, but is provided for completeness and compatibility with Delphi.

```
TPropInfo = packed record
  PropType : PTypeInfo;
  GetProc : CodePointer
  ;
  SetProc : CodePointer;
  StoredProc : CodePointer;
  Index : Integer
  ;
  Default : LongInt;
  NameIndex : SmallInt;
  PropProcs : Byte
  ;
  Name : ShortString;
end
```

The TPropInfo record describes one published property of a class. The property information of a class are stored as an array of TPropInfo records.

The Name field is stored not with 255 characters, but with just as many characters as required to store the name.

```
TPropList = Array[0..65535] of PPropInfo
```

Array of property information pointers

```
TSetPropValue = procedure (Instance: TObject; PropInfo: PPropInfo;
  const Value: Variant)
```

The callback function must set the property with name PropName of instance Instance to Value.

```
TSetVariantProp = procedure (Instance: TObject; PropInfo: PPropInfo
  ;
  const Value: Variant)
```

The callback function must set the variant property with name PropName of instance to Value.

```
TTypeData = packed record
case TTypeKind of
tkUnKnown: (
);, tkLString
: (
);, tkWString: (
);, tkVariant: (
);, tkUString: (
);
tkAString
: (
  CodePage : Word;
);
tkInteger: (
  OrdType : TOrdType;
```



```

case
  TTypeKind of
tkInteger: (
  MinValue : LongInt;
  MaxValue : LongInt
  ;
case TTypeKind of
tkEnumeration: (
  BaseType : PTypeInfo;
  NameList
  : ShortString;
);
);, tkChar: (
  MinValue : LongInt;
  MaxValue
  : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseType : PTypeInfo
  ;
  NameList : ShortString;
);
);, tkEnumeration: (
  MinValue : LongInt
  ;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseType
  : PTypeInfo;
  NameList : ShortString;
);
);, tkBool: (
  MinValue
  : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
  BaseType : PTypeInfo;
  NameList : ShortString;
);
);, tkWChar
  : (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
  BaseType : PTypeInfo;
  NameList : ShortString
  ;
);
);
tkSet: (

```

```

    CompType : PTypeInfo;
);
);, tkChar: (
    OrdType
    : TOrdType;
case TTypeKind of
tkInteger: (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType
    : PTypeInfo;
    NameList : ShortString;
);
);, tkChar: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
    BaseType : PTypeInfo;
    NameList : ShortString;
);
);, tkEnumeration
    : (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
    BaseType : PTypeInfo;
    NameList : ShortString
    ;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue : LongInt;
case
    TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList
    : ShortString;
);
);, tkWChar: (
    MinValue : LongInt;
    MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo
    ;
    NameList : ShortString;

```

```

);
);
tkSet: (
    CompType : PTypeInfo
    ;
);
);, tkEnumeration: (
    OrdType : TOrdType;
case TTypeKind of
    tkInteger: (
        MinValue : LongInt;
        MaxValue : LongInt;
case TTypeKind
    of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList : ShortString
    ;
);
);, tkChar: (
    MinValue : LongInt;
    MaxValue : LongInt;
case
    TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList
    : ShortString;
);
);, tkEnumeration: (
    MinValue : LongInt;
    MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo
    ;
    NameList : ShortString;
);
);, tkBool: (
    MinValue : LongInt
    ;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType
    : PTypeInfo;
    NameList : ShortString;
);
);, tkWChar: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of

```

```

tkEnumeration
  : (
    BaseType : PTypeInfo;
    NameList : ShortString;
  );
);
tkSet
  : (
    CompType : PTypeInfo;
  );
);, tkBool: (
  OrdType : TOrdType
  ;
case TTypeKind of
tkInteger: (
  MinValue : LongInt;
  MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseType : PTypeInfo
  ;
  NameList : ShortString;
);
);, tkChar: (
  MinValue : LongInt
  ;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
  BaseType
    : PTypeInfo;
  NameList : ShortString;
);
);, tkEnumeration: (
  MinValue : LongInt;
  MaxValue : LongInt;
case TTypeKind of
tkEnumeration
  : (
    BaseType : PTypeInfo;
    NameList : ShortString;
  );
);, tkBool
  : (
    MinValue : LongInt;
    MaxValue : LongInt;
case TTypeKind of
  tkEnumeration: (
    BaseType : PTypeInfo;
    NameList : ShortString
    ;
  );
);, tkWChar: (

```

```

    MinValue : LongInt;
    MaxValue : LongInt;
case
    TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList
    : ShortString;
);
);
tkSet: (
    CompType : PTypeInfo;
);
);, tkWChar
    : (
        OrdType : TOrdType;
case TTypeKind of
tkInteger: (
    MinValue
    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseType : PTypeInfo;
        NameList : ShortString;
);
);, tkChar
    : (
        MinValue : LongInt;
        MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
        BaseType : PTypeInfo;
        NameList : ShortString
        ;
);
);, tkEnumeration: (
    MinValue : LongInt;
    MaxValue : LongInt
    ;
case TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList
    : ShortString;
);
);, tkBool: (
    MinValue : LongInt;
    MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo

```

```

    ;
    NameList : ShortString;
);
);, tkWChar: (
    MinValue : LongInt
    ;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType
    : PTypeInfo;
    NameList : ShortString;
);
);
tkSet: (
    CompType
    : PTypeInfo;
);
);, tkSet: (
    OrdType : TOrdType;
case TTypeKind
of
tkInteger: (
    MinValue : LongInt;
    MaxValue : LongInt;
case
    TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo;
    NameList
    : ShortString;
);
);, tkChar: (
    MinValue : LongInt;
    MaxValue
    : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType : PTypeInfo
    ;
    NameList : ShortString;
);
);, tkEnumeration: (
    MinValue : LongInt
    ;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration: (
    BaseType
    : PTypeInfo;
    NameList : ShortString;
);
);, tkBool: (
    MinValue

```

```

    : LongInt;
    MaxValue : LongInt;
case TTypeKind of
tkEnumeration
    : (
        BaseType : PTypeInfo;
        NameList : ShortString;
    );
);, tkWChar
    : (
        MinValue : LongInt;
        MaxValue : LongInt;
case TTypeKind of
    tkEnumeration: (
        BaseType : PTypeInfo;
        NameList : ShortString
    );
);
tkSet: (
    CompType : PTypeInfo;
);
);
tkFloat: (
    FloatType
    : TFloatType;
);
tkSSString: (
    MaxLength : Byte;
);
tkClass: (
    ClassType : TClass;
    ParentInfo : PTypeInfo;
    PropCount : SmallInt
    ;
    UnitName : ShortString;
);
tkRecord: (
    RecSize : Integer;
    ManagedFldCount : Integer;
);
tkHelper: (
    HelperParent : PTypeInfo
    ;
    ExtendedInfo : PTypeInfo;
    HelperProps : SmallInt;
    HelperUnit
    : ShortString;
);
tkMethod: (
    MethodKind : TMethodKind;
    ParamCount
    : Byte;
    ParamList : Array[0..1023] of Char;

```

```

);
tkProcVar: (
  ProcSig
    : TProcedureSignature;
);
tkInt64: (
  MinInt64Value : Int64;
  MaxInt64Value
    : Int64;
);
tkQWord: (
  MinQWordValue : QWord;
  MaxQWordValue
    : QWord;
);
tkInterface: (
  IntfParent : PTypeInfo;
  IntfFlags
    : TIntfFlagsBase;
  GUID : TGuid;
  IntfUnit : ShortString;
);
tkInterfaceRaw
  : (
    RawIntfParent : PTypeInfo;
    RawIntfFlags : TIntfFlagsBase;
    IID : TGuid;
    RawIntfUnit : ShortString;
    IIDStr : ShortString
  );
);
tkArray: (
  ArrayData : TArrayTypeData;
);
tkDynArray: (
  elSize
    : PtrUInt;
  elType2 : PTypeInfo;
  varType : LongInt;
  elType
    : PTypeInfo;
  DynUnitName : ShortStringBase;
);
tkClassRef: (
  InstanceType
    : PTypeInfo;
);
tkPointer: (
  RefType : PTypeInfo;
);
end

```

If the `typinfo` kind is `tkClass`, then the property information follows the `UnitName` string, as an array of `TPropInfo` (1767) records.


```
TTypeInfo = record
  Kind : TTypeKind;
  Name : ShortString;
end
```

The `TypeInfo` function returns a pointer to a `TTypeInfo` record.

Note that the `Name` field is stored with as much bytes as needed to store the name, it is not padded to 255 characters. The type data immediately follows the `TTypeInfo` record as a `TTypeData` ([1775](#)) record.

```
TTypeKind = (tkUnknown, tkInteger, tkChar, tkEnumeration, tkFloat, tkSet
,
            tkMethod, tkSString, tkLString, tkAString, tkWString, tkVariant
,
            tkArray, tkRecord, tkInterface, tkClass, tkObject, tkWChar
,
            tkBool, tkInt64, tkQWord, tkDynArray, tkInterfaceRaw, tkProcVar
,
            tkUString, tkUChar, tkHelper, tkFile, tkClassRef, tkPointer
)
```

Table 78.11: Enumeration values for type TTypeKind

Value	Explanation
tkArray	Array property.
tkAString	Ansistring property.
tkBool	Boolean property.
tkChar	Char property.
tkClass	Class property.
tkClassRef	Class of type
tkDynArray	Dynamical array property.
tkEnumeration	Enumeration type property.
tkFile	File type (both text and binary)
tkFloat	Float property.
tkHelper	Helper class type.
tkInt64	Int64 property.
tkInteger	Integer property.
tkInterface	Interface property.
tkInterfaceRaw	Raw interface property.
tkLString	Longstring property.
tkMethod	Method property.
tkObject	Object property.
tkPointer	Pointer type
tkProcVar	Procedural variable
tkQWord	QWord property.
tkRecord	Record property.
tkSet	Set property.
tkSString	Shortstring property.
tkUChar	Unicode character
tkUnknown	Unknown property type.
tkUString	Unicode string
tkVariant	Variant property.
tkWChar	Widechar property.
tkWString	Widestring property.

Type of a property.

TTypeKinds = Set of TTypeKind

Set of TTypeKind (1776) enumeration.

```
TVmtFieldEntry = packed record
  FieldOffset : PtrUInt;
  TypeIndex
    : Word;
  Name : ShortString;
end
```

TVmtFieldEntry records are generated by the compiler for all fields of a record or class that have RTTI associated with them. They describe the field as known to the compiler.

```
TVmtFieldTable = packed record
```

```

    Count : Word;
    ClassTab : Pointer
  ;
  Fields : Array[0..0] of TVmtFieldEntry;
end

```

TVmtFieldTable describes the fields for which RTTI was generated. A TVmtFieldTable entry is generated by the compiler in the RTI information, it is not something one creates manually. Basically it contains a list of TVmtFieldEntry (1777) values.

78.7 Procedures and functions

78.7.1 FindPropInfo

Synopsis: Return property information by property name.

Declaration:

```

function FindPropInfo(Instance: TObject; const PropName: string)
    : PPropInfo
function FindPropInfo(Instance: TObject; const PropName: string;
    AKinds: TTypeKinds) : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string)
    : PPropInfo
function FindPropInfo(AClass: TClass; const PropName: string;
    AKinds: TTypeKinds) : PPropInfo

```

Visibility: default

Description: FindPropInfo examines the published property information of a class and returns a pointer to the property information for property PropName. The class to be examined can be specified in one of two ways:

AClass a class pointer.

Instance an instance of the class to be investigated.

If the property does not exist, a EPropertyError exception will be raised. The GetPropInfo (1788) function has the same function as the FindPropInfo function, but returns Nil if the property does not exist.

Errors: Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetPropInfo (1788), GetPropList (1789), GetPropInfos (1788)

Listing: ./typinfex/ex14.pp

Program example13;

```
{ This program demonstrates the FindPropInfo function }
```

```
{ $mode objfpc }
```

uses

```
  rttiobj , typinfo , sysutils ;
```

Var

```
  O : TMyTestObject;
```

```

PT : PTypeData;
PI : PPropInfo;
I,J : Longint;
PP : PPropList;
prl : PPropInfo;

begin
  O:=TMyTestObject.Create;
  PI:=FindPropInfo(O, 'BooleanField');
  WriteLn('FindPropInfo(Instance, BooleanField) : ',PI^.Name);
  PI:=FindPropInfo(O.ClassType, 'ByteField');
  WriteLn('FindPropInfo(Class, ByteField) : ',PI^.Name);
  Write ('FindPropInfo(Class, NonExistingProp) : ');
  Try
    PI:=FindPropInfo(O, 'NonExistingProp');
  except
    On E: Exception do
      WriteLn('Caught exception "',E.ClassName,'" with message : ',E.Message);
    end;
  O.Free;
end.

```

78.7.2 GetEnumName

Synopsis: Return name of enumeration constant.

Declaration: `function GetEnumName(TypeInfo: PTypeInfo; Value: Integer) : string`

Visibility: default

Description: `GetEnumName` scans the type information for the enumeration type described by `TypeInfo` and returns the name of the enumeration constant for the element with ordinal value equal to `Value`.

If `Value` is out of range, the first element of the enumeration type is returned. The result is returned in the case that was used in the declaration. (In earlier versions of FPC, the name was lowercased).

This can be used in combination with `GetOrdProp` to stream a property of an enumerated type.

Errors: No check is done to determine whether `TypeInfo` really points to the type information for an enumerated type.

See also: `GetOrdProp` ([1787](#)), `GetEnumValue` ([1781](#))

Listing: `./typinfex/ex9.pp`

```

program example9;

{ This program demonstrates the GetEnumName, GetEnumValue functions }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  TI : PTypeInfo;

begin
  O:=TMyTestObject.Create;

```

```

TI := GetPropInfo (O, 'MyEnumField') ^ . PropType;
WriteIn ( 'GetEnumName           : ', GetEnumName (TI, Ord (O.MyEnumField)));
WriteIn ( 'GetEnumValue ( mefirst ) : ', GetEnumName (TI, GetEnumValue (TI, 'mefirst')));
O. Free;
end.

```

78.7.3 GetEnumeratorNameCount

Synopsis: Return number of names in an enumerated type

Declaration: `function GetEnumeratorNameCount(enum1: PTypeInfo) : SizeInt`

Visibility: default

Description: `GetEnumNameCount` returns the number of values (names) in the enumerated type, described by `enum1`

Errors: No checking is done to see whether `Enum1` is really type information of an enumerated type.

See also: [GetEnumValue \(1781\)](#), [GetEnumName \(1779\)](#)

78.7.4 GetEnumeratorProp

Synopsis: Return the value of an enumeration type property.

```
Declaration: function GetEnumerator(Instance: TObject; const PropName: string) : string
              function GetEnumerator(Instance: TObject; const PropInfo: PPropInfo)
                  : string
```

Visibility: default

Description: `GetEnumProp` returns the value of an property of an enumerated type and returns the name of the enumerated value for the object `Instance`. The property whose value must be returned can be specified by its property info in `PropInfo` or by its name in `PropName`

Errors: No check is done to determine whether `PropInfo` really points to the property information for an enumerated type. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [SetEnumProp \(1798\)](#), [GetOrdProp \(1787\)](#), [GetStrProp \(1792\)](#), [GetInt64Prop \(1782\)](#), [GetMethodProp \(1783\)](#), [GetSetProp \(1791\)](#), [GetObjectProp \(1785\)](#), [GetEnumProp \(1780\)](#)

Listing: ./typinfex/ex2.pp

```
program example2;
```

```
{ This program demonstrates the GetEnumerator function }
```

```
{ $mode objfpc }
```

```
uses rttiobj,typinfo;
```

Var

```
O : TMyTestObject:
```

PI : PPropInfo;

```
TI : PTypeInfo;
```

```

begin
  O:= TMyTestObject.Create;
  PI:= GetPropInfo(O, 'MyEnumField');
  TI:= PI^.PropType;
  Writeln('Enum property      : ');
  Writeln('Value              : ', GetEnumName(TI, Ord(O.MyEnumField)));
  Writeln('Get (name)              : ', GetEnumProp(O, 'MyEnumField'));
  Writeln('Get (propinfo)          : ', GetEnumProp(O, PI));
  SetEnumProp(O, 'MyEnumField', 'meFirst');
  Writeln('Set (name, meFirst)     : ', GetEnumName(TI, Ord(O.MyEnumField)));
  SetEnumProp(O, PI, 'meSecond');
  Writeln('Set (propinfo, meSecond) : ', GetEnumName(TI, Ord(O.MyEnumField)));
  O.Free;
end.

```

78.7.5 GetEnumValue

Synopsis: Get ordinal value for enumerated type by name

Declaration: `function GetEnumValue(TypeInfo: PTypeInfo; const Name: string) : Integer`

Visibility: default

Description: `GetEnumValue` scans the type information for the enumeration type described by `TypeInfo` and returns the ordinal value for the element in the enumerated type that has identifier `Name`. The identifier is searched in a case-insensitive manner.

This can be used to set the value of enumerated properties from a stream.

For an example, see `GetEnumName` (1779).

Errors: If `Name` is not found in the list of enumerated values, then -1 is returned. No check is done whether `TypeInfo` points to the type information for an enumerated type.

See also: `GetEnumName` (1779), `SetOrdProp` (1801)

78.7.6 GetFloatProp

Synopsis: Return value of floating point property

Declaration: `function GetFloatProp(Instance: TObject; PropInfo: PPropInfo) : Extended`
`function GetFloatProp(Instance: TObject; const PropName: string)`
`: Extended`

Visibility: default

Description: `GetFloatProp` returns the value of the float property described by `PropInfo` or with name `Propname` for the object `Instance`. All float types are converted to extended.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid float property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetFloatProp` (1798), `GetOrdProp` (1787), `GetStrProp` (1792), `GetInt64Prop` (1782), `GetMethodProp` (1783), `GetSetProp` (1791), `GetObjectProp` (1785), `GetEnumProp` (1780)

Listing: `./typinfex/ex4.pp`

```

program example4;

{ This program demonstrates the GetFloatProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Real property : ');
  PI:=GetPropInfo(O, 'RealField');
  Writeln('Value           : ', O.RealField);
  Writeln('Get (name)       : ', GetFloatProp(O, 'RealField'));
  Writeln('Get (propinfo)      : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'RealField', system.Pi);
  Writeln('Set (name, pi)      : ', O.RealField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)   : ', O.RealField);
  Writeln('Extended property : ');
  PI:=GetPropInfo(O, 'ExtendedField');
  Writeln('Value           : ', O.ExtendedField);
  Writeln('Get (name)       : ', GetFloatProp(O, 'ExtendedField'));
  Writeln('Get (propinfo)    : ', GetFloatProp(O, PI));
  SetFloatProp(O, 'ExtendedField', system.Pi);
  Writeln('Set (name, pi)     : ', O.ExtendedField);
  SetFloatProp(O, PI, exp(1));
  Writeln('Set (propinfo, e)  : ', O.ExtendedField);
  O.Free;
end.

```

78.7.7 GetInt64Prop

Synopsis: return value of an Int64 property

Declaration: `function GetInt64Prop(Instance: TObject; PropInfo: PPropInfo) : Int64`
`function GetInt64Prop(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Description: Publishing of Int64 properties is not yet supported by Free Pascal. This function is provided for Delphi compatibility only at the moment.

`GetInt64Prop` returns the value of the property of type `Int64` that is described by `PropInfo` or with name `Propname` for the object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid `Int64` property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception

See also: [SetInt64Prop \(1799\)](#), [GetOrdProp \(1787\)](#), [GetStrProp \(1792\)](#), [GetFloatProp \(1781\)](#), [GetMethodProp \(1783\)](#), [GetSetProp \(1791\)](#), [GetObjectProp \(1785\)](#), [GetEnumProp \(1780\)](#)

Listing: ./typinfex/ex15.pp

```

program example15;

{ This program demonstrates the GetInt64Prop function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Int64 property : ');
  PI:=GetPropInfo(O, 'Int64Field');
  Writeln('Value           : ', O.Int64Field);
  Writeln('Get (name)       : ', GetInt64Prop(O, 'Int64Field'));
  Writeln('Get (propinfo)   : ', GetInt64Prop(O, PI));
  SetInt64Prop(O, 'Int64Field', 12345);
  Writeln('Set (name,12345) : ', O.Int64Field);
  SetInt64Prop(O, PI, 54321);
  Writeln('Set (propinfo,54321) : ', O.Int64Field);
  O.Free;
end.

```

78.7.8 GetInterfaceProp

Synopsis: Return interface-typed property

Declaration: `function GetInterfaceProp(Instance: TObject; const PropName: string) : IInterface`
`function GetInterfaceProp(Instance: TObject; PropInfo: PPropInfo) : IInterface`

Visibility: default

Description: `GetInterfaceProp` returns the interface which the property described by `PropInfo` or with name `Propname` points to for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetInterfaceProp` (1799), `GetOrdProp` (1787), `GetStrProp` (1792), `GetFloatProp` (1781), `GetInt64Prop` (1782), `GetSetProp` (1791), `GetObjectProp` (1785), `GetEnumProp` (1780)

78.7.9 GetMethodProp

Synopsis: Return value of a method property

Declaration: `function GetMethodProp(Instance: TObject; PropInfo: PPropInfo) : TMethod`
`function GetMethodProp(Instance: TObject; const PropName: string) : TMethod`

Visibility: default

Description: `GetMethodProp` returns the method the property described by `PropInfo` or with name `Propname` for object `Instance`. The return type `TMethod` is defined in the `SysUtils` unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

`Data` points to the instance of the class with the method `Code`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1800), `GetOrdProp` (1787), `GetStrProp` (1792), `GetFloatProp` (1781), `GetInt64Prop` (1782), `GetSetProp` (1791), `GetObjectProp` (1785), `GetEnumProp` (1780)

Listing: `./typinfex/ex6.pp`

```
program example6;

{ This program demonstrates the GetMethodProp function }

{$mode objfpc}

uses rttiobj, typinfo, sysutils;

Type
  TNotifyObject = Class(TObject)
    Procedure Notification1(Sender : TObject);
    Procedure Notification2(Sender : TObject);
  end;

Procedure TNotifyObject.Notification1(Sender : TObject);

begin
  Write('Received notification 1 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Procedure TNotifyObject.Notification2(Sender : TObject);

begin
  Write('Received notification 2 of object with class: ');
  WriteLn(Sender.ClassName);
end;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  NO : TNotifyObject;
  M : TMethod;

Procedure PrintMethod (Const M : TMethod);

begin
  If (M.Data=Pointer(NO)) Then
```

```

    If (M.Code=Pointer(@TNotifyObject.Notification1)) then
        Writeln('Notification1')
    else If (M.Code=Pointer(@TNotifyObject.Notification2)) then
        Writeln('Notification2')
    else
        begin
            Write('Unknown method address (data:');
            Write(hexStr(Longint(M.data),8));
            Writeln(',code:',hexstr(Longint(M.Code),8),')');
        end;
end;

begin
    O:=TMyTestObject.Create;
    NO:=TNotifyObject.Create;
    O.NotifyEvent:=@NO.Notification1;
    PI:=GetPropertyInfo(O,'NotifyEvent');
    Writeln('Method property : ');
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (name)                               : ');
    M:=GetMethodProp(O,'NotifyEvent');
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Get (propinfo)                             : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    M:=TMethod(@NO.Notification2);
    SetMethodProp(O,'NotifyEvent',M);
    Write('Set (name,Notification2)                   : ');
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    Write('Set (propinfo,Notification1) : ');
    M:=TMethod(@NO.Notification1);
    SetMethodProp(O,PI,M);
    M:=GetMethodProp(O,PI);
    PrintMethod(M);
    Write('Notifying                               : ');
    O.Notify;
    O.Free;
end.

```

78.7.10 TObjectProp

Synopsis: Return value of an object-type property.

```

Declaration: function TObjectProp(Instance: TObject; const PropName: string)
                : TObject
function TObjectProp(Instance: TObject; const PropName: string;
                    MinClass: TClass) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo) : TObject
function TObjectProp(Instance: TObject; PropInfo: PPropInfo;
                    MinClass: TClass) : TObject

```

Visibility: default

Description: `GetObjectProp` returns the object which the property described by `PropInfo` with name `Propname` points to for object `Instance`.

If `MinClass` is specified, then if the object is not descendent of class `MinClass`, then `Nil` is returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid method property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1800), `GetOrdProp` (1787), `GetStrProp` (1792), `GetFloatProp` (1781), `GetInt64Prop` (1782), `GetSetProp` (1791), `GetObjectProp` (1785), `GetEnumProp` (1780)

Listing: `./typinfex/ex5.pp`

program example5;

{ This program demonstrates the GetObjectProp function }

{ \$mode objfpc }

uses rttiobj , typinfo ;

Var

O : TMyTestObject;

PI : PPropInfo;

NO1, NO2 : TNamedObject;

begin

O := TMyTestObject.Create;

NO1 := TNamedObject.Create;

NO1.ObjectName := 'First named object';

NO2 := TNamedObject.Create;

NO2.ObjectName := 'Second named object';

O.ObjField := NO1;

WriteLn('Object property : ');

PI := GetPropInfo(O, 'ObjField');

Write('Property class : ');

WriteLn(GetObjectPropClass(O, 'ObjField').ClassName);

Write('Value : ');

WriteLn((O.ObjField as TNamedObject).ObjectName);

Write('Get (name) : ');

WriteLn((GetObjectProp(O, 'ObjField') as TNamedObject).ObjectName);

Write('Get (propinfo) : ');

WriteLn((GetObjectProp(O, PI, TObj) as TNamedObject).ObjectName);

SetObjectProp(O, 'ObjField', NO2);

Write('Set (name, NO2) : ');

WriteLn((O.ObjField as TNamedObject).ObjectName);

SetObjectProp(O, PI, NO1);

Write('Set (propinfo, NO1) : ');

WriteLn((O.ObjField as TNamedObject).ObjectName);

O.Free;

end.

78.7.11 GetObjectPropClass

Synopsis: Return class of property.

Declaration: `function GetObjectPropClass(Instance: TObject; const PropName: string)
: TClass
function GetObjectPropClass(AClass: TClass; const PropName: string)
: TClass`

Visibility: default

Description: `GetObjectPropClass` returns the declared class of the property with name `PropName`. This may not be the actual class of the property value.

For an example, see `GetObjectProp` (1785).

Errors: No checking is done whether `Instance` is non-nil. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetMethodProp` (1800), `GetOrdProp` (1787), `GetStrProp` (1792), `GetFloatProp` (1781), `GetInt64Prop` (1782)

78.7.12 GetOrdProp

Synopsis: Get the value of an ordinal property

Declaration: `function GetOrdProp(Instance: TObject; PropInfo: PPropInfo) : Int64
function GetOrdProp(Instance: TObject; const PropName: string) : Int64`

Visibility: default

Description: `GetOrdProp` returns the value of the ordinal property described by `PropInfo` or with name `PropName` for the object `Instance`. The value is returned as a longint, which should be typecasted to the needed type.

Ordinal properties that can be retrieved include:

Integers and subranges of integersThe value of the integer will be returned.

Enumerated types and subranges of enumerated typesThe ordinal value of the enumerated type will be returned.

SetsIf the base type of the set has less than 31 possible values. If a bit is set in the return value, then the corresponding element of the base ordinal class of the set type must be included in the set.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `SetOrdProp` (1801), `GetStrProp` (1792), `GetFloatProp` (1781), `GetInt64Prop` (1782), `GetMethodProp` (1783), `GetSetProp` (1791), `GetObjectProp` (1785), `GetEnumProp` (1780)

Listing: `./typinfex/ex1.pp`

```
program example1;

{ This program demonstrates the GetOrdProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
```

```

PI : PPropInfo;

begin
  O:= TMyTestObject.Create;
  WriteLn( 'Boolean property      : ');
  WriteLn( 'Value                  : ',O.BooleanField);
  WriteLn( 'Ord(Value)              : ',Ord(O.BooleanField));
  WriteLn( 'Get (name)              : ',GetOrdProp(O, 'BooleanField'));
  PI:= GetPropInfo(O, 'BooleanField');
  WriteLn( 'Get (propinfo)          : ',GetOrdProp(O, PI));
  SetOrdProp(O, 'BooleanField',Ord(False));
  WriteLn( 'Set (name,false)        : ',O.BooleanField);
  SetOrdProp(O, PI,Ord(True));
  WriteLn( 'Set (propinfo,true)    : ',O.BooleanField);
  O.Free;
end.

```

78.7.13 GetPropInfo

Synopsis: Return property type information, by property name.

Declaration: `function GetPropInfo(TypeInfo: PTypeInfo; const PropName: string) : PPropInfo`
`function GetPropInfo(TypeInfo: PTypeInfo; const PropName: string; AKinds: TTypeKinds) : PPropInfo`
`function GetPropInfo(Instance: TObject; const PropName: string) : PPropInfo`
`function GetPropInfo(Instance: TObject; const PropName: string; AKinds: TTypeKinds) : PPropInfo`
`function GetPropInfo(AClass: TClass; const PropName: string) : PPropInfo`
`function GetPropInfo(AClass: TClass; const PropName: string; AKinds: TTypeKinds) : PPropInfo`

Visibility: default

Description: `GetPropInfo` returns a pointer to the `TPropInfo` record for the `PropName` property of a class. The class to examine can be specified in one of three ways:

Instance An instance of the class.

AClass A class pointer to the class.

TypeInfo A pointer to the type information of the class.

In each of these three ways, if `AKinds` is specified, if the property has `TypeKind` which is not included in `AKinds`, `Nil` will be returned.

For an example, see most of the other functions.

Errors: If the property `PropName` does not exist, `Nil` is returned.

See also: `GetPropInfos` ([1788](#)), `GetPropList` ([1789](#))

78.7.14 GetPropInfos

Synopsis: Return a list of published properties.

Declaration: `procedure GetPropInfos(TypeInfo: PTypeInfo; PropList: PPropList)`

Visibility: default

Description: `GetPropInfos` stores pointers to the property information of all published properties of a class with class info `TypeInfo` in the list pointed to by `PropList`. The `PropList` pointer must point to a memory location that contains enough space to hold all properties of the class and its parent classes.

Errors: No checks are done to see whether `PropList` points to a memory area that is big enough to hold all pointers.

See also: `GetPropInfo` (1788), `GetPropList` (1789)

Listing: ./typinfex/ex12.pp

Program example12;

{ This program demonstrates the GetPropInfos function }

uses

rttiobj, typinfo;

Var

O : TMyTestObject;

PT : PTypeData;

PI : PTypeInfo;

I, J : Longint;

PP : PPropList;

pri : PPropInfo;

begin

O := TMyTestObject.Create;

PI := O.ClassInfo;

PT := GetTypeData(PI);

WriteLn('Property Count : ', PT^.PropCount);

GetMem(PP, PT^.PropCount * SizeOf(Pointer));

GetPropInfos(PI, PP);

For I := 0 to PT^.PropCount - 1 do

begin

With PP^[I]^ do

begin

Write('Property ', I + 1 : 3, ': ', name : 30);

writeln(' Type: ', TypeName[typinfo.PropType(O, Name)]);

end;

end;

FreeMem(PP);

O.Free;

end.

78.7.15 GetPropList

Synopsis: Return a list of a certain type of published properties.

Declaration: function `GetPropList`(TypeInfo: PTypeInfo; TypeKinds: TTypeKinds;
PropList: PPropList; Sorted: Boolean) : LongInt
function `GetPropList`(TypeInfo: PTypeInfo; out PropList: PPropList)
: SizeInt

```
function GetPropList(AClass: TClass; out PropList: PPropList) : Integer
function GetPropList(Instance: TObject; out PropList: PPropList)
    : Integer
```

Visibility: default

Description: GetPropList stores pointers to property information of the class with class info TypeInfo for properties of kind TypeKinds in the list pointed to by PropList. PropList must contain enough space to hold all properties.

The function returns the number of pointers that matched the criteria and were stored in PropList.

Errors: No checks are done to see whether PropList points to a memory area that is big enough to hold all pointers.

See also: GetPropInfos ([1788](#)), GetPropInfo ([1788](#))

Listing: ./typinfex/ex13.pp

Program example13;

{ This program demonstrates the GetPropList function }

uses

rttiobj, typinfo;

Var

O : TMyTestObject;

PT : PTypeData;

PI : PTypeInfo;

I, J : Longint;

PP : PPropList;

pri : PPropInfo;

begin

O:=TMyTestObject.Create;

PI:=O.ClassInfo;

PT:=GetTypeData(PI);

WriteLn('Total property Count : ', PT^.PropCount);

GetMem(PP, PT^.PropCount*SizeOf(Pointer));

J:=GetPropList(PI, OrdinalTypes, PP);

WriteLn('Ordinal property Count : ', J);

For I:=0 to J-1 do

begin

With PP^[I]^ do

begin

Write('Property ', i+1:3, ': ', name:30);

writeln(' Type: ', TypeName[typinfo.PropType(O, Name)]);

end;

end;

FreeMem(PP);

O.Free;

end.

78.7.16 GetPropValue

Synopsis: Get property value as a string.

Declaration: `function GetPropValue(Instance: TObject; const PropName: string) : Variant`
`function GetPropValue(Instance: TObject; const PropName: string; PreferStrings: Boolean) : Variant`
`function GetPropValue(Instance: TObject; PropInfo: PPropInfo) : Variant`
`function GetPropValue(Instance: TObject; PropInfo: PPropInfo; PreferStrings: Boolean) : Variant`

Visibility: default

Description: Due to missing Variant support, GetPropValue is not yet implemented. The declaration is provided for compatibility with Delphi.

78.7.17 GetRawInterfaceProp

Synopsis: Get a raw (CORBA) interface property.

Declaration: `function GetRawInterfaceProp(Instance: TObject; const PropName: string) : Pointer`
`function GetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo) : Pointer`

Visibility: default

Description: GetRawInterfaceProp can be used to retrieve the value of a published CORBA interface property with name PropName from object Instance. Alternatively, the required property information can be specified by PropInfo instead of the property name. In difference with the GetInterfaceProp (1783) function, no reference counting is done.

Errors: If the property PropName does not exist, an EPropertyError exception is raised.

See also: GetInterfaceProp (1783), SetRawInterfaceProp (1801)

78.7.18 GetSetProp

Synopsis: Return the value of a set property.

Declaration: `function GetSetProp(Instance: TObject; const PropName: string) : string`
`function GetSetProp(Instance: TObject; const PropName: string; Brackets: Boolean) : string`
`function GetSetProp(Instance: TObject; const PropInfo: PPropInfo; Brackets: Boolean) : string`

Visibility: default

Description: GetSetProp returns the contents of a set property as a string. The property to be returned can be specified by its name in PropName or by its property information in PropInfo.

The returned set is a string representation of the elements in the set as returned by SetToString (1803). The Brackets option can be used to enclose the string representation in square brackets.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid ordinal property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetSetProp (1802), GetStrProp (1792), GetFloatProp (1781), GetInt64Prop (1782), GetMethodProp (1783)

Listing: ./typinfex/ex7.pp

```

program example7;

{ This program demonstrates the GetSetProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

Function SetAsString (ASet : TMyEnums) : String;

Var
  i : TmyEnum;

begin
  result := '';
  For i := mefirst to methird do
    If i in ASet then
      begin
        If (Result <> '') then
          Result := Result + ', ';
          Result := Result + MyEnumNames[i];
        end;
      end;
end;

Var
  S : TMyEnums;

begin
  O := TMyTestObject.Create;
  O.SetField := [mefirst, meSecond, meThird];
  Writeln ('Set property      : ');
  Writeln ('Value                               : ', SetAsString(O.SetField));
  Writeln ('Ord(Value)                             : ', Byte(O.SetField));
  Writeln ('Get (name)                               : ', GetSetProp(O, 'SetField'));
  PI := GetPropInfo(O, 'SetField');
  Writeln ('Get (propinfo)                           : ', GetSetProp(O, PI, false));
  S := [meFirst, meThird];
  SetOrdProp(O, 'SetField', Byte(S));
  Write ('Set (name,[mefirst, methird]) : ');
  Writeln (SetAsString(O.SetField));
  S := [meSecond];
  SetOrdProp(O, PI, Byte(S));
  Write ('Set (propinfo,[meSecond])      : ');
  Writeln (SetAsString(O.SetField));
  O.Free;
end.

```

78.7.19 GetStrProp

Synopsis: Return the value of a string property.

Declaration: `function GetStrProp(Instance: TObject; PropInfo: PPropInfo) : Ansistring`

```
function GetStrProp(Instance: TObject; const PropName: string) : string
```

Visibility: default

Description: GetStrProp returns the value of the string property described by PropInfo or with name PropName for object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid string property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: SetStrProp (1802), SetWideStrProp (1804), GetOrdProp (1787), GetFloatProp (1781), GetInt64Prop (1782), GetMethodProp (1783)

Listing: ./typinfex/ex3.pp

```
program example3;

{ This program demonstrates the GetStrProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  PI:=GetPropInfo(O, 'AnsiStringField');
  Writeln('String property : ');
  Writeln('Value           : ',O.AnsiStringField);
  Writeln('Get (name)           : ',GetStrProp(O, 'AnsiStringField'));
  Writeln('Get (propinfo)         : ',GetStrProp(O, PI));
  SetStrProp(O, 'AnsiStringField', 'First');
  Writeln('Set (name, ''First'')    : ',O.AnsiStringField);
  SetStrProp(O, PI, 'Second');
  Writeln('Set (propinfo, ''Second'') : ',O.AnsiStringField);
  O.Free;
end.
```

78.7.20 GetTypeData

Synopsis: Return a pointer to type data, based on type information.

Declaration: function GetTypeData(TypeInfo: PTypeInfo) : PTypeData

Visibility: default

Description: GetTypeData returns a pointer to the TTypeData record that follows after the TTypeInfo record pointed to by TypeInfo. It essentially skips the Kind and Name fields in the TTypeInfo record.

Errors: None.

78.7.24 IsPublishedProp

Synopsis: Check whether a published property exists.

```
Declaration: function IsPublishedProp(Instance: TObject; const PropName: string)
              : Boolean
function IsPublishedProp(AClass: TClass; const PropName: string)
              : Boolean
```

Visibility: default

Description: `IsPublishedProp` returns true if a class has a published property with name `PropName`. The class can be specified in one of two ways:

A**ClassA** class pointer to the class.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: [IsStoredProp \(1795\)](#), [PropIsType \(1796\)](#)

Listing: ./typinfex/ex10.pp

```

program example10;

{ This program demonstrates the IsPublishedProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
    O : TMyTestObject;
    PI : PPropInfo;

begin
    O:=TMyTestObject.Create;
    Writeln ( 'Property tests      : ' );
    Write ( 'IsPublishedProp(O, BooleanField)      : ' );
    Writeln ( IsPublishedProp(O, 'BooleanField') );
    Write ( 'IsPublishedProp(Class, BooleanField) : ' );
    Writeln ( IsPublishedProp(O.ClassType, 'BooleanField') );
    Write ( 'IsPublishedProp(O, SomeField)          : ' );
    Writeln ( IsPublishedProp(O, 'SomeField') );
    Write ( 'IsPublishedProp(Class, SomeField)      : ' );
    Writeln ( IsPublishedProp(O.ClassType, 'SomeField') );
    O.Free;
end.

```

78.7.25 IsStoredProp

Synopsis: Check whether a property is stored.

```
Declaration: function IsStoredProp(Instance: TObject; PropInfo: PPropInfo) : Boolean
            function IsStoredProp(Instance: TObject; const PropName: string)
                                : Boolean
```

Visibility: default

Description: `IsStoredProp` returns `True` if the `Stored` modifier evaluates to `True` for the property described by `PropInfo` or with name `PropName` for object `Instance`. It returns `False` otherwise. If the function returns `True`, this indicates that the property should be written when streaming the object `Instance`.

If there was no `stored` modifier in the declaration of the property, `True` will be returned.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (1795), `PropIsType` (1796)

Listing: `./typinfex/ex11.pp`

```

program example11;

{ This program demonstrates the IsStoredProp function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;

begin
  O:=TMyTestObject.Create;
  Writeln('Stored tests      : ');
  Write('IsStoredProp(O, StoredIntegerConstFalse)    : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstFalse'));
  Write('IsStoredProp(O, StoredIntegerConstTrue)     : ');
  Writeln(IsStoredProp(O, 'StoredIntegerConstTrue'));
  Write('IsStoredProp(O, StoredIntegerMethod)         : ');
  Writeln(IsStoredProp(O, 'StoredIntegerMethod'));
  Write('IsStoredProp(O, StoredIntegerVirtualMethod)  : ');
  Writeln(IsStoredProp(O, 'StoredIntegerVirtualMethod'));
  O.Free;
end.

```

78.7.26 PropIsType

Synopsis: Check the type of a published property.

Declaration:

```

function PropIsType(Instance: TObject; const PropName: string;
                    TypeKind: TTypeKind) : Boolean
function PropIsType(AClass: TClass; const PropName: string;
                    TypeKind: TTypeKind) : Boolean

```

Visibility: default

Description: `PropIsType` returns `True` if the property with name `PropName` has type `TypeKind`. It returns `False` otherwise. The class to be examined can be specified in one of two ways:

AClass A class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (1795), `IsStoredProp` (1795), `PropType` (1797)

Listing: ./typinfex/ex16.pp

```

program example16;

{ This program demonstrates the PropIsType function }

{$mode objfpc}

uses rttiobj , typinfo;

Var
  O : TMyTestObject;

begin
  O := TMyTestObject.Create;
  Writeln( 'Property tests      : ');
  Write( 'PropIsType(O, BooleanField, tkBool)      : ');
  Writeln( PropIsType(O, 'BooleanField', tkBool));
  Write( 'PropIsType(Class, BooleanField, tkBool) : ');
  Writeln( PropIsType(O.ClassType, 'BooleanField', tkBool));
  Write( 'PropIsType(O, ByteField, tkString)      : ');
  Writeln( PropIsType(O, 'ByteField', tkString));
  Write( 'PropIsType(Class, ByteField, tkString)  : ');
  Writeln( PropIsType(O.ClassType, 'ByteField', tkString));
  O.Free;
end.

```

78.7.27 PropType

Synopsis: Return the type of a property

Declaration: `function PropType(Instance: TObject; const PropName: string) : TTypeKind`
`function PropType(AClass: TClass; const PropName: string) : TTypeKind`

Visibility: default

Description: `PropType` returns the type of the property `PropName` for a class. The class to be examined can be specified in one of 2 ways:

AClassA class pointer.

InstanceAn instance of the class.

Errors: No checks are done to ensure `Instance` or `AClass` are valid pointers. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `IsPublishedProp` (1795), `IsStoredProp` (1795), `PropIsType` (1796)

Listing: ./typinfex/ex17.pp

```

program example17;

{ This program demonstrates the PropType function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;

begin
  O:= TMyTestObject.Create;
  WriteLn( 'Property tests      : ');
  Write( 'PropType(O, BooleanField)      : ');
  WriteLn(TypeNames[PropType(O, 'BooleanField')]);
  Write( 'PropType(Class, BooleanField) : ');
  WriteLn(TypeNames[PropType(O.ClassType, 'BooleanField')]);
  Write( 'PropType(O, ByteField)          : ');
  WriteLn(TypeNames[PropType(O, 'ByteField')]);
  Write( 'PropType(Class, ByteField)      : ');
  WriteLn(TypeNames[PropType(O.ClassType, 'ByteField')]);
  O.Free;
end.

```

78.7.28 SetEnumProp

Synopsis: Set value of an enumerated-type property

Declaration: `procedure SetEnumProp(Instance: TObject; const PropName: string;
 const Value: string)
 procedure SetEnumProp(Instance: TObject; const PropInfo: PPropInfo;
 const Value: string)`

Visibility: default

Description: SetEnumProp sets the property described by PropInfo or with name PropName to Value. Value must be a string with the name of the enumerate value, i.e. it can be used as an argument to GetEnumValue (1781).

For an example, see GetEnumProp (1780).

Errors: No checks are done to ensure Instance or PropInfo are valid pointers. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetEnumProp (1780), SetStrProp (1802), SetFloatProp (1798), SetInt64Prop (1799), SetMethodProp (1800)

78.7.29 SetFloatProp

Synopsis: Set value of a float property.

Declaration: `procedure SetFloatProp(Instance: TObject; const PropName: string;
 Value: Extended)
 procedure SetFloatProp(Instance: TObject; PropInfo: PPropInfo;
 Value: Extended)`

Visibility: default

Description: SetFloatProp assigns Value to the property described by PropInfo or with name Propname for the object Instance.

For an example, see GetFloatProp (1781).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid float property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetFloatProp (1781), SetOrdProp (1801), SetStrProp (1802), SetInt64Prop (1799), SetMethodProp (1800)

78.7.30 SetInt64Prop

Synopsis: Set value of a Int64 property

Declaration:

```
procedure SetInt64Prop(Instance: TObject; PropInfo: PPropInfo;
                      const Value: Int64)
procedure SetInt64Prop(Instance: TObject; const PropName: string;
                      const Value: Int64)
```

Visibility: default

Description: SetInt64Prop assigns Value to the property of type Int64 that is described by PropInfo or with name Propname for the object Instance.

For an example, see GetInt64Prop (1782).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid Int64 property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetInt64Prop (1782), GetMethodProp (1783), SetOrdProp (1801), SetStrProp (1802), SetFloatProp (1798)

78.7.31 SetInterfaceProp

Synopsis: Set interface-valued property

Declaration:

```
procedure SetInterfaceProp(Instance: TObject; const PropName: string;
                          const Value: IInterface)
procedure SetInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
                          const Value: IInterface)
```

Visibility: default

Description: SetInterfaceProp assigns Value to the object property described by PropInfo or with name Propname for the object Instance.

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid interface property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetInterfaceProp (1783), SetObjectProp (1800), SetOrdProp (1801), SetStrProp (1802), SetFloatProp (1798), SetInt64Prop (1799), SetMethodProp (1800)

78.7.32 SetMethodProp

Synopsis: Set the value of a method property

Declaration:

```
procedure SetMethodProp(Instance: TObject; PropInfo: PPropInfo;
                        const Value: TMethod)
procedure SetMethodProp(Instance: TObject; const PropName: string;
                        const Value: TMethod)
```

Visibility: default

Description: SetMethodProp assigns Value to the method the property described by PropInfo or with name Propname for object Instance.

The type TMethod of the Value parameter is defined in the SysUtils unit as:

```
TMethod = packed record
  Code, Data: Pointer;
end;
```

Data should point to the instance of the class with the method Code.

For an example, see GetMethodProp (1783).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid method property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetMethodProp (1783), SetOrdProp (1801), SetStrProp (1802), SetFloatProp (1798), SetInt64Prop (1799)

78.7.33 SetObjectProp

Synopsis: Set the value of an object-type property.

Declaration:

```
procedure SetObjectProp(Instance: TObject; const PropName: string;
                        Value: TObject)
procedure SetObjectProp(Instance: TObject; PropInfo: PPropInfo;
                        Value: TObject)
```

Visibility: default

Description: SetObjectProp assigns Value to the object property described by PropInfo or with name Propname for the object Instance.

For an example, see GetObjectProp (1785).

Errors: No checking is done whether Instance is non-nil, or whether PropInfo describes a valid object property of Instance. Specifying an invalid property name in PropName will result in an EPropertyError exception.

See also: GetObjectProp (1785), SetOrdProp (1801), SetStrProp (1802), SetFloatProp (1798), SetInt64Prop (1799), SetMethodProp (1800)

78.7.34 SetOrdProp

Synopsis: Set value of an ordinal property

Declaration: `procedure SetOrdProp(Instance: TObject; PropInfo: PPropInfo;
Value: Int64)
procedure SetOrdProp(Instance: TObject; const PropName: string;
Value: Int64)`

Visibility: default

Description: `SetOrdProp` assigns `Value` to the ordinal property described by `PropInfo` or with name `Propname` for the object `Instance`.

Ordinal properties that can be set include:

Integers and subranges of integers The actual value of the integer must be passed.

Enumerated types and subranges of enumerated types The ordinal value of the enumerated type must be passed.

Subrange types of integers or enumerated types. Here the ordinal value must be passed.

Sets If the base type of the set has less than 31 possible values. For each possible value; the corresponding bit of `Value` must be set.

For an example, see `GetOrdProp` ([1787](#)).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetOrdProp` ([1787](#)), `SetStrProp` ([1802](#)), `SetFloatProp` ([1798](#)), `SetInt64Prop` ([1799](#)), `SetMethodProp` ([1800](#))

78.7.35 SetPropValue

Synopsis: Set property value as variant

Declaration: `procedure SetPropValue(Instance: TObject; const PropName: string;
const Value: Variant)
procedure SetPropValue(Instance: TObject; PropInfo: PPropInfo;
const Value: Variant)`

Visibility: default

Description: Due to missing `Variant` support, this function is not yet implemented; it is provided for Delphi compatibility only.

78.7.36 SetRawInterfaceProp

Synopsis: Set a raw (CORBA) interface property.

Declaration: `procedure SetRawInterfaceProp(Instance: TObject;
const PropName: string;
const Value: Pointer)
procedure SetRawInterfaceProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Pointer)`

Visibility: default

Description: `SetRawInterfaceProp` can be used to set the value of a published CORBA interface with name `PropName` from object `Instance` to `Value`. Alternatively, the required property information can be specified by `PropInfo` instead of the property name. In difference with the `SetInterfaceProp` (1799) procedure, no reference counting is done.

Errors: If the property `PropName` does not exist, an `EPropertyError` exception is raised.

See also: `SetInterfaceProp` (1799), `GetRawInterfaceProp` (1791)

78.7.37 SetSetProp

Synopsis: Set value of set-typed property.

Declaration:

```
procedure SetSetProp(Instance: TObject; const PropName: string;
                    const Value: string)
procedure SetSetProp(Instance: TObject; const PropInfo: PPropInfo;
                    const Value: string)
```

Visibility: default

Description: `SetSetProp` sets the property specified by `PropInfo` or `PropName` for object `Instance` to `Value`. `Value` is a string which contains a comma-separated list of values, each value being a string-representation of the enumerated value that should be included in the set. The value should be accepted by the `StringToSet` (1805) function.

The value can be formed using the `SetToString` (1803) function.

For an example, see `GetSetProp` (1791).

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid ordinal property of `Instance`. No range checking is performed. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetSetProp` (1791), `SetOrdProp` (1801), `SetStrProp` (1802), `SetFloatProp` (1798), `SetInt64Prop` (1799), `SetMethodProp` (1800), `SetToString` (1803), `StringToSet` (1805)

78.7.38 SetStrProp

Synopsis: Set value of a string property

Declaration:

```
procedure SetStrProp(Instance: TObject; const PropName: string;
                    const Value: AnsiString)
procedure SetStrProp(Instance: TObject; PropInfo: PPropInfo;
                    const Value: AnsiString)
```

Visibility: default

Description: `SetStrProp` assigns `Value` to the string property described by `PropInfo` or with name `Propname` for object `Instance`.

For an example, see `GetStrProp` (1792)

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid string property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetStrProp` (1792), `SetWideStrProp` (1804), `SetOrdProp` (1801), `SetFloatProp` (1798), `SetInt64Prop` (1799), `SetMethodProp` (1800)

78.7.39 SetToString

Synopsis: Convert set to a string description

```

Declaration: function SetToString(TypeInfo: PTypeInfo; Value: Integer;
                               Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: Integer;
                    Brackets: Boolean) : string
function SetToString(PropInfo: PPropInfo; Value: Integer) : string

```

Visibility: default

Description: SetToString takes an integer representation of a set (as received e.g. by GetOrdProp) and turns it into a string representing the elements in the set, based on the type information found in the PropInfo property information. By default, the string representation is not surrounded by square brackets. Setting the Brackets parameter to True will surround the string representation with brackets.

The function returns the string representation of the set.

Errors: No checking is done to see whether PropInfo points to valid property information.

See also: GetEnumName ([1779](#)), GetEnumValue ([1781](#)), StringToSet ([1805](#))

Listing: ./typinfex/ex18.pp

```

program example18;

{ This program demonstrates the SetToString function }

{$mode objfpc}

uses rttiobj, typinfo;

Var
  O : TMyTestObject;
  PI : PPropInfo;
  I : longint;

begin
  O:=TMyTestObject.Create;
  PI:=GetPropInfo(O, 'SetField');
  O.SetField :=[ mefirst, meSecond, meThird ];
  I:=GetOrdProp(O, PI);
  Writeln('Set property to string : ');
  Writeln('Value  : ', SetToString(PI, I, False));
  O.SetField :=[ mefirst, meSecond ];
  I:=GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, True));
  I:=StringToSet(PI, 'mefirst');
  SetOrdProp(O, PI, I);
  I:=GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, False));
  I:=StringToSet(PI, '[mesecond, methird]');
  SetOrdProp(O, PI, I);
  I:=GetOrdProp(O, PI);
  Writeln('Value  : ', SetToString(PI, I, True));
  O.Free;
end.

```

78.7.40 SetUnicodeStrProp

Synopsis: Set UnicodeString-valued property

Declaration: `procedure SetUnicodeStrProp(Instance: TObject; const PropName: string;
const Value: UnicodeString)
procedure SetUnicodeStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: UnicodeString)`

Visibility: default

Description: `SetUnicodeStrProp` sets the `UnicodeString` property from `Instance` to `Value`, where the property is identified by the `PropInfo` pointer or the `PropertyName`.

Errors: If no property of the indicated name exists, or it is not of type `unicodestring`, an exception will occur.

See also: `SetStrProp` ([1802](#)), `GetUnicodeStrProp` ([1794](#))

78.7.41 SetVariantProp

Synopsis: Set value of a variant property

Declaration: `procedure SetVariantProp(Instance: TObject; const PropName: string;
const Value: Variant)
procedure SetVariantProp(Instance: TObject; PropInfo: PPropInfo;
const Value: Variant)`

Visibility: default

Description: Due to missing `Variant` support, this function is not yet implemented. Provided for Delphi compatibility only.

78.7.42 SetWideStrProp

Synopsis: Set a widestring property

Declaration: `procedure SetWideStrProp(Instance: TObject; const PropName: string;
const Value: WideString)
procedure SetWideStrProp(Instance: TObject; PropInfo: PPropInfo;
const Value: WideString)`

Visibility: default

Description: `SetWideStrProp` assigns `Value` to the widestring property described by `PropInfo` or with name `Propname` for object `Instance`.

Errors: No checking is done whether `Instance` is non-nil, or whether `PropInfo` describes a valid widestring property of `Instance`. Specifying an invalid property name in `PropName` will result in an `EPropertyError` exception.

See also: `GetWideStrProp` ([1794](#)), `SetStrProp` ([1802](#)), `SetOrdProp` ([1801](#)), `SetFloatProp` ([1798](#)), `SetInt64Prop` ([1799](#)), `SetMethodProp` ([1800](#))

78.7.43 StringToSet

Synopsis: Convert string description to a set.

Declaration: `function StringToSet (PropInfo: PPropInfo; const Value: string) : Integer`
`function StringToSet (TypeInfo: PTypeInfo; const Value: string) : Integer`

Visibility: default

Description: `StringToSet` converts the string representation of a set in `Value` to a integer representation of the set, using the property information found in `PropInfo`. This property information should point to the property information of a set property. The function returns the integer representation of the set. (i.e, the set value, typecast to an integer)

The string representation can be surrounded with square brackets, and must consist of the names of the elements of the base type of the set. The base type of the set should be an enumerated type. The elements should be separated by commas, and may be surrounded by spaces. each of the names will be fed to the `GetEnumValue` (1781) function.

For an example, see `SetToString` (1803).

Errors: No checking is done to see whether `PropInfo` points to valid property information. If a wrong name is given for an enumerated value, then an `EPropertyError` will be raised.

See also: `GetEnumName` (1779), `GetEnumValue` (1781), `SetToString` (1803)

78.8 TProcedureSignature

```
TProcedureSignature = packed record
  Flags : Byte;
  CC : TCallConv
;
  ResultType : PTypeInfo;
  ParamCount : Byte;
  function GetParam
    (ParamIndex: Integer) : PProcedureParam;
end
```

`TProcedureSignature` describes a procedure/method call signature. It consists of some flags (`Flags`), a calling convention (`CC`), the result type (`ResultType`) if any, and a list of `ParamCount` parameters (of type `TProcedureParam` (1766)).

78.8.1 Method overview

Page	Method	Description
1805	<code>GetParam</code>	Get parameter signature

78.8.2 TProcedureSignature.GetParam

Synopsis: Get parameter signature

Declaration: `function GetParam (ParamIndex: Integer) : PProcedureParam`

Visibility: default

Description: `GetParam` can be used to retrieve a pointer to the description of a parameter. The index `ParamIndex` is zero-based.

Errors: In case of an invalid parameter index, `Nil` is returned.

See also: `TProcedureParam` ([1766](#))

78.9 EPropertyConvertError

78.9.1 Description

`EPropertyConvertError` is not used in the Free Pascal implementation of the `typinfo` unit, but is declared for Delphi compatibility.

78.10 EPropertyError

78.10.1 Description

Exception raised in case of an error in one of the functions.

Chapter 79

Reference for unit 'unicodedata'

79.1 Used units

Table 79.1: Used units by unit 'unicodedata'

Name	Page
System	1194

79.2 Overview

The `fpwiderstring` ([1807](#)) unit relies on having relevant unicode collation data linked in the binary. The unicode data is managed using the routines in the `unicodedata` unit. The FPC project distributes some unicode collation data in `.bco` files which can be loaded using the `LoadCollation` ([1816](#)) routines. The `LoadCollation` is the main routine of this unit.

All collation data requires at least the Default Unicode Collation Element Table to be registered (called `DUCET`). The `DUCET` encoding is provided by the `unicodeducet` unit, part of the `rtl-unicode` package.

There are two ways to register collations :

1. **at compile time**: by including the desired collation unit, for example for Russian and Japanese languages to be available you will have to include `collation_ru` and `collation_ja` from package "rtl-unicode".
2. **at runtime** using the abovementioned `LoadCollation` function.

The two ways can co-exist: some collations may be compile time included (for example for most used collations) and others can be loaded at runtime in the same application.

The binary collation files are endian sensitive:

- there are files for little endian systems named `collation__le.bco` (such as `collation_ru_le.bco` and `collation_ja_le.bco`)
- there are files for big endian systems named `collation__be.bco` (such as `collation_ru_be.bco` and `collation_ja_be.bco`).

Note that the compile time units collation units (collation_**lang**.pas) include already the unicode-ducet.pas (DUCET) unit so it is not necessary to include it manually, contrary to the binary files. So an application that only uses the binary collation files should at least include the `unicodeducet` unit or manually load the binary collation `collation_ducet_le.bco` or `collation_ducet_be.bco`, depending on the endianness of the platform. The `LoadCollation` (1816) call using a directory and the language `ducet` automatically select the correct file.

79.3 Constants, types and variables

79.3.1 Resource strings

```
SCollationNotFound = 'Collation not found : "%s".'
```

Error message when a collation is not found.

79.3.2 Constants

```
ENDIAN_SUFFIX : Array[TEndianKind] of string = ('le', 'be')
```

`ENDIAN_SUFFIX` contains the suffixes used in `LoadCollation` (1816) when constructing a collation filename for a language.

```
ERROR_INVALID_CODEPOINT_SEQUENCE = 1
```

Error exit code for `UnicodeToLower/UnicodeToUpper`

```
HIGH_SURROGATE_BEGIN = ($D800)
```

First value for high surrogate values.

```
HIGH_SURROGATE_COUNT = HIGH_SURROGATE_END - HIGH_SURROGATE_BEGIN  
+ 1
```

Number of high surrogate values.

```
HIGH_SURROGATE_END = ($DBFF)
```

Last value for high surrogate values.

```
LOW_SURROGATE_BEGIN = ($DC00)
```

First value for low surrogate values.

```
LOW_SURROGATE_END = ($DFFF)
```

Last value for low surrogate values.

```
MAX_LEGAL_UTF32 = $10FFFF
```

Maximum value of a legally encoded UTF32 value (currently unused)

MAX_WORD = (Word)

MAX_WORD is the maximum value of a WORD typed value.

ROOT_COLLATION_NAME = 'DUCET'

Name of the root collation (used if no collation name is given)

UCS4_HALF_BASE = (\$10000)

Offset for UCS4 character encoding

UCS4_HALF_MASK = (\$3FF)

Unused currently

UGC_ClosePunctuation = 14

Unicode token category: Close punctuation

UGC_CombiningMark = 6

Unicode token category: Uppercase letter

UGC_ConnectPunctuation = 11

Unicode token category: Connect punctuation

UGC_Control = 25

Unicode token category: control token

UGC_CurrencySymbol = 19

Unicode token category: Currency symbol

UGC_DashPunctuation = 12

Unicode token category: Dash punctuation

UGC_DecimalNumber = 8

Unicode token category: Uppercase letter

UGC_EnclosingMark = 7

Unicode token category: Uppercase letter

UGC_FinalPunctuation = 16

Unicode token category: Final punctuation

UGC_Format = 26

Unicode token category: Formatting token

UGC_InitialPunctuation = 15

Unicode token category: Initial punctuation

UGC_LetterNumber = 9

Unicode token category: Letter-number

UGC_LineSeparator = 23

Unicode token category: Line separator

UGC_LowercaseLetter = 1

Unicode general category: Lowercase letter

UGC_MathSymbol = 18

Unicode token category: Math symbol

UGC_ModifierLetter = 3

Unicode general category: modifier letter

UGC_ModifierSymbol = 20

Unicode token category: modifier symbol

UGC_NonSpacingMark = 5

Unicode general category: Non-spacing mark

UGC_OpenPunctuation = 13

Unicode token category: Open punctuation

UGC_OtherLetter = 4

Unicode general category: Other letter

UGC_OtherNumber = 10

Unicode token category: Other number

UGC_OtherPunctuation = 17

Unicode token category: Other punctuation

UGC_OtherSymbol = 21

Unicode token category: Other symbol

UGC_ParagraphSeparator = 24

Unicode token category: Paragraph separator

UGC_PrivateUse = 28

Unicode token category: For private use

UGC_SpaceSeparator = 22

Unicode token category: Space separator

UGC_Surrogate = 27

Unicode token category: Surrogate token

UGC_TitlecaseLetter = 2

Unicode general category: Titlecase letter

UGC_Unassigned = 29

Unicode token category: As yet unassigned

UGC_UppercaseLetter = 0

Unicode general category: Uppercase letter

ZERO_UINT24 : UInt24 = (byte2: 0; byte1: 0; byte0: 0)

TUInt24Rec value with all bytes zero.

79.3.3 Types

PUCA_DataBook = ^TUCA_DataBook

Pointer to TUCA_DataBook type.

PUCA_PropItemContextRec = ^TUCA_PropItemContextRec

Pointer to TUCA_PropItemContextRec

PUCA_PropItemContextTreeNodeRec =
^TUCA_PropItemContextTreeNodeRec

Pointer to TUCA_PropItemContextTreeNodeRec

PUCA_PropItemContextTreeRec = ^TUCA_PropItemContextTreeRec

Pointer to TUCA_PropItemContextTreeRec

PUCA_PropItemRec = ^TUCA_PropItemRec

Pointer to TUCA_PropItemRec

PUCA_PropWeights = ^TUCA_PropWeights

Pointer to TUCA_PropWeights

PUC_Prop = ^TUC_Prop

Pointer to TUC_Prop record

PUInt24 = ^UInt24

Pointer to TUInt24Rec

TCollationField = (BackWard, VariableLowLimit, VariableHighLimit)

Table 79.2: Enumeration values for type TCollationField

Value	Explanation
BackWard	Backwards encoded
VariableHighLimit	Has upper bound on variable weights
VariableLowLimit	Has lower bound on variable weights

TCollationField describes some properties of the collation data items.

TCollationFields = Set of TCollationField

Set of TCollationField

TCollationName = string

Collation name string type (fixed length)

TEndianKind = (Little, Big)

Table 79.3: Enumeration values for type TEndianKind

Value	Explanation
Big	Big-endian platform
Little	Little-endian platform

TEndianKind is an auxiliary enumerated type to enumerate the endianness of platforms.

TUCASortKey = Array of TUCASortKeyItem

Array of TUCASortKeyItem

TUCASortKeyItem = Word

Alias for WORD

```
TUCA_PropWeights = packed record
  Weights : Array[0..2] of Word;
end
```

TUC_PropWeights describes the weights of collation characteristics of a unicode character. It is an internal structure which should not be used directly, the actual structure is subject to change.

```
TUCA_VariableKind = (ucaShifted, ucaNonIgnorable, ucaBlanked,
  ucaShiftedTrimmed, ucaIgnoreSP)
```

Table 79.4: Enumeration values for type TUCA_VariableKind

Value	Explanation
ucaBlanked	Variable collation elements and any subsequent ignorable collation elements are reset so that all weights are zero
ucaIgnoreSP	Not implemented (variant of Shifted that reduces the set of variable collation elements to include only non-space characters)
ucaNonIgnorable	Variable collation elements are not reset to be quaternary collation elements
ucaShifted	Variable collation elements are reset to zero at levels one through three
ucaShiftedTrimmed	This option is the same as Shifted, except that all trailing FFFFs are trimmed from the sort key.

Options for weighting data

UInt24 = TUInt24Rec

Alias for TUInt24Rec

79.4 Procedures and functions

79.4.1 CanonicalOrder

Synopsis: Put unicode string in canonical order.

```
Declaration: procedure CanonicalOrder(var AString: UnicodeString); Overload
  procedure CanonicalOrder(AString: PUnicodeChar; const ALength: SizeInt)
    ; Overload
```

Visibility: default

Description: CanonicalOrder transforms a unicode string AString (or the alternate form using a null-terminated AString with length ALength) so it is in canonical order (as defined by the unicode specification). A string needs to be in canonical order to be able to compare strings. This function is called as part of NormalizeNFD (1817).

See also: NormalizeNFD (1817)

79.4.2 CompareSortKey

Synopsis: Compare two sort keys.

Declaration:

```
function CompareSortKey(const A: TUCASortKey; const B: TUCASortKey)
                        : Integer; Overload
function CompareSortKey(const A: TUCASortKey; const B: Array of Word)
                        : Integer; Overload
```

Visibility: default

Description: `CompareSortKey` compares 2 sort keys A and B. It returns

- a negative number if A comes alphabetically ordered before B.
- Zero if A is alphabetically identical to B.
- A positive number iff A is alphabetically ordered after B.

Sort keys can be constructed from unicode strings using `ComputeSortKey` (1814).

See also: `ComputeSortKey` (1814)

79.4.3 ComputeSortKey

Synopsis: Compute the sort key for a string

Declaration:

```
function ComputeSortKey(const AString: UnicodeString;
                        const ACollation: PUCA_DataBook) : TUCASortKey
                        ; Overload
function ComputeSortKey(const AStr: PUnicodeChar;
                        const ALength: SizeInt;
                        const ACollation: PUCA_DataBook) : TUCASortKey
                        ; Overload
```

Visibility: default

Description: `ComputeSortKey` computes the sort key for a unicode string `AString` (or the alternate form using a null-terminated `AStr` with length `ALength`) using the Unicode Collation Algorithm dat in `ACollation`. This key can then be used in `CompareSortKey` (1814) to compare unicode strings.

See also: `CompareSortKey` (1814)

79.4.4 FindCollation

Synopsis: Find a collation by name

Declaration:

```
function FindCollation(const AName: ansistring) : PUCA_DataBook
                        ; Overload
function FindCollation(const AIndex: Integer) : PUCA_DataBook; Overload
```

Visibility: default

Description: `FindCollection` searches a collation with name `AName` or index `AIndex` in the list of known collations and returns a pointer to the collation data. If the requested collation is not known, i.e. the name is not found, or the index is out of range, then `Nil` is returned. The valid index range is 0 to `GetCollationCount-1`.

See also: `GetCollationCount` (1815)

79.4.5 FreeCollation

Synopsis: Free collation data.

Declaration: `procedure FreeCollation(AItem: PUCA_DataBook)`

Visibility: default

Description: `FreeCollation` removes all structures in the collation data from memory. It will not do anything when the header field `Dynamic` is `false`. (collations loaded and registered using `LoadCollation` (1816) are always dynamic and must be freed).

See also: `LoadCollation` (1816)

79.4.6 FromUCS4

Synopsis: Convert UCS4 to `UnicodeChar`

Declaration: `procedure FromUCS4(const AValue: UCS4Char; var AHighS: UnicodeChar; var ALowS: UnicodeChar)`

Visibility: default

Description: `FromUCS4` converts the UCS4 encoded unicode character `AValue` to a set of unicode (surrogate pair) characters encoded in UTF16: `AHighS`, `ALowS`.

See also: `ToUCS4` (1818), `UnicodeIsHighSurrogate` (1818), `UnicodeIsLowSurrogate` (1818), `UnicodeIsSurrogatePair` (1819)

79.4.7 GetCollationCount

Synopsis: Return the number of known collations.

Declaration: `function GetCollationCount : Integer`

Visibility: default

Description: `GetCollationCount` returns the number of registered collations. The collation data can be retrieved by index using the `FindCollation` (1814). The maximum index is `GetCollationCount-1`.

See also: `FindCollation` (1814)

79.4.8 GetProps

Synopsis: Get unicode character data

Declaration: `function GetProps(const ACodePoint: Word) : PUC_Prop; Overload`
`function GetProps(const AHighS: UnicodeChar; const ALowS: UnicodeChar)`
`: PUC_Prop; Overload`
`function GetProps(const ACodePoint: Cardinal) : PUC_Prop; Overload`

Visibility: default

Description: `GetProps` returns a pointer to a general unicode character property data structure. The character can be specified using a word or cardinal sized codepoint (`ACodePoint`), or using a UTF16 encoded surrogate pair (`AHighS`, `ALowS`).

The returned pointer must not be freed, it points to part of a static structure.

See also: `GetPropUCA` (1816)

79.4.9 GetPropUCA

Synopsis: Get unicode collation algorithm properties for a unicode character

Declaration:

```
function GetPropUCA(const AHighS: UnicodeChar;
                   const ALowS: UnicodeChar; const ABook: PUCA_DataBook)
    : PUCA_PropItemRec; Overload
function GetPropUCA(const AChar: UnicodeChar;
                   const ABook: PUCA_DataBook) : PUCA_PropItemRec
    ; Overload
```

Visibility: default

Description: GetPropUCA returns UCA data for the unicode character (AChar) or surrogate pair AHighS, ALowS) in the collation data book ABook. If no data is available, Nil is returned.

Errors: if an invalid ABook is specified, an access violation may occur.

See also: GetProps ([1815](#))

79.4.10 IncrementalCompareString

Synopsis: Compare 2 strings using the specified collation

Declaration:

```
function IncrementalCompareString(const AStrA: PUnicodeChar;
                                const ALengthA: SizeInt;
                                const AStrB: PUnicodeChar;
                                const ALengthB: SizeInt;
                                const ACollation: PUCA_DataBook)
    : Integer; Overload
function IncrementalCompareString(const AStrA: UnicodeString;
                                const AStrB: UnicodeString;
                                const ACollation: PUCA_DataBook)
    : Integer; Overload
```

Visibility: default

Description: IncrementalCompareString creates 2 compare keys from the strings AStrA and AStrB using collation data in ACollation. The keys are computed only to the point where the two strings differ. This means the keys cannot be reused for other comparisons if the strings differ. The two strings can be specified as a unicode string or as a pointer to a null-terminated character array with a length (ALengthA and ALengthB). It returns then the result of CompareSortKey ([1814](#)).

Errors: None.

See also: ComputeSortKey ([1814](#)), CompareSortKey ([1814](#))

79.4.11 LoadCollation

Synopsis: Load a binary collation data file from file

Declaration:

```
function LoadCollation(const AData: Pointer; const ADataLength: Integer)
    : PUCA_DataBook; Overload
function LoadCollation(const AFileName: string) : PUCA_DataBook
    ; Overload
function LoadCollation(const ADirectory: string;
                       const ALanguage: string) : PUCA_DataBook
    ; Overload
```

Visibility: default

Description: `LoadCollation` loads collation data from file `AFileName`, or from a memory block `AData` with length `ADataLength`. If successful, it returns a pointer which can be used to register the collation using `RegisterCollation` (1817). If there is a problem with the data, `Nil` is returned.

The filename can also be specified as a `Directory` and language name `ALanguage`. The latter is prepended with `collation_` and appended with the native endianness of the current platform, and has extension `.bco`.

Errors: If the file containing data does not exist or has a size which is less than the encoded header size, `Nil` is returned.

See also: `RegisterCollation` (1817)

79.4.12 NormalizeNFD

Synopsis: Perform unicode normalization D on a string

Declaration:

```
function NormalizeNFD(const AString: UnicodeString) : UnicodeString
    ; Overload
function NormalizeNFD(const AStr: PUnicodeChar; ALength: SizeInt)
    : UnicodeString; Overload
```

Visibility: default

Description: `NormalizeNFD` normalizes the string `AString` (or the alternate form using a null-terminated `AStr` with length `ALength`) to Unicode Normalization Form D. The resulting string can be used to determine equivalence of unicode strings.

See also: `CanonicalOrder` (1813)

79.4.13 PrepareCollation

Synopsis: Prepare a collation for use in the list

Declaration:

```
procedure PrepareCollation(ACollation: PUCA_DataBook;
    const ABaseName: ansistring;
    const AChangedFields: TCollationFields)
```

Visibility: default

Description: `PrepareCollation` will link collation definition `ACollation` to the base collection with name `ABaseName` (if empty, it defaults to the root collation). It will also initialize some fields in the definition, copying them from the base collation, but excludes the fields enumerated in `AChangedFields`.

It should normally not be needed to call this function, it is called as part of `LoadCollation` (1816).

See also: `LoadCollation` (1816)

79.4.14 RegisterCollation

Synopsis: Register a new collation

Declaration:

```
function RegisterCollation(const ACollation: PUCA_DataBook) : Boolean
    ; Overload
function RegisterCollation(const ADirectory: string;
    const ALanguage: string) : Boolean; Overload
```

Visibility: default

Description: `RegisterCollation` registers a new collation `ACollation` in the list of known collations. The collation data can be specified directly (`ACollation`) or a name of a language (`ALanguage`) in a directory (`ADirectory`). The latter option will load the binary encoded collation from file using `LoadCollation` (1816).

If the collation is loaded correctly, `True` is returned, otherwise `False` is returned (for instance when a collation with the same name is already loaded).

See also: `UnRegisterCollation` (1820), `UnRegisterCollations` (1820), `LoadCollation` (1816)

79.4.15 ToUCS4

Synopsis: Encode unicode UTF16 surrogate pair to UCS4 character

Declaration: `function ToUCS4(const AHighS: UnicodeChar; const ALowS: UnicodeChar) : UCS4Char`

Visibility: default

Description: `ToUCS4` converts set of unicode (surrogate pair) characters encoded in UTF16: `AHighS`, `ALowS` to a UCS4 encoded unicode character.

See also: `FromUCS4` (1815), `UnicodeIsHighSurrogate` (1818), `UnicodeIsLowSurrogate` (1818), `UnicodeIsSurrogatePair` (1819)

79.4.16 UnicodeIsHighSurrogate

Synopsis: Check if a UTF16 character is the high character in a surrogate pair.

Declaration: `function UnicodeIsHighSurrogate(const AValue: UnicodeChar) : Boolean`

Visibility: default

Description: `UnicodeIsHighSurrogate` checks whether `AValue` is a valid high character of a surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for high characters in surrogate pairs.

See also: `FromUCS4` (1815), `ToUCS4` (1818), `UnicodeIsHighSurrogate` (1818), `UnicodeIsLowSurrogate` (1818), `UnicodeIsSurrogatePair` (1819)

79.4.17 UnicodeIsLowSurrogate

Synopsis: Check if a UTF16 character is the low character in a surrogate pair.

Declaration: `function UnicodeIsLowSurrogate(const AValue: UnicodeChar) : Boolean`

Visibility: default

Description: `UnicodeIsLowSurrogate` checks whether `AValue` is a valid low character of a surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for low characters in surrogate pairs.

See also: `FromUCS4` (1815), `ToUCS4` (1818), `UnicodeIsHighSurrogate` (1818), `UnicodeIsSurrogatePair` (1819)

79.4.18 `UnicodeIsSurrogatePair`

Synopsis: Check if a pair of UTF16 encoded characters is a valid surrogate pair.

Declaration: `function UnicodeIsSurrogatePair(const AHighSurrogate: UnicodeChar;
const ALowSurrogate: UnicodeChar)
: Boolean`

Visibility: default

Description: `UnicodeIsSurrogatePair` checks whether `AHighSurrogate`, `ALowSurrogate` constitute a valid surrogate pair, and returns `True` if this is the case. It does this by checking whether the values are within the bounds for high and low surrogate pairs.

See also: `FromUCS4` ([1815](#)), `ToUCS4` ([1818](#)), `UnicodeIsHighSurrogate` ([1818](#)), `UnicodeIsLowSurrogate` ([1818](#))

79.4.19 `UnicodeToLower`

Synopsis: Transform unicode string to lowercase

Declaration: `function UnicodeToLower(const AString: UnicodeString;
const AIgnoreInvalidSequence: Boolean;
out AResultString: UnicodeString) : Integer`

Visibility: default

Description: `UnicodeToLower` transforms a UTF16 unicode string `AString` to its lowercase equivalent and returns this in `AResultString`. If the transformation was succesful, then the function returns 0. A nonzero return value means an error occurred. `AResultString` will remain untouched in that case.

If a character in `AString` cannot be found in the unicode data tables, an error will be reported, unless `AIgnoreInvalidSequence` is set to `True`, in which case the character will be copied as-is to the output.

Unicode collation data can be loaded using `RegisterCollation` ([1817](#)) or `LoadCollation` ([1816](#))

Errors: On error, a nonzero value will be returned.

See also: `UnicodeToUpper` ([1819](#)), `RegisterCollation` ([1817](#)), `LoadCollation` ([1816](#))

79.4.20 `UnicodeToUpper`

Synopsis: Transform unicode string to uppercase

Declaration: `function UnicodeToUpper(const AString: UnicodeString;
const AIgnoreInvalidSequence: Boolean;
out AResultString: UnicodeString) : Integer`

Visibility: default

Description: `UnicodeToUpper` transforms a UTF16 unicode string `AString` to its uppercase equivalent and returns this in `AResultString`. If the transformation was succesful, then the function returns 0. A nonzero return value means an error occurred. `AResultString` will remain untouched in that case.

If a character in `AString` cannot be found in the unicode data tables, an error will be reported, unless `AIgnoreInvalidSequence` is set to `True`, in which case the character will be copied as-is to the output.

Unicode collation data can be loaded using `RegisterCollation` ([1817](#)) or `LoadCollation` ([1816](#))

Errors: On error, a nonzero value will be returned.

See also: [UnicodeToLower \(1819\)](#), [RegisterCollation \(1817\)](#), [LoadCollation \(1816\)](#)

79.4.21 UnregisterCollation

Synopsis: Remove a collation from the list of known collections.

Declaration: `function UnregisterCollation(const AName: ansistring) : Boolean`

Visibility: default

Description: `UnRegisterCollation` removes a collation `AName` from the list of known collations. It returns `True` if the collation was found and successfully removed.

Errors: If the collation was not found, `False` is returned.

See also: [RegisterCollation \(1817\)](#), [UnRegisterCollations \(1820\)](#), [LoadCollation \(1816\)](#)

79.4.22 UnregisterCollations

Synopsis: Unregister all collations.

Declaration: `procedure UnregisterCollations(const AFreeDynamicCollations: Boolean)`

Visibility: default

Description: `UnregisterCollations` unregisters all known collations. If `AFreeDynamicCollations` is `True`, then dynamic collations will be removed from memory using [FreeCollation \(1815\)](#). This must normally be set to `true`.

See also: [RegisterCollation \(1817\)](#), [UnRegisterCollation \(1820\)](#), [LoadCollation \(1816\)](#), [FreeCollation \(1815\)](#)

79.5 TUCA_DataBook

```
TUCA_DataBook = record
public
  Base : PUCA_DataBook;
  Version :
  TCollationName;
  CollationName : TCollationName;
  VariableWeight
  : TUCA_VariableKind;
  Backwards : Array[0..3] of Boolean;
  BMP_Table1
  : PByte;
  BMP_Table2 : PUInt24;
  OBMP_Table1 : PWord;
  OBMP_Table2
  : PUInt24;
  PropCount : Integer;
  Props : PUCA_PropItemRec;
  VariableLowLimit
  : Word;
  VariableHighLimit : Word;
```

```

Dynamic : Boolean;
function
  IsVariable(const AWeight: PUCA_PropWeights) : Boolean;
end

```

TUCA_DataBook describes a Unicode Collation Algorithm data set. data sets can be registered using the RegisterCollation (1817) function or loaded from file using LoadCollation (1816). A collation data book must be specified when comparing unicode strings.

79.5.1 Method overview

Page	Method	Description
1821	IsVariable	Check if a weight is a variable weight

79.5.2 TUCA_DataBook.IsVariable

Synopsis: Check if a weight is a variable weight

Declaration: function IsVariable(const AWeight: PUCA_PropWeights) : Boolean

Visibility: public

Description: IsVariable checks whether AWeight is between the VariableLowLimit and VariableHighLimit limits.

79.6 TUCA_PropItemContextRec

```

TUCA_PropItemContextRec = packed record
public
  CodePointCount :
    Byte;
  WeightCount : Byte;
  function GetCodePoints : PUInt24;
  function GetWeights : PUCA_PropWeights;
end

```

This is an internal structure which should not be used directly, the actual structure is subject to change.

79.6.1 Method overview

Page	Method	Description
1821	GetCodePoints	get the address of actual code points.
1822	GetWeights	Get the Address of actual weights.

79.6.2 TUCA_PropItemContextRec.GetCodePoints

Synopsis: get the address of actual code points.

Declaration: function GetCodePoints : PUInt24

Visibility: public

79.6.3 TUCA_PropltemContextRec.GetWeights

Synopsis: Get the Address of actual weights.

Declaration: function GetWeights : PUCA_PropWeights

Visibility: public

79.7 TUCA_PropItemContextTreeNodeRec

```
TUCA_PropItemContextTreeNodeRec = packed record
public
  Left : Word
  ;
  Right : Word;
  Data : TUCA_PropItemContextRec;
  function GetLeftNode
  : PUCA_PropItemContextTreeNodeRec;
  function GetRightNode : PUCA_PropItemContextTreeNodeRec
  ;
end
```

This is an internal structure for the tree which should not be used directly, the actual structure is subject to change.

79.7.1 Method overview

Page	Method	Description
1822	GetLeftNode	Access to left tree node data
1822	GetRightNode	Access to right tree node data

79.7.2 TUCA_PropltemContextTreeNodeRec.GetLeftNode

Synopsis: Access to left tree node data

Declaration: function GetLeftNode : PUCA_PropItemContextTreeNodeRec

Visibility: public

79.7.3 TUCA_PropltemContextTreeNodeRec.GetRightNode

Synopsis: Access to right tree node data

Declaration: function GetRightNode : PUCA_PropItemContextTreeNodeRec

Visibility: public

79.8 TUCA_PropItemContextTreeRec

```
TUCA_PropItemContextTreeRec = packed record
public
  Size : UInt24
```

```

;
function GetData : PUCA_PropItemContextTreeNodeRec;
property
Data : PUCA_PropItemContextTreeNodeRec;
function Find(const AChars
: PUInt24; const ACharCount: Integer;
out ANode: PUCA_PropItemContextTreeNodeRec
) : Boolean;
end

```

This is an internal tree structure for storing unicode collation data which should not be used directly, the actual structure is subject to change.

79.8.1 Method overview

Page	Method	Description
1823	Find	Find data for encoded character
1823	GetData	Access to tree data (getter for Data property)

79.8.2 Property overview

Page	Properties	Access	Description
1823	Data	r	Read-only access to tree data

79.8.3 TUCA_PropltemContextTreeRec.GetData

Synopsis: Access to tree data (getter for Data property)

Declaration: `function GetData : PUCA_PropItemContextTreeNodeRec`

Visibility: public

79.8.4 TUCA_PropltemContextTreeRec.Find

Synopsis: Find data for encoded character

Declaration: `function Find(const AChars: PUInt24; const ACharCount: Integer; out ANode: PUCA_PropItemContextTreeNodeRec) : Boolean`

Visibility: public

Description: Find searches the tree for the collation data for the character encoded in AChars (ACharCount). It returns true if the data was found, false if not. A pointer to the collation data is returned in ANode.

79.8.5 TUCA_PropltemContextTreeRec.Data

Synopsis: Read-only access to tree data

Declaration: `Property Data : PUCA_PropItemContextTreeNodeRec`

Visibility: public

Access: Read

79.9 TUCA_PropItemRec

```

TUCA_PropItemRec = packed record
private
    FLAG_VALID = 0;
    FLAG_CODEPOINT
    = 1;
    FLAG_CONTEXTUAL = 2;
    FLAG_DELETION = 3;
    FLAG_COMPRESS_WEIGHT_1
    = 6;
    FLAG_COMPRESS_WEIGHT_2 = 7;
    function GetCodePoint : UInt24
    ;
public
    WeightLength : Byte;
    ChildCount : Byte;
    Size : Word
    ;
    Flags : Byte;
    function HasCodePoint : Boolean;
    property CodePoint
    : UInt24;
    function IsValid : Boolean;
    procedure GetWeightArray
    (ADest: PUCA_PropWeights);
    function GetSelfOnlySize : Cardinal;
    function GetContextual : Boolean;
    property Contextual : Boolean
    ;
    function GetContext : PUCA_PropItemContextTreeRec;
    function
    IsDeleted : Boolean;
    function IsWeightCompress_1 : Boolean;
    function
    IsWeightCompress_2 : Boolean;
end

```

TUCA_PropItemRec encodes 1 entry from the Unicode Collation data in an encoded form.

79.9.1 Method overview

Page	Method	Description
1826	GetContext	Access to context data
1825	GetContextual	Check if the contextual bit is set in the flags (getter for Contextual)
1825	GetSelfOnlySize	Size of this item data (in bytes).
1825	GetWeightArray	Return an array of weights
1825	HasCodePoint	Check flags whether a codepoint is present.
1826	IsDeleted	Check flags if deleted bit is set
1825	IsValid	Check flags for validity
1826	IsWeightCompress_1	Check whether weight compression flag 1 is set
1826	IsWeightCompress_2	Check whether weight compression flag 2 is set

79.9.2 Property overview

Page	Properties	Access	Description
1826	CodePoint	r	Get the codepoint
1826	Contextual	r	Check if the contextual bit is set in the flags

79.9.3 TUCA_PropltemRec.HasCodePoint

Synopsis: Check flags whether a codepoint is present.

Declaration: `function HasCodePoint : Boolean`

Visibility: public

79.9.4 TUCA_PropltemRec.IsValid

Synopsis: Check flags for validity

Declaration: `function IsValid : Boolean`

Visibility: public

79.9.5 TUCA_PropltemRec.GetWeightArray

Synopsis: Return an array of weights

Declaration: `procedure GetWeightArray (ADest: PUCA_PropWeights)`

Visibility: public

Description: `GetWeightArray` returns an array with the weights in `ADest`. `ADest` must point to enough room for `WeightLength` weights.

79.9.6 TUCA_PropltemRec.GetSelfOnlySize

Synopsis: Size of this item data (in bytes).

Declaration: `function GetSelfOnlySize : Cardinal`

Visibility: public

Description: Return the size of the item's data and properties.

79.9.7 TUCA_PropltemRec.GetContextual

Synopsis: Check if the contextual bit is set in the flags (getter for Contextual)

Declaration: `function GetContextual : Boolean`

Visibility: public

79.9.8 TUCA_PropltemRec.GetContext

Synopsis: Access to context data

Declaration: `function GetContext : PUCA_PropItemContextTreeRec`

Visibility: public

Description: `GetContext` returns a pointer to the context data. It is `Nil` if the context flag is not set.

79.9.9 TUCA_PropltemRec.IsDeleted

Synopsis: Check flags if deleted bit is set

Declaration: `function IsDeleted : Boolean`

Visibility: public

79.9.10 TUCA_PropltemRec.IsWeightCompress_1

Synopsis: Check whether weight compression flag 1 is set

Declaration: `function IsWeightCompress_1 : Boolean`

Visibility: public

79.9.11 TUCA_PropltemRec.IsWeightCompress_2

Synopsis: Check whether weight compression flag 2 is set

Declaration: `function IsWeightCompress_2 : Boolean`

Visibility: public

79.9.12 TUCA_PropltemRec.CodePoint

Synopsis: Get the codepoint

Declaration: `Property CodePoint : UInt24`

Visibility: public

Access: Read

Description: Access to codepoint if `HasCodePoint` returns true. If `HasCodePoint` returns false, an exception will be raised.

79.9.13 TUCA_PropltemRec.Contextual

Synopsis: Check if the contextual bit is set in the flags

Declaration: `Property Contextual : Boolean`

Visibility: public

Access: Read

79.10 TUC_Prop

```

TUC_Prop = packed record
private
    function GetCategory : Byte;
    procedure SetCategory(AValue: Byte);
    function GetWhiteSpace : Boolean
    ;
    procedure SetWhiteSpace(AValue: Boolean);
    function GetHangulSyllable
    : Boolean;
    procedure SetHangulSyllable(AValue: Boolean);
    function
    GetNumericValue : Double;
public
    CategoryData : Byte;
    CCC : Byte
    ;
    NumericIndex : Byte;
    SimpleUpperCase : UInt24;
    SimpleLowerCase
    : UInt24;
    DecompositionID : SmallInt;
    property Category : Byte
    ;
    property WhiteSpace : Boolean;
    property HangulSyllable : Boolean
    ;
    property NumericValue : Double;
end

```

TUC_Prop describes the collation characteristics of a unicode character. It is an internal structure which should not be used directly, the actual structure is subject to change.

79.10.1 Property overview

Page	Properties	Access	Description
1827	Category	rw	Get the category
1828	HangulSyllable	rw	Is the character a hangul syllable
1828	NumericValue	r	Numeric value
1828	WhiteSpace	rw	Is the character considered whitespace

79.10.2 TUC_Prop.Category

Synopsis: Get the category

Declaration: Property Category : Byte

Visibility: public

Access: Read,Write

Description: CategoryData provides access to the category part of CategoryData (encoded).

79.10.3 TUC_Prop.WhiteSpace

Synopsis: Is the character considered whitespace

Declaration: `Property WhiteSpace : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `WhiteSpace` provides easy access to the `WhiteSpace` part of `CategoryData` (encoded).

79.10.4 TUC_Prop.HangulSyllable

Synopsis: Is the character a hangul syllable

Declaration: `Property HangulSyllable : Boolean`

Visibility: `public`

Access: `Read,Write`

Description: `WhiteSpace` provides easy access to the `HangulSyllable` part of `CategoryData` (encoded).

79.10.5 TUC_Prop.NumericValue

Synopsis: Numeric value

Declaration: `Property NumericValue : Double`

Visibility: `public`

Access: `Read`

Description: `NumericValue` uses `numericalindex` to get the numerical value.

79.11 TUInt24Rec

```
TUInt24Rec = packed record
public
    byte2 : Byte;
    byte1 : Byte;
    byte0 : Byte;
    TUInt24Rec.class operator implicit(a: TUInt24Rec
    ) : Cardinal;
    TUInt24Rec.class operator implicit(a: TUInt24Rec)
    : LongInt;
    TUInt24Rec.class operator implicit(a: TUInt24Rec) :
    Word;
    TUInt24Rec.class operator implicit(a: TUInt24Rec) : Byte
    ;
    TUInt24Rec.class operator implicit(a: Cardinal) : TUInt24Rec;
    TUInt24Rec.class operator equal(a: TUInt24Rec; b: TUInt24Rec)
    : Boolean;
    TUInt24Rec.class operator equal(a: TUInt24Rec; b: Cardinal
    ) : Boolean;
```

```

TUInt24Rec.class operator equal(a: Cardinal; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: LongInt
) : Boolean;
TUInt24Rec.class operator equal(a: LongInt; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: Word
) : Boolean;
TUInt24Rec.class operator equal(a: Word; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator equal(a: TUInt24Rec; b: Byte
) : Boolean;
TUInt24Rec.class operator equal(a: Byte; b: TUInt24Rec
) : Boolean;
TUInt24Rec.class operator notequal(a: TUInt24Rec; b
: TUInt24Rec)
                                : Boolean;

TUInt24Rec
.class operator notequal(a: TUInt24Rec; b: Cardinal) : Boolean;
TUInt24Rec.class operator notequal(a: Cardinal; b: TUInt24Rec) :
Boolean;
TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b
: TUInt24Rec)
                                : Boolean;
TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: Cardinal
)
                                : Boolean;

TUInt24Rec
.class operator greaterthan(a: Cardinal; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: TUInt24Rec;
b: TUInt24Rec) : Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: TUInt24Rec; b: Cardinal)
: Boolean;
TUInt24Rec.class operator
greaterthanorequal(a: Cardinal; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator
lessthan(a: TUInt24Rec; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator lessthan(a: TUInt24Rec
; b: Cardinal) : Boolean;
TUInt24Rec.class operator lessthan(a:
Cardinal; b: TUInt24Rec) : Boolean;
TUInt24Rec.class operator lessthanorequal
(a: TUInt24Rec; b: TUInt24Rec)
: Boolean;
TUInt24Rec.class operator lessthanorequal(a
: TUInt24Rec; b: Cardinal)
: Boolean;
TUInt24Rec.class operator lessthanorequal(a: Cardinal
; b: TUInt24Rec)

```

```
                                : Boolean
;
end
```

Unicode data exists mostly of 24-bit data (3 bytes). This type is meant to deal efficiently with this data. it has members to split out the data in bytes, and functions to query the various properties stored in the data.

79.11.1 Method overview

Page	Method	Description
1835	<code>equal(Byte,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value equals a byte value.
1834	<code>equal(Cardinal,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value equals a cardinal value.
1835	<code>equal(LongInt,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value equals a longint value.
1835	<code>equal(TUInt24Rec,Byte):Boolean</code>	Check whether a TUInt24Rec value equals a byte value.
1834	<code>equal(TUInt24Rec,Cardinal):Boolean</code>	Check if cardinal and TUInt24Rec are equal
1834	<code>equal(TUInt24Rec,LongInt):Boolean</code>	Check whether a TUInt24Rec value equals a longint value.
1834	<code>equal(TUInt24Rec,TUInt24Rec):Boolean</code>	Determine equality of 2 TUInt24Rec records
1835	<code>equal(TUInt24Rec,Word):Boolean</code>	Check whether a TUInt24Rec value equals a word value.
1835	<code>equal(Word,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value equals a word value.
1836	<code>greaterthan(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is greater than a TUInt24Rec value
1836	<code>greaterthan(TUInt24Rec,Cardinal):Boolean</code>	Check whether a TUInt24Rec value is greater than a cardinal value
1836	<code>greaterthan(TUInt24Rec,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value is greater than another TUInt24Rec value
1837	<code>greaterthanorequal(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is greater than or equal to a TUInt24Rec value
1837	<code>greaterthanorequal(TUInt24Rec,Cardinal):Boolean</code>	Check whether a TUInt24Rec value is greater than or equal to a cardinal value
1837	<code>greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean</code>	Check whether a TUInt24Rec value is greater than or equal to a cardinal value
1834	<code>implicit(Cardinal):TUInt24Rec</code>	Assign TUInt24Rec from Cardinal
1833	<code>implicit(TUInt24Rec):Byte</code>	Assign TUInt24Rec to byte
1833	<code>implicit(TUInt24Rec):Cardinal</code>	Assign TUInt24Rec to cardinal
1833	<code>implicit(TUInt24Rec):LongInt</code>	Assign TUInt24Rec to longint
1833	<code>implicit(TUInt24Rec):Word</code>	Assign TUInt24Rec to word
1838	<code>lessthan(Cardinal,TUInt24Rec):Boolean</code>	Check whether a cardinal value is less than a TUInt24Rec value
1837	<code>lessthan(TUInt24Rec,Cardinal):Boolean</code>	Check whether a TUInt24Rec value is

79.11.2 TUInt24Rec.implicit(TUInt24Rec):Cardinal

Synopsis: Assign TUInt24Rec to cardinal

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Cardinal`

Visibility: public

Description: Assign to cardinal, byte0 to MSB and so on.

See also: `TUInt24Rec.implicit(TUInt24Rec):LongInt` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Word` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Byte` ([1833](#)), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` ([1834](#)), `TUInt24Rec.implicit(Longint):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Word):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Byte):TUInt24Rec` ([1830](#))

79.11.3 TUInt24Rec.implicit(TUInt24Rec):LongInt

Synopsis: Assign TUInt24Rec to longint

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : LongInt`

Visibility: public

Description: Assign to cardinal, byte0 to MSB and so on.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Word` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Byte` ([1833](#))

79.11.4 TUInt24Rec.implicit(TUInt24Rec):Word

Synopsis: Assign TUInt24Rec to word

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Word`

Visibility: public

Description: Assign to word, byte0 to MSB, byte1 to MSB.

Errors: If the value is too big (>\$FFFF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Longint` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Byte` ([1833](#)), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` ([1834](#)), `TUInt24Rec.implicit(Longint):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Word):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Byte):TUInt24Rec` ([1830](#))

79.11.5 TUInt24Rec.implicit(TUInt24Rec):Byte

Synopsis: Assign TUInt24Rec to byte

Declaration: `TUInt24Rec.class operator implicit(a: TUInt24Rec) : Byte`

Visibility: public

Description: Assign to byte, byte0 is assigned.

Errors: If the value is too big (>\$FF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):Cardinal` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Longint` ([1833](#)), `TUInt24Rec.implicit(TUInt24Rec):Word` ([1833](#)), `TUInt24Rec.implicit(Cardinal):TUInt24Rec` ([1834](#)), `TUInt24Rec.implicit(Longint):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Word):TUInt24Rec` ([1830](#)), `TUInt24Rec.implicit(Byte):TUInt24Rec` ([1830](#))

79.11.6 TUInt24Rec.implicit(Cardinal):TUInt24Rec

Synopsis: Assign TUInt24Rec from Cardinal

Declaration: `TUInt24Rec.class operator implicit(a: Cardinal) : TUInt24Rec`

Visibility: public

Description: Assign from cardinal, byte0 to MSB.

Errors: If the value is too big (>\$FFFFFF) to be assigned, an overflow error occurs.

See also: `TUInt24Rec.implicit(TUInt24Rec):LongInt` (1833), `TUInt24Rec.implicit(TUInt24Rec):Word` (1833), `TUInt24Rec.implicit(TUInt24Rec):Byte` (1833), `TUInt24Rec.implicit(LongInt):TUInt24Rec` (1830), `TUInt24Rec.implicit(Word):TUInt24Rec` (1830), `TUInt24Rec.implicit(Byte):TUInt24Rec` (1830)

79.11.7 TUInt24Rec.equal(TUInt24Rec,TUInt24Rec):Boolean

Synopsis: Determine equality of 2 TUInt24Rec records

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The 2 records are considered equal if the 3 bytes are equal.

79.11.8 TUInt24Rec.equal(TUInt24Rec,Cardinal):Boolean

Synopsis: Check if cardinal and TUInt24Rec are equal

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The cardinal b is considered equal to a if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

79.11.9 TUInt24Rec.equal(Cardinal,TUInt24Rec):Boolean

Synopsis: Check whether a TUInt24Rec value equals a cardinal value.

Declaration: `TUInt24Rec.class operator equal(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The cardinal a is considered equal to b if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

79.11.10 TUInt24Rec.equal(TUInt24Rec,LongInt):Boolean

Synopsis: Check whether a TUInt24Rec value equals a longint value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: LongInt) : Boolean`

Visibility: public

Description: The longint b is considered equal to a if the fourth byte (LSB) is zero, and the first three bytes equal byte0, byte1, and byte2.

79.11.11 `TUInt24Rec.equal(LongInt,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a longint value.

Declaration: `TUInt24Rec.class operator equal(a: LongInt; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The longint `a` is considered equal to `b` if the fourth byte (LSB) is zero, and the first three bytes equal `byte0`, `byte1`, and `byte2`.

79.11.12 `TUInt24Rec.equal(TUInt24Rec,Word):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a word value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Word) : Boolean`

Visibility: public

Description: The word `b` is considered equal to `a` if its 2 bytes equal `byte0`, `byte1` and `byte2` is zero.

79.11.13 `TUInt24Rec.equal(Word,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a word value.

Declaration: `TUInt24Rec.class operator equal(a: Word; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The word `a` is considered equal to `b` if its 2 bytes equal `byte0`, `byte1` and `byte2` is zero.

79.11.14 `TUInt24Rec.equal(TUInt24Rec,Byte):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a byte value.

Declaration: `TUInt24Rec.class operator equal(a: TUInt24Rec; b: Byte) : Boolean`

Visibility: public

Description: The byte `b` is considered equal to `a` if it equals `byte0` and `byte1` and `byte1` are zero.

79.11.15 `TUInt24Rec.equal(Byte,TUInt24Rec):Boolean`

Synopsis: Check whether a `TUInt24Rec` value equals a byte value.

Declaration: `TUInt24Rec.class operator equal(a: Byte; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The byte `b` is considered equal to `a` if it equals `byte0` and `byte1` and `byte1` are zero.

79.11.16 `TUInt24Rec.notequal(TUInt24Rec,TUInt24Rec):Boolean`

Synopsis: Check whether 2 `TUInt24Rec` values differ.

Declaration: `TUInt24Rec.class operator notequal(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing `byte0`, `byte1` and `byte2`.

79.11.17 **TUInt24Rec.notequal(TUInt24Rec, Cardinal): Boolean**

Synopsis: Check whether a TUInt24Rec value differs from a cardinal value.

Declaration: `TUInt24Rec.class operator notequal(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The cardinal `a` is considered not equal to `b` if the fourth byte (LSB) is nonzero, or one of the first three bytes differ from `byte0`, `byte1`, and `byte2`.

79.11.18 **TUInt24Rec.notequal(Cardinal, TUInt24Rec): Boolean**

Synopsis: Check whether a TUInt24Rec value differs from a cardinal value.

Declaration: `TUInt24Rec.class operator notequal(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: The cardinal `a` is considered not equal to `b` if the fourth byte (LSB) is nonzero, or one of the first three bytes differ from `byte0`, `byte1`, and `byte2`.

79.11.19 **TUInt24Rec.greaterthan(TUInt24Rec, TUInt24Rec): Boolean**

Synopsis: Check whether a TUInt24Rec value is greater than another TUInt24Rec value

Declaration: `TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 bytes `byte0`, `byte1` and `byte2`

79.11.20 **TUInt24Rec.greaterthan(TUInt24Rec, Cardinal): Boolean**

Synopsis: Check whether a TUInt24Rec value is greater than a cardinal value

Declaration: `TUInt24Rec.class operator greaterthan(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.21 **TUInt24Rec.greaterthan(Cardinal, TUInt24Rec): Boolean**

Synopsis: Check whether a cardinal value is greater than a TUInt24Rec value

Declaration: `TUInt24Rec.class operator greaterthan(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.22 **TUInt24Rec.greaterthanorequal(TUInt24Rec,TUInt24Rec):Boolean**

Synopsis: Check whether a TUInt24Rec value is greater than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: TUInt24Rec;
b: TUInt24Rec) : Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.23 **TUInt24Rec.greaterthanorequal(TUInt24Rec,Cardinal):Boolean**

Synopsis: Check whether a TUInt24Rec value is greater than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.24 **TUInt24Rec.greaterthanorequal(Cardinal,TUInt24Rec):Boolean**

Synopsis: Check whether a cardinal value is greater than or equal to a TUInt24Rec value

Declaration: `TUInt24Rec.class operator greaterthanorequal(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.25 **TUInt24Rec.less than(TUInt24Rec,TUInt24Rec):Boolean**

Synopsis: Check whether a TUInt24Rec value is less than another TUInt24Rec value

Declaration: `TUInt24Rec.class operator less than(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing the bytes `byte0`, `byte1` and `byte2`.

79.11.26 **TUInt24Rec.less than(TUInt24Rec,Cardinal):Boolean**

Synopsis: Check whether a TUInt24Rec value is less than a cardinal value

Declaration: `TUInt24Rec.class operator less than(a: TUInt24Rec; b: Cardinal) : Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.27 TUInt24Rec.less-than(Cardinal,TUInt24Rec):Boolean

Synopsis: Check whether a cardinal value is less than a TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than(a: Cardinal; b: TUInt24Rec) : Boolean`

Visibility: public

Description: Check whether a cardinal value is less than a TUInt24Rec value

79.11.28 TUInt24Rec.less-than-or-equal(TUInt24Rec,TUInt24Rec):Boolean

Synopsis: Check whether a TUInt24Rec value is less than or equal to another TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: TUInt24Rec; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing the bytes `byte0`, `byte1` and `byte2`.

79.11.29 TUInt24Rec.less-than-or-equal(TUInt24Rec,Cardinal):Boolean

Synopsis: Check whether a TUInt24Rec value is less than or equal to a cardinal value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: TUInt24Rec; b: Cardinal)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

79.11.30 TUInt24Rec.less-than-or-equal(Cardinal,TUInt24Rec):Boolean

Synopsis: Check whether a cardinal value is less than or equal to a TUInt24Rec value

Declaration: `TUInt24Rec.class operator less-than-or-equal(a: Cardinal; b: TUInt24Rec)
: Boolean`

Visibility: public

Description: The comparison is done by comparing 3 first bytes of the cardinal value with bytes `byte0`, `byte1` and `byte2`.

Chapter 80

Reference for unit 'unicodeducet'

80.1 Used units

Table 80.1: Used units by unit 'unicodeducet'

Name	Page
System	1194

80.2 Overview

The `unicodeducet` unit registers the root Unicode collation (DUCET). This collation is needed by all other collations, so any collation unit will include this file.

This unit does not contain any routines. It simply registers the collation in the initialization section of the unit, so including the unit in the `uses` clause of the program is sufficient.

Chapter 81

Reference for unit 'Unix'

81.1 Used units

Table 81.1: Used units by unit 'Unix'

Name	Page
BaseUnix	124
System	1194
unixtype	1879

81.2 Constants, types and variables

81.2.1 Constants

`ARG_MAX = UnixType.ARG_MAX`

Maximum number of arguments to a program.

`fs_ext = $137d`

File system type (TStatFS ([1855](#))): (ext) Extended

`fs_ext2 = $ef53`

File system type (TStatFS ([1855](#))): (ext2) Second extended

`fs_iso = $9660`

File system type (TStatFS ([1855](#))): ISO 9660

`fs_minix = $137f`

File system type (TStatFS ([1855](#))): Minix

`fs_minix_30 = $138f`

File system type (TStatFS (1855)): Minix 3.0

fs_minix_V2 = \$2468

File system type (TStatFS (1855)): Minix V2

fs_msdos = \$4d44

File system type (TStatFS (1855)): MSDOS (FAT)

fs_nfs = \$6969

File system type (TStatFS (1855)): NFS

fs_old_ext2 = \$ef51

File system type (TStatFS (1855)): (ext2) Old second extended

fs_proc = \$9fa0

File system type (TStatFS (1855)): PROC fs

fs_xia = \$012FD16D

File system type (TStatFS (1855)): XIA

IOctl_TCGETS = \$5401

IOCTL call number: get Terminal Control settings

LOCK_EX = 2

FpFlock (1864) Exclusive lock

LOCK_NB = 4

FpFlock (1864) Non-blocking operation

LOCK_SH = 1

FpFlock (1864) Shared lock

LOCK_UN = 8

FpFlock (1864) unlock

MAP_FAILED = baseunix.MAP_FAILED

Error return value for mmap: mmap operation failed.

MAP_FIXED = baseunix.MAP_FIXED

#rtl.baseunix.FpMMap (190) map type: Interpret addr exactly

MAP_PRIVATE = baseunix.MAP_PRIVATE

#rtl.baseunix.FpMMap (190) map type: Changes are private

MAP_SHARED = baseunix.MAP_SHARED

#rtl.baseunix.FpMMap (190) map type: Share changes

MAP_TYPE = baseunix.MAP_TYPE

#rtl.baseunix.FpMMap (190) map type: Bitmask for type of mapping

MS_ASYNC = 1deprecated

Asynchronous operation flag for msync call

MS_INVALIDATE = 2deprecated

Invalidate other mappings of file flag for msync call

MS_SYNC = 4deprecated

Synchronous operation flag for msync call

NAME_MAX = UnixType.NAME_MAX

Maximum filename length.

Open_Accmode = 3

Bitmask to determine access mode in open flags.

Open_Append = 2 shl 9

File open mode: Append to file

Open_Creat = 1 shl 6

File open mode: Create if file does not yet exist.

Open_Direct = 4 shl 12

File open mode: Minimize caching effects

Open_Directory = 2 shl 15

File open mode: File must be directory.

Open_Excl = 2 shl 6

File open mode: Open exclusively

`Open_LargeFile = 1 shl 15`

File open mode: Open for 64-bit I/O

`Open_NDelay = Open_NonBlock`

File open mode: Alias for `Open_NonBlock` ([1843](#))

`Open_NoCtty = 4 shl 6`

File open mode: No TTY control.

`Open_NoFollow = 4 shl 15`

File open mode: Fail if file is symbolic link.

`Open_NonBlock = 4 shl 9`

File open mode: Open in non-blocking mode

`Open_RdOnly = 0`

File open mode: Read only

`Open_RdWr = 2`

File open mode: Read/Write

`Open_Sync = 1 shl 12`

File open mode: Write to disc at once

`Open_Trunc = 1 shl 9`

File open mode: Truncate file to length 0

`Open_WrOnly = 1`

File open mode: Write only

`PATH_MAX = UnixType.PATH_MAX`

Maximum pathname length.

`PRIO_PGRP = UnixType.PRIO_PGRP`

`#rtl.baseunix.fpGetPriority` ([184](#)) option: Get process group priority.

`PRIO_PROCESS = UnixType.PRIO_PROCESS`

#rtl.baseunix.fpGetPriority (184) option: Get process priority.

PRIO_USER = UnixType.PRIO_USER

#rtl.baseunix.fpGetPriority (184) option: Get user priority.

PROT_EXEC = baseunix.PROT_EXEC

#rtl.baseunix.FpMMap (190) memory access: page can be executed

PROT_NONE = baseunix.PROT_NONE

#rtl.baseunix.FpMMap (190) memory access: page can not be accessed

PROT_READ = baseunix.PROT_READ

#rtl.baseunix.FpMMap (190) memory access: page can be read

PROT_WRITE = baseunix.PROT_WRITE

#rtl.baseunix.FpMMap (190) memory access: page can be written

P_IN = 1

Input file descriptor of pipe pair.

P_OUT = 2

Output file descriptor of pipe pair.

SIG_MAXSIG = UnixType.SIG_MAXSIG

Maximum system signal number.

STAT_IFBLK = \$6000

File (#rtl.baseunix.stat (160) record) mode: Block device

STAT_IFCHR = \$2000

File (#rtl.baseunix.stat (160) record) mode: Character device

STAT_IFDIR = \$4000

File (#rtl.baseunix.stat (160) record) mode: Directory

STAT_IFIFO = \$1000

File (#rtl.baseunix.stat (160) record) mode: FIFO

STAT_IFLNK = \$a000

File (#rtl.baseunix.stat (160) record) mode: Link

STAT_IFMT = \$f000

File (#rtl.baseunix.stat (160) record) mode: File type bit mask

STAT_IFREG = \$8000

File (#rtl.baseunix.stat (160) record) mode: Regular file

STAT_IFSOCK = \$c000

File (#rtl.baseunix.stat (160) record) mode: Socket

STAT_IRGRP = STAT_IROTH shl 3

File (#rtl.baseunix.stat (160) record) mode: Group read permission

STAT_IROTH = \$4

File (#rtl.baseunix.stat (160) record) mode: Other read permission

STAT_IRUSR = STAT_IROTH shl 6

File (#rtl.baseunix.stat (160) record) mode: Owner read permission

STAT_IRWXG = STAT_IRWXO shl 3

File (#rtl.baseunix.stat (160) record) mode: Group permission bits mask

STAT_IRWXO = \$7

File (#rtl.baseunix.stat (160) record) mode: Other permission bits mask

STAT_IRWXU = STAT_IRWXO shl 6

File (#rtl.baseunix.stat (160) record) mode: Owner permission bits mask

STAT_ISGID = \$0400

File (#rtl.baseunix.stat (160) record) mode: GID bit set

STAT_ISUID = \$0800

File (#rtl.baseunix.stat (160) record) mode: UID bit set

STAT_ISVTX = \$0200

File (#rtl.baseunix.stat (160) record) mode: Sticky bit set

STAT_IWGRP = STAT_IWOTH shl 3

File (#rtl.baseunix.stat (160) record) mode: Group write permission

STAT_IWOTH = \$2

File (#rtl.baseunix.stat (160) record) mode: Other write permission

STAT_IWUSR = STAT_IWOTH shl 6

File (#rtl.baseunix.stat (160) record) mode: Owner write permission

STAT_IXGRP = STAT_IXOTH shl 3

File (#rtl.baseunix.stat (160) record) mode: Others execute permission

STAT_IXOTH = \$1

File (#rtl.baseunix.stat (160) record) mode: Others execute permission

STAT_IXUSR = STAT_IXOTH shl 6

File (#rtl.baseunix.stat (160) record) mode: Others execute permission

SYS_NMLN = UnixType.SYS_NMLN

Max system name length.

Wait_Any = -1

#rtl.baseunix.fpWaitPID (218): Wait on any process

Wait_Clone = \$80000000

#rtl.baseunix.fpWaitPID (218): Wait on clone processes only.

Wait_MyPGRP = 0

#rtl.baseunix.fpWaitPID (218): Wait processes from current process group

Wait_NoHang = 1

#rtl.baseunix.fpWaitPID (218): Do not wait

Wait_UnTraced = 2

#rtl.baseunix.fpWaitPID (218): Also report stopped but untraced processes

81.2.2 Types

`cbool = UnixType.cbool`

Boolean type

`cchar = UnixType.cchar`

Alias for `#rtl.UnixType.cchar` ([1881](#))

`cdouble = UnixType.cdouble`

Double precision real format.

`cfloat = UnixType.cfloat`

Floating-point real format

`cint = UnixType.cint`

C type: integer (natural size)

`cint16 = UnixType.cint16`

C type: 16 bits sized, signed integer.

`cint32 = UnixType.cint32`

C type: 32 bits sized, signed integer.

`cint64 = UnixType.cint64`

C type: 64 bits sized, signed integer.

`cint8 = UnixType.cint8`

C type: 8 bits sized, signed integer.

`clock_t = UnixType.clock_t`

Clock ticks type

`clong = UnixType.clong`

C type: long signed integer (double sized)

`clonglong = UnixType.clonglong`

C type: 64-bit (double long) signed integer.

`coff_t = UnixType.TOff`

character offset type.

```
cschar = UnixType.cschar
```

Signed character type

```
cshort = UnixType.cshort
```

C type: short signed integer (half sized)

```
csigned = UnixType.csigned
```

csigned is an alias for cint ([1847](#)).

```
csint = UnixType.csint
```

Signed integer

```
csize_t = UnixType.size_t
```

Character size type.

```
cslong = UnixType.cslong
```

The size is CPU dependent.

```
cslonglong = UnixType.cslonglong
```

cslonglong is an alias for clonglong ([1847](#)).

```
csshort = UnixType.csshort
```

Short signed integer type

```
cuchar = UnixType.cuchar
```

Alias for #rtl.UnixType.cuchar ([1882](#))

```
cuint = UnixType.cuint
```

C type: unsigned integer (natural size)

```
cuint16 = UnixType.cuint16
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = UnixType.cuint32
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = UnixType.cuint64
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = UnixType.cuint8
```

C type: 8 bits sized, unsigned integer.

```
culong = UnixType.culong
```

C type: long unsigned integer (double sized)

```
culonglong = UnixType.culonglong
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = UnixType.cunsigned
```

Alias for `#rtl.unixtype.cunsigned` ([1883](#))

```
cushort = UnixType.cushort
```

C type: short unsigned integer (half sized)

```
dev_t = UnixType.dev_t
```

Device descriptor type.

```
gid_t = UnixType.gid_t
```

Group ID type.

```
ino_t = UnixType.ino_t
```

Inode type.

```
mode_t = UnixType.mode_t
```

Inode mode type.

```
nlink_t = UnixType.nlink_t
```

Number of links type.

```
off_t = UnixType.off_t
```

Offset type.

```
pbool = UnixType.pbool
```

Pointer to boolean type `cbool` ([1847](#))

```
pcchar = UnixType.pcchar
```

Alias for `#rtl.UnixType.pcchar` (1884)

`pcdouble = UnixType.pcdouble`

Pointer to `cdouble` (148) type.

`pcfloat = UnixType.pcfloating`

Pointer to `cfloat` (148) type.

`pcint = UnixType.pcint`

Pointer to `cInt` (1847) type.

`pcint16 = UnixType.pcint16`

Pointer to 16-bit signed integer type

`pcint32 = UnixType.pcint32`

Pointer to signed 32-bit integer type

`pcint64 = UnixType.pcint64`

Pointer to signed 64-bit integer type

`pcint8 = UnixType.pcint8`

Pointer to 8-bits signed integer type

`pClock = UnixType.pClock`

Pointer to `TClock` (1854) type.

`pclong = UnixType.pclong`

Pointer to `cLong` (1847) type.

`pclonglong = UnixType.pclonglong`

Pointer to `longlong` type.

`pcschar = UnixType.pcschar`

Pointer to character type `cschar` (1848).

`pcshort = UnixType.pcsshort`

Pointer to `cShort` (1848) type.

`pcsigned = UnixType.pcsigned`

Pointer to signed integer type `csigned` (1848).

```
pcsint = UnixType.pcsint
```

Pointer to signed integer type `csint` (1848)

```
pcsize_t = UnixType.psize_t
```

Pointer to character size type `pcsize_t`.

```
pcslong = UnixType.pcslong
```

Pointer of the signed long `clong` (1848)

```
pcslonglong = UnixType.pcslonglong
```

Pointer to Signed longlong type `clonglong` (1848)

```
pcsshort = UnixType.pcsshort
```

Pointer to short signed integer type `csshort` (1848)

```
pcuchar = UnixType.pcuchar
```

Alias for `#rtl.UnixType.pcuchar` (1886)

```
pcuint = UnixType.pcuint
```

Pointer to `cUInt` (1848) type.

```
pcuint16 = UnixType.pcuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = UnixType.pcuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = UnixType.pcuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = UnixType.pcuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = UnixType.pculong
```

Pointer to `cuLong` (1849) type.

```
pculonglong = UnixType.pculonglong
```

Unsigned longlong type

`pcunsigned = UnixType.pcunsigned`

Alias for `#rtl.unixtype.pcunsigned` (1886)

`pcushort = UnixType.pcushort`

Pointer to `cuShort` (1849) type.

`pDev = UnixType.pDev`

Pointer to `TDev` (1854) type.

`pGid = UnixType.pGid`

Pointer to `TGid` (1854) type.

`pid_t = UnixType.pid_t`

Process ID type.

`pIno = UnixType.pIno`

Pointer to `TIno` (1854) type.

`pMode = UnixType.pMode`

Pointer to `TMode` (1855) type.

`pnLink = UnixType.pnLink`

Pointer to `TnLink` (1855) type.

`pOff = UnixType.pOff`

Pointer to `TOff` (1855) type.

`pPid = UnixType.pPid`

Pointer to `TPid` (1855) type.

`pSize = UnixType.pSize`

Pointer to `TSize` (1855) type.

`pSize_t = UnixType.pSize_t`

Pointer to type `Size_t`.

`pSocklen = UnixType.pSocklen`

Pointer to TSockLen (1855) type.

```
psSize = UnixType.psSize
```

Pointer to TsSize (1855) type

```
pstatfs = UnixType.PStatFs
```

Pointer to statfs type

```
pthread_cond_t = UnixType.pthread_cond_t
```

Thread conditional variable type.

```
pthread_mutex_t = UnixType.pthread_mutex_t
```

Thread mutex type.

```
pthread_t = UnixType.pthread_t
```

Posix thread type.

```
pTime = UnixType.pTime
```

Pointer to TTime (1855) type.

```
ptimespec = UnixType.ptimespec
```

Pointer to timespec (1854) type.

```
ptimeval = UnixType.ptimeval
```

Pointer to timeval (1854) type.

```
ptime_t = UnixType.ptime_t
```

Pointer to time_t (1854) type.

```
pUid = UnixType.pUid
```

Pointer to TUid (1855) type.

```
size_t = UnixType.size_t
```

Size specification type.

```
socklen_t = UnixType.socklen_t
```

Socket address length type.

```
ssize_t = UnixType.ssize_t
```

Small size type.

```
TClock = UnixType.TClock
```

Alias for clock_t (1847) type.

```
TDev = UnixType.TDev
```

Alias for dev_t (1849) type.

```
TFSearchOption = (NoCurrentDirectory, CurrentDirectoryFirst,  
    CurrentDirectoryLast)
```

Table 81.2: Enumeration values for type TFSearchOption

Value	Explanation
CurrentDirectoryFirst	Search the current directory first, before all directories in the search path.
CurrentDirectoryLast	Search the current directory last, after all directories in the search path
NoCurrentDirectory	Do not search the current directory unless it is specified in the search path.

Describes the search strategy used by FSearch (1866)

```
TGid = UnixType.TGid
```

Alias for gid_t (1849) type.

```
timespec = UnixType.timespec
```

Short time specification type.

```
timeval = UnixType.timeval
```

Time specification type.

```
time_t = UnixType.time_t
```

Time span type

```
TIno = UnixType.TIno
```

Alias for ino_t (1849) type.

```
TIOctlRequest = UnixType.TIOctlRequest
```

Alias for the TIOctlRequest (1891) type in unixtypes

```
TMode = UnixType.TMode
```

Alias for `mode_t` (1849) type.

`TnLink = UnixType.TnLink`

Alias for `nlink_t` (1849) type.

`TOff = UnixType.TOff`

Alias for `off_t` (1849) type.

`TPid = UnixType.TPid`

Alias for `pid_t` (1852) type.

`Tpipe = baseunix.tfilides deprecated`

Array describing a pipe pair of filedescriptors.

`TSize = UnixType.TSize`

Alias for `size_t` (1853) type

`TSocklen = UnixType.TSocklen`

Alias for `socklen_t` (1853) type.

`TsSize = UnixType.TsSize`

Alias for `ssize_t` (1854) type

`tstatfs = UnixType.TStatFs`

`StatFS` returns in `Info` information about the filesystem on which the file `Path` resides. `Info` is of type `TStatFS` (1892).

The function returns zero if the call was succesful, a nonzero value is returned if the call failed.

`TTime = UnixType.TTime`

Alias for `TTime` (1855) type.

`Ttimespec = UnixType.Ttimespec`

Alias for `TimeSpec` (1854) type.

`TTimeVal = UnixType.TTimeVal`

Alias for `timeval` (1854) type.

`TUId = UnixType.TUId`

Alias for `uid_t` (1855) type.

`uid_t = UnixType.uid_t`

User ID type

81.2.3 Variables

`tzdaylight` : Boolean

Indicates whether daylight savings time is active.

`tzname` : Array[boolean] of PChar

Timezone name.

81.3 Procedures and functions

81.3.1 AssignPipe

Synopsis: Create a set of pipe file handlers

Declaration: `function AssignPipe(var pipe_in: cint; var pipe_out: cint) : cint`
`function AssignPipe(var pipe_in: text; var pipe_out: text) : cint`
`function AssignPipe(var pipe_in: File; var pipe_out: File) : cint`

Visibility: default

Description: `AssignPipe` creates a pipe, i.e. two file objects, one for input, one for output. What is written to `Pipe_out`, can be read from `Pipe_in`.

This call is overloaded. The in and out pipe can take three forms: an typed or untyped file, a text file or a file descriptor.

If a text file is passed then reading and writing from/to the pipe can be done through the usual `Readln(Pipe_in, ...)` and `Writeln(Pipe_out, ...)` procedures.

The function returns `True` if everything went successfully, `False` otherwise.

Errors: In case the function fails and returns `False`, extended error information is returned by the `FpGetErrno` (181) function:

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

See also: `POpen` (1869), `#rtl.baseunix.FpMkFifo` (190)

Listing: `./unixex/ex36.pp`

Program Example36;

{ Program to demonstrate the AssignPipe function. }

Uses BaseUnix, Unix;

Var pipi, pipo : Text;
 s : String;

begin

Writeln ('Assigning Pipes.');

If assignpipe(pipi, pipo) <> 0 **then**

Writeln ('Error assigning pipes !', fpgeterrno);

Writeln ('Writing to pipe, and flushing.');

Writeln (pipo, 'This is a textstring'); close(pipo);

```

Writeln ( 'Reading from pipe.' );
While not eof(pipi) do
begin
  Readln (pipi,s);
  Writeln ( 'Read from pipe : ',s);
end;
close (pipi);
writeln ( 'Closed pipes.' );
writeln
end.

```

81.3.2 AssignStream

Synopsis: Assign stream for in and output to a program

Declaration: `function AssignStream(var StreamIn: text; var Streamout: text; const Prog: ansiString; const args: Array of ansistring) : cint`
`function AssignStream(var StreamIn: text; var Streamout: text; var streamerr: text; const Prog: ansiString; const args: Array of ansistring) : cint`

Visibility: default

Description: `AssignStream` creates a 2 or 3 pipes, i.e. two (or three) file objects, one for input, one for output, (and one for standard error) the other ends of these pipes are connected to standard input and output (and standard error) of `Prog`. `Prog` is the path of a program (including path). The options for the program can be specified in `Args`.

What is written to `StreamOut`, will go to the standard input of `Prog`. Whatever is written by `Prog` to it's standard output can be read from `StreamIn`. Whatever is written by `Prog` to it's standard error read from `StreamErr`, if present.

Reading and writing happens through the usual `Readln(StreamIn,...)` and `Writeln (StreamOut,...)` procedures.

Remark: You should *not* use `Reset` or `Rewrite` on a file opened with `POpen`. This will close the file before re-opening it again, thereby closing the connection with the program.

The function returns the process ID of the spawned process, or -1 in case of error.

Errors: Extended error information is returned by the `FpGetErrno` ([181](#)) function.

sys_enfile Too many file descriptors for this process.

sys_enfile The system file table is full.

Other errors include the ones by the `fork` and `exec` programs

See also: `AssignPipe` ([1856](#)), `POpen` ([1869](#))

Listing: `./unixex/ex38.pp`

Program `Example38`;

{ Program to demonstrate the AssignStream function. }

Uses `BaseUnix, Unix`;

Var `Si, So : Text`;

```

S : String;
i : longint;

begin
  if not (paramstr(1)='-son') then
    begin
      Writeln ('Calling son');
      Assignstream (Si,So,'./ex38',[ '-son']);
      if fpgeterrno<>0 then
        begin
          writeln ('AssignStream failed !');
          halt(1);
        end;
      Writeln ('Speaking to son');
      For i:=1 to 10 do
        begin
          writeln (so,'Hello son !');
          if ioresult<>0 then writeln ('Can''t speak to son...');
        end;
      For i:=1 to 3 do writeln (so,'Hello chap !');
      close (so);
      while not eof(si) do
        begin
          readln (si,s);
          writeln ('Father: Son said : ',S);
        end;
      Writeln ('Stopped conversation');
      Close (Si);
      Writeln ('Put down phone');
    end
  Else
    begin
      Writeln ('This is the son ');
      While not eof (input) do
        begin
          readln (s);
          if pos ('Hello son !',S)<>0 then
            Writeln ('Hello Dad !')
          else
            writeln ('Who are you ?');
          end;
        close (output);
      end
    end
end.

```

81.3.3 FpExecL

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecL(const PathName: AnsiString;
const S: Array of AnsiString) : cint`

Visibility: default

Description: `FpExecL` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The current process' environment is passed to the program. On success, `FpExecL` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (181) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eLOOPThe path contains a circular reference (via symlinks).

See also: `FpExecve` (175), `FpExecv` (1861), `FpExecvp` (1862), `FpExecle` (1859), `FpExeclp` (1860), `FpFork` (178)

Listing: ./unixex/ex77.pp

Program Example77;

{ Program to demonstrate the FPEXecL function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
 FpExecL ('/bin/ls' , ['-l']);

end.

81.3.4 FpExecLE

Synopsis: Execute process (using argument list, environment)

Declaration: `function FpExecLE(const PathName: AnsiString;
 const S: Array of AnsiString; MyEnv: PPChar) : cint`

Visibility: default

Description: `FpExecLE` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` must be an absolute pathname. The environment in `MyEnv` is passed to the program. On success, `FpExecLE` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (181) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` (175), `FpExecv` (1861), `FpExecvp` (1862), `FpExecl` (1858), `FpExeclp` (1860), `FpFork` (178)

Listing: ./unixex/ex11.pp

Program Example11;

{ Program to demonstrate the Execl function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is NOT looked for in PATH environment variable. }
{ envp is defined in the system unit. }
 Execl ('/bin/ls -l', envp);

end.

81.3.5 FpExecLP

Synopsis: Execute process (using argument list, environment; search path)

Declaration: `function FpExecLP(const PathName: AnsiString;
 const S: Array of AnsiString) : cint`

Visibility: default

Description: `FpExecLP` replaces the currently running program with the program, specified in `PathName`. `S` is an array of command options. The executable in `PathName` is searched in the path, if it isn't an absolute filename. The current environment is passed to the program. On success, `FpExecLP` does not return.

Errors: Extended error information is returned by the `FpGetErrno` (181) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel, or to split command line.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` (175), `FpExecv` (1861), `FpExecvp` (1862), `FpExecl` (1859), `FpExeclp` (1858), `FpFork` (178)

Listing: ./unixex/ex76.pp

Program Example76;

{ Program to demonstrate the FpExeclp function. }

Uses Unix, strings;

begin

{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
{ envp is defined in the system unit. }
 FpExeclp ('ls', ['-l']);

end.

81.3.6 FpExecLPE

Synopsis: Execute a program in the path, and pass it an environment

Declaration: function FpExecLPE(const PathName: AnsiString;
 const S: Array of AnsiString; env: PPChar) : cint

Visibility: default

Description: FpExecLPE does the same as FpExecLP (1860), but additionally it specifies the environment for the new process in env, a pointer to a null-terminated array of null-terminated strings.

Errors: On success, this function does not return.

See also: FpExecLP (1860), FpExecLE (1859)

81.3.7 FpExecV

Synopsis: Execute process

Declaration: function FpExecV(const PathName: AnsiString; args: PPChar) : cint

Visibility: default

Description: FpExecV replaces the currently running program with the program, specified in PathName. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The current environment is passed to the program. On success, FpExecV does not return.

Errors: Extended error information is returned by the FpGetErrno (181) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` ([175](#)), `FpExecvp` ([1862](#)), `FpExecle` ([1859](#)), `FpExecl` ([1858](#)), `FpExeclp` ([1860](#)), `FpFork` ([178](#))

Listing: `./unixex/ex8.pp`

Program `Example8`;

{ Program to demonstrate the Execv function. }

Uses `Unix`, `strings`;

Const `Arg0` : `PChar` = `'/bin/lS'`;
 `Arg1` : `Pchar` = `'-l'`;

Var `PP` : `PPchar`;

begin

`GetMem` (`PP`, `3 * SizeOf (Pchar)`);

`PP[0]` := `Arg0`;

`PP[1]` := `Arg1`;

`PP[3]` := `Nil`;

{ Execute '/bin/lS -l', with current environment }

`fpExecv` (`'/bin/lS'`, `pp`);

end.

81.3.8 FpExecVP

Synopsis: Execute process, search path

Declaration: `function FpExecVP(const PathName: AnsiString; args: PPChar) : cint`

Visibility: `default`

Description: `FpExecVP` replaces the currently running program with the program, specified in `PathName`. The executable in `path` is searched in the path, if it isn't an absolute filename. It gives the program the options in `args`. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be `nil`. The current environment is passed to the program. On success, `execvp` does not return.

Errors: Extended error information is returned by the `FpGetErrno` ([181](#)) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: `FpExecve` ([175](#)), `FpExecv` ([1861](#)), `FpExecle` ([1859](#)), `FpExecl` ([1858](#)), `FpExeclp` ([1860](#)), `FpFork` ([178](#))

Listing: ./unixex/ex79.pp

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
 Arg1 : Pchar = '-l';

Var PP : PPchar;

begin

GetMem (PP, 3***SizeOf**(Pchar));
 PP[0] := Arg0;
 PP[1] := Arg1;
 PP[2] := **Nil**;
{ Execute 'ls -l', with current environment. }
{ 'ls' is looked for in PATH environment variable. }
 fpExecvp ('ls', pp);

end.

81.3.9 FpExecVPE

Synopsis: Execute process, search path using environment

Declaration: function FpExecVPE(const PathName: AnsiString; args: PPChar;
 env: PPChar) : cint

Visibility: default

Description: FpExecVP replaces the currently running program with the program, specified in PathName. The executable in path is searched in the path, if it isn't an absolute filename. It gives the program the options in args. This is a pointer to an array of pointers to null-terminated strings. The last pointer in this array should be nil. The environment in Env is passed to the program. On success, execvp does not return.

Errors: Extended error information is returned by the FpGetErrno (181) function:

sys_eaccessFile is not a regular file, or has no execute permission. A component of the path has no search permission.

sys_epermThe file system is mounted *noexec*.

sys_e2bigArgument list too big.

sys_enoexecThe magic number in the file is incorrect.

sys_enoentThe file does not exist.

sys_enomemNot enough memory for kernel.

sys_enotdirA component of the path is not a directory.

sys_eloopThe path contains a circular reference (via symlinks).

See also: FpExecve (175), FpExecv (1861), FpExecl (1859), FpExecl (1858), FpExeclp (1860), FpFork (178)

Listing: ./unixex/ex79.pp

```

Program Example79;

{ Program to demonstrate the FpExecVP function. }

Uses Unix, strings;

Const Arg0 : PChar = 'ls';
        Arg1 : Pchar = '-l';

Var PP : PPchar;

begin
  GetMem (PP,3*SizeOf(Pchar));
  PP[0]:=Arg0;
  PP[1]:=Arg1;
  PP[2]:=Nil;
  { Execute 'ls -l', with current environment. }
  { 'ls' is looked for in PATH environment variable.}
  fpExecvp ('ls',pp);
end.

```

81.3.10 fpFlock

Synopsis: Lock a file (advisory lock)

Declaration: function fpFlock(var T: text; mode: cint) : cint
 function fpFlock(var F: File; mode: cint) : cint
 function fpFlock(fd: cint; mode: cint) : cint

Visibility: default

Description: FpFlock implements file locking. it sets or removes a lock on the file F. F can be of type Text or File, or it can be a Linux filedescriptor (a longint) Mode can be one of the following constants :

LOCK_SHsets a shared lock.

LOCK_EXsets an exclusive lock.

LOCK_UNunlocks the file.

LOCK_NBThis can be OR-ed together with the other. If this is done the application doesn't block when locking.

The function returns zero if successful, a nonzero return value indicates an error.

Errors: Extended error information is returned by the FpGetErrno ([181](#)) function:

See also: #rtl.baseunix.FpFcntl ([176](#)), FSync ([1840](#))

81.3.11 fpfStatFS

Synopsis: Retrieve filesystem information.

Declaration: function fpfStatFS(Fd: cint; Info: pstatfs) : cint

Visibility: default

Description: `fpStatFS` returns in `Info` information about the filesystem on which the open file descriptor `fd` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpStatFS` (1865), `#rtl.baseunix.fpfStat` (178)

81.3.12 `fpfsync`

Synopsis: Flush cached data to disk

Declaration: `function fpfsync(fd: cint) : cint`

Visibility: default

Description: `fpfsync` forces the system to write all paged (in-memory) changes to file descriptor `fd` to disk. If the call was succesful, 0 is returned.

Errors: On error, a nonzero error-code is returned.

81.3.13 `fpgettimeofday`

Synopsis: Return kernel time of day in GMT

Declaration: `function fpgettimeofday(tp: timeval; tzp: ptimzone) : cint`

Visibility: default

Description: `FpGetTimeOfDay` returns the number of seconds since 00:00, January 1 1970, GMT in a `timeval` record. This time NOT corrected any way, not taking into account timezones, daylight savings time and so on.

It is simply a wrapper to the kernel system call.

Errors: None.

81.3.14 `fpStatFS`

Synopsis: Retrieve filesystem information.

Declaration: `function fpStatFS(Path: PChar; Info: pstatfs) : cint`
`function fpStatFS(Path: ansistring; Info: pstatfs) : cint`

Visibility: default

Description: `fpStatFS` returns in `Info` information about the filesystem on which the file or path `Path` resides. `Info` is of type `tstatfs`. The function returns 0 if the call was succesfull, or an error code if the call failed.

Errors: On error, a non-zero error code is returned

See also: `fpStatFS` (1864), `#rtl.baseunix.fpfStat` (210)

81.3.15 fpSystem

Synopsis: Execute and feed command to system shell

Declaration: `function fpSystem(const Command: string) : cint`
`function fpSystem(const Command: AnsiString) : cint`

Visibility: default

Description: `FpSystem` invokes the bash shell (`/bin/sh`), and feeds it the command `Command` (using the `-c` option). The function then waits for the command to complete, and then returns the exit status of the command in `wait(3)` format, or 127 if it could not complete the `FpFork` (178) or `FpExecve` (175) calls. To convert the return value of `fpssystem` to the real return value use `WEXITSTATUS()` (220).

Errors: Errors are reported in `(fpget)ErrNo` (181)

See also: `POpen` (1869), `FpFork` (178), `FpExecve` (175)

Listing: `./unixex/ex80.pp`

```

program example56;

uses Unix;

{ Program to demonstrate the Shell function }

Var S : Longint;

begin
  Writeln ('Output of ls -l *.pp');
  S:=fpSystem('ls -l *.pp');
  Writeln ('Command exited with status : ',S);
end.

```

81.3.16 FSearch

Synopsis: Search for file in search path.

Declaration: `function FSearch(const path: AnsiString; dirlist: AnsiString;`
`CurrentDirStrategy: TFSearchOption) : AnsiString`
`function FSearch(const path: AnsiString; dirlist: AnsiString)`
`: AnsiString`

Visibility: default

Description: `FSearch` searches in `DirList`, a colon separated list of directories, for a file named `Path`. It then returns a path to the found file.

The `CurrentDirStrategy` determines how the current directory is treated when searching:

NoCurrentDirectory Do not search the current directory unless it is specified in the search path.

CurrentDirectoryFirstSearch the current directory first, before all directories in the search path.

CurrentDirectoryLastSearch the current directory last, after all directories in the search path

It is mainly provided to mimic DOS search path behaviour. Default behaviour is to search the current directory first.

Errors: An empty string if no such file was found.

See also: `#rtl.unixutil.FNMatch` ([1894](#))

Listing: `./unixex/ex46.pp`

Program `Example46;`

{ Program to demonstrate the FSearch function. }

Uses `BaseUnix, Unix, Strings;`

begin

`WriteLn ('Is is in : ', FSearch ('Is', strpas(fpGetenv('PATH'))));`
end.

81.3.17 GetDomainName

Synopsis: Return current domain name

Declaration: `function GetDomainName : string`

Visibility: `default`

Description: Get the domain name of the machine on which the process is running. An empty string is returned if the domain is not set.

Errors: None.

See also: `GetHostName` ([1867](#))

Listing: `./unixex/ex39.pp`

Program `Example39;`

{ Program to demonstrate the GetDomainName function. }

Uses `Unix;`

begin

`WriteLn ('Domain name of this machine is : ', GetDomainName);`
end.

81.3.18 GetHostName

Synopsis: Return host name

Declaration: `function GetHostName : string`

Visibility: `default`

Description: Get the hostname of the machine on which the process is running. An empty string is returned if hostname is not set.

Errors: None.

See also: `GetDomainName` ([1867](#))

Listing: `./unixex/ex40.pp`

Program Example40;

{ Program to demonstrate the GetHostName function. }

Uses unix;

begin

WriteLn ('Name of this machine is : ',GetHostName);
end.

81.3.19 GetLocalTimezone

Synopsis: Return local timzeone information

Declaration: `procedure GetLocalTimezone(timer: cint; var leap_correct: cint;
 var leap_hit: cint)
 procedure GetLocalTimezone(timer: cint)`

Visibility: default

Description: `GetLocalTimezone` returns the local timezone information. It also initializes the `TZSeconds` variable, which is used to correct the epoch time to local time.

There should never be any need to call this function directly. It is called by the initialization routines of the Linux unit.

See also: `GetTimezoneFile` ([1868](#)), `ReadTimezoneFile` ([1870](#))

81.3.20 GetTimezoneFile

Synopsis: Return name of timezone information file

Declaration: `function GetTimezoneFile : string`

Visibility: default

Description: `GetTimezoneFile` returns the location of the current timezone file. The location of file is determined as follows:

- 1.If `/etc/timezone` exists, it is read, and the contents of this file is returned. This should work on Debian systems.
- 2.If `/usr/lib/zoneinfo/localtime` exists, then it is returned. (this file is a symlink to the timezone file on SuSE systems)
- 3.If `/etc/localtime` exists, then it is returned. (this file is a symlink to the timezone file on RedHat systems)

Errors: If no file was found, an empty string is returned.

See also: `ReadTimezoneFile` ([1870](#))

81.3.21 PClose

Synopsis: Close file opened with POpen (1869)

Declaration: `function PClose(var F: File) : cint`
`function PClose(var F: text) : cint`

Visibility: default

Description: `PClose` closes a file opened with `POpen` (1869). It waits for the command to complete, and then returns the exit status of the command.

For an example, see `POpen` (1869)

Errors: Extended error information is returned by the `FpGetErrno` (181) function.

See also: `POpen` (1869)

81.3.22 POpen

Synopsis: Pipe file to standard input/output of program

Declaration: `function POpen(var F: text; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: File; const Prog: RawByteString; rw: Char) : cint`
`function POpen(var F: text; const Prog: UnicodeString; rw: Char) : cint`
`function POpen(var F: File; const Prog: UnicodeString; rw: Char) : cint`

Visibility: default

Description: `POpen` runs the command specified in `Prog`, and redirects the standard in or output of the command to the other end of the pipe `F`. The parameter `rw` indicates the direction of the pipe. If it is set to 'W', then `F` can be used to write data, which will then be read by the command from `stdin`. If it is set to 'R', then the standard output of the command can be read from `F`. `F` should be reset or rewritten prior to using it. `F` can be of type `Text` or `File`. A file opened with `POpen` can be closed with `Close`, but also with `PClose` (1869). The result is the same, but `PClose` returns the exit status of the command `Prog`.

Errors: Extended error information is returned by the `FpGetErrno` (181) function. Errors are essentially those of the `Execve`, `Dup` and `AssignPipe` commands.

See also: `AssignPipe` (1856), `PClose` (1869)

Listing: `./unixex/ex37.pp`

Program `Example37`;

```
{ Program to demonstrate the Popen function. }
```

```
uses BaseUnix, Unix;
```

```
var f : text;  
    i : longint;
```

```
begin
```

```
  writeln ('Creating a shell script to which echoes its arguments');  
  writeln ('and input back to stdout');  
  assign (f, 'test21a');  
  rewrite (f);  
  writeln (f, '#!/bin/sh');
```

```

writeln (f, 'echo this is the child speaking.... ');
writeln (f, 'echo got arguments \*$*\');
writeln (f, 'cat');
writeln (f, 'exit 2');
writeln (f);
close (f);
fpchmod ('test21a', &755);
popen (f, './test21a arg1 arg2', 'W');
if fpgeterrno <> 0 then
    writeln ('error from POpen : errno : ', fpgeterrno);
for i:=1 to 10 do
    writeln (f, 'This is written to the pipe, and should appear on stdout. ');
Flush(f);
Writeln ('The script exited with status : ', PClose (f));
writeln;
writeln ('Press <return> to remove shell script. ');
readln;
assign (f, 'test21a');
erase (f)
end.

```

81.3.23 ReadTimezoneFile

Synopsis: Read the timezone file and initialize time routines

Declaration: `procedure ReadTimezoneFile(fn: string)`

Visibility: default

Description: `ReadTimezoneFile` reads the timezone file `fn` and initializes the local time routines based on the information found there.

There should be no need to call this function. The initialization routines of the linux unit call this routine at unit startup.

Errors: None.

See also: `GetTimezoneFile` ([1868](#)), `GetLocalTimezone` ([1868](#))

81.3.24 ReReadLocalTime

Synopsis: Re-Read the local time files.

Declaration: `procedure ReReadLocalTime`

Visibility: default

Description: `ReReadLocalTime` can be used to re-initialize the local timezone information.

To speed up conversion of epoch (UTC) time to local time, the timezone information is loaded only once, at program startup. Calling this routine re-reads the timezone information using current timezone settings.

The `EpochToLocal` ([1895](#)) function uses timezone information to transform epoch time to local time. This timezone information does not change while the application is running: in particular, on DST transitions or when the timezone files change, the time returned by local time routines will be wrong.

See also: `Date` ([1499](#)), `Time` ([1597](#)), `Now` ([1564](#)), `EpochToLocal` ([1895](#))

81.3.25 SeekDir

Synopsis: Seek to position in directory

Declaration: `procedure SeekDir(p: pDir; loc: clong)`

Visibility: default

Description: `SeekDir` sets the directory pointer to the `loc`-th entry in the directory structure pointed to by `p`.

For an example, see `#rtl.baseunix.fpOpenDir` (194).

Errors: Extended error information is returned by the `FpGetErrno` (181) function:

See also: `#rtl.baseunix.fpCloseDir` (172), `#rtl.baseunix.fpReadDir` (199), `#rtl.baseunix.fpOpenDir` (194), `TellDir` (1872)

81.3.26 SelectText

Synopsis: Wait for event on text file.

Declaration: `function SelectText(var T: Text; TimeOut: ptimeval) : cint`
`function SelectText(var T: Text; TimeOut: cint) : cint`

Visibility: default

Description: `SelectText` executes the `FpSelect` (202) call on a file of type `Text`. You can specify a timeout in `TimeOut`. The `SelectText` call determines itself whether it should check for read or write, depending on how the file was opened : With `Reset` it is checked for reading, with `Rewrite` and `Append` it is checked for writing.

Errors: See `#rtl.baseunix.FpSelect` (202). `SYS_EBADF` can also mean that the file wasn't opened.

See also: `#rtl.baseunix.FpSelect` (202)

81.3.27 SigRaise

Synopsis: Raise a signal (send to current process)

Declaration: `procedure SigRaise(sig: Integer)`

Visibility: default

Description: `SigRaise` sends a `Sig` signal to the current process.

Errors: None.

See also: `#rtl.baseunix.FpKill` (186), `#rtl.baseunix.FpGetPid` (183)

Listing: `./unixex/ex65.pp`

Program `example64`;

{ Program to demonstrate the fpKill/getPID function. }

uses `Unix`, `BaseUnix`;

Var

`oa, na : PSigActionrec`;

```

Procedure DoSig(sig : Longint);cdecl;

begin
  writeln('Receiving signal: ',sig);
end;

begin
  new(na);
  new(oa);
  na^.sa_handler:=SigActionHandler(@DoSig);
  fillchar(na^.Sa_Mask,sizeof(na^.Sa_Mask),#0);
  na^.Sa_Flags:=0;
  { $ifdef Linux }
  // this member is linux only, and afaik even there arcane
  na^.Sa_Restorer:=Nil;
  { $endif }
  if fpSigAction(SigUsrc1,na,oa)<>0 then
    begin
      writeln('Error: ',fpgeterrno);
      halt(1);
    end;
    Writeln('Sending USR1 (',sigusr1,') signal to self. ');
    fpKill(fpgetPID,sigusr1);
  end.

```

81.3.28 TellDir

Synopsis: Return current location in a directory

Declaration: function TellDir(p: pDir) : TOff

Visibility: default

Description: TellDir returns the current location in the directory structure pointed to by p. It returns -1 on failure.

For an example, see #rtl.baseunix.fpOpenDir ([194](#)).

See also: #rtl.baseunix.fpCloseDir ([172](#)), #rtl.baseunix.fpReadDir ([199](#)), #rtl.baseunix.fpOpenDir ([194](#)), SeekDir ([1871](#))

81.3.29 WaitProcess

Synopsis: Wait for process to terminate.

Declaration: function WaitProcess(Pid: cint) : cint

Visibility: default

Description: WaitProcess waits for process PID to exit. WaitProcess is equivalent to the #rtl.baseunix.FpWaitPID ([218](#)) call:

```
FpWaitPid(PID,@result,0)
```

Handles of Signal interrupts (errno=EINTR), and returns the Exitcode of Process PID (>=0) or - Status if it was terminated

Errors: None.

See also: [#rtl.baseunix.FpWaitPID \(218\)](#), [#rtl.baseunix.WTERMSIG \(221\)](#), [#rtl.baseunix.WSTOPSIG \(220\)](#), [#rtl.baseunix.WIFEXITED \(220\)](#), [WIFSTOPPED \(1873\)](#), [#rtl.baseunix.WIFSIGNALLED \(220\)](#), [W_EXITCODE \(1873\)](#), [W_STOPCODE \(1873\)](#), [#rtl.baseunix.WEXITSTATUS \(220\)](#)

81.3.30 WIFSTOPPED

Synopsis: Check whether the process is currently stopped.

Declaration: `function WIFSTOPPED(Status: Integer) : Boolean`

Visibility: default

Description: `WIFSTOPPED` checks `Status` and returns `true` if the process is currently stopped. This is only possible if `WUNTRACED` was specified in the options of [FpWaitPID \(218\)](#).

See also: [#rtl.baseunix.FpWaitPID \(218\)](#), [WaitProcess \(1872\)](#), [#rtl.baseunix.WTERMSIG \(221\)](#), [#rtl.baseunix.WSTOPSIG \(220\)](#), [#rtl.baseunix.WIFEXITED \(220\)](#), [#rtl.baseunix.WIFSIGNALLED \(220\)](#), [W_EXITCODE \(1873\)](#), [W_STOPCODE \(1873\)](#), [#rtl.baseunix.WEXITSTATUS \(220\)](#)

81.3.31 W_EXITCODE

Synopsis: Construct an exit status based on an return code and signal.

Declaration: `function W_EXITCODE(ReturnCode: Integer; Signal: Integer) : Integer`

Visibility: default

Description: `W_EXITCODE` combines `ReturnCode` and `Signal` to a status code fit for `WaitPid`.

See also: [#rtl.baseunix.FpWaitPID \(218\)](#), [WaitProcess \(1872\)](#), [#rtl.baseunix.WTERMSIG \(221\)](#), [#rtl.baseunix.WSTOPSIG \(220\)](#), [#rtl.baseunix.WIFEXITED \(220\)](#), [WIFSTOPPED \(1873\)](#), [#rtl.baseunix.WIFSIGNALLED \(220\)](#), [W_EXITCODE \(1873\)](#), [W_STOPCODE \(1873\)](#), [#rtl.baseunix.WEXITSTATUS \(220\)](#)

81.3.32 W_STOPCODE

Synopsis: Construct an exit status based on a signal.

Declaration: `function W_STOPCODE(Signal: Integer) : Integer`

Visibility: default

Description: `W_STOPCODE` constructs an exit status based on `Signal`, which will cause [WIFSIGNALLED \(220\)](#) to return `True`

See also: [#rtl.baseunix.FpWaitPID \(218\)](#), [WaitProcess \(1872\)](#), [#rtl.baseunix.WTERMSIG \(221\)](#), [#rtl.baseunix.WSTOPSIG \(220\)](#), [#rtl.baseunix.WIFEXITED \(220\)](#), [WIFSTOPPED \(1873\)](#), [#rtl.baseunix.WIFSIGNALLED \(220\)](#), [W_EXITCODE \(1873\)](#), [#rtl.baseunix.WEXITSTATUS \(220\)](#)

Chapter 82

Reference for unit 'unixcp'

82.1 Used units

Table 82.1: Used units by unit 'unixcp'

Name	Page
BaseUnix	124
System	1194

82.2 Overview

The `unixcp` unit provides routines to handle mapping of code page names to numerical values as used in `libiconv`. The `GetCodepageByName` ([1877](#)) function is the main function for this. The `GetCodepageData` ([1878](#)) can be used to map a code page number to a name. These function can be used for instance to map code page information in environment variables to code page numbers used in string encodings. The supported code page names are the ones commonly in use in `libiconv`.

This unit is used for example in unit `cwstring` ([535](#)).

82.3 Constants, types and variables

82.3.1 Constants

```
UnixCpMap : Array[-1..UnixCpMapLimit] of TUnixCpData = ((cp: 0; name
: 'UTF-8'), (cp: 37; name: 'IBM037'), (cp: 37; name: 'IBM-037'),
(cp: 154; name: 'CP154'), (cp: 154; name: 'CYRILLIC-ASIAN'), (cp:
154; name: 'PT154'), (cp: 154; name: 'PTCP154'), (cp: 154; name:
'CSPTCP154'), (cp: 437; name: '437'), (cp: 437; name: 'CP437'),
(cp: 437; name: 'IBM-437'), (cp: 437; name: 'CSPC8CODEPAGE437'),
(cp: 437; name: 'IBM437'), (cp: 500; name: 'IBM500'), (cp: 500; name
: 'IBM-500'), (cp: 708; name: 'ASMO-708'), (cp: 720; name: 'DOS-720'
), (cp: 737; name: 'CP737'), (cp: 737; name: 'ibm737'), (cp: 775;
name: 'CP775'), (cp: 775; name: 'IBM775'), (cp: 775; name: 'CSPC775BALTIC'
), (cp: 775; name: 'ibm775'), (cp: 850; name: '850'), (cp: 850; name
: 'CP850'), (cp: 850; name: 'IBM850'), (cp: 850; name: 'CSPC850MULTILINGUAL'
```

), (cp: 850; name: 'ibm850'), (cp: 852; name: '852'), (cp: 852; name: 'CP852'), (cp: 852; name: 'IBM852'), (cp: 852; name: 'CSPCP852'), (cp: 852; name: 'ibm852'), (cp: 853; name: 'CP853'), (cp: 855; name: '855'), (cp: 855; name: 'CP855'), (cp: 855; name: 'IBM855'), (cp: 855; name: 'CSIBM855'), (cp: 855; name: 'IBM855'), (cp: 857; name: '857'), (cp: 857; name: 'CP857'), (cp: 857; name: 'IBM857'), (cp: 857; name: 'CSIBM857'), (cp: 857; name: 'ibm857'), (cp: 858; name: 'CP858'), (cp: 858; name: 'IBM00858'), (cp: 860; name: '860'), (cp: 860; name: 'CP860'), (cp: 860; name: 'IBM860'), (cp: 860; name: 'CSIBM860'), (cp: 860; name: 'IBM860'), (cp: 861; name: '861'), (cp: 861; name: 'CP-IS'), (cp: 861; name: 'CP861'), (cp: 861; name: 'IBM861'), (cp: 861; name: 'CSIBM861'), (cp: 861; name: 'ibm861'), (cp: 862; name: '862'), (cp: 862; name: 'CP862'), (cp: 862; name: 'IBM862'), (cp: 862; name: 'CSPC862LATINHEBREW'), (cp: 862; name: 'DOS-862'), (cp: 863; name: '863'), (cp: 863; name: 'CP863'), (cp: 863; name: 'CSIBM863'), (cp: 863; name: 'IBM863'), (cp: 864; name: 'CP864'), (cp: 864; name: 'CSIBM864'), (cp: 864; name: 'IBM864'), (cp: 865; name: '865'), (cp: 865; name: 'IBM-865'), (cp: 865; name: 'CP865'), (cp: 865; name: 'CSIBM865'), (cp: 865; name: 'IBM865'), (cp: 866; name: '866'), (cp: 866; name: 'CP866'), (cp: 866; name: 'IBM866'), (cp: 866; name: 'CSIBM866'), (cp: 866; name: 'cp866'), (cp: 869; name: '869'), (cp: 869; name: 'IBM-869'), (cp: 869; name: 'CP-GR'), (cp: 869; name: 'CP869'), (cp: 869; name: 'IBM869'), (cp: 869; name: 'CSIBM869'), (cp: 869; name: 'ibm869'), (cp: 870; name: 'IBM870'), (cp: 874; name: 'CP874'), (cp: 874; name: 'WINDOWS-874'), (cp: 874; name: 'windows-874'), (cp: 875; name: 'cp875'), (cp: 932; name: 'CP932'), (cp: 932; name: 'IBM-943'), (cp: 932; name: 'MS932'), (cp: 932; name: 'SHIFFT_JIS'), (cp: 932; name: 'SHIFFT_JIS-MS'), (cp: 932; name: 'SJIS'), (cp: 932; name: 'SJIS-MS'), (cp: 932; name: 'SJIS-OPEN'), (cp: 932; name: 'SJIS-WIN'), (cp: 932; name: 'WINDOWS-31J'), (cp: 932; name: 'WINDOWS-932'), (cp: 932; name: 'CSWINDOWS31J'), (cp: 932; name: 'shift_jis'), (cp: 932; name: 'shift-jis'), (cp: 936; name: 'CP936'), (cp: 936; name: 'GBK'), (cp: 936; name: 'MS936'), (cp: 936; name: 'WINDOWS-936'), (cp: 936; name: 'gb2312'), (cp: 949; name: 'CP949'), (cp: 949; name: 'UHC'), (cp: 949; name: 'EUC-KR'), (cp: 949; name: 'ks_c_5601-1987'), (cp: 950; name: 'CP950'), (cp: 950; name: 'BIG5'), (cp: 950; name: 'big5'), (cp: 1026; name: 'IBM1026'), (cp: 1047; name: 'IBM01047'), (cp: 1125; name: 'CP1125'), (cp: 1125; name: 'IBM-1125'), (cp: 1133; name: 'CP1133'), (cp: 1133; name: 'IBM-1133'), (cp: 1133; name: 'IBM-CP1133'), (cp: 1140; name: 'IBM01140'), (cp: 1141; name: 'IBM01141'), (cp: 1142; name: 'IBM01142'), (cp: 1143; name: 'IBM01143'), (cp: 1144; name: 'IBM01144'), (cp: 1145; name: 'IBM01145'), (cp: 1146; name: 'IBM01146'), (cp: 1147; name: 'IBM01147'), (cp: 1148; name: 'IBM01148'), (cp: 1149; name: 'IBM01149'), (cp: 1200; name: 'UTF-16LE'), (cp: 1200; name: 'UTF16LE'), (cp: 1200; name: 'UCS-2LE'), (cp: 1200; name: 'CP1200'), (cp: 1201; name: 'UTF-16BE'), (cp: 1201; name: 'UTF16BE'), (cp: 1201; name: 'UCS-2BE'), (cp: 1201; name: 'unicodeFFFE'), (cp: 1201; name: 'CP1201'), (cp: 1250; name: 'CP1250'), (cp: 1250; name: 'MS-EE'), (cp: 1250; name: 'WINDOWS-1250'), (cp: 1250; name: 'windows-1250'), (cp: 1251; name: 'CP1251'), (cp: 1251; name: 'MS-CYRL'), (cp: 1251; name: 'WINDOWS-1251'), (cp: 1251; name: 'windows-1251'), (cp: 1252; name: 'CP819'), (cp: 1252; name: 'IBM819'), (cp: 1252; name: 'CP1252'), (cp: 1252; name: 'MS-ANSI'), (cp: 1252; name: 'WINDOWS-1252'), (cp: 1252; name: 'windows-1252'

```

), (cp: 1253; name: 'CP1253'), (cp: 1253; name: 'MS-GREEK'), (cp:
1253; name: 'WINDOWS-1253'), (cp: 1253; name: 'windows-1253'), (cp
: 1254; name: 'CP1254'), (cp: 1254; name: 'MS-TURK'), (cp: 1254; name
: 'WINDOWS-1254'), (cp: 1254; name: 'windows-1254'), (cp: 1255; name
: 'CP1255'), (cp: 1255; name: 'MS-HEBR'), (cp: 1255; name: 'WINDOWS-1255'
), (cp: 1255; name: 'windows-1255'), (cp: 1256; name: 'CP1256'),
(cp: 1256; name: 'MS-ARAB'), (cp: 1256; name: 'WINDOWS-1256'), (cp
: 1256; name: 'windows-1256'), (cp: 1257; name: 'CP1257'), (cp: 1257
; name: 'WINBALTRIM'), (cp: 1257; name: 'WINDOWS-1257'), (cp: 1257
; name: 'windows-1257'), (cp: 1258; name: 'CP1258'), (cp: 1258; name
: 'WINDOWS-1258'), (cp: 1258; name: 'windows-1258'), (cp: 1361; name
: 'CP1361'), (cp: 1361; name: 'JOHAB'), (cp: 1361; name: 'Johab')
, (cp: 10000; name: 'macintosh'), (cp: 10001; name: 'x-mac-japanese'
), (cp: 10002; name: 'x-mac-chinesetrad'), (cp: 10003; name: 'x-mac-korean'
), (cp: 10004; name: 'x-mac-arabic'), (cp: 10005; name: 'x-mac-hebrew'
), (cp: 10006; name: 'x-mac-greek'), (cp: 10007; name: 'x-mac-cyrillic'
), (cp: 10008; name: 'x-mac-chinesesimp'), (cp: 10010; name: 'x-mac-romanian'
), (cp: 10017; name: 'x-mac-ukrainian'), (cp: 10021; name: 'x-mac-thai'
), (cp: 10029; name: 'x-mac-ce'), (cp: 10079; name: 'x-mac-icelandic'
), (cp: 10081; name: 'x-mac-turkish'), (cp: 10082; name: 'x-mac-croatian'
), (cp: 12000; name: 'UTF-32LE'), (cp: 12000; name: 'CP12000'), (cp
: 12000; name: 'UTF32LE'), (cp: 12001; name: 'UTF-32BE'), (cp: 12001
; name: 'CP12001'), (cp: 12001; name: 'UTF32BE'), (cp: 20000; name
: 'x-Chinese_CNS'), (cp: 20001; name: 'x-cp20001'), (cp: 20002; name
: 'x_Chinese-Eten'), (cp: 20003; name: 'x-cp20003'), (cp: 20004; name
: 'x-cp20004'), (cp: 20005; name: 'x-cp20005'), (cp: 20105; name:
'x-IA5'), (cp: 20106; name: 'x-IA5-German'), (cp: 20107; name: 'x-IA5-Swedish'
), (cp: 20108; name: 'x-IA5-Norwegian'), (cp: 20127; name: 'US-ASCII'
), (cp: 20127; name: 'ASCII'), (cp: 20127; name: 'ANSI_X3.4-1968'
), (cp: 20127; name: 'ANSI_X3.4-1986'), (cp: 20127; name: 'CP367'
), (cp: 20127; name: 'IBM367'), (cp: 20127; name: 'ISO-IR-6'), (cp
: 20127; name: 'ISO646-US'), (cp: 20127; name: 'ISO_646.IRV:1991'
), (cp: 20127; name: 'US'), (cp: 20127; name: 'CSASCII'), (cp: 20127
; name: 'us-ascii'), (cp: 20261; name: 'x-cp20261'), (cp: 20269; name
: 'x-cp20269'), (cp: 20273; name: 'IBM273'), (cp: 20277; name: 'IBM277'
), (cp: 20278; name: 'IBM278'), (cp: 20280; name: 'IBM280'), (cp:
20284; name: 'IBM284'), (cp: 20285; name: 'IBM285'), (cp: 20290;
name: 'IBM290'), (cp: 20297; name: 'IBM297'), (cp: 20420; name: 'IBM420'
), (cp: 20423; name: 'IBM423'), (cp: 20424; name: 'IBM424'), (cp:
20833; name: 'x-EBCDIC-KoreanExtended'), (cp: 20838; name: 'IBM-Thai'
), (cp: 20866; name: 'koi8-r'), (cp: 20871; name: 'IBM871'), (cp:
20880; name: 'IBM880'), (cp: 20905; name: 'IBM905'), (cp: 20924;
name: 'IBM00924'), (cp: 20932; name: 'EUC-JP'), (cp: 20936; name
: 'x-cp20936'), (cp: 20949; name: 'x-cp20949'), (cp: 21025; name:
'cp1025'), (cp: 21866; name: 'koi8-u'), (cp: 28591; name: 'ISO-8859-1'
), (cp: 28591; name: 'ISO-IR-100'), (cp: 28591; name: 'ISO8859-1'
), (cp: 28591; name: 'ISO_8859-1'), (cp: 28591; name: 'ISO_8859-1:1987'
), (cp: 28591; name: 'L1'), (cp: 28591; name: 'LATIN1'), (cp: 28591
; name: 'CSISOLATIN1'), (cp: 28591; name: 'iso-8859-1'), (cp: 28591
; name: 'iso8859-1'), (cp: 28592; name: 'iso-8859-2'), (cp: 28592
; name: 'iso8859-2'), (cp: 28593; name: 'iso-8859-3'), (cp: 28593
; name: 'iso8859-3'), (cp: 28594; name: 'iso-8859-4'), (cp: 28594
; name: 'iso8859-4'), (cp: 28595; name: 'iso-8859-5'), (cp: 28595
; name: 'iso8859-5'), (cp: 28596; name: 'iso-8859-6'), (cp: 28596

```

```

; name: 'iso8859-6'), (cp: 28597; name: 'iso-8859-7'), (cp: 28597
; name: 'iso8859-7'), (cp: 28598; name: 'iso-8859-8'), (cp: 28598
; name: 'iso8859-8'), (cp: 28599; name: 'iso-8859-9'), (cp: 28599
; name: 'iso8859-9'), (cp: 28603; name: 'iso-8859-13'), (cp: 28603
; name: 'iso8859-13'), (cp: 28605; name: 'iso-8859-15'), (cp: 28605
; name: 'iso8859-15'), (cp: 29001; name: 'x-Europa'), (cp: 38598;
name: 'iso-8859-8-i'), (cp: 38598; name: 'iso8859-8-i'), (cp: 50220
; name: 'iso-2022-jp'), (cp: 50221; name: 'ISO-2022-JP'), (cp: 50221
; name: 'CP50221'), (cp: 50221; name: 'ISO-2022-JP-MS'), (cp: 50221
; name: 'ISO2022-JP'), (cp: 50221; name: 'ISO2022-JP-MS'), (cp: 50221
; name: 'MS50221'), (cp: 50221; name: 'WINDOWS-50221'), (cp: 50221
; name: 'csISO2022JP'), (cp: 50222; name: 'iso-2022-jp'), (cp: 50225
; name: 'iso-2022-kr'), (cp: 50225; name: 'iso2022-kr'), (cp: 50227
; name: 'x-cp50227'), (cp: 51932; name: 'EUC-JP'), (cp: 51932; name
: 'CP51932'), (cp: 51932; name: 'MS51932'), (cp: 51932; name: 'WINDOWS-51932'
), (cp: 51932; name: 'euc-jp'), (cp: 51936; name: 'EUC-CN'), (cp:
51949; name: 'euc-kr'), (cp: 52936; name: 'hz-gb-2312'), (cp: 54936
; name: 'GB18030'), (cp: 57002; name: 'x-iscii-de'), (cp: 57003; name
: 'x-iscii-be'), (cp: 57004; name: 'x-iscii-ta'), (cp: 57005; name
: 'x-iscii-te'), (cp: 57006; name: 'x-iscii-as'), (cp: 57007; name
: 'x-iscii-or'), (cp: 57008; name: 'x-iscii-ka'), (cp: 57009; name
: 'x-iscii-ma'), (cp: 57010; name: 'x-iscii-gu'), (cp: 57011; name
: 'x-iscii-pa'), (cp: 65001; name: 'UTF-8'), (cp: 65001; name: 'CP65001'
), (cp: 65001; name: 'UTF8'))

```

UnixCpMap is a fixed structure with codepage number/codepage name pairs. It is used in `GetCodepageData` (1878), `GetSystemCodepage` (1878) and `GetCodepageByName` (1877) to map code page names to numbers and vice versa.

The map is ordered on code page number, and for equal code page numbers, the names are ordered so the most common one is used first.

UnixCpMapLimit = 406 - 83

Number of code pages in map UnixCpMap.

82.3.2 Types

```

TUnixCpData = record
  cp : Word;
  name : ansistring;
end

```

TUnixCpData contains 2 fields necessary to construct a map between code page number (cp) and name (name).

82.4 Procedures and functions

82.4.1 GetCodepageByName

Synopsis: Find code page by name

Declaration: `function GetCodepageByName(cpname: RawByteString) : TSystemCodePage`

Visibility: default

Description: `GetCodepageByName` returns the code page number matching `cpname`. The supported code page names are the ones commonly in use in `libiconv`. Names are searched case-sentively, with the exception that 'cpN' is converted to 'CPN', where N is a digit.

Errors: If no matching code page name is found, `CP_NONE` is returned.

See also: `UnixCpMap` ([1877](#)), `GetSystemCodepage` ([1878](#)), `GetCodepageData` ([1878](#))

82.4.2 GetCodepageData

Synopsis: Return index of codepage.

Declaration: `function GetCodepageData(cp: TSystemCodePage) : LongInt`

Visibility: default

Description: `GetCodepageData` returns the index of the first entry in `UnixCpMap` ([1877](#)) which matches `cp`. Since the entries are ordered by code page number, this means the entries can be scanned for alternate code names starting at this index.

Errors: If no matching code page is found, -1 is returned.

See also: `UnixCpMap` ([1877](#)), `GetSystemCodepage` ([1878](#)), `GetCodepageByName` ([1877](#))

82.4.3 GetSystemCodepage

Synopsis: Return the system code page based on the program environment.

Declaration: `function GetSystemCodepage : TSystemCodePage`

Visibility: default

Description: `GetSystemCodepage` returns the system code page, based on one of the environment variables `LC_ALL`, `LC_CTYPE` or `LANG`. The first non-empty variable (in the order mentioned here) is used.

Errors: If none is found, then a system default is used: Linux and Darwin use `CP_UTF8`, others use `CP_ASCII`.

See also: `UnixCpMap` ([1877](#)), `GetSystemCodepage` ([1878](#)), `GetCodepageByName` ([1877](#))

Chapter 83

Reference for unit 'unixtype'

83.1 Used units

Table 83.1: Used units by unit 'unixtype'

Name	Page
System	1194

83.2 Overview

The `unixtype` unit contains the definitions of basic unix types. It was initially implemented by Marco van de Voort.

When porting to a new unix platform, this unit should be adapted to the sizes and conventions of the platform to which the compiler is ported.

83.3 Constants, types and variables

83.3.1 Constants

`ARG_MAX = 131072`

Max number of command-line arguments.

`NAME_MAX = 255`

Max length (in bytes) of filename

`PATH_MAX = 4095`

Max length (in bytes) of pathname

`Prio_PGrp = 1`

#rtl.baseunix.fpGetPriority (184) option: Get process group priority.

Prio_Process = 0

#rtl.baseunix.fpGetPriority (184) option: Get process priority.

Prio_User = 2

#rtl.baseunix.fpGetPriority (184) option: Get user priority.

pthread_rwlocksize = 56

Size of pthread_rwlock_t _data structure

SIG_MAXSIG = 128

Maximum signal number.

SYS_NMLN = 65

Max system namelength

_PTHREAD_MUTEX_ADAPTIVE_NP = 3

Mutex options:

_PTHREAD_MUTEX_DEFAULT = _PTHREAD_MUTEX_NORMAL

Mutex options:

_PTHREAD_MUTEX_ERRORCHECK = _PTHREAD_MUTEX_ERRORCHECK_NP

Mutex options:

_PTHREAD_MUTEX_ERRORCHECK_NP = 2

Mutex options: double lock returns an error code.

_PTHREAD_MUTEX_FAST_NP = _PTHREAD_MUTEX_ADAPTIVE_NP

Mutex options: Fast mutex

_PTHREAD_MUTEX_NORMAL = _PTHREAD_MUTEX_TIMED_NP

Mutex options:

_PTHREAD_MUTEX_RECURSIVE = _PTHREAD_MUTEX_RECURSIVE_NP

Mutex options:

_PTHREAD_MUTEX_RECURSIVE_NP = 1

Mutex options: recursive mutex

_PTHREAD_MUTEX_TIMED_NP = 0

Mutex options: ?

83.3.2 Types

`cbool = longbool`

Boolean type

`cchar = cint8`

C type: 8-bit signed integer

`cdouble = Double`

Double precision real format.

`cfloat = single`

Floating-point real format

`cint = cint32`

C type: integer (natural size)

`cint16 = SmallInt`

C type: 16 bits sized, signed integer.

`cint32 = LongInt`

C type: 32 bits sized, signed integer.

`cint64 = Int64`

C type: 64 bits sized, signed integer.

`cint8 = ShortInt`

C type: 8 bits sized, signed integer.

`clock_t = cuint64`

Clock ticks type

`clong = Int64`

C type: long signed integer (double sized)

`longdouble = extended`

Usually translates to an extended, but is CPU dependent.

`longlong = cint64`

C type: 64-bit (double long) signed integer.

```
cschar = cint8
```

Signed character type

```
cshort = cint16
```

C type: short signed integer (half sized)

```
csigned = cint
```

csigned is an alias for cint ([1881](#)).

```
csint = cint32
```

Signed integer

```
cslong = Int64
```

The size is CPU dependent.

```
cslonglong = cint64
```

cslonglong is an alias for clonglong ([1882](#)).

```
csshort = cint16
```

Short signed integer type

```
cuchar = cuint8
```

C type: 8-bit unsigned integer

```
cuint = cuint32
```

C type: unsigned integer (natural size)

```
cuint16 = Word
```

C type: 16 bits sized, unsigned integer.

```
cuint32 = LongWord
```

C type: 32 bits sized, unsigned integer.

```
cuint64 = QWord
```

C type: 64 bits sized, unsigned integer.

```
cuint8 = Byte
```

C type: 8 bits sized, unsigned integer.

```
culong = QWord
```

C type: long unsigned integer (double sized)

```
culonglong = uint64
```

C type: 64-bit (double long) unsigned integer.

```
cunsigned = uint
```

Alias for `#rtl.unixtype.cuint` ([1882](#))

```
cushort = uint16
```

C type: short unsigned integer (half sized)

```
dev_t = uint64
```

Device descriptor type.

```
gid_t = uint32
```

Group ID type.

```
ino64_t = uint64
```

`ino64_t` is an inode type capable of containing 64-bit inodes.

```
ino_t = clong
```

Inode type.

```
ipc_pid_t = cint
```

Process ID

```
kDev_t = ushort
```

Kernel device type

```
mbstate_t = record
  __count : cint;
  __value : mbstate_value_t;
end
```

This type should never be used directly.

```

mbstate_value_t = record
case Byte of
0: (
  __wch : wint_t;
);
1
  : (
  __wchb : Array[0..3] of Char;
);
end

```

This type should never be used directly. It is part of the `mbstate_t` ([1883](#)) type.

```
mode_t = cint
```

Inode mode type.

```
nlink_t = cuint32
```

Number of links type.

```
off64_t = cint64
```

64-bit offset type.

```
off_t = cint64
```

Offset type.

```
pcbool = ^cbool
```

Pointer to boolean type `cbool` ([1881](#))

```
pcchar = ^cchar
```

Pointer to `#rtl.UnixType.cchar` ([1881](#))

```
pcdouble = ^cdouble
```

Pointer to `cdouble` ([1881](#)) type.

```
pcfloat = ^cfloat
```

Pointer to `cfloat` ([1881](#)) type.

```
pcint = ^cint
```

Pointer to `cInt` ([1881](#)) type.

```
pcint16 = ^cint16
```

Pointer to 16-bit signed integer type

```
pcint32 = ^cint32
```

Pointer to signed 32-bit integer type

```
pcint64 = ^cint64
```

Pointer to signed 64-bit integer type

```
pcint8 = ^cint8
```

Pointer to 8-bits signed integer type

```
pClock = ^clock_t
```

Pointer to TClock (1891) type.

```
pclong = ^clong
```

Pointer to cLong (1881) type.

```
pclongdouble = ^clongdouble
```

Pointer to the long double type clongdouble (1881)

```
pclonglong = ^clonglong
```

Pointer to longlong type.

```
pcschar = ^cschar
```

Pointer to character type cschar (1882).

```
pcshort = ^cshort
```

Pointer to cShort (1882) type.

```
pcsigned = ^csigned
```

Pointer to signed integer type csigned (1882).

```
pcsint = ^csint
```

Pointer to signed integer type csint (1882)

```
pcslong = ^cslong
```

Pointer of the signed long cslong (1882)

```
pcslonglong = ^cslonglong
```

Pointer to Signed longlong type cslonglong (1882)

```
pcsshort = ^csshort
```

Pointer to short signed integer type csshort (1882)

```
pcuchar = ^cuchar
```

Pointer to #rtl.UnixType.cuchar (1882)

```
pcuint = ^cuint
```

Pointer to cUInt (1882) type.

```
pcuint16 = ^cuint16
```

Pointer to 16-bit unsigned integer type

```
pcuint32 = ^cuint32
```

Pointer to unsigned 32-bit integer type

```
pcuint64 = ^cuint64
```

Pointer to unsigned 64-bit integer type

```
pcuint8 = ^cuint8
```

Pointer to 8-bits unsigned integer type

```
pculong = ^culong
```

Pointer to cuLong (1883) type.

```
pculonglong = ^culonglong
```

Unsigned longlong type

```
pcunsigned = ^cunsigned
```

Pointer to #rtl.unixtype.cunsigned (1883)

```
pcushort = ^cushort
```

Pointer to cuShort (1883) type.

```
pDev = ^dev_t
```

Pointer to TDev (1891) type.

```
pGid = ^gid_t
```

Pointer to TGid (1891) type.

```
pid_t = cint
```

Process ID type.

```
pIno = ^ino_t
```

Pointer to TIno (1891) type.

```
pIno64 = ^ino64_t
```

Pointer to ino64_t (1883)

```
pkDev = ^kDev_t
```

Pointer to TkDev (1891) type.

```
pmbstate_t = ^mbstate_t
```

Pointer to mbstate_t (1883) type

```
pMode = ^mode_t
```

Pointer to TMode (1891) type.

```
pnLink = ^nlink_t
```

Pointer to TnLink (1892) type.

```
pOff = ^off_t
```

Pointer to TOff (1892) type.

```
pOff64 = ^off64_t
```

Pointer to off64_t type

```
pPid = ^pid_t
```

Pointer to TPid (1892) type.

```
pSize = ^size_t
```

Pointer to TSize (1892) type.

```
psize_t = pSize
```

Pointer to size_t (1890) type.

```
pSockLen = ^socklen_t
```


Pointer to TSocketLen (1892) type.

```
pSSize = ^ssize_t
```

Pointer to TStatFS (1892) type

```
PStatFS = ^TStatfs
```

Pointer to TStatFS (1892) type.

```
pthread_attr_t = record
  __detachstate : cint;
  __schedpolicy :
  cint;
  __schedparam : sched_param;
  __inheritsched : cint;
  __scope
  : cint;
  __guardsize : size_t;
  __stackaddr_set : cint;
  __stackaddr
  : pointer;
  __stacksize : size_t;
end
```

pthread_attr_t describes the thread attributes. It should be considered an opaque record, the names of the fields can change anytime. Use the appropriate functions to set the thread attributes.

```
pthread_condattr_t = record
  __dummy : cint;
end
```

pthread_condattr_t describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_cond_t = record
  __c_lock : _pthread_fastlock;
  __c_waiting
  : pointer;
  __padding : Array[0..48-1-sizeof(_pthread_fastlock)
  -sizeof(pointer)-sizeof(clonglong)] of Byte;
  __align : clonglong
  ;
end
```

pthread_cond_t describes a thread conditional variable. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_key_t = cint
```

Thread local storage key (opaque)

```
pthread_mutexattr_t = record
  __mutexkind : cint;
end
```

`pthread_mutexattr_t` describes the attributes of a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_mutex_t = record
  __m_reserved : cint;
  __m_count : cint
  ;
  __m_owner : pointer;
  __m_kind : cint;
  __m_lock : _pthread_fastlock
  ;
end
```

`_pthread_mutex_t` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlockattr_t = record
  __lockkind : cint;
  __pshared : cint
  ;
end
```

`pthread_rwlockattr_t` describes the attributes of a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_rwlock_t = record
case Boolean of
False: (
  _data : Array
    [0..pthread_rwlocksize-1] of Char;
);
True: (
  align : clong;
);
end
```

`pthread_rwlock_t` describes a lock. It should be considered an opaque record, the names of the fields can change anytime.

```
pthread_t = culong
```

Thread description record

```
pTime = ^time_t
```

Pointer to TTime (1892) type.

```
ptimespec = ^timespec
```

Pointer to timespec (1891) record.

```
ptimeval = ^timeval
```

Pointer to timeval (1891) record.

```
ptime_t = ^time_t
```

Pointer to time_t (1891) type.

```
pUid = ^uid_t
```

Pointer to TUid (1893) type.

```
pwchar_t = ^wchar_t
```

Pointer to wchar_t (1893) type.

```
sched_param = record
  __sched_priority : cint;
end
```

Scheduling parameter description record.

```
sem_t = record
  __sem_lock : _pthread_fastlock;
  __sem_value : cint
  ;
  __sem_waiting : pointer;
end
```

`sem_t` describes a thread semaphore. It should be considered an opaque record, the names of the fields can change anytime.

```
size_t = uint64
```

Size specification type.

```
socklen_t = uint32
```

Socket address length type.

```
ssize_t = int64
```

Small size type.

```
TClock = clock_t
```

Alias for `clock_t` (1881) type.

```
TDev = dev_t
```

Alias for `dev_t` (1883) type.

```
TGid = gid_t
```

Alias for `gid_t` (1883) type.

```
timespec = record
    tv_sec : time_t;
    tv_nsec : clong;
end
```

Record specifying time interval.

```
timeval = record
    tv_sec : time_t;
    tv_usec : clong;
end
```

Time specification type.

```
time_t = cint64
```

Time span type

```
TIno = ino_t
```

Alias for `ino_t` (1883) type.

```
TIno64 = ino64_t
```

Alias for `ino64_t` (1883)

```
TIOCtlRequest = cint
```

Opaque type used in `FpIOctl` (185)

```
TkDev = kDev_t
```

Alias for `kDev_t` (1883) type.

```
TMode = mode_t
```

Alias for `mode_t` (1884) type.

```
TnLink = nlink_t
```

Alias for `nlink_t` (1884) type.

`TOff = off_t`

Alias for `off_t` (1884) type.

`TOff64 = off64_t`

Alias for `off64_t` type.

`TPid = pid_t`

Alias for `pid_t` (1887) type.

`TSize = size_t`

Alias for `size_t` (1890) type

`TSockLen = socklen_t`

Alias for `socklen_t` (1890) type.

`TSSize = ssize_t`

Alias for `ssize_t` (1890) type

```
TStatfs = record
  fstype : clong;
  bsize : clong;
  blocks : culong
  ;
  bfree : culong;
  bavail : culong;
  files : culong;
  ffree
  : culong;
  fsid : Array[0..1] of cint;
  namelen : clong;
  frsize
  : clong;
  spare : Array[0..4] of clong;
end
```

Record describing a file system in the `unix.fpstatfs` (1879) call.

`TTime = time_t`

Alias for `TTime` (1892) type.

`TTimeSpec = timespec`

Alias for `TimeSpec` (1891) type.

TTimeVal = timeval

Alias for TimeVal (1891) record.

TUid = uid_t

Alias for uid_t (1893) type.

uid_t = cuint32

User ID type

wchar_t = cint32

Wide character type.

wint_t = cint32

Wide character size type.

```
_pthread_fastlock = record
  __status : clong;
  __spinlock : cint
;
end
```

`_pthread_fastlock` describes a thread mutex. It should be considered an opaque record, the names of the fields can change anytime.

Chapter 84

Reference for unit 'unixutil'

84.1 Used units

Table 84.1: Used units by unit 'unixutil'

Name	Page
System	1194

84.2 Overview

The UnixUtil unit contains some of the routines that were present in the old Linux unit, but which do not really belong in the unix ([1840](#)) or baseunix ([124](#)) units.

Most of the functions described here have cross-platform counterparts in the SysUtils ([1442](#)) unit. It is therefore recommended to use that unit.

84.3 Constants, types and variables

84.3.1 Types

`ComStr = string deprecated`

Command-line string type.

`DirStr = string deprecated`

Filename directory part string type.

`ExtStr = string deprecated`

Filename extension part string type.

`NameStr = string deprecated`

Filename name part string type.

PathStr = string deprecated

Filename full path string type.

84.3.2 Variables

Tzseconds : LongInt

Seconds west of GMT

84.4 Procedures and functions

84.4.1 ArrayStringToPPchar

Synopsis: Concert an array of string to an array of null-terminated strings

Declaration: `function ArrayStringToPPchar(const S: Array of AnsiString;
reserveentries: LongInt) : PPChar`

Visibility: default

Description: `ArrayStringToPPchar` creates an array of null-terminated strings that point to strings which are the same as the strings in the array `S`. The function returns a pointer to this array. The array and the strings it contains must be disposed of after being used, because it they are allocated on the heap.

The `ReserveEntries` parameter tells `ArrayStringToPPchar` to allocate room at the end of the array for another `ReserveEntries` entries.

Errors: If not enough memory is available, an error may occur.

See also: `StringToPPChar` ([1898](#))

84.4.2 EpochToLocal

Synopsis: Convert epoch time to local time

Declaration: `procedure EpochToLocal(epoch: LongInt; var year: Word; var month: Word;
var day: Word; var hour: Word; var minute: Word;
var second: Word)`

Visibility: default

Description: Converts the epoch time (=Number of seconds since 00:00:00, January 1, 1970, corrected for your time zone) to local date and time.

This function takes into account the timzeone settings of your system.

Errors: None

See also: `LocalToEpoch` ([1897](#))

Listing: `./unutilx/ex3.pp`

Program Example3;

{ Program to demonstrate the EpochToLocal function. }

Uses BaseUnix, Unix, UnixUtil;

Var Year, month, day, hour, minute, seconds : Word;

begin

EpochToLocal (FTime, Year, month, day, hour, minute, seconds);

Writeln ('Current date : ', Day:2, '/', Month:2, '/', Year:4);

Writeln ('Current time : ', Hour:2, ':', minute:2, ':', seconds:2);

end.

84.4.3 GetFS

Synopsis: Return file selector

Declaration: function GetFS(var T: Text) : LongInt
function GetFS(var F: File) : LongInt

Visibility: default

Description: GetFS returns the file selector that the kernel provided for your file. In principle you don't need this file selector. Only for some calls it is needed, such as the #rtl.baseunix.fpSelect ([202](#)) call or so.

Errors: In case the file was not opened, then -1 is returned.

See also: #rtl.baseunix.fpSelect ([202](#))

Listing: ./unutilx/ex34.pp

Program Example33;

{ Program to demonstrate the SelectText function. }

Uses Unix;

Var tv : TimeVal;

begin

Writeln ('Press the <ENTER> to continue the program.');

{ Wait until File descriptor 0 (=Input) changes }

SelectText (Input, **nil**);

{ Get rid of <ENTER> in buffer }

readln;

Writeln ('Press <ENTER> key in less than 2 seconds...');

tv.tv_sec:=2;

tv.tv_sec:=0;

if SelectText (Input, @tv)>0 **then**

Writeln ('Thank you !')

else

Writeln ('Too late !');

end.

84.4.4 GregorianToJulian

Synopsis: Converts a gregorian date to a julian date

Declaration: `function GregorianToJulian (Year: LongInt; Month: LongInt; Day: LongInt)
: LongInt`

Visibility: default

Description: `GregorianToJulian` takes a gregorian date and converts it to a Julian day.

Errors: None.

See also: `JulianToGregorian` ([1897](#))

84.4.5 JulianToGregorian

Synopsis: Converts a julian date to a gregorian date

Declaration: `procedure JulianToGregorian (JulianDN: LongInt; var Year: Word;
var Month: Word; var Day: Word)`

Visibility: default

Description: `JulianToGregorian` takes a julian day and converts it to a gregorian date. (Start of the Julian Date count is from 0 at 12 noon 1 JAN -4712 (4713 BC),)

Errors: None.

See also: `GregorianToJulian` ([1897](#))

84.4.6 LocalToEpoch

Synopsis: Convert local time to epoch (unix) time

Declaration: `function LocalToEpoch (year: Word; month: Word; day: Word; hour: Word;
minute: Word; second: Word) : LongInt`

Visibility: default

Description: Converts the Local time to epoch time (=Number of seconds since 00:00:00, January 1, 1970).

Errors: None

See also: `EpochToLocal` ([1895](#))

Listing: ./unutilx/ex4.pp

Program Example4;

{ Program to demonstrate the LocalToEpoch function. }

Uses UnixUtil;

Var year, month, day, hour, minute, second : Word;

begin

Write ('Year : '); **readln** (Year);
Write ('Month : '); **readln** (Month);
Write ('Day : '); **readln** (Day);

```

Write ( 'Hour      : '); readln (Hour);
Write ( 'Minute   : '); readln (Minute);
Write ( 'Seonds   : '); readln (Second);
Write ( 'This is  : ');
Write ( LocalToEpoch (year , month , day , hour , minute , second ));
Writeln ( ' seconds past 00:00 1/1/1980 ');
end.

```

84.4.7 StringToPPChar

Synopsis: Split string in list of null-terminated strings

Declaration: function StringToPPChar(S: PChar; ReserveEntries: Integer) : PPChar
function StringToPPChar(var S: AnsiString; ReserveEntries: Integer)
: PPChar

Visibility: default

Description: StringToPPChar splits the string S in words, replacing any whitespace with zero characters. It returns a pointer to an array of pchars that point to the first letters of the words in S. This array is terminated by a Nil pointer.

The function does *not* add a zero character to the end of the string unless it ends on whitespace.

The function reserves memory on the heap to store the array of PChar; The caller is responsible for freeing this memory.

This function can be called to create arguments for the various Exec calls.

Errors: None.

See also: ArrayStringToPPchar ([1895](#)), #rtl.baseunix.FpExecve ([175](#))

Listing: ./unutilx/ex70.pp

Program Example70;

{ Program to demonstrate the StringToPPchar function. }

Uses UnixUtil;

Var S : **String**;
P : PPChar;
I : longint;

begin
// remark whitespace at end.
S:= 'This is a string with words. ';
P:=StringToPPChar(S,0);
I:=0;
While P[I]<>Nil **do**
 begin
 Writeln ('Word ', i , ' : ', P[I]);
 Inc(I);
 end;
FreeMem(P, i*SizeOf(Pchar));
end.

Chapter 85

Reference for unit 'video'

85.1 Used units

Table 85.1: Used units by unit 'video'

Name	Page
System	1194

85.2 Overview

The `Video` unit implements a screen access layer which is system independent. It can be used to write on the screen in a system-independent way, which should be optimal on all platforms for which the unit is implemented.

The working of the `Video` is simple: After calling `InitVideo` ([1917](#)), the array `VideoBuf` contains a representation of the video screen of size `ScreenWidth*ScreenHeight`, going from left to right and top to bottom when walking the array elements: `VideoBuf[0]` contains the character and color code of the top-left character on the screen. `VideoBuf[ScreenWidth]` contains the data for the character in the first column of the second row on the screen, and so on.

To write to the 'screen', the text to be written should be written to the `VideoBuf` array. Calling `UpdateScreen` ([1920](#)) will then cp the text to the screen in the most optimal way. (an example can be found further on).

The color attribute is a combination of the foreground and background color, plus the blink bit. The bits describe the various color combinations:

bits 0-3 The foreground color. Can be set using all color constants.

bits 4-6 The background color. Can be set using a subset of the color constants.

bit 7 The blinking bit. If this bit is set, the character will appear blinking.

Each possible color has a constant associated with it, see the constants section for a list of constants. The foreground and background color can be combined to a color attribute with the following code:

```
Attr:=ForeGroundColor + (BackGroundColor shl 4);
```

The color attribute can be logically or-ed with the blink attribute to produce a blinking character:

```
Attr:=Attr or blink;
```

But not all drivers may support this.

The contents of the `VideoBuf` array may be modified: This is 'writing' to the screen. As soon as everything that needs to be written in the array is in the `VideoBuf` array, calling `UpdateScreen` will copy the contents of the array screen to the screen, in a manner that is as efficient as possible.

The updating of the screen can be prohibited to optimize performance; To this end, the `LockScreenUpdate` (1917) function can be used: This will increment an internal counter. As long as the counter differs from zero, calling `UpdateScreen` (1920) will not do anything. The counter can be lowered with `UnlockScreenUpdate` (1920). When it reaches zero, the next call to `UpdateScreen` (1920) will actually update the screen. This is useful when having nested procedures that do a lot of screen writing.

The video unit also presents an interface for custom screen drivers, thus it is possible to override the default screen driver with a custom screen driver, see the `SetVideoDriver` (1919) call. The current video driver can be retrieved using the `GetVideoDriver` (1914) call.

Remark: The video unit should *not* be used together with the CRT unit. Doing so will result in very strange behaviour, possibly program crashes.

85.3 Examples utility unit

The examples in this section make use of the unit `vidutil`, which contains the `TextOut` function. This function writes a text to the screen at a given location. It looks as follows:

Listing: `./videoex/vidutil.pp`

```
unit vidutil;

Interface

uses
  video;

Procedure TextOut(X,Y : Word;Const S : String);

Implementation

Procedure TextOut(X,Y : Word;Const S : String);

Var
  W,P,I,M : Word;

begin
  P:=((X-1)+(Y-1)*ScreenWidth);
  M:=Length(S);
  If P+M>ScreenWidth*ScreenHeight then
    M:=ScreenWidth*ScreenHeight-P;
  For I:=1 to M do
    VideoBuf^[P+I-1]:=Ord(S[I])+($07 shl 8);
  end;
end.
```

85.4 Writing a custom video driver

Writing a custom video driver is not difficult, and generally means implementing a couple of functions, which should be registered with the `SetVideoDriver` (1919) function. The various functions that can be implemented are located in the `TVideoDriver` (1909) record:

```
TVideoDriver = Record
  InitDriver      : Procedure;
  DoneDriver      : Procedure;
  UpdateScreen    : Procedure(Force : Boolean);
  ClearScreen     : Procedure;
  SetVideoMode    : Function (Const Mode : TVideoMode) : Boolean;
  GetVideoModeCount : Function : Word;
  GetVideoModeData : Function(Index : Word; Var Data : TVideoMode) : Boolean;
  SetCursorPos    : procedure (NewCursorX, NewCursorY: Word);
  GetCursorPos    : function : Word;
  SetCursorType   : procedure (NewType: Word);
  GetCursorType   : function : Word;
end;
```

Not all of these functions must be implemented. In fact, the only absolutely necessary function to write a functioning driver is the `UpdateScreen` function. The general calls in the `Video` unit will check which functionality is implemented by the driver.

The functionality of these calls is the same as the functionality of the calls in the `video` unit, so the expected behaviour can be found in the previous section. Some of the calls, however, need some additional remarks.

InitDriver Called by `InitVideo`, this function should initialize any data structures needed for the functionality of the driver, maybe do some screen initializations. The function is guaranteed to be called only once; It can only be called again after a call to `DoneVideo`. The variables `ScreenWidth` and `ScreenHeight` should be initialized correctly after a call to this function, as the `InitVideo` call will initialize the `VideoBuf` and `OldVideoBuf` arrays based on their values.

DoneDriver This should clean up any structures that have been initialized in the `InitDriver` function. It should possibly also restore the screen as it was before the driver was initialized. The `VideoBuf` and `OldVideoBuf` arrays will be disposed of by the general `DoneVideo` call.

UpdateScreen This is the only required function of the driver. It should update the screen based on the `VideoBuf` array's contents. It can optimize this process by comparing the values with values in the `OldVideoBuf` array. After updating the screen, the `UpdateScreen` procedure should update the `OldVideoBuf` by itself. If the `Force` parameter is `True`, the whole screen should be updated, not just the changed values.

ClearScreen If there is a faster way to clear the screen than to write spaces in all character cells, then it can be implemented here. If the driver does not implement this function, then the general routines will write spaces in all video cells, and will call `UpdateScreen(True)`.

SetVideoMode Should set the desired video mode, if available. It should return `True` if the mode was set, `False` if not.

GetVideoModeCount Should return the number of supported video modes. If no modes are supported, this function should not be implemented; the general routines will return 1. (for the current mode)

GetVideoModeData Should return the data for the `Index`-th mode; `Index` is zero based. The function should return true if the data was returned correctly, false if `Index` contains an invalid index. If this is not implemented, then the general routine will return the current video mode when `Index` equals 0.

GetCapabilities If this function is not implemented, zero (i.e. no capabilities) will be returned by the general function.

The following unit shows how to override a video driver, with a driver that writes debug information to a file. The unit can be used in any of the demonstration programs, by simply including it in the `uses` clause. Setting `DetailedVideoLogging` to `True` will create a more detailed log (but will also slow down functioning)

Listing: `./videoex/viddbg.pp`

```
unit viddbg;
```

```
Interface
```

```
uses video;
```

```
Procedure StartVideoLogging;
```

```
Procedure StopVideoLogging;
```

```
Function IsVideoLogging : Boolean;
```

```
Procedure SetVideoLogFileName(FileName : String);
```

```
Const
```

```
    DetailedVideoLogging : Boolean = False;
```

```
Implementation
```

```
uses sysutils , keyboard;
```

```
var
```

```
    NewVideoDriver ,
    OldVideoDriver : TVideoDriver;
    Active , Logging : Boolean;
    LogFileName : String;
    VideoLog : Text;
```

```
Function TimeStamp : String;
```

```
begin
```

```
    TimeStamp := FormatDateTime( 'hh:nn:ss' , Time ( ) );
```

```
end;
```

```
Procedure StartVideoLogging;
```

```
begin
```

```
    Logging := True;
```

```
    WriteLn(VideoLog, 'Start logging video operations at: ', TimeStamp);
```

```
end;
```

```
Procedure StopVideoLogging;
```

```
begin
```

```
    WriteLn(VideoLog, 'Stop logging video operations at: ', TimeStamp);
```

```
    Logging := False;
```

```

end;

Function IsVideoLogging : Boolean;

begin
  IsVideoLogging:=Logging;
end;

Var
  ColUpd,RowUpd : Array[0..1024] of Integer;

Procedure DumpScreenStatistics(Force : Boolean);

Var
  I,Count : Integer;

begin
  If Force then
    Write(VideoLog,'forced ');
    WriteLn(VideoLog,'video update at ',TimeStamp,' : ');
    FillChar(ColUpd,SizeOf(ColUpd),#0);
    FillChar(RowUpd,SizeOf(RowUpd),#0);
    Count:=0;
    For I:=0 to VideoBufSize div SizeOf(TVideoCell) do
      begin
        If VideoBuf^[I]<>OldVideoBuf^[I] then
          begin
            Inc(Count);
            Inc(ColUpd[I mod ScreenWidth]);
            Inc(RowUpd[I div ScreenHeight]);
          end;
      end;
    Write(VideoLog,Count,' videocells differed divided over ');
    Count:=0;
    For I:=0 to ScreenWidth-1 do
      If ColUpd[I]<>0 then
        Inc(Count);
    Write(VideoLog,Count,' columns and ');
    Count:=0;
    For I:=0 to ScreenHeight-1 do
      If RowUpd[I]<>0 then
        Inc(Count);
    WriteLn(VideoLog,Count,' rows. ');
    If DetailedVideoLogging Then
      begin
        For I:=0 to ScreenWidth-1 do
          If (ColUpd[I]<>0) then
            WriteLn(VideoLog,'Col ',I,' : ',ColUpd[I]:3,' rows changed');
        For I:=0 to ScreenHeight-1 do
          If (RowUpd[I]<>0) then
            WriteLn(VideoLog,'Row ',I,' : ',RowUpd[I]:3,' columns changed');
      end;
    end;

Procedure LogUpdateScreen(Force : Boolean);

begin
  If Logging then

```



```

        DumpScreenStatistics ( Force );
        OldVideoDriver . UpdateScreen ( Force );
    end;

Procedure LogInitVideo ;

begin
    OldVideoDriver . InitDriver ( );
    Assign ( VideoLog , logFileName );
    Rewrite ( VideoLog );
    Active := True ;
    StartVideoLogging ;
end;

Procedure LogDoneVideo ;

begin
    StopVideoLogging ;
    Close ( VideoLog );
    Active := False ;
    OldVideoDriver . DoneDriver ( );
end;

Procedure SetVideoLogFileName ( FileName : String );

begin
    If Not Active then
        LogFileName := FileName ;
    end;

Initialization
    GetVideoDriver ( OldVideoDriver );
    NewVideoDriver := OldVideoDriver ;
    NewVideoDriver . UpdateScreen := @LogUpdateScreen ;
    NewVideoDriver . InitDriver := @LogInitVideo ;
    NewVideoDriver . DoneDriver := @LogDoneVideo ;
    LogFileName := ' Video . log ' ;
    Logging := False ;
    SetVideoDriver ( NewVideoDriver );
end.

```

85.5 Constants, types and variables

85.5.1 Constants

Black = 0

Black color attribute

Blink = 128

Blink attribute

Blue = 1

Blue color attribute

Brown = 6

Brown color attribute

cpBlink = \$0002

Video driver supports blink attribute

cpChangeCursor = \$0020

Video driver supports changing cursor shape.

cpChangeFont = \$0008

Video driver supports changing screen font.

cpChangeMode = \$0010

Video driver supports changing mode

cpColor = \$0004

Video driver supports color

cpUnderLine = \$0001

Video driver supports underline attribute

crBlock = 2

Block cursor

crHalfBlock = 3

Half block cursor

crHidden = 0

Hide cursor

crUnderLine = 1

Underline cursor

Cyan = 3

Cyan color attribute

DarkGray = 8

Dark gray color attribute

```
errOk = 0
```

No error

```
ErrorCode : LongInt = ErrOK
```

Error code returned by the last operation.

```
ErrorHandler : TErrorHandler = @DefaultErrorHandler
```

The `ErrorHandler` variable can be set to a custom-error handling function. It is set by default to the `DefaultErrorHandler` ([1911](#)) function.

```
ErrorInfo : Pointer = Nil
```

Pointer to extended error information.

```
errVioBase = 1000
```

Base value for video errors

```
errVioInit = errVioBase + 1
```

Video driver initialization error.

```
errVioNoSuchMode = errVioBase + 3
```

Invalid video mode

```
errVioNotSupported = errVioBase + 2
```

Unsupported video function

```
FVMaxWidth = 240
```

Maximum screen buffer width.

```
Green = 2
```

Green color attribute

```
iso_codepages = [iso01, iso02, iso03, iso04, iso05, iso06, iso07,
  iso08, iso09, iso10, iso13, iso14, iso15]
```

`iso_codepages` is a set containing all code pages that use an ISO encoding.

```
LightBlue = 9
```

Light Blue color attribute

LightCyan = 11

Light cyan color attribute

LightGray = 7

Light gray color attribute

LightGreen = 10

Light green color attribute

LightMagenta = 13

Light magenta color attribute

LightRed = 12

Light red color attribute

LowAscii = True

On some systems, the low 32 values of the DOS code page are necessary for the ASCII control codes and cannot be displayed by programs. If LowAscii is true, you can use the low 32 ASCII values. If it is false, you must avoid using them.

LowAscii can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to LowAscii, or take its address.

Magenta = 5

Magenta color attribute

NoExtendedFrame = False

The VT100 character set only has line drawing characters consisting of a single line. If this value is true, the line drawing characters with two lines will be automatically converted to single lines.

NoExtendedFrame can be implemented either through a constant, variable or property. You should under no circumstances assume that you can write to NoExtendedFrame, or take its address.

Red = 4

Red color attribute

ScreenHeight : Word = 0

Current screen height

ScreenWidth : Word = 0

Current screen Width

```
vga_codepages = [cp437, cp850, cp852, cp866]
```

`vga_codepages` is a set containing all code pages that can be considered a normal vga font (as in use on early VGA cards) Note that KOI8-R has line drawing characters in wrong place.

```
vioOK = 0
```

No errors occurred

```
White = 15
```

White color attribute

```
Yellow = 14
```

Yellow color attribute

85.5.2 Types

```
PVideoBuf = ^TVideoBuf
```

Pointer type to TVideoBuf ([1909](#))

```
PVideoCell = ^TVideoCell
```

Pointer type to TVideoCell ([1909](#))

```
PVideoMode = ^TVideoMode
```

Pointer to TVideoMode ([1909](#)) record.

```
TErrorHandler = function(Code: LongInt; Info: Pointer)
    : TErrorHandlerReturnValue
```

The `TErrorHandler` function is used to register an own error handling function. It should be used when installing a custom error handling function, and must return one of the above values.

`Code` should contain the error code for the error condition, and the `Info` parameter may contain any data type specific to the error code passed to the function.

```
TErrorHandlerReturnValue = (errRetry, errAbort, errContinue)
```

Table 85.2: Enumeration values for type TErrorHandlerReturnValue

Value	Explanation
<code>errAbort</code>	abort and return error code
<code>errContinue</code>	abort without returning an errorcode.
<code>errRetry</code>	retry the operation

Type used to report and respond to error conditions

```
TVideoBuf = Array[0..32759] of TVideoCell
```

The TVideoBuf type represents the screen.

```
TVideoCell = Word
```

TVideoCell describes one character on the screen. One of the bytes contains the color attribute with which the character is drawn on the screen, and the other byte contains the ASCII code of the character to be drawn. The exact position of the different bytes in the record is operating system specific. On most little-endian systems, the high byte represents the color attribute, while the low-byte represents the ASCII code of the character to be drawn.

```
TVideoDriver = record
  InitDriver : procedure;
  DoneDriver : procedure
  ;
  UpdateScreen : procedure(Force: Boolean);
  ClearScreen : procedure
  ;
  SetVideoMode : function(const Mode: TVideoMode) : Boolean;
  GetVideoModeCount
  : function : Word;
  GetVideoModeData : function(Index: Word; var
  Data: TVideoMode) : Boolean;
  SetCursorPos : procedure(NewCursorX
  : Word; NewCursorY: Word);
  GetCursorType : function : Word;
  SetCursorType
  : procedure(NewType: Word);
  GetCapabilities : function : Word;
end
```

TVideoDriver record can be used to install a custom video driver, with the SetVideoDriver [\(1919\)](#) call.

An explanation of all fields can be found there.

```
TVideoMode = record
  Col : Word;
  Row : Word;
  Color : Boolean
  ;
end
```

The TVideoMode record describes a videomode. Its fields are self-explaining: Col, Row describe the number of columns and rows on the screen for this mode. Color is True if this mode supports colors, or False if not.

```
TVideoModeSelector = function(const VideoMode: TVideoMode;
  Params: LongInt) : Boolean
```

Video mode selection callback prototype.

85.5.3 Variables

`CursorLines` : Byte

`CursorLines` is a bitmask which determines which cursor lines are visible and which are not. Each set bit corresponds to a cursorline being shown.

This variable is not supported on all platforms, so it should be used sparingly.

`CursorX` : Word

Current horizontal position in the screen where items will be written.

`CursorY` : Word

Current vertical position in the screen where items will be written.

`external_codepage` : Tencoding

This variable is for internal use only and should not be used.

`internal_codepage` : Tencoding

This variable is for internal use only and should not be used.

`OldVideoBuf` : PVideoBuf

The `OldVideoBuf` contains the state of the video screen after the last screen update. The `UpdateScreen` (1920) function uses this array to decide which characters on screen should be updated, and which not.

Note that the `OldVideoBuf` array may be ignored by some drivers, so it should not be used. The Array is in the interface section of the video unit mainly so drivers that need it can make use of it.

`ScreenColor` : Boolean

`ScreenColor` indicates whether the current screen supports colors.

`VideoBuf` : PVideoBuf

`VideoBuf` forms the heart of the `Video` unit: This variable represents the physical screen. Writing to this array and calling `UpdateScreen` (1920) will write the actual characters to the screen.

`VideoBufSize` : LongInt

Current size of the video buffer pointed to by `VideoBuf` (1910)

85.6 Procedures and functions

85.6.1 ClearScreen

Synopsis: Clear the video screen.

Visibility: default

Description: `DoneVideo` disables the Video driver if the video driver is active. If the videodriver was already disabled or not yet initialized, it does nothing. Disabling the driver means it will clean up any allocated resources, possibly restore the screen in the state it was before `InitVideo` was called. Particularly, the `VideoBuf` and `OldVideoBuf` arrays are no longer valid after a call to `DoneVideo`. The `DoneVideo` should always be called if `InitVideo` was called. Failing to do so may leave the screen in an unusable state after the program exits.

For an example, see most other functions.

Errors: Normally none. If the driver reports an error, this is done through the `ErrorCode` variable.

See also: `InitVideo` ([1917](#))

85.6.4 GetCapabilities

Synopsis: Get current driver capabilities.

Declaration: `function GetCapabilities : Word`

Visibility: default

Description: `GetCapabilities` returns the capabilities of the current driver. It is an or-ed combination of the following constants:

cpUnderLineVideo driver supports underline attribute

cpBlinkVideo driver supports blink attribute

cpColorVideo driver supports color

cpChangeFontVideo driver supports changing screen font.

cpChangeModeVideo driver supports changing mode

cpChangeCursorVideo driver supports changing cursor shape.

Note that the video driver should not yet be initialized to use this function. It is a property of the driver.

Errors: None.

See also: `GetCursorType` ([1913](#)), `GetVideoDriver` ([1914](#))

Listing: `./videoex/ex4.pp`

Program `Example4`;

{ Program to demonstrate the GetCapabilities function. }

Uses `video`;

Var

`W: Word`;

Procedure `TestCap`(`Cap: Word`; `Msg : String`);

begin

Write(`Msg`, ' : ');

If (`W and Cap=Cap`) **then**

WriteLn('Yes')

```

    else
        Writeln( 'No' );
    end;

begin
    W:= GetCapabilities;
    Writeln( 'Video driver supports following functionality' );
    TestCap(cpUnderLine, 'Underlined characters');
    TestCap(cpBlink, 'Blinking characters');
    TestCap(cpColor, 'Color characters');
    TestCap(cpChangeFont, 'Changing font');
    TestCap(cpChangeMode, 'Changing video mode');
    TestCap(cpChangeCursor, 'Changing cursor shape');
end.

```

85.6.5 GetCursorType

Synopsis: Get screen cursor type

Declaration: `function GetCursorType : Word`

Visibility: default

Description: `GetCursorType` returns the current cursor type. It is one of the following values:

crHidden Hide cursor
crUnderLine Underline cursor
crBlock Block cursor
crHalfBlock Half block cursor

Note that not all drivers support all types of cursors.

Errors: None.

See also: `SetCursorType` ([1919](#)), `GetCapabilities` ([1912](#))

Listing: `./videoex/ex5.pp`

Program Example5;

{ Program to demonstrate the GetCursorType function. }

Uses video, keyboard, vidutil;

Const

CursorTypes : **Array**[crHidden..crHalfBlock] **of string** =
 ('Hidden', 'UnderLine', 'Block', 'HalfBlock');

begin

```

    InitVideo;
    InitKeyboard;
    TextOut(1,1, 'Cursor type: '+CursorTypes[GetCursorType]);
    TextOut(1,2, 'Press any key to exit. ');
    UpdateScreen(False);
    GetKeyEvent;
    DoneKeyboard;
    DoneVideo;
end.

```

85.6.6 GetLockScreenCount

Synopsis: Get the screen lock update count.

Declaration: `function GetLockScreenCount : Integer`

Visibility: default

Description: `GetLockScreenCount` returns the current lock level. When the lock level is zero, a call to `UpdateScreen` (1920) will actually update the screen.

Errors: None.

See also: `LockScreenUpdate` (1917), `UnlockScreenUpdate` (1920), `UpdateScreen` (1920)

Listing: `./videoex/ex6.pp`

Program Example6;

{ Program to demonstrate the GetLockScreenCount function. }

Uses video, keyboard, vidutil;

Var

 I : Longint;
 S : **String**;

begin

```
  InitVideo;
  InitKeyboard;
  TextOut(1,1,'Press key till new text appears. ');
  UpdateScreen(False);
  Randomize;
  For I:=0 to Random(10)+1 do
    LockScreenUpdate;
  I:=0;
  While GetLockScreenCount<>0 do
    begin
      Inc(I);
      Str(I,S);
      UnlockScreenUpdate;
      GetKeyEvent;
      TextOut(1,1,'UnLockScreenUpdate had to be called '+S+' times ');
      UpdateScreen(False);
    end;
  TextOut(1,2,'Press any key to end. ');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.
```

85.6.7 GetVideoDriver

Synopsis: Get a copy of the current video driver.

Declaration: `procedure GetVideoDriver(var Driver: TVideoDriver)`

Visibility: default

Description: `GetVideoDriver` returns the currently active video driver record in `Driver`. It can be used to clone the current video driver, or to override certain parts of it using the `SetVideoDriver` (1919) call.

Errors: None.

See also: `SetVideoDriver` (1919)

85.6.8 GetVideoMode

Synopsis: Return current video mode

Declaration: `procedure GetVideoMode(var Mode: TVideoMode)`

Visibility: default

Description: `GetVideoMode` returns the settings of the currently active video mode. The `row`, `col` fields indicate the dimensions of the current video mode, and `Color` is true if the current video supports colors.

See also: `SetVideoMode` (1919), `GetVideoModeData` (1917)

Listing: `./videoex/ex7.pp`

Program `Example7`;

{ Program to demonstrate the GetVideoMode function. }

Uses `video`, `keyboard`, `vidutil`;

Var

`M` : `TVideoMode`;

`S` : **String**;

begin

`InitVideo`;

`InitKeyboard`;

`GetVideoMode(M)`;

if `M.Color` **then**

`TextOut(1,1,'Current mode has color')`

else

`TextOut(1,1,'Current mode does not have color');`

Str(`M.Row`,`S`);

`TextOut(1,2,'Number of rows : '+S);`

Str(`M.Col`,`S`);

`TextOut(1,3,'Number of columns : '+S);`

`Textout(1,4,'Press any key to exit.');`

`UpdateScreen(False)`;

`GetKeyEvent`;

`DoneKeyboard`;

`DoneVideo`;

end.

85.6.9 GetVideoModeCount

Synopsis: Get the number of video modes supported by the driver.

Declaration: `function GetVideoModeCount : Word`

Visibility: default

Description: `GetVideoModeCount` returns the number of video modes that the current driver supports. If the driver does not support switching of modes, then 1 is returned.

This function can be used in conjunction with the `GetVideoModeData` (1917) function to retrieve data for the supported video modes.

Errors: None.

See also: `GetVideoModeData` (1917), `GetVideoMode` (1915)

Listing: `./videoex/ex8.pp`

Program `Example8;`

{ Program to demonstrate the GetVideoModeCount function. }

Uses `video, keyboard, vidutil;`

Procedure `DumpMode (M : TVideoMode; Index : Integer);`

Var

`S : String;`

begin

```

  Str(Index:2,S);
  inc(Index);
  TextOut(1,Index,'Data for mode '+S+' : ');
  if M.Color then
    TextOut(19,Index,'  color,')
  else
    TextOut(19,Index,'No color,');
  Str(M.Row:3,S);
  TextOut(28,Index,S+' rows');
  Str(M.Col:3,S);
  TextOut(36,Index,S+' columns');
end;
```

Var

```

  i,Count : Integer;
  m : TVideoMode;
```

begin

```

  InitVideo;
  InitKeyboard;
  Count:=GetVideoModeCount;
  For I:=1 to Count do
    begin
      GetVideoModeData(I-1,M);
      DumpMode(M,I-1);
    end;
  TextOut(1,Count+1,'Press any key to exit');
  UpdateScreen(False);
  GetKeyEvent;
  DoneKeyboard;
  DoneVideo;
end.
```

85.6.10 GetVideoModeData

Synopsis: Get the specifications for a video mode

Declaration: `function GetVideoModeData(Index: Word; var Data: TVideoMode) : Boolean`

Visibility: default

Description: `GetVideoModeData` returns the characteristics of the `Index`-th video mode in `Data`. `Index` is zero based, and has a maximum value of `GetVideoModeCount-1`. If the current driver does not support setting of modes (`GetVideoModeCount=1`) and `Index` is zero, the current mode is returned.

The function returns `True` if the mode data was retrieved successfully, `False` otherwise.

For an example, see `GetVideoModeCount` (1915).

Errors: In case `Index` has a wrong value, `False` is returned.

See also: `GetVideoModeCount` (1915), `SetVideoMode` (1919), `GetVideoMode` (1915)

85.6.11 InitVideo

Synopsis: Initialize video driver.

Declaration: `procedure InitVideo`

Visibility: default

Description: `InitVideo` initializes the video subsystem. If the video system was already initialized, it does nothing. After the driver has been initialized, the `VideoBuf` and `OldVideoBuf` pointers are initialized, based on the `ScreenWidth` and `ScreenHeight` variables. When this is done, the screen is cleared.

For an example, see most other functions.

Errors: if the driver fails to initialize, the `ErrorCode` variable is set.

See also: `DoneVideo` (1911)

85.6.12 LockScreenUpdate

Synopsis: Prevent further screen updates.

Declaration: `procedure LockScreenUpdate`

Visibility: default

Description: `LockScreenUpdate` increments the screen update lock count with one. As long as the screen update lock count is not zero, `UpdateScreen` (1920) will not actually update the screen.

This function can be used to optimize screen updating: If a lot of writing on the screen needs to be done (by possibly unknown functions), calling `LockScreenUpdate` before the drawing, and `UnlockScreenUpdate` (1920) after the drawing, followed by a `UpdateScreen` (1920) call, all writing will be shown on screen at once.

For an example, see `GetLockScreenCount` (1914).

Errors: None.

See also: `UpdateScreen` (1920), `UnlockScreenUpdate` (1920), `GetLockScreenCount` (1914)

85.6.13 SetCursorPos

Synopsis: Set write cursor position.

Declaration: `procedure SetCursorPos (NewCursorX: Word; NewCursorY: Word)`

Visibility: default

Description: `SetCursorPos` positions the cursor on the given position: Column `NewCursorX` and row `NewCursorY`. The origin of the screen is the upper left corner, and has coordinates `(0, 0)`.

The current position is stored in the `CursorX` and `CursorY` variables.

Errors: None.

See also: `SetCursorType` ([1919](#))

Listing: `./videoex/ex2.pp`

```

program example2;

uses video , keyboard;

Var
  P,PP,D : Integer;
  K: TKeyEvent;

  Procedure PutSquare (P : Integer; C : Char);

begin
  VideoBuf^[P]:=Ord(C)+($07 shl 8);
  VideoBuf^[P+ScreenWidth]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+1]:=Ord(c)+($07 shl 8);
  VideoBuf^[P+ScreenWidth+1]:=Ord(c)+($07 shl 8);
end;

begin
  InitVideo;
  InitKeyBoard;
  P:=0;
  PP:=-1;
  Repeat
    If PP<>-1 then
      PutSquare(PP, ' ');
      PutSquare(P, '#');
      SetCursorPos(P Mod ScreenWidth,P div ScreenWidth);
      UpdateScreen(False);
      PP:=P;
    Repeat
      D:=0;
      K:=TranslateKeyEvent(GetKeyEvent);
      Case GetKeyEventCode(K) of
        kbdLeft : If (P Mod ScreenWidth)<>0 then
          D:=-1;
        kbdUp : If P>=ScreenWidth then
          D:=-ScreenWidth;
        kbdRight : If ((P+2) Mod ScreenWidth)<>0 then
          D:=1;
        kbdDown : if (P<(VideoBufSize div 2)-(ScreenWidth*2)) then
          D:=ScreenWidth;

```

```

    end;
    Until (D<>0) or (GetKeyEventChar(K)= 'q' );
    P:=P+D;
    until GetKeyEventChar(K)= 'q' ;
    DoneKeyBoard;
    DoneVideo;
end.

```

85.6.14 SetCursorType

Synopsis: Set cursor type

Declaration: `procedure SetCursorType(NewType: Word)`

Visibility: default

Description: `SetCursorType` sets the cursor to the type specified in `NewType`.

```

crHidden Hide cursor
crUnderLine Underline cursor
crBlock Block cursor
crHalfBlock Half block cursor

```

Errors: None.

See also: `SetCursorPos` ([1918](#))

85.6.15 SetVideoDriver

Synopsis: Install a new video driver.

Declaration: `function SetVideoDriver(const Driver: TVideoDriver) : Boolean`

Visibility: default

Description: `SetVideoDriver` sets the videodriver to be used to `Driver`. If the current videodriver is initialized (after a call to `InitVideo`) then it does nothing and returns `False`.

A new driver can only be installed if the previous driver was not yet activated (i.e. before a call to `InitVideo` ([1917](#))) or after it was deactivated (i.e after a call to `DoneVideo`).

For more information about installing a videodriver, see `viddriver` ([1901](#)).

For an example, see the section on writing a custom video driver.

Errors: If the current driver is initialized, then `False` is returned.

See also: `viddriver` ([1901](#))

85.6.16 SetVideoMode

Synopsis: Set current video mode.

Declaration: `function SetVideoMode(const Mode: TVideoMode) : Boolean`

Visibility: default

Description: `SetVideoMode` sets the video mode to the mode specified in `Mode`:

If the call was succesful, then the screen will have `Col` columns and `Row` rows, and will be displaying in color if `Color` is `True`.

The function returns `True` if the mode was set succesfully, `False` otherwise.

Note that the video mode may not always be set. E.g. a console on Linux or a telnet session cannot always set the mode. It is important to check the error value returned by this function if it was not succesful.

The mode can be set when the video driver has not yet been initialized (i.e. before `InitVideo` (1917) was called) In that case, the video mode will be stored, and after the driver was initialized, an attempt will be made to set the requested mode. Changing the video driver before the call to `InitVideo` will clear the stored video mode.

To know which modes are valid, use the `GetVideoModeCount` (1915) and `GetVideoModeData` (1917) functions. To retrieve the current video mode, use the `GetVideoMode` (1915) procedure.

Errors: If the specified mode cannot be set, then `errVioNoSuchMode` may be set in `ErrorCode`

See also: `GetVideoModeCount` (1915), `GetVideoModeData` (1917), `GetVideoMode` (1915)

85.6.17 UnlockScreenUpdate

Synopsis: Unlock screen update.

Declaration: `procedure UnlockScreenUpdate`

Visibility: `default`

Description: `UnlockScreenUpdate` decrements the screen update lock count with one if it is larger than zero. When the lock count reaches zero, the `UpdateScreen` (1920) will actually update the screen. No screen update will be performed as long as the screen update lock count is nonzero. This mechanism can be used to increase screen performance in case a lot of writing is done.

It is important to make sure that each call to `LockScreenUpdate` (1917) is matched by exactly one call to `UnlockScreenUpdate`

For an example, see `GetLockScreenCount` (1914).

Errors: None.

See also: `LockScreenUpdate` (1917), `GetLockScreenCount` (1914), `UpdateScreen` (1920)

85.6.18 UpdateScreen

Synopsis: Update physical screen with internal screen image.

Declaration: `procedure UpdateScreen(Force: Boolean)`

Visibility: `default`

Description: `UpdateScreen` synchronizes the actual screen with the contents of the `VideoBuf` internal buffer. The parameter `Force` specifies whether the whole screen has to be redrawn (`Force=True`) or only parts that have changed since the last update of the screen.

The `Video` unit keeps an internal copy of the screen as it last wrote it to the screen (in the `OldVideoBuf` array). The current contents of `VideoBuf` are examined to see what locations on the screen need to be updated. On slow terminals (e.g. a Linux telnet session) this mechanism can speed up the screen redraw considerably.

On platforms where mouse cursor visibility is not guaranteed to be preserved during screen updates this routine has to restore the mouse cursor after the update (usually by calling `HideMouse` from unit `Mouse` before the real update and `ShowMouse` afterwards).

For an example, see most other functions.

Errors: None.

See also: `ClearScreen` ([1910](#))

Chapter 86

Reference for unit 'winCRT'

86.1 Used units

Table 86.1: Used units by unit 'winCRT'

Name	Page
System	1194

86.2 Overview

The `winCRT` unit provides some auxiliary routines for use with the `graph` ([782](#)) unit, namely keyboard support. It has no connection with the `crt` ([511](#)) unit, nor with the Turbo-Pascal for Windows `WinCrt` unit. As such, it should not be used by end users. Refer to the `crt` ([511](#)) unit instead.

86.3 Constants, types and variables

86.3.1 Variables

`directvideo` : Boolean

On windows, this variable is ignored.

`lastmode` : Word

Is supposed to contain the last used video mode, but is actually unused.

86.4 Procedures and functions

86.4.1 `delay`

Synopsis: Pause program execution

Declaration: `procedure delay(ms: Word)`

Visibility: default

Description: Delay stops program execution for the indicated number ms of milliseconds.

See also: sound ([1923](#)), nosound ([1923](#))

86.4.2 keypressed

Synopsis: Check if a key was pressed.

Declaration: `function keypressed : Boolean`

Visibility: default

Description: KeyPressed returns True if the user pressed a key, or False if not. It does not wait for the user to press a key.

See also: readkey ([1923](#))

86.4.3 nosound

Synopsis: Stop the speaker

Declaration: `procedure nosound`

Visibility: default

Description: NoSound does nothing, windows does not support this.

See also: sound ([1923](#))

86.4.4 readkey

Synopsis: Read a key from the keyboard

Declaration: `function readkey : Char`

Visibility: default

Description: ReadKey reads a key from the keyboard, and returns the ASCII value of the key, or the scancode of the key in case it is a special key.

The function waits until a key is pressed.

See also: KeyPressed ([1923](#))

86.4.5 sound

Synopsis: Sound PC speaker

Declaration: `procedure sound(hz: Word)`

Visibility: default

Description: Sound sounds the PC speaker. It emits a tone with frequency Hz for 500 milliseconds. (the time argument is required by the windows API)

See also: nosound ([1923](#))

86.4.6 **textmode**

Synopsis: Set indicated text mode

Declaration: `procedure textmode(mode: Integer)`

Visibility: `default`

Description: `TextMode` does nothing.

Chapter 87

Reference for unit 'windirs'

87.1 Used units

Table 87.1: Used units by unit 'windirs'

Name	Page
System	1194
windows	??

87.2 Overview

This unit contains only one function: `GetWindowsSpecialDir` ([1928](#)). It is a simple pascal wrapper around the `shfolder.dll` library, and is available under Windows only.

87.3 Constants, types and variables

87.3.1 Constants

`CSIDL_ADMINTOOLS` = `$0030`

ID for the personal "Start Menu\Programs\Administrative tools" folder (In the user's personal folder)

`CSIDL_APPDATA` = `$001A`

ID for the roaming "Application Data" folder (in the user's personal folder)

`CSIDL_CDBURN_AREA` = `$003B`

ID for the personal "Local Settings\Application Data\Microsoft\CD Burning" folder (Under "All users" folder)

`CSIDL_COMMON_ADMINTOOLS` = `$002F`

ID for the common "Start Menu\Programs\Administrative tools" folder (Under "All users" folder)

CSIDL_COMMON_APPDATA = \$0023

ID for the common "Application Data" folder (Under "All users" folder)

CSIDL_COMMON_DESKTOPDIRECTORY = \$0019

ID for the public "Desktop" folder (Under "All users" folder)

CSIDL_COMMON_DOCUMENTS = \$002E

ID for the common "Documents" folder (Under "All users" folder)

CSIDL_COMMON_FAVORITES = \$001F

ID for the public "Favorites" folder (Under "All users" folder)

CSIDL_COMMON_MUSIC = \$0035

ID for the common "Documents\My Music" folder (Under "All users" folder)

CSIDL_COMMON_PICTURES = \$0036

ID for the common "Documents\My Pictures" folder (Under "All users" folder)

CSIDL_COMMON_PROGRAMS = \$0017

ID for the public "Programs" folder (Under "All users" Start menu folder)

CSIDL_COMMON_STARTMENU = \$0016

ID for the public "Start Menu" folder (Under "All users")

CSIDL_COMMON_STARTUP = \$0018

ID for the public "Startup" folder (Under "All users\Start menu\Programs" folder)

CSIDL_COMMON_TEMPLATES = \$002D

ID for the common "Templates" folder (Under "All users" folder)

CSIDL_COMMON_VIDEO = \$0037

ID for the common "Documents\My Video" folder (Under "All users" folder)

CSIDL_COOKIES = \$0021

ID for the "Cookies" folder (in the user's personal folder)

CSIDL_DESKTOPDIRECTORY = \$0010

ID for the "Desktop" folder (in the user's personal folder)

CSIDL_FAVORITES = \$0006

ID for the "Favourites" folder (in the user's personal folder)

CSIDL_FLAG_CREATE = \$8000

Flag to specify if the requested folder must be created if it didn't exist yet.

CSIDL_HISTORY = \$0022

ID for the "History" folder (in the user's personal folder)

CSIDL_INTERNET_CACHE = \$0020

ID for the "Temporary Internet Files" folder (in the user's personal folder)

CSIDL_LOCAL_APPDATA = \$001C

ID for the local "Application Data" folder (in the user's personal folder)

CSIDL_MYMUSIC = \$000D

ID for the "My Music" folder (in the user's personal folder)

CSIDL_MYPICTURES = \$0027

ID for the "My Pictures" folder (in the user's personal folder)

CSIDL_MYVIDEO = \$000E

ID for the "My Videos" folder (in the user's personal folder)

CSIDL_NETHOOD = \$0013

ID for the "Nethood" folder (in the user's personal folder)

CSIDL_PERSONAL = \$0005

ID for the "My Documents" folder (in the user's personal folder)

CSIDL_PRINTHOOD = \$001B

ID for the "Printhood" folder (in the user's personal folder)

CSIDL_PROFILE = \$0028

ID for the user's personal folder

CSIDL_PROFILES = \$003E

ID for the parent folder for the user's folders

CSIDL_PROGRAMS = \$0002

ID for the "Program files" folder

CSIDL_PROGRAM_FILES = \$0026

ID for the "Program Files" folder (alias for CSIDL_PROGRAMS)

CSIDL_PROGRAM_FILES_COMMON = \$002B

ID for the Common folder under the "Program Files" folder.

CSIDL_RECENT = \$0008

ID for the "Recent" folder (in the user's personal folder)

CSIDL_SENDTO = \$0009

ID for the "Send to" folder (in the user's personal folder)

CSIDL_STARTMENU = \$000B

ID for the "Start menu" folder (in the user's personal folder)

CSIDL_STARTUP = \$0007

ID for the "Startup" menu folder (in the user's personal folder)

CSIDL_SYSTEM = \$0025

ID for the Windows System32 dir.

CSIDL_TEMPLATES = \$0015

ID for the "Templates" folder (in the user's personal folder)

CSIDL_WINDOWS = \$0024

ID for the Windows installation dir.

87.4 Procedures and functions

87.4.1 GetWindowsSpecialDir

Synopsis: Get the location of a special directory.

Declaration: `function GetWindowsSpecialDir(ID: Integer; CreateIfNotExists: Boolean)
: string`

Visibility: default

Description: `GetWindowsSpecialDir` can be used to get the path of special folders on the Windows system. The locations are identified using one of the `CSIDL_*` constants. If the ID of a location is or-ed with the `CSIDL_FLAG_CREATE` constant, then the directory will be created if it didn't exist yet (and the user has sufficient rights to do so).

Errors: On error, an empty string is returned.

87.4.2 GetWindowsSpecialDirUnicode

Declaration: `function GetWindowsSpecialDirUnicode(ID: Integer;
CreateIfNotExists: Boolean)
: UnicodeString`

Visibility: default

87.4.3 GetWindowsSystemDirectory

Declaration: `function GetWindowsSystemDirectory : string`

Visibility: default

87.4.4 GetWindowsSystemDirectoryUnicode

Declaration: `function GetWindowsSystemDirectoryUnicode : UnicodeString`

Visibility: default

Chapter 88

Reference for unit 'x86'

88.1 Used units

Table 88.1: Used units by unit 'x86'

Name	Page
BaseUnix	124
System	1194

88.2 Overview

The x86 unit contains some of the routines that were present in the 1.0.X Linux unit, and which were Intel (PC) architecture specific.

These calls have been preserved for compatibility, but should be considered deprecated: they are not portable and may not even work on future Linux versions.

88.3 Procedures and functions

88.3.1 fpIOperm

Synopsis: Set permission on IO ports

Declaration: `function fpIOperm(From: Cardinal; Num: Cardinal; Value: cint) : cint`

Visibility: default

Description: `fpIOperm` sets permissions on `Num` ports starting with port `From` to `Value`. The function returns zero if the call was successful, a nonzero value otherwise.

Note:

- This works ONLY as root.
- Only the first `0x03ff` ports can be set.
- When doing a `FpFork` ([178](#)), the permissions are reset. When doing a `FpExecVE` ([175](#)) they are kept.

Errors: Extended error information can be retrieved with `FpGetErrno` ([181](#))

88.3.2 fpIoPL

Synopsis: Set I/O privilege level

Declaration: `function fpIoPL(Level: cint) : cint`

Visibility: default

Description: `FpIoPL` sets the I/O privilege level. It is intended for completeness only, one should normally not use it.

88.3.3 ReadPort

Synopsis: Read data from a PC port

Declaration: `procedure ReadPort(Port: LongInt; var Value: Byte)`
`procedure ReadPort(Port: LongInt; var Value: LongInt)`
`procedure ReadPort(Port: LongInt; var Value: Word)`

Visibility: default

Description: `ReadPort` reads one Byte, Word or Longint from port `Port` into `Value`.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1930), `ReadPortB` (1931), `ReadPortW` (1932), `ReadPortL` (1932), `WritePort` (1932), `WritePortB` (1933), `WritePortL` (1933), `WritePortW` (1933)

88.3.4 ReadPortB

Synopsis: Read bytes from a PC port

Declaration: `function ReadPortB(Port: LongInt) : Byte`
`procedure ReadPortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortB` reads `Count` bytes from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` bytes.

The functional form of `ReadPortB` reads 1 byte from port `B` and returns the byte that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1930), `ReadPort` (1931), `ReadPortW` (1932), `ReadPortL` (1932), `WritePort` (1932), `WritePortB` (1933), `WritePortL` (1933), `WritePortW` (1933)

88.3.5 ReadPortL

Synopsis: Read longints from a PC port

Declaration: `function ReadPortL(Port: LongInt) : LongInt`
`procedure ReadPortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortL` reads `Count` longints from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` Longints.

The functional form of `ReadPortL` reads 1 longint from port `B` and returns the longint that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1930), `ReadPort` (1931), `ReadPortW` (1932), `ReadPortB` (1931), `WritePort` (1932), `WritePortB` (1933), `WritePortL` (1933), `WritePortW` (1933)

88.3.6 ReadPortW

Synopsis: Read Words from a PC port

Declaration: `function ReadPortW(Port: LongInt) : Word`
`procedure ReadPortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The procedural form of `ReadPortW` reads `Count` words from port `Port` and stores them in `Buf`. There must be enough memory allocated at `Buf` to store `Count` words.

The functional form of `ReadPortW` reads 1 word from port `B` and returns the word that was read.

Note that you need permission to read a port. This permission can be set by the root user with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions read this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1930), `ReadPort` (1931), `ReadPortB` (1931), `ReadPortL` (1932), `WritePort` (1932), `WritePortB` (1933), `WritePortL` (1933), `WritePortW` (1933)

88.3.7 WritePort

Synopsis: Write data to PC port

Declaration: `procedure WritePort(Port: LongInt; Value: Byte)`
`procedure WritePort(Port: LongInt; Value: LongInt)`
`procedure WritePort(Port: LongInt; Value: Word)`

Visibility: default

Description: `WritePort` writes `Value` – 1 byte, `Word` or longint – to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1930\)](#), [WritePortB \(1933\)](#), [WritePortL \(1933\)](#), [WritePortW \(1933\)](#), [ReadPortB \(1931\)](#), [ReadPortL \(1932\)](#), [ReadPortW \(1932\)](#)

88.3.8 WritePortB

Synopsis: Write byte to PC port

Declaration: `procedure WritePortB(Port: LongInt; Value: Byte)`
`procedure WritePortB(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1930\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1930\)](#), [WritePort \(1932\)](#), [WritePortL \(1933\)](#), [WritePortW \(1933\)](#), [ReadPortB \(1931\)](#), [ReadPortL \(1932\)](#), [ReadPortW \(1932\)](#)

88.3.9 WritePortL

Synopsis: Write longint to PC port.

Declaration: `procedure WritePortL(Port: LongInt; Value: LongInt)`
`procedure WritePortL(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortL` writes 1 longint to port `Port`. The second form writes `Count` longints from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the [FpIOPerm \(1930\)](#) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: [FpIOPerm \(1930\)](#), [WritePort \(1932\)](#), [WritePortB \(1933\)](#), [WritePortW \(1933\)](#), [ReadPortB \(1931\)](#), [ReadPortL \(1932\)](#), [ReadPortW \(1932\)](#)

88.3.10 WritePortW

Synopsis: Write Word to PC port

Declaration: `procedure WritePortW(Port: LongInt; Value: Word)`
`procedure WritePortW(Port: LongInt; var Buf; Count: LongInt)`

Visibility: default

Description: The first form of `WritePortB` writes 1 byte to port `Port`. The second form writes `Count` bytes from `Buf` to port `Port`.

Remark: You need permission to write to a port. This permission can be set with root permission with the `FpIOPerm` (1930) call.

Errors: In case of an error (not enough permissions to write to this port), runtime 216 (*Access Violation*) will occur.

See also: `FpIOPerm` (1930), `WritePort` (1932), `WritePortL` (1933), `WritePortB` (1933), `ReadPortB` (1931), `ReadPortL` (1932), `ReadPortW` (1932)