

globus gssapi gsi  
7.8

Generated by Doxygen 1.7.4

Tue Jun 7 2011 13:21:33

## Contents

<b>1</b>	<b>Deprecated List</b>	<b>1</b>
<b>2</b>	<b>Module Index</b>	<b>1</b>
2.1	Modules . . . . .	1
<b>3</b>	<b>Module Documentation</b>	<b>1</b>
3.1	Functions for manipulating a buffer set . . . . .	1
3.2	GSI GSS-API Constants . . . . .	2
3.3	Activation . . . . .	2
3.3.1	Detailed Description . . . . .	2
3.3.2	Define Documentation . . . . .	2
3.4	GSS Req Flags . . . . .	2
3.4.1	Detailed Description . . . . .	2
3.4.2	Define Documentation . . . . .	3
3.5	GSS Ret Flags . . . . .	3
3.5.1	Detailed Description . . . . .	3
3.5.2	Define Documentation . . . . .	3

## 1 Deprecated List

**Global** [GSS\\_C\\_GLOBUS\\_ACCEPT\\_PROXY\\_SIGNED\\_BY\\_LIMITED\\_PROXY\\_FLAG](#) We now accept proxies signed by limited proxies if they are limited or independent.

## 2 Module Index

### 2.1 Modules

Here is a list of all modules:

<b>Functions for manipulating a buffer set</b>	<b>1</b>
<b>GSI GSS-API Constants</b>	<b>2</b>
<b>Activation</b>	<b>2</b>
<b>GSS Req Flags</b>	<b>2</b>
<b>GSS Ret Flags</b>	<b>3</b>

## 3 Module Documentation

### 3.1 Functions for manipulating a buffer set

## 3.2 GSI GSS-API Constants

### 3.3 Activation

Globus GSI GSSAPI uses standard Globus module activation and deactivation.

#### Defines

- `#define GLOBUS_GSI_GSSAPI_MODULE`

#### 3.3.1 Detailed Description

Globus GSI GSSAPI uses standard Globus module activation and deactivation. Before any Globus GSI GSSAPI functions are called, the following function should be called:

```
globus_module_activate(GLOBUS_GSI_GSSAPI_MODULE)
```

This function returns `GLOBUS_SUCCESS` if Globus GSI GSSAPI was successfully initialized, and you are therefore allowed to subsequently call Globus GSI GSSAPI functions. Otherwise, an error code is returned, and Globus GSI GSSAPI functions should not subsequently be called. This function may be called multiple times.

To deactivate Globus GSI GSSAPI, the following function should be called:

```
globus_module_deactivate(GLOBUS_GSI_GSSAPI_MODULE)
```

This function should be called once for each time Globus GSI GSSAPI was activated.

Note that it is not mandatory to call the above functions.

#### 3.3.2 Define Documentation

##### 3.3.2.1 `#define GLOBUS_GSI_GSSAPI_MODULE`

Module descriptor.

## 3.4 GSS Req Flags

These macros set the REQUESTED type of context - these should be set (or not) in the context's `req_flags` (or in the context's `ret_flags` if `accept_sec_context` is being called)

#### Defines

- `#define GSS_C_GLOBUS_DONT_ACCEPT_LIMITED_PROXY_FLAG 8192`
- `#define GSS_C_GLOBUS_DELEGATE_LIMITED_PROXY_FLAG 4096`
- `#define GSS_C_GLOBUS_ACCEPT_PROXY_SIGNED_BY_LIMITED_PROXY_FLAG 32768`

#### 3.4.1 Detailed Description

These macros set the REQUESTED type of context - these should be set (or not) in the context's `req_flags` (or in the context's `ret_flags` if `accept_sec_context` is being called)

### 3.4.2 Define Documentation

#### 3.4.2.1 `#define GSS_C_GLOBUS_DONT_ACCEPT_LIMITED_PROXY_FLAG 8192`

Set if you don't want a context to accept a limited proxy.

If this flag is set, and a limited proxy is received, the call will not be successful and the context will not be set up

#### 3.4.2.2 `#define GSS_C_GLOBUS_DELEGATE_LIMITED_PROXY_FLAG 4096`

Set if you want the delegated proxy to be a limited proxy.

#### 3.4.2.3 `#define GSS_C_GLOBUS_ACCEPT_PROXY_SIGNED_BY_LIMITED_PROXY_FLAG 32768`

Set if you want to accept proxies signed by limited proxies.

### Deprecated

We now accept proxies signed by limited proxies if they are limited or independent.

## 3.5 GSS Ret Flags

These macros set the RETURNED context type - these will be set (or not) in the context's `ret_flags`.

### Defines

- `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_FLAG 8192`
- `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_DURING_DELEGATION_FLAG 4096`

### 3.5.1 Detailed Description

These macros set the RETURNED context type - these will be set (or not) in the context's `ret_flags`.

### 3.5.2 Define Documentation

#### 3.5.2.1 `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_FLAG 8192`

If the proxy received is a limited proxy, this flag will be set in the returned context flags (`ret_flags`)

#### 3.5.2.2 `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_DURING_DELEGATION_FLAG 4096`

If the proxy received is a limited proxy received during delegation, this flag is set in the returned flags.

## Index

Activation, [1](#)

    GLOBUS\_GSI\_GSSAPI\_MODULE, [2](#)

Functions for manipulating a buffer set, [1](#)

GLOBUS\_GSI\_GSSAPI\_MODULE

    Activation, [2](#)

GSI GSS-API Constants, [1](#)

GSS Req Flags, [2](#)

    GSS\_C\_GLOBUS\_ACCEPT\_PROXY\_SIGNED\_BY\_-  
        LIMITED\_PROXY\_FLAG, [2](#)

    GSS\_C\_GLOBUS\_DELEGATE\_LIMITED\_PROXY\_-  
        FLAG, [2](#)

    GSS\_C\_GLOBUS\_DONT\_ACCEPT\_LIMITED\_PROXY\_-  
        FLAG, [2](#)

GSS Ret Flags, [2](#)

    GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_-  
        DURING\_DELEGATION\_FLAG, [3](#)

    GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_-  
        FLAG, [3](#)

GSS\_C\_GLOBUS\_ACCEPT\_PROXY\_SIGNED\_BY\_LIMITED\_-  
    PROXY\_FLAG

    GSS Req Flags, [2](#)

GSS\_C\_GLOBUS\_DELEGATE\_LIMITED\_PROXY\_FLAG

    GSS Req Flags, [2](#)

GSS\_C\_GLOBUS\_DONT\_ACCEPT\_LIMITED\_PROXY\_-  
    FLAG

    GSS Req Flags, [2](#)

GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_DURING\_-  
    DELEGATION\_FLAG

    GSS Ret Flags, [3](#)

GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_FLAG

    GSS Ret Flags, [3](#)