

globus gram job manager callout error

2.1

Generated by Doxygen 1.8.3.1

Thu Nov 7 2013 12:33:50

Contents

1 Module Index	1
1.1 Modules	1
2 Module Documentation	1
2.1 Activation	1
2.1.1 Detailed Description	1
2.1.2 Macro Definition Documentation	2
2.2 Datatypes	3
2.2.1 Detailed Description	3
2.2.2 Enumeration Type Documentation	3
Index	4

1 Module Index

1.1 Modules

Here is a list of all modules:

Activation	1
Datatypes	3

2 Module Documentation

2.1 Activation

Macros

- #define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE

2.1.1 Detailed Description

Globus GRAM Jobmanager Callout Error API uses standard Globus module activation and deactivation. Before any Globus GRAM Jobmanager Callout Error API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function returns GLOBUS_SUCCESS if the Globus GRAM Jobmanager Callout Error API was successfully initialized, and you are therefore allowed to subsequently call Globus GRAM Jobmanager Callout Error API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GRAM Jobmanager Callout Error API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE)
```

This function should be called once for each time Globus GRAM Jobmanager Callout Error API was activated.

2.1.2 Macro Definition Documentation

2.1.2.1 #define GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE

Module descriptor.

2.2 Datatypes

Enumerations

- enum `globus_gram_jobmanager_callout_error_t`{
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS` = 0,
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR` = 1,
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED` = 2,
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB` = 3,
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE` = 4,
`GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST` = 5 }

2.2.1 Detailed Description

2.2.2 Enumeration Type Documentation

2.2.2.1 enum `globus_gram_jobmanager_callout_error_t`

GRAM Jobmanager Callout Error codes.

Enumerator

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CREDS` Credentials not accepted.

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_SYSTEM_ERROR` Authorization system misconfigured.

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED` Authorization denied.

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_INVALID_JOB` Authorization denied - invalid job id.

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHZ_DENIED_BAD_EXECUTABLE` Authorization denied - executable not allowed.

`GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST` Last marker - never used.

Index

Activation, 1
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE, 1

Datatypes, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED_BAD_EXECUTABLE, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED_INVALID_JOB, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_SYSTEM_ERROR, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CRED, 2
 GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST, 2
 globus_gram_jobmanager_callout_error_t, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED_BAD_EXECUTABLE
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_DENIED_INVALID_JOB
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_AUTHORIZATION_SYSTEM_ERROR
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_BAD_CRED
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_LAST
 Datatypes, 2

GLOBUS_GRAM_JOBMANAGER_CALLOUT_ERROR_MODULE
 Activation, 1

globus_gram_jobmanager_callout_error_t
 Datatypes, 2